

FMC Linux Setup

[FMC Linux Home Page](#)

-
- ↓ [Worker Nodes and Control Nodes](#)
 - ↓ [Worker Node Setup](#)
 - ↓ [Unauthenticated Worker Node Setup](#)
 - ↓ [Authenticated Worker Node Setup](#)
 - ↓ [Control Node Setup](#)
 - ↓ [Unauthenticated Control Node Setup](#)
 - ↓ [Authenticated Control Node Setup](#)
-


Worker Nodes and Control Nodes

FMC consists, at present, of 16 server processes. In a typical farm setup, among these processes:

- The 11 Monitor Servers ([coalSrv\(8\)](#), [cpuinfoSrv\(8\)](#), [cpustatSrv\(8\)](#), [fsSrv\(8\)](#), [irqSrv\(8\)](#), [memSrv\(8\)](#), [osSrv\(8\)](#), [nifSrv\(8\)](#), [psSrv\(8\)](#), [smartSrv\(8\)](#) and [tcpipSrv\(8\)](#)) have to run on *each* farm node;
- The Message Logger Server ([_logSrv\(8\)](#)) and the Task Manager Server ([_tmSrv\(8\)](#)) and the Configuration Manager Server ([_cmSrv\(8\)](#)) also have to run on *each* farm node;
- The Power Manager Server ([_ipmiSrv\(8\)](#)) and the Process Controller Server ([_pcSrv\(8\)](#)) need not to run on each farm node: they can run instead on a *reduced* number of nodes (**Control Nodes**) which control the other nodes (**Worker Nodes**).

In order for this 16 servers to work an additional server process is needed — the **DIM Name Server** — which must be in execution on a node hereinafter referred as **DIM_DNS_NODE**. Concerning the configuration of the DIM network communication layer, refer to the documents in <http://dim.web.cern.ch/dim/>.

Furthermore, in the FMC setup choice, consider that the **Power Manager** ([_ipmiSrv\(8\)](#)) is able to switch on and off the other nodes, but it is not able to switch on and off the node on which it is running.



[to top](#)

Worker Node Setup

In this setup only the **Message Logger Server**, the **Task Manager Server** and the **Configuration Manager Server** are started on the current node (by the System V start-up scripts `/etc/rc.d/init.d/fmc`). The 11 **Monitor Servers** are then started on the current node by the **Process Controller Server** running on the **Control Node** which controls the current node.

[to top](#)

Unauthenticated Worker Node Setup

- Install the RPM:
`ipmitool-1.8.9-1.slc4.`
- Download:
`dim-v17r7-1.RHEL4.i386.rpm` (32 bit)
or
`dim-v17r7-1.RHEL4.x86_64.rpm` (64 bit)
from <http://lhcb-dag.web.cern.ch/lhcb-dag/online-rpm-repo/index.html> and install it.
- Download:
`FMC-X.X.X-X.RHEL4.i386.rpm` (32 bit)
or
`FMC-X.X.X-X.RHEL4.x86_64.rpm` (64 bit)

from <http://lhcb-dag.web.cern.ch/lhcb-dag/online-rpm-repo/index.html> or
[/afs.cern.ch/lhcb/project/web/online/online-rpm-repo/slc4X/](http://afs.cern.ch/lhcb/project/web/online/online-rpm-repo/slc4X/).

- Type:
`rpm -ivh FMC-X.X.X-X.RHEL4.i386.rpm` (32 bit)
or
`rpm -ivh FMC-X.X.X-X.RHEL4.x86_64.rpm` (64 bit).
- Create the user:
`online.`
- Edit the text file
[/etc/sysconfig/dim](#)
as described in [this link](#) to define the DIM Name Server node.
- Edit the text file
[/etc/sysconfig/fmc](#)
as described in [this link](#) to choose the FMC Servers to be started by the System V start-up scripts as follows:

```
# -----
LOG_SRV=yes                # Message Logger Server
TM_SRV=yes                 # Task Manager Server
CM_SRV=yes                 # Configuration Manager Server
PC_SRV=no                  # Process Controller Server
IPMI_SRV=no                # Power Manager Server
# -----
LOG_ARGS="-S 200"
TM_ARGS="-p 2 -u online -U root --no-auth"
CM_ARGS=""
PC_ARGS="-u online -g online --no-auth"
IPMI_ARGS="-t 0"
# -----
```

- Edit the text file:
[/etc/cmSrv.conf](#)
as described in [this link](#) to set-up the Configuration Manager file access configuration.
- Edit the text file
[/etc/cmSrv.allow](#)
as described in [this link](#) to set-up the Configuration Manager user@host access configuration.
- To start FMC tools immediately, type:
`service fmc start`
- To start automatically the FMC tools at each bootstrap, type:
`chkconfig --levels 345 fmc on`
`chkconfig --levels 0126 fmc off`

[to top](#)

Authenticated Worker Node Setup

- Install the RPM:
`ipmitool-1.8.9-1.slc4.`
- Download:
`dim-v17r7-1.RHEL4.i386.rpm` (32 bit)
or
`dim-v17r7-1.RHEL4.x86_64.rpm` (64 bit)
from <http://lhcb-dag.web.cern.ch/lhcb-dag/online-rpm-repo/index.html> and install it.
- Download:
`FMC-X.X.X-X.RHEL4.i386.rpm` (32 bit)
or
`FMC-X.X.X-X.RHEL4.x86_64.rpm` (64 bit)
from <http://lhcb-dag.web.cern.ch/lhcb-dag/online-rpm-repo/index.html> or

</afs/cern.ch/lhcb/project/web/online/online-rpm-repo/slc4X/>.

- Type:
`rpm -ivh FMC-X.X.X-X.RHEL4.i386.rpm` (32 bit)
 or
`rpm -ivh FMC-X.X.X-X.RHEL4.x86_64.rpm` (64 bit).
- Create the user:
`online.`
- Edit the text file
</etc/sysconfig/dim>
 as described in [this link](#) to define the DIM Name Server node.
- Edit the text file
</etc/sysconfig/fmc>
 as described in [this link](#) to choose the FMC Servers to be started by the System V start-up scripts as follows:

```
# -----
LOG_SRV=yes                # Message Logger Server
TM_SRV=yes                 # Task Manager Server
CM_SRV=yes                 # Configuration Manager Server
PC_SRV=no                  # Process Controller Server
IPMI_SRV=no                # Power Manager Server
# -----
LOG_ARGS="-S 200"
TM_ARGS="-p 2 -u online -U root"
CM_ARGS=""
PC_ARGS="-u online -g online"
IPMI_ARGS="-t 0"
# -----
```

- Edit the text file:
</etc/cmSrv.conf>
 as described in [this link](#) to set-up the Configuration Manager file access configuration.
- Edit the text file
</etc/cmSrv.allow>
 as described in [this link](#) to set-up the Configuration Manager user@host access configuration.
- Edit the text file
</etc/tmSrv.allow>
 as described in [this link](#) to set-up the Task Manager user@host access configuration.
- To start FMC tools immediately, type:
`service fmc start`
- To start automatically the FMC tools at each bootstrap, type:
`chkconfig --levels 345 fmc on`
`chkconfig --levels 0126 fmc off`

[to top](#)

Control Node Setup

In this setup **all** the FMC servers are started on the current node. The **Message Logger Server**, the **Task Manager Server**, the **Configuration Manager Server**, the **Power Manager Server** and the **Process Controller Server** are started by the System file start-up script (`/etc/rc.d/init.d/fmc`). The **11 Monitor Servers** are then started by the Process Controller Server running on the current node.

[to top](#)

Unauthenticated Control Node Setup

- Install the RPM:
`ipmitool-1.8.9-1.slc4.`
- Download:
`dim-v17r7-1.RHEL4.i386.rpm` (32 bit)
or
`dim-v17r7-1.RHEL4.x86_64.rpm` (64 bit)
from <http://lhcb-dag.web.cern.ch/lhcb-dag/online-rpm-repo/index.html> and install it.
- Download:
`FMC-X.X.X-X.RHEL4.i386.rpm` (32 bit)
or
`FMC-X.X.X-X.RHEL4.x86_64.rpm` (64 bit)
from <http://lhcb-dag.web.cern.ch/lhcb-dag/online-rpm-repo/index.html> or
[/afs.cern.ch/lhcb/project/web/online/online-rpm-repo/slc4X/](http://afs.cern.ch/lhcb/project/web/online/online-rpm-repo/slc4X/).
- Type:
`rpm -ivh FMC-X.X.X-X.RHEL4.i386.rpm` (32 bit)
or
`rpm -ivh FMC-X.X.X-X.RHEL4.x86_64.rpm` (64 bit).
- Create the user:
`online.`
- Edit the text file
[/etc/sysconfig/dim](#)
as described in [this link](#) to define the DIM Name Server node.
- Edit the text file
[/etc/sysconfig/fmc](#)
as described in [this link](#) to choose the FMC Servers to be started by the System V start-up scripts as follows:

```
# -----
LOG_SRV=yes                # Message Logger Server
TM_SRV=yes                 # Task Manager Server
CM_SRV=yes                 # Configuration Manager Server
PC_SRV=yes                 # Process Controller Server
IPMI_SRV=yes               # Power Manager Server
# -----
LOG_ARGS="-S 200"
TM_ARGS="-p 2 -u online -U root --no-auth"
CM_ARGS=""
PC_ARGS="-u online -g online --no-auth"
IPMI_ARGS="-t 0"
# -----
```

- Edit the text file:
[/etc/cmSrv.conf](#)
as described in [this link](#) to set-up the Configuration Manager file access configuration.
- Edit the text file
[/etc/cmSrv.allow](#)
as described in [this link](#) to set-up the Configuration Manager user@host access configuration.
- Edit the text file
[/etc/ipmiSrv.conf](#)
as described in [this link](#) to define the default IPMI username and password and the per-node IPMI configuration.
- Edit the text file
[/etc/pcSrv.conf](#)
as described in [this link](#) to define the list of the worker nodes which have to be controlled by the Process Controller Server running on the current node. The list must include also the current node.
- Edit the text file
[/etc/pcSrv.init](#)

as described in [this link](#) to check the Monitor Servers to be started on the controlled worker nodes by the Process Controller Server running on the current nodes.

- To start FMC tools immediately, type:
`service fmc start`
- To start automatically the FMC tools at each bootstrap, type:
`chkconfig --levels 345 fmc on`
`chkconfig --levels 0126 fmc off`

[to top](#)

Authenticated Control Node Setup

- Install the RPM:
`ipmitool-1.8.9-1.slc4.`
- Download:
`dim-v17r7-1.RHEL4.i386.rpm` (32 bit)
or
`dim-v17r7-1.RHEL4.x86_64.rpm` (64 bit)
from <http://lhcb-daq.web.cern.ch/lhcb-daq/online-rpm-repo/index.html> and install it.
- Download:
`FMC-X.X.X-X.RHEL4.i386.rpm` (32 bit)
or
`FMC-X.X.X-X.RHEL4.x86_64.rpm` (64 bit)
from <http://lhcb-daq.web.cern.ch/lhcb-daq/online-rpm-repo/index.html> or
[/afs/cern.ch/lhcb/project/web/online/online-rpm-repo/slc4X/](http://afs.cern.ch/lhcb/project/web/online/online-rpm-repo/slc4X/).
- Type:
`rpm -ivh FMC-X.X.X-X.RHEL4.i386.rpm` (32 bit)
or
`rpm -ivh FMC-X.X.X-X.RHEL4.x86_64.rpm` (64 bit).
- Create the user:
`online.`
- Edit the text file
[/etc/sysconfig/dim](#)
as described in [this link](#) to define the DIM Name Server node.
- Edit the text file
[/etc/sysconfig/fmc](#)
as described in [this link](#) to choose the FMC Servers to be started by the System V start-up scripts as follows:

```
# -----
LOG_SRV=yes                # Message Logger Server
TM_SRV=yes                 # Task Manager Server
CM_SRV=yes                 # Configuration Manager Server
PC_SRV=yes                 # Process Controller Server
IPMI_SRV=yes               # Power Manager Server
# -----
LOG_ARGS="-S 200"
TM_ARGS="-p 2 -u online -U root"
CM_ARGS=""
PC_ARGS="-u online -g online"
IPMI_ARGS="-t 0"
# -----
```

- Edit the text file:
[/etc/cmSrv.conf](#)
as described in [this link](#) to set-up the Configuration Manager file access configuration.
- Edit the text file
[/etc/cmSrv.allow](#)

- as described in [this link](#) to set-up the Configuration Manager user@host access configuration.
- Edit the text file
[/etc/tmSrv.allow](#)
as described in [this link](#) to set-up the Task Manager user@host access configuration.
- Edit the text file
[/etc/ipmiSrv.conf](#)
as described in [this link](#) to define the default IPMI username and password and the per-node IPMI configuration.
- Edit the text file
[/etc/pcSrv.conf](#)
as described in [this link](#) to define the list of the worker nodes which have to be controlled by the Process Controller Server running on the current node. The list must include also the current node.
- Edit the text file
[/etc/pcSrv.init](#)
as described in [this link](#) to check the Monitor Servers to be started on the controlled worker nodes by the Process Controller Server running on the current nodes.
- Edit the text file
[/etc/pcSrv.allow](#)
as described in [this link](#) to set-up the Pocess Controller user@host access configuration.
- To start FMC tools immediately, type:
`service fmc start`
- To start automatically the FMC tools at each bootstrap, type:
`chkconfig --levels 345 fmc on`
`chkconfig --levels 0126 fmc off`

[to top](#)

[FMC Linux Home Page](#)

-- [DomenicoGalli](#), 18 Nov 2008 - 09:38

Revision: r1.9 - 18 Nov 2008 - 09:38 - [DomenicoGalli](#)

[LHCbBologna](#) > FmcSetup

Copyright © 1999–2009 by the contributing authors. All material on this collaboration platform is the property of the contributing authors.

Ideas, requests, problems regarding TWiki? [Send feedback](#)