



We are now Refinitiv, formerly the Financial and Risk business of Thomson Reuters. We've set a bold course for the future – both ours and yours – and are introducing our new brand to the world.

As our brand migration will be gradual, you will see traces of our past through documentation, videos, and digital platforms.

Thank you for joining us on our brand journey.



# Transport API C Edition V3.3.1

## VALUE ADDED COMPONENTS

### DEVELOPERS GUIDE C EDITION



© Thomson Reuters 2015 - 2019. All rights reserved.

Thomson Reuters, by publishing this document, does not guarantee that any information contained herein is and will remain accurate or that use of the information will ensure correct and faultless operation of the relevant service or equipment. Thomson Reuters, its agents and employees, shall not be held liable to or through any user for any loss or damage whatsoever resulting from reliance on the information contained herein.

This document contains information proprietary to Thomson Reuters and may not be reproduced, disclosed, or used in whole or part without the express written permission of Thomson Reuters.

Any Software, including but not limited to, the code, screen, structure, sequence, and organization thereof, and Documentation are protected by national copyright laws and international treaty provisions. This manual is subject to U.S. and other national export regulations.

Nothing in this document is intended, nor does it, alter the legal obligations, responsibilities or relationship between yourself and Thomson Reuters as set out in the contract existing between us.

# Contents

<b>Chapter 1</b>	<b>Introduction .....</b>	<b>1</b>
1.1	About this Manual .....	1
1.2	Audience .....	1
1.3	Programming Language.....	1
1.4	Acronyms and Abbreviations .....	1
1.5	References .....	3
1.6	Documentation Feedback .....	3
1.7	Document Conventions.....	3
1.7.1	<i>Typographic</i> .....	3
1.7.2	<i>Document Structure</i> .....	3
1.7.3	<i>Diagrams</i> .....	4
<b>Chapter 2</b>	<b>Product Description and Overview .....</b>	<b>5</b>
2.1	What is the Transport API? .....	5
2.2	What are Transport API Value Added Components? .....	5
2.3	Transport API Reactor .....	6
2.4	OMM Consumer Watchlist .....	7
2.4.1	<i>Data Stream Aggregation and Recovery</i> .....	7
2.4.2	<i>ADS Multicast Consumption</i> .....	7
2.4.3	<i>Additional Features</i> .....	8
2.4.4	<i>Usage Notes</i> .....	8
2.4.5	<i>Configuring Multicast Connections</i> .....	8
2.5	Administration Domain Model Representations .....	9
2.6	Value Added Utilities .....	9
2.7	Value Added Cache .....	9
<b>Chapter 3</b>	<b>Building an OMM Consumer .....</b>	<b>10</b>
3.1	Overview .....	10
3.2	Leverage Existing or Create New RsslReactor .....	10
3.3	Implement Callbacks and Populate Role .....	10
3.4	Establish Connection using rsslReactorConnect .....	11
3.5	Issue Requests and/or Post Information .....	11
3.6	Log Out and Shut Down.....	12
3.7	Additional Consumer Details .....	12
<b>Chapter 4</b>	<b>Building an OMM Interactive Provider .....</b>	<b>13</b>
4.1	Overview .....	13
4.2	Leverage Existing or Create New RsslReactor .....	13
4.3	Create an RsslServer .....	14
4.4	Implement Callbacks and Populate Role .....	14
4.5	Associate Incoming Connections Using rsslReactorAccept.....	14
4.6	Perform Login Process.....	15
4.7	Provide Source Directory Information .....	15
4.8	Provide or Download Necessary Dictionaries .....	16
4.9	Handle Requests and Post Messages .....	16
4.10	Disconnect Consumers and Shut Down .....	17
4.11	Additional Interactive Provider Details .....	17
<b>Chapter 5</b>	<b>Building an OMM Non-Interactive Provider .....</b>	<b>18</b>
5.1	Building an OMM Non-Interactive Provider Overview .....	18

5.2	Leverage Existing or Create New RsslReactor .....	18
5.3	Implement Callbacks and Populate Role .....	19
5.4	Establish Connection using rsslReactorConnect .....	19
5.5	Perform Dictionary Download .....	20
5.6	Provide Content .....	20
5.7	Log Out and Shut Down .....	20
5.8	Additional Non-Interactive Provider Details .....	21
<b>Chapter 6</b>	<b>Reactor Detailed View .....</b>	<b>22</b>
6.1	Concepts .....	22
6.1.1	<i>Functionality: Transport API Versus Transport API Reactor</i> .....	23
6.1.2	<i>Reactor Error Handling</i> .....	24
6.1.3	<i>Reactor Error Info Codes</i> .....	24
6.1.4	<i>Transport API Reactor Application Lifecycle</i> .....	25
6.2	Reactor Use .....	26
6.2.1	<i>Creating a Reactor</i> .....	26
6.2.2	<i>Destroying a Reactor</i> .....	28
6.3	Reactor Channel Use .....	28
6.3.1	<i>Reactor Channel Roles</i> .....	31
6.3.2	<i>Reactor Channel Role: OMM Consumer</i> .....	32
6.3.3	<i>Reactor Channel Role: OMM Provider</i> .....	34
6.3.4	<i>Reactor Channel Role: OMM Non-Interactive Provider</i> .....	35
6.3.5	<i>Reactor Channel: Role Union</i> .....	36
6.4	Managing Reactor Channels .....	37
6.4.1	<i>Adding Reactor Channels</i> .....	37
6.4.2	<i>Removing Reactor Channels</i> .....	42
6.5	Reporting on Channel Statistics .....	43
6.6	Dispatching Data .....	43
6.6.1	<i>rsslReactorDispatch Function</i> .....	43
6.6.2	<i>Reactor Callback Functions</i> .....	45
6.6.3	<i>Reactor Callback: Channel Event</i> .....	45
6.6.4	<i>Reactor Callback: Default Message</i> .....	48
6.6.5	<i>Reactor Callback: RDM Login Message</i> .....	49
6.6.6	<i>Reactor Callback: RDM Directory Message</i> .....	51
6.6.7	<i>Reactor Callback: RDM Dictionary Message</i> .....	52
6.7	Writing Data .....	53
6.7.1	<i>Writing Data using rsslReactorSubmitMsg()</i> .....	54
6.7.2	<i>Writing data using rsslReactorSubmit()</i> .....	56
6.8	Creating and Using Tunnel Streams .....	64
6.8.1	<i>Authenticating a Tunnel Stream</i> .....	65
6.8.2	<i>Opening a Tunnel Stream</i> .....	66
6.8.3	<i>Negotiating Stream Behaviors: Class of Service</i> .....	67
6.8.4	<i>Tunnel Stream Callback Functions and Event Types</i> .....	71
6.8.5	<i>Opening a Tunnel Stream Code Sample</i> .....	74
6.8.6	<i>Accepting Tunnel Streams</i> .....	75
6.8.7	<i>Receiving Content on a TunnelStream</i> .....	79
6.8.8	<i>Sending Content on a TunnelStream</i> .....	80
6.9	Cloud Connectivity .....	84
6.9.1	<i>rsslReactorQueryServiceDiscovery</i> .....	84
6.9.2	<i>OAuth Credential Management</i> .....	86
6.10	Reactor Utility Functions .....	89
6.10.1	<i>General Reactor Utility Functions</i> .....	89
6.10.2	<i>RsslReactorChannelInfo Structure Members</i> .....	89
6.10.3	<i>rsslReactorIoctl Option Values</i> .....	90

<b>Chapter 7</b>	<b>Consuming Data from the Cloud .....</b>	<b>91</b>
7.1	Overview .....	91
7.2	Encrypted Connections .....	91
7.3	Authentication Token Management .....	92
7.3.1	<i>Client_ID (AppKey)</i> .....	92
7.3.2	<i>Obtaining Initial Access and Refresh Tokens</i> .....	92
7.3.3	<i>Refreshing the Access Token and Sending a Login Reissue</i> .....	93
7.3.4	<i>Managing the Password and Client Secret</i> .....	94
7.3.5	<i>Session Management per User Credential</i> .....	94
7.4	Service Discovery .....	95
7.5	Consuming Market Data .....	96
7.6	HTTP Error Handling for Reactor Token Reissues .....	96
7.7	Cloud Connection Use Cases .....	97
7.7.1	<i>Session Management Use Case</i> .....	97
7.7.2	<i>Disabling the Watchlist</i> .....	97
7.7.3	<i>Query Service Discovery</i> .....	97
<b>Chapter 8</b>	<b>Administration Domain Models Detailed View .....</b>	<b>99</b>
8.1	Concepts .....	99
8.2	RDM Message Base .....	100
8.2.1	<i>RSSL RDM Message Base Structure Members</i> .....	100
8.2.2	<i>RSSL RDM Message Types</i> .....	100
8.2.3	<i>RSSL RDM Encoding and Decoding Functions</i> .....	101
8.3	RDM Login Domain .....	101
8.3.1	<i>RSSL RDM Login Request</i> .....	102
8.3.2	<i>RSSL RDM Login Refresh</i> .....	106
8.3.3	<i>RSSL RDM Login Status</i> .....	114
8.3.4	<i>RSSL RDM Login Close</i> .....	116
8.3.5	<i>RSSL RDM Consumer Connection Status</i> .....	116
8.3.6	<i>Login Post Message Use</i> .....	118
8.3.7	<i>Login Ack Message Use</i> .....	118
8.3.8	<i>RSSL RDM Login Message Union</i> .....	118
8.3.9	<i>Login Encoding and Decoding</i> .....	119
8.4	Source Directory Domain .....	124
8.4.1	<i>RSSL RDM Directory Request</i> .....	124
8.4.2	<i>RSSL RDM Directory Refresh</i> .....	125
8.4.3	<i>RSSL RDM Directory Update</i> .....	126
8.4.4	<i>RSSL RDM Directory Status</i> .....	128
8.4.5	<i>RSSL RDM Directory Close</i> .....	129
8.4.6	<i>RSSL RDM Consumer Status</i> .....	129
8.4.7	<i>Source Directory RDM Service</i> .....	130
8.4.8	<i>Source Directory RDM Service Info</i> .....	132
8.4.9	<i>Source Directory RDM Service State</i> .....	134
8.4.10	<i>Source Directory RDM Service Group State</i> .....	135
8.4.11	<i>Source Directory RDM Service Load</i> .....	136
8.4.12	<i>Source Directory RDM Service Data</i> .....	137
8.4.13	<i>Source Directory RDM Service Link Information</i> .....	138
8.4.14	<i>Source Directory RDM Service Link</i> .....	139
8.4.15	<i>Source Directory RDM Sequenced Multicast Information</i> .....	140
8.4.16	<i>RSSL RDM Directory Message Union</i> .....	142
8.4.17	<i>Source Directory Encoding and Decoding</i> .....	142
8.5	Dictionary Domain .....	149
8.5.1	<i>RSSL RDM Dictionary Request</i> .....	149
8.5.2	<i>RSSL RDM Dictionary Refresh</i> .....	150
8.5.3	<i>RSSL RDM Dictionary Status</i> .....	152

8.5.4	<i>RSSL RDM Dictionary Close</i> .....	153
8.5.5	<i>RSSL RDM Dictionary Message Union</i> .....	153
8.5.6	<i>Dictionary Encoding and Decoding</i> .....	154
8.6	<b>RDM Queue Messages</b> .....	159
8.6.1	<i>Queue Data Message Persistence</i> .....	159
8.6.2	<i>Queue Request</i> .....	159
8.6.3	<i>Queue Refresh</i> .....	159
8.6.4	<i>Queue Status</i> .....	160
8.6.5	<i>Queue Close</i> .....	160
8.6.6	<i>Queue Data</i> .....	161
8.6.7	<i>QueueDataExpired</i> .....	163
8.6.8	<i>Queue Ack</i> .....	164
<b>Chapter 9</b>	<b>Value Added Utilities</b> .....	<b>166</b>
9.1	Utility Overview .....	166
9.2	Memory Buffer .....	166
9.3	Using the Memory Buffer .....	166
<b>Chapter 10</b>	<b>Payload Cache Detailed View</b> .....	<b>168</b>
10.1	Concepts .....	168
10.2	Payload Cache .....	168
10.2.1	<i>Managing the Payload Cache</i> .....	169
10.2.2	<i>Cache Error Handling</i> .....	169
10.2.3	<i>Payload Cache Instances</i> .....	170
10.2.4	<i>Managing RDM Field Dictionaries for Payload Cache</i> .....	170
10.2.5	<i>Payload Cache Utilities</i> .....	173
10.3	Payload Cache Entries .....	173
10.3.1	<i>Managing Payload Cache Entries</i> .....	173
10.3.2	<i>Applying Data</i> .....	174
10.3.3	<i>Retrieving Data</i> .....	175

## List of Figures

Figure 1.	Network Diagram Notation .....	4
Figure 2.	UML Diagram Notation.....	4
Figure 3.	OMM APIs with Value Added Components .....	5
Figure 4.	Transport API Value Added Components .....	6
Figure 5.	Consuming Multicast Data with the Transport API Reactor .....	7
Figure 6.	Transport API Reactor Thread Model .....	22
Figure 7.	Transport API Reactor Application Lifecycle .....	25
Figure 8.	Flow Chart for writing data via rsslReactorSubmit .....	57
Figure 9.	Tunnel Stream Illustration .....	65
Figure 10.	Obtaining an Authentication Token .....	92
Figure 11.	Login Reissue .....	93
Figure 12.	Service Discovery .....	95
Figure 13.	Consumer Application using Cache to Store Payload Data for Item Streams .....	168



# List of Tables

Table 1:	Acronyms and Abbreviations .....	1
Table 2:	Transport API Functionality and Transport API Reactor Comparison.....	23
Table 3:	<b>RsslErrorInfo</b> Structure Members .....	24
Table 4:	Reactor Error Info Codes .....	24
Table 5:	<b>RsslReactor</b> Structure Members.....	26
Table 6:	<b>RsslReactor</b> Creation Function .....	26
Table 7:	<b>RsslCreateReactorOptions</b> Structure Members .....	27
Table 8:	<b>RsslCreateReactorOptions</b> Utility Function .....	27
Table 9:	<b>RsslReactor</b> Destruction Function .....	28
Table 10:	<b>RsslReactorChannel</b> Structure Members.....	29
Table 11:	<b>RsslReactorChannelRoleBase</b> Structure Members .....	31
Table 12:	<b>RsslReactorChannelRoleBase.role</b> Enumerated Values .....	31
Table 13:	<b>RsslReactorOMMConsumerRole</b> Structure Members .....	32
Table 14:	<b>RsslReactorOMMConsumerRole.dictionaryDownloadMode</b> Enumerated Values .....	33
Table 15:	OMM Consumer Role Watchlist Options .....	34
Table 16:	<b>RsslReactorOMMConsumerRole</b> Utility Function .....	34
Table 17:	<b>RsslReactorOMMProviderRole</b> Structure Members .....	34
Table 18:	<b>RsslReactorOMMProviderRole</b> Utility Function .....	35
Table 19:	<b>RsslReactorOMNIProviderRole</b> Structure Members .....	35
Table 20:	<b>RsslReactorOMNIProviderRole</b> Utility Function .....	36
Table 21:	<b>RsslReactorChannelRole</b> Union Members .....	36
Table 22:	<b>RsslReactorChannelRole</b> Utility Function .....	36
Table 23:	<b>rsslReactorConnect</b> Function .....	37
Table 24:	<b>RsslReactorConnectOptions</b> Structure Members.....	37
Table 25:	<b>RsslReactorConnectInfo</b> Structure Members.....	38
Table 26:	<b>RsslReactorConnectOptions</b> Utility Function .....	39
Table 27:	<b>rsslReactorAccept</b> Function .....	41
Table 28:	<b>RsslReactorAcceptOptions</b> Structure Members .....	41
Table 29:	<b>RsslReactorAcceptOptions</b> Utility Function .....	42
Table 30:	<b>rsslReactorCloseChannel</b> Function .....	42
Table 31:	<b>rsslReactorDispatch</b> Function .....	44
Table 32:	<b>RsslReactorDispatchOptions</b> Structure Members .....	44
Table 33:	<b>RsslReactorDispatchOptions</b> Utility Function .....	44
Table 34:	<b>RsslReactorCallbackRet</b> Callback Return Codes .....	45
Table 35:	<b>RsslReactorChannelEvent</b> Structure Members.....	45
Table 36:	<b>RsslReactorChannelEventType</b> Enumeration Values .....	46
Table 37:	<b>RsslReactorChannelEvent</b> Utility Functions.....	47
Table 38:	<b>RsslMsgEvent</b> Structure Members.....	48
Table 39:	<b>RsslMsgEvent</b> Utility Function.....	49
Table 40:	<b>RsslRDMLLoginMsgEvent</b> Structure Members .....	49
Table 41:	<b>RsslRDMLLoginMsgEvent</b> Utility Function .....	50
Table 42:	<b>RsslRDMDirectoryMsgEvent</b> Structure Members .....	51
Table 43:	<b>RsslRDMDirectoryMsgEvent</b> Utility Function .....	51
Table 44:	<b>RsslRDMDictionaryMsgEvent</b> Structure Members .....	52
Table 45:	<b>RsslRDMDictionaryMsgEvent</b> Utility Function .....	52
Table 46:	<b>rsslReactorSubmitMsg</b> Function.....	54
Table 47:	<b>RsslReactorSubmitMsgOptions</b> Structure Members .....	54
Table 48:	<b>RsslReactorRequestMsgOptions</b> Structure Members .....	55
Table 49:	<b>RsslReactorSubmitMsgOptions</b> Utility Function .....	55
Table 50:	<b>rsslReactorSubmitMsg</b> Return Codes.....	55
Table 51:	Reactor Buffer Management Functions .....	58

Table 52:	<b>rsslReactorGetBuffer</b> Return Values .....	58
Table 53:	<b>rsslReactorSubmit</b> Function .....	59
Table 54:	<b>RsslReactorSubmitOptions</b> Structure Members .....	60
Table 55:	<b>rsslReactorSubmit</b> Return Codes .....	60
Table 56:	<b>RsslReactorSubmitOptions</b> Utility Function .....	61
Table 57:	<b>rsslReactorPackBuffer</b> Function .....	62
Table 58:	<b>rsslReactorPackBuffer</b> Return Values .....	63
Table 59:	<b>RsslTunnelStreamAuthInfo</b> Structure Members .....	66
Table 60:	<b>rsslReactorOpenTunnelStream</b> Method .....	66
Table 61:	<b>RsslTunnelStreamOpenOptions</b> .....	<b>66</b>
Table 62:	<b>RsslClassOfService.common</b> Structure Members .....	68
Table 63:	<b>RsslClassOfService.authentication</b> Structure Members .....	68
Table 64:	<b>RsslClassOfService.flowControl</b> Structure Members .....	68
Table 65:	<b>RsslClassOfService.dataIntegrity</b> Structure Members .....	70
Table 66:	<b>RsslClassOfService.guarantee</b> Structure Members .....	70
Table 67:	Tunnel Stream Callback Event Types .....	71
Table 68:	Tunnel Stream Callback Functions .....	72
Table 69:	Tunnel Stream Callback Event Types .....	73
Table 70:	<b>RsslTunnelStreamRequestEvent</b> Structure Members .....	76
Table 71:	<b>rsslReactorAcceptTunnelStream</b> Function .....	76
Table 72:	<b>RsslReactorAcceptTunnelStreamOptions</b> Options .....	77
Table 73:	<b>rsslReactorRejectTunnelStream</b> Function .....	77
Table 74:	<b>RsslReactorRejectTunnelStreamOptions</b> Options .....	77
Table 75:	Tunnel Stream Buffer Methods .....	80
Table 76:	Tunnel Stream Submit Method .....	80
Table 77:	<b>RsslTunnelStreamSubmitOptions</b> Structure Members .....	81
Table 78:	<b>RsslTunnelStreamSubmitMsgOptions</b> Structure Members .....	81
Table 79:	<b>rsslReactorCloseTunnelStream</b> Method .....	82
Table 80:	<b>RsslTunnelStreamCloseOptions</b> Structure Members .....	82
Table 81:	<b>rsslReactorQueryServiceDiscovery</b> Method .....	84
Table 82:	<b>RsslReactorServiceDiscoveryOptions</b> Structure Members .....	84
Table 83:	<b>RsslReactorDiscoveryTransportProtocol</b> Enumerations .....	85
Table 84:	<b>RsslReactorDiscoveryDataFormatProtocol</b> Enumerations .....	85
Table 85:	<b>RsslReactorServiceEndpointEvent</b> Structure Members .....	85
Table 86:	<b>RsslReactorServiceEndpointEvent</b> Structure Members .....	86
Table 87:	<b>RsslReactorOAuthCredential</b> structure Members .....	86
Table 88:	<b>RsslReactorOAuthCredentialEvent</b> Structure Members .....	87
Table 89:	.....	87
Table 90:	<b>rsslReactorSubmitOAuthCredentialRenewal</b> .....	88
Table 91:	<b>rsslReactorSubmitOAuthCredentialRenewal</b> Options .....	88
Table 92:	<b>RsslReactorOAuthCredentialRenewalMode</b> Enums .....	89
Table 93:	Reactor Utility Functions .....	89
Table 94:	<b>RsslReactorChannelInfo</b> Structure Members .....	89
Table 95:	Domains Representations in the Administration Domain Model Value Added Component .....	99
Table 96:	<b>RsslRDMMsgBase</b> Structure Members .....	100
Table 97:	<b>RsslRDMMsg</b> .....	100
Table 98:	RDM Encoding and Decoding Functions .....	101
Table 99:	<b>RsslRDMLLoginRequest</b> Structure Members .....	102
Table 100:	<b>RsslRDMLLoginRequest</b> Flags .....	105
Table 101:	<b>RsslRDMLLoginRequest</b> Utility Functions .....	106
Table 102:	<b>RsslRDMLLoginRefresh</b> Structure Members .....	106
Table 103:	<b>RsslRDMLLoginRefresh</b> Flags .....	110
Table 104:	<b>RsslRDMLLoginRefresh</b> Utility Functions .....	112
Table 105:	<b>RsslRDMServerInfo</b> Structure Members .....	112
Table 106:	<b>RsslRDMServerInfo</b> Flags .....	112

Table 107:	<b>RsslRDMServerInfo</b> Utility Functions .....	113
Table 108:	<b>RsslRDMLoginStatus</b> Structure Members .....	114
Table 109:	<b>RsslRDMLoginStatus</b> Flags .....	115
Table 110:	<b>RsslRDMLoginStatus</b> Utility Functions .....	116
Table 111:	<b>RsslRDMLoginClose</b> Structure Member .....	116
Table 112:	<b>RsslRDMLoginClose</b> Utility Functions .....	116
Table 113:	<b>RsslRDMLoginConsumerConnectionStatus</b> Structure Members .....	117
Table 114:	<b>RsslRDMLoginConsumerConnectionStatus</b> Flags .....	117
Table 115:	<b>RsslRDMLoginWarmStandbyInfo</b> Structure Members .....	117
Table 116:	<b>RDMLoginServerTypes</b> Enumeration Values .....	117
Table 117:	<b>RsslRDMLoginConsumerConnectionStatus</b> Utility Functions .....	118
Table 118:	<b>RsslRDMLoginMsg</b> Union Members .....	118
Table 119:	<b>RsslRDMLoginMsg</b> Utility Functions .....	119
Table 120:	RDM Login Encoding and Decoding Functions .....	119
Table 121:	<b>RsslRDMDirectoryRequest</b> Structure Members .....	124
Table 122:	<b>RsslRDMDirectoryRequest</b> Flags .....	125
Table 123:	<b>RsslRDMDirectoryRequest</b> Utility Functions .....	125
Table 124:	<b>RsslRDMDirectoryRefresh</b> Structure Members .....	125
Table 125:	<b>RsslRDMDirectoryRefresh</b> Flags .....	126
Table 126:	<b>RsslRDMDirectoryRefresh</b> Utility Functions .....	126
Table 127:	<b>RsslRDMDirectoryUpdate</b> Structure Members .....	127
Table 128:	<b>RsslRDMDirectoryUpdate</b> Flags .....	127
Table 129:	<b>RsslRDMDirectoryUpdate</b> Utility Functions .....	128
Table 130:	<b>RsslRDMDirectoryStatus</b> Structure Members .....	128
Table 131:	<b>RsslRDMDirectoryStatus</b> Flags .....	129
Table 132:	<b>RsslRDMDirectoryStatus</b> Utility Functions .....	129
Table 133:	<b>RsslRDMDirectoryClose</b> Structure Member .....	129
Table 134:	<b>RsslRDMDirectoryClose</b> Utility Functions .....	129
Table 135:	<b>RsslRDMDirectoryConsumerStatus</b> Structure Members .....	130
Table 136:	<b>RsslRDMDirectoryConsumerStatusService</b> Structure Members .....	130
Table 137:	<b>RsslRDMDirectoryConsumerStatus</b> Utility Functions .....	130
Table 138:	<b>RsslRDMService</b> Structure Members .....	131
Table 139:	<b>RsslRDMService</b> Flags .....	131
Table 140:	<b>RsslRDMService</b> Utility Function .....	132
Table 141:	<b>RsslRDMServiceInfo</b> Structure Members .....	132
Table 142:	<b>RsslRDMServiceInfo</b> Flags .....	134
Table 143:	<b>RsslRDMServiceInfo</b> Utility Functions .....	134
Table 144:	<b>RsslRDMServiceState</b> Structure Members .....	134
Table 145:	<b>RsslRDMServiceState</b> Flags .....	135
Table 146:	<b>RsslRDMServiceState</b> Utility Functions .....	135
Table 147:	<b>RsslRDMServiceGroupState</b> Structure Members .....	135
Table 148:	<b>RsslRDMServiceGroupState</b> Flags .....	136
Table 149:	<b>RsslRDMServiceGroupState</b> Utility Functions .....	136
Table 150:	<b>RsslRDMServiceLoad</b> Structure Members .....	136
Table 151:	<b>RsslRDMServiceLoad</b> Flags .....	137
Table 152:	<b>RsslRDMServiceLoad</b> Utility Functions .....	137
Table 153:	<b>RsslRDMServiceData</b> Structure Members .....	137
Table 154:	<b>RsslRDMServiceData</b> Flags .....	138
Table 155:	<b>RsslRDMServiceData</b> Utility Functions .....	138
Table 156:	<b>RsslRDMServiceLinkInfo</b> Structure Members .....	139
Table 157:	<b>RsslRDMServiceLinkInfo</b> Utility Functions .....	139
Table 158:	<b>RsslRDMServiceLink</b> Structure Members .....	139
Table 159:	<b>RsslRDMServiceLink</b> Flags .....	140
Table 160:	<b>RsslRDMServiceLink</b> Utility Functions .....	140
Table 161:	<b>RsslRDMServiceSeqMcastInfo</b> Structure Members .....	140

Table 162:	RSSL RDM Service Sequenced Multicast Info Enumeration Values .....	141
Table 163:	RSSL RDM Address/Port Information Structure Members .....	141
Table 164:	<b>RsslRDMServiceSeqMcastInfo</b> Utility Functions .....	141
Table 165:	<b>RsslRDMDirectoryMsg</b> Union Members .....	142
Table 166:	<b>RsslRDMDirectoryMsg</b> Utility Functions .....	142
Table 167:	RDM Directory Encoding and Decoding Functions .....	142
Table 168:	<b>RsslRDMDictionaryRequest</b> Structure Members .....	149
Table 169:	<b>RsslRDMDictionaryRequest</b> Flag .....	149
Table 170:	<b>RsslRDMDictionaryRequest</b> Utility Functions .....	150
Table 171:	<b>RsslRDMDictionaryRefresh</b> Structure Members .....	150
Table 172:	<b>RsslRDMDictionaryRefreshFlags</b> .....	151
Table 173:	<b>RsslRDMDictionaryRefresh</b> Utility Functions .....	152
Table 174:	<b>RsslRDMDictionaryStatus</b> Structure Members .....	152
Table 175:	<b>RsslRDMDictionaryStatus</b> Flags .....	152
Table 176:	<b>RsslRDMDictionaryStatus</b> Utility Functions .....	153
Table 177:	<b>RsslRDMDictionaryClose</b> Structure Members .....	153
Table 178:	<b>RsslRDMDictionaryClose</b> Utility Functions .....	153
Table 179:	<b>RsslRDMDictionaryMsg</b> Union Members .....	153
Table 180:	<b>RsslRDMDictionaryMsg</b> Utility Functions .....	154
Table 181:	RDM Dictionary Encoding and Decoding Functions .....	154
Table 182:	<b>RsslRDMQueueRequest</b> Members .....	159
Table 183:	<b>RsslRDMQueueRefresh</b> Members .....	160
Table 184:	<b>RsslRDMQueueStatus</b> Members .....	160
Table 185:	<b>RsslRDMQueueClose</b> Members .....	160
Table 186:	<b>RsslRDMQueueData</b> Members .....	161
Table 187:	Queue Data Flag .....	161
Table 188:	<b>RsslRDMQueueTimeoutCodes</b> .....	162
Table 189:	Queue Data Message Encoding Methods .....	162
Table 190:	RsslRDMQueueDataExpired Structure Members .....	163
Table 191:	<b>RsslRDMQueueDataUndeliverableCodes</b> .....	164
Table 192:	<b>RsslRDMQueueAck</b> .....	164
Table 193:	Memory Buffer Functions .....	166
Table 194:	Payload Cache Management Functions .....	169
Table 195:	<b>RsslCacheError</b> Structure Members .....	169
Table 196:	Function for Cache Error Handling .....	169
Table 197:	Functions for Managing Cache Instances .....	170
Table 198:	<b>RsslPayloadCacheConfigOptions</b> Structure Members .....	170
Table 199:	Functions for Setting Dictionary to Cache .....	171
Table 200:	Payload Cache Utility Functions .....	173
Table 201:	Payload Cache Entry Management Functions .....	173
Table 202:	Functions for Applying and Retrieving Cache Entry Data .....	175
Table 203:	Functions for Using the Payload Cursor .....	176

# Chapter 1 Introduction

## 1.1 About this Manual

This document is authored by Transport API architects and programmers who encountered and resolved many of the issues the reader might face. Several of its authors have designed, developed, and maintained the Transport API product and other Thomson Reuters products which leverage it. As such, this document is concise and addresses realistic scenarios and use cases.

This guide documents the functionality and capabilities of the Transport API C Edition Value Added Components. In addition to connecting to itself, the Transport API can also connect to and leverage many different Thomson Reuters and customer components. If you want the Transport API to interact with other components, consult that specific component's documentation to determine the best way to configure and interact with these other devices.

## 1.2 Audience

This manual provides information and examples that aid programmers using the Transport API C Edition Value Added Components. The level of material covered assumes that the reader is a user or a member of the programming staff involved in the design, coding, and test phases for applications which will use the Transport API or its Value Added Components. It is assumed that the reader is familiar with the data types, classes, operational characteristics, and user requirements of real-time data delivery networks, and has experience developing products using the C programming language in a networked environment. Although Transport API Value Added Components offer alternate entry points to Transport API functionality, it is recommended that users are familiar with general Transport API usage and interfaces.

## 1.3 Programming Language

The Transport API Value Added Components are written to both the C and Java languages. This guide discusses concepts related to the C Edition. All code samples in this document, value added component source, and all example applications provided with the product are written accordingly.

## 1.4 Acronyms and Abbreviations

ACRONYM	MEANING
ADH	Advanced Data Hub is the horizontally scalable service component within Thomson Reuters Enterprise Platform (TREP) providing high availability for publication and contribution messaging, subscription management with optional persistence, conflation and delay capabilities.
ADS	Advanced Distribution Server is the horizontally scalable distribution component within Thomson Reuters Enterprise Platform (TREP) providing highly available services for tailored streaming and snapshot data, publication and contribution messaging with optional persistence, conflation and delay capabilities.
API	Application Programming Interface
ASCII	American Standard Code for Information Interchange

**Table 1: Acronyms and Abbreviations**

ACRONYM	MEANING
ATS	Advanced Transformation System
DACS	Data Access Control System
DMM	Domain Message Model
EDP	Elektron Data Platform
EED	Elektron Edge Device
EMA	Elektron Message API, referred to simply as the Message API
EOA	Elektron Object API, referred to simply as the Object API.
ETA	Elektron Transport API, referred to simply as the Transport API. Formerly referred to as UPA.
EWA	Elektron Web API
HTTP	Hypertext Transfer Protocol
HTTPS	Hypertext Transfer Protocol (Secure)
IDN	Integrated Data Network
NIP	Non-Interactive Provider
OMM	Open Message Model
QoS	Quality of Service
RDM	Reuters Domain Model
Reactor	The Reactor is a low-level, open-source, easy-to-use layer above ETA. It offers heartbeat management, connection and item recovery, and many other features to help simplify application code for users.
RFA	Robust Foundation API
RMTES	Reuters Multi-Lingual Text Encoding Standard
RSSL	Reuters Source Sink Library
RWF	Reuters Wire Format, a Thomson Reuters proprietary format.
SOA	Service Oriented Architecture
SSL	Source Sink Library
TREP	Thomson Reuters Enterprise Platform
UML	Unified Modeling Language
UTF-8	8-bit Unicode Transformation Format

Table 1: Acronyms and Abbreviations



## 1.5 References

1. Transport API C Edition *RDM Usage Guide*
2. *API Concepts Guide*
3. *Reuters Multilingual Text Encoding Standard Specification*
4. *Transport API C Edition Developers Guide*
5. The [Thomson Reuters Professional Developer Community](#)

## 1.6 Documentation Feedback

While we make every effort to ensure the documentation is accurate and up-to-date, if you notice any errors, or would like to see more details on a particular topic, you have the following options:

- Send us your comments via email at [apidocumentation@thomsonreuters.com](mailto:apidocumentation@thomsonreuters.com).
- Add your comments to the PDF using Adobe's **Comment** feature. After adding your comments, submit the entire PDF to Thomson Reuters by clicking **Send File** in the **File** menu. Use the [apidocumentation@thomsonreuters.com](mailto:apidocumentation@thomsonreuters.com) address.

## 1.7 Document Conventions

- Typographic
- Document Structure
- Diagrams

### 1.7.1 Typographic

- Structures, methods, in-line code snippets, and types are shown in **orange**, *Courier New* font.
- Parameters, filenames, tools, utilities, and directories are shown in **Bold** font.
- Document titles and variable values are shown in *italics*.
- When initially introduced, concepts are shown in ***Bold, Italics***.
- Longer code examples are shown in Courier New font against an orange background. For example:

```
/* decode contents into the filter list structure */
if ((retVal = rsslDecodeFilterList(&decIter, &filterList)) >= RSSL_RET_SUCCESS)
{
    /* create single filter entry and reuse while decoding each entry */
    RsslFilterEntry filterEntry = RSSL_INIT_FILTER_ENTRY;
```

### 1.7.2 Document Structure

- General Concepts
- Detailed Concepts
- Interface Definitions
- Example Code

### 1.7.3 Diagrams

Diagrams that depict the interaction between components on a network use the following notation:











	Feed Handler, Enterprise Platform server, or other application		Network of multiple servers
	Transport API application		Point-to-point connection showing direction of primary data flow
	Application with local daemon		Point-to-point connection showing direction of client connecting to server
	Multicast network		Data from external source (e.g. consolidated network or exchange)
	Connection to Multicast network, no primary data flow direction		Connection to Multicast network showing direction of primary data flow

Figure 1. Network Diagram Notation





	Object
	Inheritance: object on left is like object on right
	Composition: object on left is made up of some number of objects on right
	Composition: object on left is made up of one object on right

Figure 2. UML Diagram Notation



## Chapter 2 Product Description and Overview

### 2.1 What is the Transport API?

The Transport API is a low-level Transport API that provides the most flexible development environment to the application developer. It is the foundation on which all Thomson Reuters OMM-based components are built. The Transport API allows applications to achieve the highest throughput and lowest latency available with any OMM API, but requires applications to perform all message encoding/decoding and manage all aspects of network connectivity. The Transport API, Elektron Message API, and the Robust Foundation API (RFA) make up the set of OMM API offerings.




Figure 3. OMM APIs with Value Added Components

The Transport API Value Added Components provide alternate entry points for applications to leverage OMM-Based APIs with more ease and simplicity. These optional components help to offload much of the connection management code and perform encoding and decoding of some key OMM domain representations. Unlike older domain-based APIs that lock the user into capabilities or ease-of-use into the highest layer of API, Value Added components are independently implemented for use with the Transport API and RFA in their native languages (Example: Transport API in C and Java, RFA in C++ and Java). These implementations are then shipped with their respective API products as options for the application developer that may want these additional capabilities.

### 2.2 What are Transport API Value Added Components?

The Value Added Components simplify and compliment the use of the Transport API. These components (depicted in green in Figure 4) are offered along side the Transport API to maximize the user experience and allow for more intuitive, straight forward, and rapid creation of Transport API applications. Applications can write directly to the Transport API interfaces or commingle some or all Value Added Components. The choice to leverage these components is up to the application developer; you do not need to use Value Added Components to use the Transport API. Using Transport API Value Added Components, you can choose and customize the balance between ultra high-performance raw access and ease-of-use feature functionality. Value Added Components are written to the Transport API interfaces and are designed to work alongside the Transport API. Their interfaces have a similar look and feel to Transport API interfaces to provide simple migration and consistent use between all components and the Transport API.

All value added components provide fully supported library and header files ready to build into new or existing Transport API applications. Examples and documentation are provided to show the full power and capability of the component.

Some value added components provide buildable source code<sup>1</sup> to allow for customization and modification to suit specific user needs. This source code serves the following purposes:

- Clients may want to provide their own implementation of the component. Rather than starting from scratch, clients can modify the component to jump start their development efforts.

**Note:** If a client customizes a component's code, the client is responsible for its support and maintenance.

- Clients might want to build a new component that has similar behaviors to an existing component. Clients can leverage the code of one component to jump start their development efforts.
- Clients may want to collaborate in troubleshooting or suggesting improvements to the component for everyone's benefit.




Figure 4. Transport API Value Added Components

## 2.3 Transport API Reactor

The **Transport API reactor** is a connection management and event processing component that can significantly reduce the amount of code an application must write to leverage OMM in its own functions and to connect to other OMM-based devices. Consumer, interactive provider, and non-interactive provider applications can use the reactor and leverage it in managing consumer and non-interactive provider start-up processes, including user log in, source directory establishment, and dictionary download. The reactor also supports dispatching of events to user-implemented callback functions. In addition, it handles the flushing of user-written content and manages network pings on the user's behalf. The connection recovery feature allows the reactor to automatically recover from disconnects. Value Added domain representations are coupled with the reactor, allowing domain specific callbacks to be presented with their respective domain representation for easier, more logical access to content. For more information, refer to Chapter 6, Reactor Detailed View. This component depends on the Value Added Administration Domain Model Representation component, the Value Added Utilities, Transport API Reliable Transport Package, Transport API Message Package, and Transport API Data Package.

To access all Transport API reactor functionality, including the Administration Domain Model Representations, an application must include **rsslReactor.h**.

1. Thomson Reuters fully supports the use of its pre-built library and header files. Provided source code can help with user troubleshooting and debugging. However, the user, not Thomson Reuters, is responsible for supporting any modifications to the provided source.

## 2.4 OMM Consumer Watchlist

The **RsslReactor** features a per-channel watchlist that provides a wealth of functionality for OMM Consumer applications. The watchlist automatically performs various recovery behaviors for which developers would normally need to account.

The watchlist supports consuming from TCP-based connections (**RSSL\_CONN\_TYPE\_SOCKET**) and multicast networks (**RSSL\_CONN\_TYPE\_RELIABLE\_MULTICAST**). The reactor uses the watchlist to provide the same interaction model for both TCP and Multicast communications, so that application developers need not write code specific to either system.

For details on configuring the **RsslReactor** to enable the consumer watchlist, refer to Section 6.3.2.

### 2.4.1 Data Stream Aggregation and Recovery

The watchlist automatically recovers data streams in response to failure conditions, such as disconnects and unavailable services, so that applications do not need special handling for these conditions. As conditions are resolved, the watchlist will re-request items on the application's behalf. Applications can also use this function to request data before a connection is fully established.

To recover from disconnects using a watchlist, enable the reactor's connection recovery. Options to reconnect disconnected channels are detailed in Section 6.4.1.2.

For efficient bandwidth usage, the watchlist also combines multiple requests for the same item into a single stream and forwards response messages to each requested stream as appropriate.

### 2.4.2 ADS Multicast Consumption

The watchlist can request and consume data from an ADS configured to provide data over a multicast network.

When multicasting data, the ADS provides data through two paths: a broadcast network that sends messages intended for multiple consumers (such as item updates), and a unicast channel, for messages directed at a particular consumer (such as refreshes to satisfy an item request). The watchlist synchronizes messages delivered over these paths with each other and provides them to streams opened by the application.




Figure 5. Consuming Multicast Data with the Transport API Reactor

The watchlist also provides additional recovery for lost data by:

- Periodically re-requesting unanswered requests.
- Detecting and recovering from gaps in sequenced data streams.
- Identifying disconnects with the ADS and recovering streams provided by the ADS.

For notes on configuring multicast, refer to Section 2.4.5.

### 2.4.3 Additional Features

The watchlist provides additional features for convenience:

- Group and Service Status Fanout: The `RsslReactor` maintains a directory stream to receive service updates. As group status messages or service status messages are received, the `RsslReactor` forwards the status to all affected streams via `RsslStatusMsgs`.
- QoS Range Matching: The `RsslReactor` will accept and aggregate item requests that specify a range of `RsslQos`, or requests that do not specify an `RsslQos`. After comparing these requests with the QoS from the providing service, the watchlist uses the best matching QoS.
- Support for Enhanced Symbol List Behaviors: The `RsslReactor` supports data streams when requesting a Symbol List item. For details on requesting Symbol list data streams, refer to the *Transport API C Edition RDM Usage Guide*.
- Support for Batch Requests: The `RsslReactor` will accept batch requests regardless of whether the connected provider supports them.

### 2.4.4 Usage Notes

Applications should note the following when enabling the watchlist:

- The application must use the `to send messages`. It cannot use `rsslReactorSubmit`.
- Only one login stream should be opened per `RsslReactorChannel`.
- To prevent unnecessary bandwidth use, the watchlist will not recover a dictionary request after a complete refresh is received.
- As private streams are intended for content delivery between two specific points, the watchlist does not aggregate nor recover them.
- The `RsslReactorOMMConsumerRole.dictionaryDownloadMode` option is not supported when the watchlist is enabled.

### 2.4.5 Configuring Multicast Connections

The watchlist supports consuming traffic only from a segmented network, where the ADS multicast network is separated from the consumer's (as illustrated in Figure 5). When configuring the connection, specify both `RsslReactorConnectOpts.rsslConnectOptions.sendAddress` and `recvAddress`.

ADS multicast provides a hash with many messages so that consumers can filter unwanted content. To improve performance, consumer applications that share networks with other consumers might want to enable this filtering. Filtering can be enabled by setting the `RSSL_MCAST_FILTERING_ON` flag in the `RsslReactorConnectOpts.rsslConnectOptions.multicastOpts`. The watchlist automatically handles filter registration for relevant data.

ADSs may configure multiple multicast networks to balance the traffic load. You can configure `RsslReactorChannels` to receive from multiple multicast addresses (by specifying a comma-separated list of addresses to the `recvAddress`).

For information on creating consumer connections, refer to Section 6.4.1.1 and `RsslConnectOptions` in the *Transport API C Edition Developers Guide*. Section 6.4.1.6 provides code that configures a connection to consume multicast from an ADS.

## 2.5 Administration Domain Model Representations

The **Administration Domain Model Representations** are RDM-specific representations of the OMM administrative domain models. This Value Added Component contains structures that represent the messages within the Login, Source Directory, and Dictionary domains. All structures follow the formatting and naming specified in the *Transport API C Edition RDM Usage Guide*, so access to content is logical and specific to the content being represented. This component also handles all encoding and decoding functionality for these domain models, so the application needs only to manipulate the message's structure members to send or receive this content. This not only significantly reduces the amount of code an application needs to interact with OMM devices (i.e., TREP infrastructure), but also ensures that encoding/decoding for these domain models follow OMM-specified formatting rules. Applications can use this Value Added Component directly to help with encoding, decoding, and representation of these domain models. When using the Transport API Reactor, this component is embedded to manage and present callbacks with a domain-specific representation of content. For more information, refer to Chapter 8, Administration Domain Models Detailed View. This component depends on the Value Added Utilities, Transport API Message Package, and Transport API Data Package.

To access all data package functionality, an application must include **rssIRDMMsg.h**.

## 2.6 Value Added Utilities

The Value Added Utilities are a collection of helper constructs, mainly used by the Transport API Reactor. Included is a multi-purpose memory buffer type that can help with flexible, reusable memory - this is leveraged by the Administration Domain Model Representations when encoding or decoding messages. Other Value Added Utilities include a simple queue, mutex locks, thread helper functionality, and a simple event alerting component.

## 2.7 Value Added Cache

Applications can leverage the OMM payload cache feature. Using the payload cache, an application can maintain a local store of the OMM container data it consumes, publishes, or transforms. The cache maintains the latest values of the OMM data entries: container values update to reflect the most recent refresh and update message payloads whenever the application receives them. The Transport API retrieves data from the cache entry in the form of an encoded OMM container. The payload cache is independent of other Value Added components, and only requires the Transport API Message Package and Transport API Data Package. Only library and API header files are available for the cache component.

## Chapter 3 Building an OMM Consumer

---

### 3.1 Overview

This chapter provides an overview of how to create an OMM Consumer application using the Transport API Reactor and Administration Domain Model Representation Value Added Components. The Value Added Components simplify the work done by an OMM consumer application when establishing a connection to other OMM interactive provider applications, including the Enterprise Platform, Data Feed Direct, and Elektron. After the Reactor indicates that the connection is ready, an OMM Consumer can then consume (i.e., send data requests and receive responses) and publish data (i.e., post data).

The general process can be summarized by the following steps.

- Leverage existing or create new **RsslReactor**
- Implement callbacks and populate role
- Establish connection using **rsslReactorConnect**
- Issue requests and/or post information
- Log out and shut down

The **rsslIVAConsumer** example application, included with the Transport API product, provides one implementation of an OMM consumer application that uses the Transport API Value Added Components. The application is written with simplicity in mind and demonstrates usage of the Transport API and Transport API Value Added Components. Portions of functionality have been abstracted and can easily be reused, though you might need to modify it to achieve your own unique performance and functionality goals.

### 3.2 Leverage Existing or Create New RsslReactor

The **RsslReactor** can manage one or multiple **RsslReactorChannel** structures. This functionality allows the application to associate OMM Consumer connections with an existing **RsslReactor**, having it manage more than one connection, or to create a new **RsslReactor** to use with the connection.

To create a new **RsslReactor**, the application must use the **rsslCreateReactor** function. This will create any necessary memory and threads that the **RsslReactor** uses to manage **RsslReactorChannels** and their content flow. If the application is using an existing **RsslReactor**, there is nothing additional to do.

Detailed information about the **RsslReactor** and its creation are available in Section 6.2.1.

### 3.3 Implement Callbacks and Populate Role

Before creating the OMM consumer connection, the application needs to specify callback functions to use for all inbound content. The callback functions are specified on a per **RsslReactorChannel** basis so each channel can have its own unique callback functions or existing callback functions can be specified and shared across multiple **RsslReactorChannels**.

Use of an **RsslReactor** requires the use of several callback functions. The application must have the following:

- **RsslReactorChannelEventCallback**, which returns information about the **RsslReactorChannel** and its state (e.g., connection up)
- **RsslDefaultMsgCallback**, which processes all data not handled by other optional callbacks.

In addition to the required callbacks, an OMM Consumer can specify several administrative domain-specific callback functions. Available domain-specific callbacks include:

- **RsslRDMLLoginMsgCallback**, which processes all data for the RDM Login domain.
- **RsslRDMDirectoryMsgCallback**, which processes all data for the RDM Source Directory domain.
- **RsslRDMDictionaryMsgCallback**, which processes all data for the RDM Dictionary domain.

The **RsslReactorOMMConsumerRole** structure should be populated with all callback information for the **RsslReactorChannel**.

The **RsslReactorOMMConsumerRole** allows the application to provide login, directory, and dictionary request information. This can be initialized with default information. The callback functions are specified on the **RsslReactorOMMConsumerRole** structure or with specific information according to the application and user. The **RsslReactor** will use this information when starting up the **RsslReactorChannel**.

Detailed information about the **RsslReactorOMMConsumerRole** is in Section 6.3.1. Information about the various callback functions and their specifications are available in Section 6.6.2.

## 3.4 Establish Connection using **rsslReactorConnect**

After populating the **RsslReactorOMMConsumerRole**, the application can use **rsslReactorConnect** to create a new outbound connection. **rsslReactorConnect** will create an OMM consumer type connection using the provided configuration and role information.

After establishing the underlying connection, a channel event is returned to the application's **RsslReactorChannelEventCallback**; this provides the **RsslReactorChannel** and the state of the current connection. At this point, the application can begin using the **rsslReactorDispatch** function to dispatch directly on this **RsslReactorChannel**, or continue using **rsslReactorDispatch** to dispatch across all channels associated with the **RsslReactor**.

The **RsslReactor** will use the login, directory, and dictionary information specified on the **RsslReactorOMMConsumerRole** to perform all channel initialization for the user. After a user has logged in, received a source directory response, and downloaded field dictionaries, a channel event is returned to inform the application that the connection is ready.

The **rsslReactorConnect** function is described in Section 6.4.1.1. Dispatching is described in Section 6.6.

## 3.5 Issue Requests and/or Post Information

After the **RsslReactorChannel** is established, the channel can be used to request additional content. When issuing the request, the consuming application can use the **serviceId** of the desired service, along with the stream's identifying information. Requests can be sent for any domain using the formats defined in that domain model specification. Domains provided by Thomson Reuters are defined in the *Transport API C Edition RDM Usage Guide*. This content will be returned to the application via the **RsslDefaultMsgCallback**.

At this point, an OMM consumer application can also post information to capable provider applications. All content requested, received, or posted is encoded and decoded using the Transport API Message Package and the Transport API Data Package described in the *Transport API C Edition Developers Guide*.

## 3.6 Log Out and Shut Down

When the consumer application is done retrieving or posting content, the consumer can close the `RsslReactorChannel` by calling `rsslReactorCloseChannel`. This will close all item streams and log out the user. Prior to closing the `RsslReactorChannel`, the application should release any unwritten pool buffers to ensure proper memory cleanup.

If the application is done with the `RsslReactor`, the `rsslDestroyReactor` function can be used to shutdown and clean up any `RsslReactor` resources.

- Closing an `RsslReactorChannel` is described in Section 6.4.2.
- Shutting down an `RsslReactor` is described in Section 6.2.2.

## 3.7 Additional Consumer Details

The following locations provide specific details about using OMM consumers, the Transport API, and Transport API Value Added Components:

- The `rsslIVACConsumer` application demonstrates one way of implementing of an OMM consumer application that uses Transport API Value Added Components. The application's source code and **ReadMe** file contain additional information about specific implementation and behaviors.
- Chapter 6 provides a detailed look at the Transport API Reactor.
- Chapter 8 provides more information about the Administration Domain Model Representations.
- The *Transport API C Edition Developers Guide* provides specific Transport API encoder/decoder and transport usage information.
- The *Transport API C Edition RDM Usage Guide* provides specific information about the DMMs used by this application type.



## Chapter 4 Building an OMM Interactive Provider

---

### 4.1 Overview

This chapter provides a high-level description of how to create an OMM interactive provider application using the Transport API Reactor and Administration Domain Model Representation Value Added Components. An OMM interactive provider application opens a listening socket on a well-known port allowing OMM Consumer applications to connect. The Transport API Value Added Components simplify the work done by an OMM interactive provider application when accepting connections and handling requests from OMM consumers.

The following steps summarize this process:

- Leverage an existing **RsslReactor**, or create a new one
- Create an **RsslServer**
- Implement callbacks and populate role
- Associate incoming connections using **rsslReactorAccept**
- Perform login process
- Provide source directory information
- Provide necessary dictionaries
- Handle requests and post messages
- Disconnect consumers and shut down

Included with the Transport API product, the **rsslIVAPProvider** example application provides one way of implementing an OMM interactive provider application that uses the Transport API Value Added Components. The application is written with simplicity in mind and demonstrates the use of the Transport API and Transport API Value Added Components. Portions of the functionality are abstracted for easy reuse, though you might need to customize it to achieve your own unique performance and functionality goals.

### 4.2 Leverage Existing or Create New RsslReactor

The **RsslReactor** can manage one or multiple **RsslReactorChannel** structures. This allows the application to choose to associate OMM provider connections with an existing **RsslReactor**, have it manage more than one connection, or create a new **RsslReactor** to use with the connection.

If the application is creating a new **RsslReactor**, the **rsslCreateReactor** function is used. This will create any necessary memory and threads that the **RsslReactor** uses to manage **RsslReactorChannels** and their content flow. If the application is using an existing **RsslReactor**, there is nothing additional to do.

Detailed information about the **RsslReactor** and its creation are available in Section 6.2.1.

## 4.3 Create an RsslServer

The first step of any Transport API Interactive Provider application is to establish a listening socket, usually on a well-known port so that consumer applications can easily connect. The provider uses the `rsslBind` function to open the port and listen for incoming connection attempts. This uses the standard Transport API Transport functionality described in the *Transport API C Edition Developers Guide*.

Whenever an OMM consumer application attempts to connect, the provider will use the `RsslServer` and associate the incoming connections with an `RsslReactor`, which will accept the connection and perform any initialization as described in Section 4.4 and Section 4.5.

## 4.4 Implement Callbacks and Populate Role

Before accepting an incoming connection with an OMM provider, the application needs to specify callback functions to use for all inbound content. Callback functions are specified on a per `RsslReactorChannel` basis so each channel can have its own unique callback functions or existing callback functions can be specified and shared across multiple `RsslReactorChannels`.

The following callback functions are required for use with an `RsslReactor`:

- `RsslReactorChannelEventCallback`, which returns information about the `RsslReactorChannel` and its state (e.g., connection up)
- `RsslDefaultMsgCallback`, which processes all data not handled by other optional callbacks.

In addition to the required callbacks, an OMM provider can specify several administrative domain-specific callback functions. Available domain-specific callbacks are:

- `RsslRDMLLoginMsgCallback`, which processes all data for the RDM Login domain.
- `RsslRDMDirectoryMsgCallback`, which processes all data for the RDM Source Directory domain.
- `RsslRDMDictionaryMsgCallback`, which processes all data for the RDM Dictionary domain.

The `RsslReactorOMMProviderRole` structure should be populated with all callback information for the `RsslReactorChannel`.

Detailed information about the `RsslReactorOMMProviderRole` is in Section 6.3.1. Information about the various callback functions and their specifications are available in Section 6.6.2.

## 4.5 Associate Incoming Connections Using `rsslReactorAccept`

After the `RsslReactorOMMProviderRole` is populated, the application can use `rsslReactorAccept` to accept a new inbound connection. `rsslReactorAccept` will accept an OMM provider connection from the passed-in `RsslServer` using provided configuration and role information.

When the underlying connection is established, a channel event is returned to the application's `RsslReactorChannelEventCallback`; this will provide the `RsslReactorChannel` and indicate the current connection state. At this point, the application can begin using the `rsslReactorDispatch` function to dispatch directly on this `RsslReactorChannel`, or continue using `rsslReactorDispatch` to dispatch across all channels associated with the `RsslReactor`.

The `RsslReactor` will perform all channel initialization and pass any administrative domain information to the application via the callbacks specified with the `RsslReactorOMMProviderRole`.

- For more details on the `rsslReactorAccept` function, refer to Section 6.4.1.7.
- For more details on dispatching, refer to Section 6.6.

## 4.6 Perform Login Process

Applications authenticate with one another using the Login domain model. An OMM interactive provider must handle consumer Login request messages and supply appropriate responses. Login information will be provided to the application via the `RsslRDMLLoginMsgCallback`, when specified on the `RsslReactorOMMProviderRole`.

After receiving a Login request, an interactive provider can perform any necessary authentication and permissioning.

- If the interactive provider grants access, it should send an `RsslRDMLLoginRefresh` to convey that the user successfully connected. This message should indicate the feature set supported by the provider application.
- If the interactive provider denies access, it should send an `RsslRDMLLoginStatus`, closing the connection and informing the user of the reason for denial.

Login messages can be encoded and decoded using the `RsslRDMLLoginMsg`. More details and code examples are in Section 8.3.

All content requested, received, or posted is encoded and decoded using the Transport API Message Package and the Transport API Data Package described in the *Transport API C Edition Developers Guide*.

Information about the Login domain and expected content formatting is available in the *Transport API C Edition RDM Usage Guide*.

## 4.7 Provide Source Directory Information

The Source Directory domain model conveys information about all available services in the system. An OMM consumer typically requests a Source Directory to retrieve information about available services and their capabilities. This includes information about supported domain types, the service's state, the QoS, and any item group information associated with the service. Thomson Reuters recommends that at a minimum, an interactive provider supply the Info, State, and Group filters for the Source Directory.

- The Source Directory Info filter contains the name and `serviceId` for each available service. The interactive provider should populate the filter with information specific to the services it provides.
- The Source Directory State filter contains status information for the service informing the consumer whether the service is Up (available), or Down (unavailable).
- The Source Directory Group filter conveys item group status information, including information about group states, as well as the merging of groups. If a provider determines that a group of items is no longer available, it can convey this information by sending either individual item status messages (for each affected stream) or a Directory message containing the item group status information. Additional information about item groups is available in the *Transport API C Edition Developers Guide*.

Source Directory messages can be encoded and decoded using the `RsslRDMDirectoryMsg`. More details and code examples are in Section 8.4.

All content requested, received, or posted is encoded and decoded using the Transport API Message Package and the Transport API Data Package described in the *Transport API C Edition Developers Guide*.

Information about the Source Directory domain and expected content formatting is available in the *Transport API C Edition RDM Usage Guide*.

## 4.8 Provide or Download Necessary Dictionaries

Some data requires the use of a dictionary for encoding or decoding. The dictionary typically defines type and formatting information, and tells the application how to encode or decode information. Content that uses the `RsslFieldList` type requires the use of a field dictionary (usually the Thomson Reuters **RDMFieldDictionary**, though it can instead be a user-defined or modified field dictionary).

The Source Directory message should notify the consumer about dictionaries needed to decode content sent by the provider. If the consumer needs a dictionary to decode content, it is ideal that the interactive provider application also make this dictionary available to consumers for download. The provider can inform the consumer whether the dictionary is available via the Source Directory.

If consuming from an ADH and providing content downstream, a provider application can also download the RWFFId and RWFEnum dictionaries. Using these dictionaries, the Transport API can retrieve appropriate dictionary information for providing field list content. A provider can use this feature to ensure they are using the appropriate version of the dictionary or to encode data. An ADH that supports provider dictionary downloads sends a Login request message containing the **SupportProviderDictionaryDownload** login element. The Transport API sends the dictionary request using the Dictionary domain model.<sup>1</sup> For details on using the Login domain and expected message content, refer to the *Transport API C Edition RDM Usage Guide*.

Dictionary messages can be encoded and decoded using the `RsslRDMDictionaryMsg`. More details and code examples are in Section 8.5. Dictionary requests will be provided via the `RsslRDMDictionaryMsgCallback`, when specified on the `RsslReactorOMMProviderRole`.

Whether loading a dictionary from file or requesting it from an ADH, the Transport API offers several utility functions for loading, downloading, and managing a properly-formatted field dictionary. The Transport API also has utility functions that help the provider encode into an appropriate format for downloading or decoding downloaded dictionaries.

- All content requested, received, or posted is encoded and decoded using the Transport API Message Package and the Transport API Data Package described in the *Transport API C Edition Developers Guide*.
- Information about the Dictionary domain, dictionary utility functions, and expected content formatting is available in the *Transport API C Edition RDM Usage Guide*.

## 4.9 Handle Requests and Post Messages

A provider can receive a request for any domain, though this should typically be limited to the domain capabilities indicated in the Source Directory. When a request is received, the provider application must determine if it can satisfy the request by:

- Comparing `msgKey` identification information
- Determining whether it can provide the requested QoS
- Ensuring that the consumer does not already have a stream open for the requested information

If a provider can service a request, it should send appropriate responses. However, if the provider cannot satisfy the request, the provider should send an `RsslStatusMsg` to indicate the reason and close the stream. All requests and responses should follow specific formatting as defined in the domain model specification. The *Transport API C Edition RDM Usage Guide* defines all domains provided by Thomson Reuters. This content will be returned to the application via the `RsslDefaultMsgCallback`.

The provider can specify that it supports post messages via the `RsslRDMLoginRefresh`. If a provider application receives a post message, the provider should determine the correct handling for the post. This depends on the application's role in the system and might involve storing the post in its cache or passing it farther up into the system. If the provider is the destination

---

1. Because this is instantiated by the provider, the application should use a `streamId` with a negative value. Additional details are provided in subsequent chapters.

for the post, the provider should send any requested acknowledgments, following the guidelines described in the *Transport API C Edition Developers Guide*. Any posted content will be returned to the application via the `RsslDefaultMsgCallback`.

All content requested, received, or posted is encoded and decoded using the Transport API Message Package and the Transport API Data Package described in the *Transport API C Edition Developers Guide*.

## 4.10 Disconnect Consumers and Shut Down

If the `RsslReactor` application must shut down, it can either leave consumer connections intact or shut them down. If the provider decides to close consumer connections, the provider should send an `RsslStatusMsg` on each connection's Login stream closing the stream. At this point, the consumer should assume that its other open streams are also closed.

It can then close the `RsslReactorChannels` by calling `rsslReactorCloseChannel`. Prior to closing the `RsslReactorChannel`, the application should release any unwritten pool buffers to ensure proper memory cleanup.

If the application is done with the `RsslReactor`, the `rsslDestroyReactor` function can be used to shutdown and cleanup any `RsslReactor` resources.

- Closing an `RsslReactorChannel` is described in Section 6.4.2.
- Shutting down an `RsslReactor` is described in Section 6.2.2.

## 4.11 Additional Interactive Provider Details

For specific details about OMM interactive providers, the Transport API, and Transport API Value Added Component use, refer to the following locations:

- The `rsslVAPProvider` application demonstrates one implementation of an OMM interactive provider application that uses Transport API Value Added Components. The application's source code and **ReadMe** file have additional information about specific implementation and behaviors.
- Chapter 6 provides a detailed look at the Transport API Reactor.
- Chapter 8 provides more information about the Administration Domain Model Representations.
- The *Transport API C Edition Developers Guide* provides specific Transport API encoder/decoder and transport usage information.
- The *Transport API C Edition RDM Usage Guide* provides specific information about the DMMs used by this application type.

## Chapter 5 Building an OMM Non-Interactive Provider

---

### 5.1 Building an OMM Non-Interactive Provider Overview

This chapter provides an overview of how to create an OMM non-interactive provider application using the Transport API Reactor and Administration Domain Model Representation Value Added Components. The Value Added Components simplify the work done by an OMM non-interactive provider application when establishing a connection to ADH devices. After the reactor indicates that the connection is ready, an OMM non-interactive provider can publish information into the ADH cache without needing to handle requests for the information. The ADH and other Enterprise Platform components can cache the information and provide it to any OMM consumer applications that indicate interest.

The general process can be summarized by the following steps.

- Leverage existing or create new **RsslReactor**
- Implement callbacks and populate role
- Establish connection using **rsslReactorConnect**
- Perform dictionary download
- Provide content
- Log out and shut down

The **rsslIVANIPProvider** example application, included with the Transport API product, provides one implementation of an OMM non-interactive provider application that uses the Transport API Value Added Components. The application is written with simplicity in mind and demonstrates usage of the Transport API and Transport API Value Added Components. Portions of functionality have been abstracted and can easily be reused, though you might need to modify it to achieve your own unique performance and functionality goals.

### 5.2 Leverage Existing or Create New RsslReactor

The **RsslReactor** can manage one or multiple **RsslReactorChannel** structures. This allows the application to choose to associate OMM non-interactive provider connections with an existing **RsslReactor**, having it manage more than one connection, or to create a new **RsslReactor** to use with the connection.

If the application is creating a new **RsslReactor**, the **rsslCreateReactor** function is used. This will create any necessary memory and threads that the **RsslReactor** uses to manage **RsslReactorChannel** and their content flow. If the application is using an existing **RsslReactor**, there is nothing more to do.

Detailed information about the **RsslReactor** and its creation are available in Section 6.2.1.

## 5.3 Implement Callbacks and Populate Role

Before creating the OMM non-interactive provider connection, the application needs to specify callback functions to use for all inbound content. Callback functions are specified on a per `RsslReactorChannel` basis so each channel can have its own unique callback functions or existing callback functions can be specified and shared across multiple `RsslReactorChannels`.

An `RsslReactor` requires the use of the following callback functions:

- `RsslReactorChannelEventCallback`, which returns information about the `RsslReactorChannel` and its state (e.g., connection up)
- `RsslDefaultMsgCallback`, which processes all data not handled by other optional callbacks.

Additionally, an OMM non-interactive provider can specify the administrative domain-specific callback function `RsslRDMLoginMsgCallback`, which processes all data for the RDM Login domain.

The `RsslReactorOMMNIProviderRole` structure should be populated with all callback information for the `RsslReactorChannel`. `RsslReactorOMMNIProviderRole` allows the application to provide login request and initial directory refresh information. This can be initialized with default information. Callback functions are specified on the `RsslReactorOMMNIProviderRole` structure or with specific information according to the application and user. The `RsslReactor` will use this information when starting up the `RsslReactorChannel`.

- For detailed information on the `RsslReactorOMMNIProviderRole`, refer to Section 6.3.1.
- For information on the various callback functions and their specifications, refer to Section 6.6.2.

## 5.4 Establish Connection using `rsslReactorConnect`

After populating the `RsslReactorOMMNIProviderRole`, the application can use `rsslReactorConnect` to create a new outbound connection. `rsslReactorConnect` will create an OMM non-interactive provider type connection using the provided configuration and role information.

When the underlying connection is established, a channel event will be returned to the application's `RsslReactorChannelEventCallback`, which provides the `RsslReactorChannel` and indicates the current connection state. At this point, the application can begin using the `rsslReactorDispatch` function to dispatch directly on this `RsslReactorChannel`, or continue using `rsslReactorDispatch` to dispatch across all channels associated with the `RsslReactor`.

The `RsslReactor` will use the login and directory information specified on the `RsslReactorOMMNIProviderRole` to perform all channel initialization for the user. After the user is logged in and has sent a source directory response, a channel event is returned to inform the application that the connection is ready.

- For further details on the `rsslReactorConnect` function, refer to Section 6.4.1.1.
- For further details on dispatching, refer to Section 6.6.



## 5.5 Perform Dictionary Download

If connected to a supporting ADH, an OMM non-interactive provider can download the RWFFId and RWFEnum dictionaries to retrieve the appropriate dictionary information for providing field list content. An OMM non-interactive provider can use this feature to ensure they use the appropriate version of the dictionary or to encode data. To support the Provider Dictionary Download feature, the ADH sends a Login response message containing the `SupportProviderDictionaryDownload` login element. The dictionary request is sent using the Dictionary domain model.<sup>1</sup>

The Transport API offers several utility functions for downloading and managing a properly-formatted field dictionary. The provider can also use utility functions to encode the dictionary into an appropriate format for downloading or decoding.

For details on using the Login domain, expected message content, and available dictionary utility functions, refer to the *Transport API C Edition RDM Usage Guide*.

## 5.6 Provide Content

After the `RsslReactorChannel` is established, it can begin pushing content to the ADH. Each unique information stream should begin with an `RsslRefreshMsg`, conveying all necessary identification information for the content. Because the provider instantiates this information, a negative value `streamId` should be used for all streams. The initial identifying refresh can be followed by other status or update messages.

All content is encoded and decoded using the Transport API Message Java Codec Package and the Transport API Data Package described in the *Transport API C Edition Developers Guide*.

## 5.7 Log Out and Shut Down

When the Consumer application is done retrieving or posting content, it can close the `RsslReactorChannel` by calling `rsslReactorCloseChannel`. This will close all item streams and log out the user. Prior to closing the `RsslReactorChannel`, the application should release any unwritten pool buffers to ensure proper memory cleanup.

If the application is done with the `RsslReactor`, the `rsslDestroyReactor` function can be used to shutdown and cleanup any `RsslReactor` resources.

- For details on closing an `RsslReactorChannel`, refer to Section 6.4.2.
- Shutting down an `RsslReactor` is described in Section 6.2.2.

---

1. Because the provider instantiates this request, the application should use a streamId with a negative value. Additional details are provided in subsequent chapters.



## 5.8 Additional Non-Interactive Provider Details

The following locations discuss specific details about using OMM non-interactive providers and the Transport API:

- The **rssIVANIPProvider** application demonstrates one implementation of an OMM non-interactive provider application that uses Transport API Value Added Components. The application's source code and **ReadMe** file have additional information about the specific implementation and behaviors.
- Chapter 6 provides a detailed look at the Transport API Reactor.
- Chapter 8 provides more information about Administration Domain Model Representations.
- The *Transport API C Edition Developers Guide* provides specific Transport API encoder/decoder and transport usage information.
- The *Transport API C Edition RDM Usage Guide* provides specific information about the DMMs used by this application type.

## Chapter 6 Reactor Detailed View

### 6.1 Concepts

The **Transport API Reactor** is a connection management and event processing component that can significantly reduce the amount of code an application must write to leverage OMM. This component helps simplify many aspects of a typical Transport API application, regardless of whether the application is an OMM consumer, OMM interactive provider, or OMM non-interactive provider. The Transport API Reactor can help manage Consumer and Non-Interactive Provider start up processing, including user log in, source directory establishment, and dictionary download. It also allows for dispatching of events to user-implemented callback functions, handles flushing of user-written content, and manages network pings on the user's behalf. Value Added domain representations are coupled with the reactor, allowing domain-specific callbacks to be presented with their respective domain representation for easier, more logical access to content. For a list and comparison of Transport API and Transport API Reactor functionalities, refer to Section 6.1.1.

The Transport API Reactor internally depends on the Administration Domain Model Representation component. This allows the user to provide and consume the administrative RDM types in a more logical format. This additionally hides encoding and decoding of these domains from the Reactor user, all interaction is via a simple structural representation. More information about the Administration Domain Model Representation value added component is available in Chapter 8. The Transport API Reactor also leverages several utility components, contained in the Value Added Utilities. This includes constructs like mutex locks, a simple queue, and memory buffers.

The Transport API Reactor helps to manage the life-cycle of a connection on the user's behalf. When a channel is associated with a reactor, the reactor performs all necessary transport level initialization and alerts the user, via a callback, when the connection is up, ready for use, or is down. An application can simultaneously run multiple unique reactor instances, where each reactor instance can associate and manage a single channel or multiple channels. This functionality allows users to quickly and easily horizontally scale their application to leverage multi-core systems or distribute content across multiple connections.

Each instance of the Transport API Reactor leverages multiple threads to help manage inbound and outbound data efficiently. The following figure illustrates a high-level view of the reactor threading model.




Figure 6. Transport API Reactor Thread Model

There are two main threads associated with each Transport API Reactor instance. The application thread is the main driver of the reactor; all event dispatching (e.g., reading), callback processing, and submitting of data to the Transport API is done from this thread. Such architecture reduces latency and simplifies any threading model associated with user-defined callback functions – because callbacks happen from the application thread, a single-threaded application does not need to have additional mutex locking. The Transport API Reactor also leverages an internal worker thread. The worker thread flushes any queued outbound data and manages outbound network pings for all channels associated with the Reactor.

The application drives the reactor with the use of a dispatch function. The dispatch function reads content from the network, performs some light processing to handle inbound network pings, and provides the information to the user through a series of per-channel, user-defined callback functions. Callback functions are separated based on whether they are reactor callbacks or channel callbacks. Channel callbacks are separated by domain, with a default callback where all unhandled domains or non-OMM content are provided to the user. The application can choose whether to dispatch on a single channel or across all channels managed by the reactor. The application can leverage an I/O notification mechanism (e.g. select, poll) or periodically call dispatch – it is all up to the user.

### 6.1.1 Functionality: Transport API Versus Transport API Reactor

FUNCTIONALITY	TRANSPORT API	TRANSPORT API REACTOR
Programmatic Configuration	X	X
Programmatic Logging	X	X
Controlled Fragmentation and Assembly of Large Messages	X	X
Controlled Locking / Threading Model	X	X
Controlled Message Buffers with Ability to Change During Runtime	X	X
Controlled Message Packing	X	X
Support for Unified and Segmented Network Connection Types	X	X
Network Ping Management	***	X
Automatic Flushing of Data	***	X
User-Defined Callbacks for Data	***	X
User Login	***	X
Requesting Source Directory	***	X
Downloading Field Dictionary	***	X
Loading Field Dictionary File	***	X
Session Management	***	X
***: Transport API users can implement this functionality themselves. They can also use or modify the Transport API Reactor functionality.		

**Table 2: Transport API Functionality and Transport API Reactor Comparison**

## 6.1.2 Reactor Error Handling

The `RsslErrorInfo` structure is used to return error or warning information to the application. This can be returned from the various reactor functions as well as part of a callback function.

- If returned directly from a reactor function: an error occurred while processing in that function.
- If returned as part of a callback function: an error has occurred on one of the channels managed by the reactor.

`RsslErrorInfo` members are as follows:

STRUCTURE MEMBER	DESCRIPTION
<code>rsslErrorInfoCode</code>	An informational code about this error. Indicates whether it reports a failure condition or is intended to provide non-failure-related information to the user. For details on available codes, refer to Table 8.
<code>rsslError</code>	Returns an <code>rsslError</code> structure (i.e., the underlying error information from the Transport API). <code>rsslError</code> includes a pointer to the <code>RsslChannel</code> on which the error occurred, both a Transport API and a system error number, and more descriptive error text. The <code>rsslError</code> and its values are described in the <i>Transport API C Edition Developers Guide</i> .
<code>errorLocation</code>	Provides information about the file and line on which the error occurred. Detailed error text is provided via the <code>rsslError</code> portion of this structure.  <code>RsslErrorInfo.errorLocation</code> length is limited to 1,024 bytes.

Table 3: `RsslErrorInfo` Structure Members

## 6.1.3 Reactor Error Info Codes

It is important that the application monitors return values from the `RsslReactor` callbacks and functions. Error codes indicate whether the returned `RsslErrorInfo` is the result of a failure condition or is simply providing information regarding a successful operation.

RETURN CODE	DESCRIPTION
<code>RSSL_EIC_SUCCESS</code>	Indicates a success code. Used to inform the user of success and provide additional information.
<code>RSSL_EIC_FAILURE</code>	A general failure has occurred. The <code>RsslErrorInfo</code> code contains more information about the specific error.

Table 4: Reactor Error Info Codes

### 6.1.4 Transport API Reactor Application Lifecycle

The following figure depicts the typical lifecycle of an application using the Transport API Reactor, as well as associated function calls. Subsequent sections in this document provide more detailed information.




Figure 7. Transport API Reactor Application Lifecycle

## 6.2 Reactor Use

This section describes use of **RsslReactor**. The **RsslReactor** manages **RsslReactorChannels** (described in Section 6.3). An understanding of both constructs is necessary for application writers.

Before creating any **RsslReactor** instance, the user must ensure that the Transport API has been properly initialized. This is accomplished through the use of the **rsslInitialize** function, as documented in the *Transport API C Edition Developers Guide*. Because the **RsslReactor** internally leverages multiple threads, the **RSSL\_LOCK\_GLOBAL\_AND\_CHANNEL** option must be specified in the call to **rsslInitialize**. After the Transport API has been properly initialized, the application can create an **RsslReactor** instance. The **RsslReactor** is represented by a structure as defined in the following table.

**Note:** An application can leverage multiple **RsslReactor** instances to scale across multiple cores and distribute their **RsslReactorChannels** as needed.

STRUCTURE MEMBER	DESCRIPTION
eventFd	Represents a file descriptor that can be used in some kind of I/O notification mechanism (e.g. select, poll). This file descriptor is associated with <b>RsslReactorChannel</b> connection events or <b>RsslReactor</b> specific events, for example an <b>RsslReactorChannel</b> <b>up</b> or <b>down</b> notification. All <b>RsslReactorChannel</b> data event notification occurs on the <b>RsslReactorChannel</b> 's specific <b>socketId</b> , as detailed in Section 6.3.
userSpecPtr	A pointer that can be set by the user of the <b>RsslReactor</b> . This value can be set directly or via the creation options. This information can be useful for identifying a specific instance of an <b>RsslReactor</b> or coupling this <b>RsslReactor</b> with other user-defined information.

Table 5: **RsslReactor** Structure Members

### 6.2.1 Creating a Reactor

The lifecycle of an **RsslReactor** is controlled by the application, which controls creation and destruction of each reactor instance. The following sections describe creation functionality in more detail.

#### 6.2.1.1 Reactor Creation

The creation of an **RsslReactor** instance can be accomplished through the use of the following function.

**Note:** Before the first use of any Transport API Reactor functionality, the application must ensure that **rsslInitialize** has been called with the **RSSL\_LOCK\_GLOBAL\_AND\_CHANNEL** option.

FUNCTION NAME	DESCRIPTION
rsslCreateReactor	Creates an <b>RsslReactor</b> instance, including all necessary internal memory and threads. After creating the <b>RsslReactor</b> , <b>RsslReactorChannels</b> can be associated, as described in Section 6.3. Options are passed in via the <b>RsslCreateReactorOptions</b> , as defined in Section 6.2.1.2.

Table 6: **RsslReactor** Creation Function

### 6.2.1.2 RsslCreateReactorOptions Structure Members

STRUCTURE MEMBER	DESCRIPTION
dispatchDecodeMemoryBufferSize	The size, in bytes, of an internally created memory buffer. The memory buffer is used by the <b>RsslReactor</b> when performing any necessary message decoding required for callbacks. When cleared, defaults to 65,536 bytes.
port	<b>Deprecated.</b> <b>RsslReactor</b> now chooses an ephemeral port upon creation. Any values specified in this parameter are ignored.
reissueTokenAttemptInterval	The time (in milliseconds) that the <b>RsslReactor</b> waits before attempting to reissue the token. The minimum interval is 1000 milliseconds, while the default setting is 5000.
reissueTokenAttemptLimit	The maximum number of times the <b>RsslReactor</b> attempts to reissue the token. If set to default (i.e., -1), there is no maximum limit.
restRequestTimeOut	Specifies the timeout (in seconds) for token service and service discovery request. If the request times out, the Transport API Reactor resends the token reissue and the timeout restarts. When using the <b>rsslReactorConnect()</b> method, if the request times out, the Reactor does not retry. If set to <b>0</b> , there is no timeout. By default, the Transport API behaves as if set to <b>90</b> .
serviceDiscoveryURL	Specifies the URL of the EDP Gateway on which the ESDK API performs a service discovery.
tokenReissueRatio	Specifies a ratio to multiply the access token's expiration time (in seconds) to determine the length of time the <b>RsslReactor</b> waits before retrieving a new access token and refreshing its connection to ERT in the cloud. The valid range is from <b>0.05</b> to <b>0.95</b> . By default, the Transport API behaves as if set to <b>0.8</b> .
tokenServiceURL	Specifies the URL of the EDP Gateway from which the ESDK API obtains an authentication token.
userSpecPtr	A pointer that can be set by the application. This value is preserved and stored in the <b>userSpecPtr</b> of the <b>RsslReactor</b> returned from <b>rsslCreateReactor</b> . This information can be useful for coupling this <b>RsslChannel</b> with other user-created information, such as a watch list associated with this connection.

Table 7: **RsslCreateReactorOptions** Structure Members

### 6.2.1.3 RsslCreateReactorOptions Utility Function

The Transport API provides the following utility function for use with the **RsslCreateReactorOptions**.

FUNCTION NAME	DESCRIPTION
rsslClearCreateReactorOptions	Clears the <b>RsslCreateReactorOptions</b> structure. Useful for structure reuse.

Table 8: **RsslCreateReactorOptions** Utility Function

## 6.2.2 Destroying a Reactor

The lifecycle of an `RsslReactor` is controlled by the application, which controls creation and destruction of each reactor instance. The following sections describe destruction functionality in more detail.

### 6.2.2.1 Reactor Destruction

When the application no longer requires an `RsslReactor` instance, it can destroy it using the following function.

FUNCTION NAME	DESCRIPTION
<code>rsslDestroyReactor</code>	Destroys an <code>RsslReactor</code> instance, including all internal memory and threads. This also sends <code>RsslReactorChannelEvents</code> , indicating channel down, to all <code>RsslReactorChannels</code> associated with this <code>RsslReactor</code> .

Table 9: `RsslReactor` Destruction Function

### 6.2.2.2 Reactor Creation and Destruction Example

```
RsslCreateReactorOptions reactorCreateOptions;

/* Use of reactors requires that RSSL be initialized with both global
 * and per-channel locks. */
ret = rsslInitialize(RSSL_LOCK_GLOBAL_AND_CHANNEL, &rsslError);

rsslClearCreateReactorOptions(&reactorCreateOptions);

/* Create the RsslReactor. */
pReactor = rsslCreateReactor(&reactorCreateOptions, &rsslErrorInfo);

/* Any use of the reactor occurs here -- see following sections for all other functionality */

/* Destroy the RsslReactor. */
ret = rsslDestroyReactor(pReactor, &rsslErrorInfo);

/* Uninitialize RSSL. */
ret = rsslUninitialize();
```

Code Example 1: Reactor Creation and Destruction Example

## 6.3 Reactor Channel Use

The `RsslReactorChannel` structure is used to represent a connection that can send or receive information across a network. This structure is used to represent a connection, regardless of whether it is an outbound connection or a connection accepted by a listening socket via an `RsslServer`. The `RsslReactorChannel` is the application's point of access, used to perform any action on the connection that it represents (e.g. dispatching events, writing, disconnecting, etc). See the subsequent sections for more information about `RsslReactorChannel` and how to associate with an `RsslReactor`.



**Note:** Only Transport API Reactor functions, like those defined in this chapter, should be called on a channel managed by an `RsslReactor`.

The following table describes the members of the `RsslReactorChannel` structure.

STRUCTURE MEMBER	DESCRIPTION
hostname	Provides the name of the host to which a consumer or NIP application connects.
majorVersion	When an <code>RsslReactorChannel</code> is up ( <code>RSSL_RC_CET_CHANNEL_UP</code> ), this is populated with the major version number associated with the content sent on this connection. Typically only minor version increases are associated with a fully backward compatible change or extension. The Transport API Reactor will leverage the versioning information for any content it is encoding or decoding. Proper use of versioning should be handled by the application for any other application encoded or decoded content. For more information on versioning, refer to the <i>Transport API C Edition Developers Guide</i> .
minorVersion	When an <code>RsslReactorChannel</code> is up ( <code>RSSL_RC_CET_CHANNEL_UP</code> ), this is populated with the minor version number associated with the content sent on this connection. Typically, a minor version increase is associated with a fully backward compatible change or extension. The Transport API Reactor will leverage the versioning information for any content it is encoding or decoding. Proper use of versioning should be handled by the application for any other application encoded or decoded content. For more information on versioning, refer to the <i>Transport API C Edition Developers Guide</i> .
oldSocketId	It is possible for a file descriptor to change over time, typically due to some kind of connection keep-alive mechanism. If this occurs, this is typically communicated via a callback indicating <code>RSSL_RC_CET_FD_CHANGE</code> . The previous <code>RsslReactorChannel</code> is stored in <code>oldSocketId</code> so the application can properly unregister and then register the new <code>socketId</code> with their I/O notification mechanism.
protocolType	When an <code>RsslReactorChannel</code> is up ( <code>RSSL_RC_CET_CHANNEL_UP</code> ), this is populated with the <code>protocolType</code> associated with the content being sent on this connection. If the server indicates a <code>protocolType</code> that does not match the <code>protocolType</code> specified by the client, the connection is rejected. The Transport API Reactor will leverage the versioning information for any content it is encoding or decoding. Proper use of versioning should be handled by the application for any other application encoded or decoded content. For more information on versioning, refer to the <i>Transport API C Edition Developers Guide</i> .
pRsslChannel	A pointer to the underlying <code>RsslChannel</code> structure, as defined in the <i>Transport API C Edition Developers Guide</i> , mainly for reference purposes. All operations should be performed using the Transport API Reactor functionality; the application should not use this <code>RsslChannel</code> directly with any RSSL Transport functionality.
pRsslServer	A pointer to the underlying <code>RsslServer</code> structure, as defined in the <i>Transport API C Edition Developers Guide</i> , mainly for reference purposes. This is populated only if the channel was created via the <code>rsslReactorAccept</code> function, as described in Section 6.4.1.7.

**Table 10: `RsslReactorChannel` Structure Members**

STRUCTURE MEMBER	DESCRIPTION
socketId	Represents a file descriptor that can be used in some kind of I/O notification mechanism (e.g. select, poll) to alert users when dispatch is required on a specific <code>RsslReactorChannel</code> . This is the file descriptor associated with this end of the network connection; the file descriptor value may be different from the other end of the connection.
userSpecPtr	A pointer that can be set by the user of the <code>RsslChannel</code> . This value can be set directly or via the <code>RsslReactorConnectOptions</code> and <code>RsslReactorAcceptOptions</code> . This information can be useful for coupling this <code>RsslReactorChannel</code> with other user-created information, such as a watch list associated with this connection.

Table 10: `RsslReactorChannel` Structure Members (Continued)

### 6.3.1 Reactor Channel Roles

An `RsslReactorChannel` can be configured to fulfill several specific roles, which overlap with the typical OMM application types. Provided role definitions include:

- `RsslReactorOMMConsumerRole` for OMM Consumer applications
- `RsslReactorOMMProviderRole` for OMM Interactive Provider applications
- `RsslReactorOMMNIProviderRole` for OMM Non-Interactive Provider applications

All roles have the same common element, the `RsslReactorChannelRoleBase`.

#### 6.3.1.1 RsslReactorChannelRoleBase Structure

`RsslReactorChannelRoleBase` contains information and callback functions common to all role types and consists of the following members:

STRUCTURE MEMBER	DESCRIPTION
channelEventCallback	This <code>RsslReactorChannel</code> 's user-defined callback function to handle all <code>RsslReactorChannel</code> specific events, like <code>RSSL_RC_CET_CHANNEL_UP</code> or <code>RSSL_RC_CET_CHANNEL_DOWN</code> . This callback function is required for all role types. This callback is defined in more detail in Section 6.6.2.
defaultMsgCallback	This <code>RsslReactorChannel</code> 's user-defined callback function to handle <code>RsslMsg</code> content not handled by another domain-specific callback function. This callback function is required for all role types and is defined in more detail in Section 6.6.2.
roleType	The role type enumeration value, as defined in Section 6.3.1.2.

Table 11: `RsslReactorChannelRoleBase` Structure Members

#### 6.3.1.2 roleType Enumerations

ENUMERATED NAME	DESCRIPTION
<code>RSSL_RC_RT_INIT</code>	Role is not specified. This is intended for structure initialization only.
<code>RSSL_RC_RT_OMM_CONSUMER</code>	Indicates that the <code>RsslReactorChannel</code> should act as an OMM Consumer.
<code>RSSL_RC_RT_OMM_NI_PROVIDER</code>	Indicates that the <code>RsslReactorChannel</code> should act as an OMM Non-Interactive Provider.
<code>RSSL_RC_RT_OMM_PROVIDER</code>	Indicates that the <code>RsslReactorChannel</code> should act as an OMM Interactive Provider.

Table 12: `RsslReactorChannelRoleBase.role` Enumerated Values

## 6.3.2 Reactor Channel Role: OMM Consumer

When an `RsslReactorChannel` is acting as an OMM Consumer application, it connects to an OMM Interactive Provider. As part of this process it is expected to perform a login to the system. Once the login is completed, the consumer acquires a source directory, which provides information about the available services and their capabilities. Additionally, a consumer can download or load field dictionaries, providing information to help decode some types of content. The messages that are exchanged during this connection establishment process are administrative RDMs and are described in the *Transport API C Edition RDM Usage Guide*.

An `RsslReactorChannel` in a consumer role helps to simplify this connection process by exchanging these messages on the user's behalf. The user can choose to provide specific information or leverage a default populated message, which uses the information of the user currently logged into the machine running the application. In addition, the Transport API Reactor allows the application to specify user-defined callback functions to handle the processing of received messages on a per-domain basis.

### 6.3.2.1 OMM Consumer Role

When creating an `RsslReactorChannel`, this information can be specified with the `RsslReactorOMMConsumerRole` structure as follows:

STRUCTURE MEMBER	DESCRIPTION
base	The role base structure, as defined in Section 6.3.1.1.
clientId	Specifies a unique ID defined for an application that makes an EDP token service request. If <code>clientId</code> is not set, the ESDK API uses the value of <code>userName</code> supplied by the user or application. Using <code>clientId</code> is <b>required</b> when connecting to an ADS in the cloud. For details on connecting to an ADS in the cloud, refer to Chapter 7. You can generate and manage Client IDs at the following URL: <a href="https://emea1.apps.cp.thomsonreuters.com/apps/AppkeyGenerator">https://emea1.apps.cp.thomsonreuters.com/apps/AppkeyGenerator</a> (you need an Eikon login to access this page).
dictionaryDownloadMode	Informs the <code>RsslReactorChannel</code> of the method to use when requesting dictionaries. Allowable modes are defined in Section 6.3.2.2.
dictionaryMsgCallback	This <code>RsslReactorChannel</code> 's user-defined callback function to handle dictionary message content. If not specified, all received dictionary messages will be passed to the <code>defaultMsgCallback</code> . <ul style="list-style-type: none"> <li>For more details on this callback, refer to Section 6.6.2.</li> <li>Dictionary messages are described in Section 8.5.</li> </ul>
directoryMsgCallback	This <code>RsslReactorChannel</code> 's user-defined callback function to handle directory message content. If not specified, all received directory messages will be passed to the <code>defaultMsgCallback</code> . <ul style="list-style-type: none"> <li>For more details on this callback, refer to Section 6.6.2.</li> <li>Directory messages are described in Section 8.4.</li> </ul>
loginMsgCallback	This <code>RsslReactorChannel</code> 's user-defined callback function to handle login message content. If not specified, all received login messages will be passed to the <code>defaultMsgCallback</code> . <ul style="list-style-type: none"> <li>For more details on this callback, refer to Section 6.6.2.</li> <li>Login messages are described in Section 8.3.</li> </ul>

**Table 13: `RsslReactorOMMConsumerRole` Structure Members**

STRUCTURE MEMBER	DESCRIPTION
pOAuthCredential	A pointer to the <code>RsslReactorOAuthCredential</code> structure which specifies the user's OAuth credentials. For details on the <code>RsslReactorOAuthCredential</code> structure, refer to Section 6.9.2.1. Use the <code>RsslReactorOAuthCredential</code> structure if the application must create and send the login message; in this case the application must also manage the login life cycle.
pDirectoryRequest	The <code>RsslRDMDirectoryRequest</code> (defined in Section 8.4.1) sent during the connection establishment process. This can be populated with specific source directory request information or invoke the <code>rsslInitDefaultRDMDirectoryRequest</code> function to populate with default information. <ul style="list-style-type: none"> <li>If this parameter is specified, a <code>pDirectoryRequest</code> is required.</li> <li>If this parameter is empty, a directory request is not sent to the system.</li> </ul>
pLoginRequest	The <code>RsslRDMLLoginRequest</code> (defined in Section 8.3.1) sent during the connection establishment process. This can be populated with a user's specific information or invoke the <code>rsslInitDefaultRDMLLoginRequest</code> function to populate with default information. If this parameter is empty, a login is not sent to the system; useful for systems that do not require a login. Use <code>pLoginRequest</code> when the application needs the Transport API Reactor to send the initial login request.
watchlistOptions	Configurable options for the consumer watchlist. Options are described in more detail in Section 6.3.2.3.

Table 13: `RsslReactorOMMConsumerRole` Structure Members (Continued)

### 6.3.2.2 OMM Consumer Role Dictionary Download Modes

There are several dictionary download options available to an `RsslReactorChannel`. The application can determine which option is desired and specify using the `RsslReactorOMMConsumerRole.dictionaryDownloadMode` parameter.

ENUMERATED NAME	DESCRIPTION
RSSL_RC_DICTIONARY_DOWNLOAD_FIRST_AVAILABLE	The <code>RsslReactor</code> will search received directory messages for the <code>RDMFieldDictionary</code> (RWFFld) and the <code>enumtype.def</code> (RWFEnum) dictionaries. Once found, the <code>RsslReactor</code> will request these dictionaries for the application. After transmission is completed, the streams are closed because this content does not update.
RSSL_RC_DICTIONARY_DOWNLOAD_NONE	The <code>RsslReactor</code> will not request dictionaries for this <code>RsslReactorChannel</code> . This is typically used when the application has loaded a file-based dictionary or has acquired the dictionary elsewhere.

Table 14: `RsslReactorOMMConsumerRole.dictionaryDownloadMode` Enumerated Values

### 6.3.2.3 OMM Consumer Role Watchlist Options

The consumer may enable an internal watchlist and configure behaviors. For more detail on the consumer watchlist feature, refer to Section 2.4.

OPTION	DESCRIPTION
enableWatchlist	Enables the watchlist.
itemCountHint	Can improve performance when used with the watchlist. If possible, set this to the approximate number of item requests the application expects to open.
maxOutstandingPosts	Sets the maximum allowable number of on-stream posts waiting for acknowledgment before the reactor disconnects.
obeyOpenWindow	Sets whether the <code>RsslReactor</code> obeys the OpenWindow of services advertised in a provider's Source Directory response.
postAckTimeout	Sets the time (in milliseconds) a stream waits to receive an ACK for an outstanding post before forwarding a negative acknowledgment <code>RsslAckMsg</code> to the application.
requestTimeout	Sets the time (in milliseconds) the watchlist waits for a response to a request.

Table 15: OMM Consumer Role Watchlist Options

### 6.3.2.4 OMM Consumer Role Utility Method

The Transport API provides the following utility function for use with the `RsslReactorOMMConsumerRole`.

FUNCTION NAME	DESCRIPTION
<code>rsslClearOMMConsumerRole</code>	Clears the <code>RsslReactorOMMConsumerRole</code> structure. Useful for structure reuse.

Table 16: `RsslReactorOMMConsumerRole` Utility Function

### 6.3.3 Reactor Channel Role: OMM Provider

When an `RsslReactorChannel` is acting as an OMM provider application, it allows connections from OMM consumer applications. As part of this process it is expected to respond to login requests and source directory information requests. Additionally, a provider can optionally allow consumers to download field dictionaries. Messages exchanged during this connection establishment process are administrative RDMs and are described in the *Transport API C Edition RDM Usage Guide*.

An `RsslReactorChannel` in an interactive provider role allows the application to specify user-defined callback functions to handle the processing of received messages on a per-domain basis.

#### 6.3.3.1 OMM Provider Role Members

When creating an `RsslReactorChannel`, this information can be specified with the `RsslReactorOMMProviderRole` structure, as follows:

STRUCTURE MEMBER	DESCRIPTION
base	The role base structure, as defined in Section 6.3.1.1.
dictionaryMsgCallback	<p>This <code>RsslReactorChannel</code>'s user-defined callback function to handle dictionary message content. If unspecified, all received dictionary messages will be passed to the <code>defaultMsgCallback</code>.</p> <ul style="list-style-type: none"> <li>For further details on this callback, refer to Section 6.6.2.</li> <li>Dictionary messages are described in Section 8.5.</li> </ul>

Table 17: `RsslReactorOMMProviderRole` Structure Members

STRUCTURE MEMBER	DESCRIPTION
directoryMsgCallback	This <code>RsslReactorChannel</code> 's user-defined callback function to handle directory message content. If unspecified, all received directory messages will be passed to the <code>defaultMsgCallback</code> . <ul style="list-style-type: none"> <li>For further details on this callback, refer to Section 6.6.2.</li> <li>Directory messages are described in Section 8.4.</li> </ul>
loginMsgCallback	This <code>RsslReactorChannel</code> 's user-defined callback function to handle login message content. If unspecified, all received login messages are passed to the <code>defaultMsgCallback</code> . <ul style="list-style-type: none"> <li>For further details on this callback, refer to Section 6.6.2.</li> <li>Login messages are described in Section 8.3.</li> </ul>
tunnelStreamListenerCallback	This <code>RsslReactorChannel</code> 's user-defined callback for accepting or rejecting tunnel streams. For further details on this callback, refer to Section 6.8.6.

Table 17: `RsslReactorOMMProviderRole` Structure Members (Continued)

### 6.3.3.2 OMM Provider Role Utility Function

The Transport API provides the following utility function for use with the `RsslReactorOMMProviderRole`.

FUNCTION NAME	DESCRIPTION
<code>rsslClearOMMProviderRole</code>	Clears the <code>RsslReactorOMMProviderRole</code> structure. Useful for structure reuse.

Table 18: `RsslReactorOMMProviderRole` Utility Function

### 6.3.4 Reactor Channel Role: OMM Non-Interactive Provider

When an `RsslReactorChannel` acts as an OMM Non-Interactive Provider application, it connects to an Enterprise Platform ADH and logs into the system. After login, the non-interactive provider publishes a source directory, which provides information about the available services and their capabilities. Messages exchanged while establishing the connection are administrative RDMs and are described in the *Transport API C Edition RDM Usage Guide*.

An `RsslReactorChannel` in a non-interactive provider role helps to simplify this connection process by exchanging these messages on the user's behalf. The user can choose to provide specific information or leverage a default populated message, which uses the information of the user currently logged into the machine running the application. In addition, the Transport API Reactor allows the application to specify user-defined callback functions to handle the processing of received messages on a per-domain basis.

#### 6.3.4.1 OMM Non-Interactive Role Members

When creating an `RsslReactorChannel`, this information can be specified with the `RsslReactorOMMNIPProviderRole` structure, as follows:

STRUCTURE MEMBER	DESCRIPTION
base	The role base structure, as defined in Section 6.3.1.1.

Table 19: `RsslReactorOMMNIPProviderRole` Structure Members

STRUCTURE MEMBER	DESCRIPTION
pLoginRequest	The <code>RsslRDMLLoginRequest</code> , defined in Section 8.3.1, sent when establishing a connection. You can populate this with a user's specific information or invoke the <code>rsslInitDefaultRDMLLoginRequest</code> function to populate with a default set of information. If empty, a login is not sent to the system; useful for systems that do not require a login.
pDirectoryRefresh	The <code>RsslRDMDirectoryRefresh</code> , defined in Section 8.4.2, sent when establishing a connection. You can populate this with specific source directory refresh information. <ul style="list-style-type: none"> <li>If this parameter is specified, a <code>pDirectoryRefresh</code> is required.</li> <li>If this parameter is left empty, a directory request is not sent to the system.</li> </ul>
loginMsgCallback	The <code>RsslReactorChannel</code> 's user-defined callback function that handles login message content. If unspecified, all received login messages are passed to the <code>defaultMsgCallback</code> . For further details on this callback, refer to Section 6.6.2.

Table 19: `RsslReactorOMMNIPProviderRole` Structure Members (Continued)

### 6.3.4.2 OMM Non-Interactive Provider Role Utility Function

The Transport API provides the following utility function for use with the `RsslReactorOMMNIPProviderRole`.

FUNCTION NAME	DESCRIPTION
<code>rsslClearOMMNIPProviderRole</code>	Clears the <code>RsslReactorOMMNIPProviderRole</code> structure. Useful for structure reuse.

Table 20: `RsslReactorOMMNIPProviderRole` Utility Function

### 6.3.5 Reactor Channel: Role Union

A union is provided that allows use of any of the role structures. This is mainly for use within the `RsslReactor` implementation; however it is documented in the event that it can be useful to an application.

#### 6.3.5.1 Union Members

UNION MEMBER	DESCRIPTION
base	The role's base structure, as defined in Table 11.
ommConsumerRole	The <code>RsslReactorOMMConsumerRole</code> , as defined in Section 6.3.2.
ommProviderRole	The <code>RsslReactorOMMProviderRole</code> , as defined in Section 6.3.3.
ommNIPProviderRole	The <code>RsslReactorOMMNIPProviderRole</code> , as defined in Section 6.3.4.

Table 21: `RsslReactorChannelRole` Union Members

#### 6.3.5.2 Union Utility Function

The Transport API provides the following utility function for use with the `RsslReactorOMMProviderRole`.

FUNCTION NAME	DESCRIPTION
<code>rsslClearReactorChannelRole</code>	Clears the <code>RsslReactorChannelRole</code> union.

Table 22: `RsslReactorChannelRole` Utility Function



## 6.4 Managing Reactor Channels

### 6.4.1 Adding Reactor Channels

A single `RsslReactor` instance can manage multiple `RsslReactorChannels`. An `RsslReactorChannel` can be instantiated as an outbound client style connection or as a connection that is accepted from an `RsslServer`. Thus, users can mix connection styles within or across Reactors and have consistent usage and behavior.

**Note:** A single `RsslReactor` can simultaneously manage `RsslReactorChannels` from `rsslReactorConnect` and `rsslReactorAccept`.

#### 6.4.1.1 Reactor Connect

The `rsslReactorConnect` function will create a new `RsslReactorChannel` and associate it with an `RsslReactor`. This function creates a new outbound connection. The `RsslReactorChannel` is returned to the application via a callback, as described in Section 6.6.2, at which point it begins dispatching.

Client applications can specify that `RsslReactor` automatically reconnect an `RsslReactorChannel` whenever a connection fails. To enable this, the application sets the appropriate members of the `RsslReactorConnectOptions` structure. The application can specify that `RsslReactor` reconnect the `RsslReactorChannel` to the same host, or to one from among multiple hosts.

Consumer applications can combine the reactor connect feature with the watchlist feature to enable recovery of item streams across connections. For more information on the watchlist feature, refer to Section 2.4.

FUNCTION NAME	DESCRIPTION
<code>rsslReactorConnect</code>	Creates an <code>RsslReactorChannel</code> that makes an outbound connection to the configured host. This establishes a connection in a manner similar to the <code>rsslConnect</code> function, as described in the <i>Transport API C Edition Developers Guide</i> . Connection options are passed in via the <code>RsslReactorConnectOptions</code> , as defined in Section 6.4.1.2.  <code>RsslReactorChannel</code> specific information, such as the per-channel callback functions, the type of behavior, default RDM messages, and such are passed in via the <code>RsslReactorChannelRole</code> , as defined in Section 6.3.1.

Table 23: `rsslReactorConnect` Function

#### 6.4.1.2 RsslReactorConnectOptions Structure Members

STRUCTURE MEMBER	DESCRIPTION
<code>connectionCount</code>	Specifies the number of connections listed in <code>reactorConnectionList</code> . If set to 0, <code>rsslConnectOptions</code> is used.
<code>connectionDebugFlags</code>	Specifies a set of <code>RsslDebugFlags</code> for use when calling user-set debug callbacks as set by <code>rsslSetDebugFunctions</code> . If set to 0, debug callbacks are not used
<code>initializationTimeout</code>	Specifies the amount of time (in seconds) to wait to successfully establish an <code>RsslReactorChannel</code> . If a <code>RsslReactorChannel</code> is not established in this timeframe, an event is dispatched to the application to indicate that the <code>RsslReactorChannel</code> is down.

Table 24: `RsslReactorConnectOptions` Structure Members

STRUCTURE MEMBER	DESCRIPTION
reactorConnectionList	Specifies an array of connection information. When used with <code>reconnectAttemptLimit</code> , the <code>RsslReactor</code> attempts to connect to each host in the list with each reconnection attempt.
reconnectAttemptLimit	The maximum number of times the <code>RsslReactor</code> attempts to reconnect a channel when it fails. If set to <code>-1</code> , there is no limit.
reconnectMinDelay	Specifies the minimum length of time the <code>RsslReactor</code> waits (in milliseconds) before attempting to reconnect a failed channel. The time increases with each reconnection attempt, from <code>reconnectMinDelay</code> to <code>reconnectMaxDelay</code> .
reconnectMaxDelay	Specifies the maximum length of time the <code>RsslReactor</code> waits (in milliseconds) before attempting to reconnect a failed channel. The time increases with each reconnection attempt, from <code>reconnectMinDelay</code> to <code>reconnectMaxDelay</code> .
rsslConnectOptions	Specifies information ( <code>rsslConnectOptions</code> ) about the host or network to which to connect, the type of connection to use, and other transport-specific configuration information associated with the underlying <code>rsslConnect</code> function. This is described in more detail in the <i>Transport API C Edition Developers Guide</i> .
statisticFlags	Specifies <code>RsslReactorChannelStatisticFlags</code> which set the type of statistics reporting (if any) to perform on the <code>RsslReactor</code> channel. <code>RsslReactorChannelStatisticFlags</code> uses the following enums: <ul style="list-style-type: none"> <li><code>RSSL_RC_ST_NONE</code> (or <code>0x0000</code>): Turns off statistics reporting.</li> <li><code>RSSL_RC_ST_READ</code> (or <code>0x0001</code>): Turns on statistics reporting for the number of bytes read and the number of uncompressed bytes read.</li> <li><code>RSSL_RC_ST_WRITE</code> (or <code>0x0002</code>): Turns on statistics reporting for the number of bytes written and uncompressed bytes written.</li> <li><code>RSSL_RC_ST_PING</code> (or <code>0x0004</code>): Turns on statistics reporting for the number of pings received and the number of pings sent.</li> </ul>

Table 24: RsslReactorConnectOptions Structure Members (Continued)

#### 6.4.1.3 RsslReactorConnectInfo Structure Members

CLASS MEMBER	DESCRIPTION
rsslConnectOptions	Specifies information ( <code>rsslConnectOptions</code> ) about the host or network to which to connect, the type of connection to use, and other transport-specific configuration information associated with the underlying <code>rsslConnect</code> function. This is described in more detail in the <i>Transport API C Edition Developers Guide</i> .
enableSessionManagement	Specifies whether the channel manages the authentication token on behalf of the user used to keep the session alive. Boolean. If set to <code>true</code> , the channel obtains the authentication token and refreshes it on behalf of user to keep session active. The default setting is <code>false</code> .
initializationTimeout	Specifies the amount of time (in seconds) to wait to successfully establish an <code>RsslReactorChannel</code> . If a <code>RsslReactorChannel</code> is not established in this timeframe, an event is dispatched to the application to indicate that the <code>RsslReactorChannel</code> is down.

Table 25: RsslReactorConnectInfo Structure Members

CLASS MEMBER	DESCRIPTION
location	Specifies the cloud location (e.g., <code>us-east</code> ) of the service provider endpoint to which the ESDK API establishes a connection. If <code>location</code> is not specified, the default setting is <code>us-east</code> . In any particular cloud location, the <code>Reactor</code> connects to the endpoint that provides two available zones for the location (e.g., <code>[us-east-1a, us-east-1b]</code> ).
pAuthTokenEventCallback	A callback function that receives <code>RsslReactorAuthTokenEvents</code> . The Reactor requests a token for the Consumer (i.e., disabling watchlist) and NiProvider applications to send login requests and reissues with the token.

Table 25: `RsslReactorConnectInfo` Structure Members (Continued)

#### 6.4.1.4 RsslReactorConnectOptions Utility Function

The Transport API provides the following utility function for use with the `RsslReactorConnectOptions`.

FUNCTION NAME	DESCRIPTION
<code>rsslClearReactorConnectOptions</code>	Clears the <code>RsslReactorConnectOptions</code> structure. Useful for structure reuse.

Table 26: `RsslReactorConnectOptions` Utility Function

#### 6.4.1.5 rsslReactorConnect Example

```

RsslReactorConnectOptions reactorConnectOpts;
RsslReactorOMMConsumerRole consumerRole;

RsslRDMLLoginRequest loginRequest;
RsslRDMDirectoryRequest directoryRequest;

/* Configure connection options.*/
rsslClearReactorConnectOptions(&reactorConnectOpts);
reactorConnectOpts.rsslConnectOptions.connectionInfo.unified.address = "localhost";
reactorConnectOpts.rsslConnectOptions.connectionInfo.unified.serviceName = "14002";

/* Configure a role for this connection as an OMM Consumer. */
rsslClearOMMConsumerRole(&consumerRole);

/* Set the functions to which rsslDispatch will deliver events. */
consumerRole.base.channelEventCallback = channelEventCallback;
consumerRole.base.defaultMsgCallback = defaultMsgCallback;
consumerRole.loginMsgCallback = loginMsgCallback;
consumerRole.directoryMsgCallback = directoryMsgCallback;
consumerRole.dictionaryMsgCallback = dictionaryMsgCallback;

/* Prepare a login request. Once the channel is initialized this message will be sent. */
rsslInitDefaultRDMLLoginRequest(&loginRequest, 1);
consumerRole.pLoginRequest = &loginRequest;

```

```

/* Prepare a directory request. Once the application has logged in, this message will be sent. */
rsslInitDefaultRDMDirectoryRequest(&directoryRequest, 2);
consumerRole.pDirectoryRequest = &directoryRequest;

/* Add the connection to the RsslReactor. */
ret = rsslReactorConnect(pReactor, &reactorConnectOpts, (RsslReactorChannelRole*)&consumerRole,
    &rsslErrorInfo);

```

### Code Example 2: **rsslReactorConnect** Example

#### 6.4.1.6 rsslReactorConnect Segmented Multicast Consumer Example

```

RsslReactorConnectOptions reactorConnectOpts;
RsslReactorOMMConsumerRole consumerRole;

RsslRDMLLoginRequest loginRequest;
RsslRDMDirectoryRequest directoryRequest;

/* Configure connection options.*/
rsslClearReactorConnectOptions(&reactorConnectOpts);
reactorConnectInfo.rsslConnectOptions.connectionType = RSSL_CONN_TYPE_RELIABLE_MCAST;

/* Configure outgoing network */
reactorConnectOpts.rsslConnectOptions.connectionInfo.segmented.sendAddress = "232.6.6.1";
reactorConnectOpts.rsslConnectOptions.connectionInfo.segmented.sendServiceName = "30010";

/* Configure incoming network. This example listens to two multicast networks. */
reactorConnectOpts.rsslConnectOptions.connectionInfo.segmented.recvAddress = "232.6.6.2,232.6.6.4";
reactorConnectOpts.rsslConnectOptions.connectionInfo.segmented.recvServiceName = "30011";
reactorConnectOpts.rsslConnectOptions.connectionInfo.segmented.unicastServiceName = "55555";

/* Enable filtering of incoming multicast traffic. */
reactorConnectOpts.rsslConnectOptions.multicastOpts.flags = RSSL_MCAST_FILTERING_ON;

/* Configure a role for this connection as an OMM Consumer. */
rsslClearOMMConsumerRole(&consumerRole);

/* Set the functions to which rsslDispatch will deliver events. */
consumerRole.base.channelEventCallback = channelEventCallback;
consumerRole.base.defaultMsgCallback = defaultMsgCallback;
consumerRole.loginMsgCallback = loginMsgCallback;
consumerRole.directoryMsgCallback = directoryMsgCallback;
consumerRole.dictionaryMsgCallback = dictionaryMsgCallback;

/* Prepare a login request. Once the channel is initialized this message will be sent. */
rsslInitDefaultRDMLLoginRequest(&loginRequest, 1);
consumerRole.pLoginRequest = &loginRequest;

```

```

/* Prepare a directory request. Once the application has logged in, this message will be sent. */
rsslInitDefaultRDMDirectoryRequest(&directoryRequest, 2);
consumerRole.pDirectoryRequest = &directoryRequest;

/* Add the connection to the RsslReactor. */
ret = rsslReactorConnect(pReactor, &reactorConnectOpts, (RsslReactorChannelRole*)&consumerRole,
    &rsslErrorInfo);

```

### Code Example 3: **rsslReactorConnect** Segmented Multicast Consumer Example

#### 6.4.1.7 Reactor Accept

The **rsslReactorAccept** function creates a new **RsslReactorChannel** and associates it with an **RsslReactor**. This function accepts the connection from an already running **RsslServer**. The **RsslReactorChannel** will be returned to the application via a callback, as described in Section 6.6.2, at which point it can begin dispatching on the channel.

FUNCTION NAME	DESCRIPTION
<b>rsslReactorAccept</b>	<p>Creates an <b>RsslReactorChannel</b> by accepting it from an <b>RsslServer</b>. This establishes a connection in a manner similar to the <b>rsslAccept</b> function, as described in the <i>Transport API C Edition Developers Guide</i>.</p> <ul style="list-style-type: none"> <li>• Connection options are passed in via <b>RsslReactorAcceptOptions</b>, as defined in Section 6.4.1.8.</li> <li>• <b>RsslReactorChannel</b>-specific information (such as the per-channel callback functions, the type of behavior, default RDM messages, and etc.) are passed in via the <b>RsslReactorChannelRole</b>, as defined in Section 6.3.1.</li> </ul>

Table 27: **rsslReactorAccept** Function

#### 6.4.1.8 RsslReactorAcceptOptions Structure Members

STRUCTURE MEMBER	DESCRIPTION
<b>rsslAcceptOptions</b>	The <b>RsslAcceptOptions</b> associated with the underlying <b>rsslAccept</b> function. This includes an option to reject the connection as well as a <b>userSpecPtr</b> . This is described in more detail in the <i>Transport API C Edition Developers Guide</i> .
<b>initializationTimeout</b>	The amount of time (in seconds) to wait for the successful connection establishment of an <b>RsslReactorChannel</b> . If a timeout occurs, an event is dispatched to the application to indicate that the <b>RsslReactorChannel</b> is down.

Table 28: **RsslReactorAcceptOptions** Structure Members

### 6.4.1.9 RsslReactorAcceptOptions Utility Function

The Transport API provides the following utility function for use with the `RsslReactorAcceptOptions`.

FUNCTION NAME	DESCRIPTION
<code>rsslClearReactorAcceptOptions</code>	Clears the <code>RsslReactorAcceptOptions</code> structure. Useful for structure reuse.

Table 29: `RsslReactorAcceptOptions` Utility Function

### 6.4.1.10 rsslReactorAccept Example

```
RsslReactorAcceptOptions reactorAcceptOpts;
RsslReactorOMMProviderRole providerRole;

/* Configure accept options.*/
rsslClearReactorAcceptOptions (&reactorAcceptOpts);

/* Configure a role for this connection as an OMM Provider. */
rsslClearOMMProviderRole (&providerRole);
providerRole.base.channelEventCallback = channelEventCallback;
providerRole.base.defaultMsgCallback = defaultMsgCallback;
providerRole.loginMsgCallback = loginMsgCallback;
providerRole.directoryMsgCallback = directoryMsgCallback;
providerRole.dictionaryMsgCallback = dictionaryMsgCallback;

/* Add the connection to the RsslReactor. */
rsslClearReactorAcceptOptions (&reactorAcceptOpts);
ret = rsslReactorAccept (pReactor, pRsslServer, &reactorAcceptOpts,
                        (RsslReactorChannelRole*)&providerRole, &rsslErrorInfo);
```

Code Example 4: `rsslReactorAccept` Example

## 6.4.2 Removing Reactor Channels

### 6.4.2.1 rsslReactorClose Function

You use the following function to remove an `RsslReactorChannel` from an `RsslReactor` instance. It can also close and clean up resources associated with the `RsslReactorChannel`.

FUNCTION NAME	DESCRIPTION
<code>rsslReactorCloseChannel</code>	Removes an <code>RsslReactorChannel</code> from the corresponding <code>RsslReactor</code> and cleans up associated resources. This additionally invokes the <code>rsslCloseChannel</code> function, as described in the <i>Transport API C Edition Developers Guide</i> , to clean up any resources associated with the underlying <code>RsslChannel</code> .  This function can be called from either outside or within a callback.

Table 30: `rsslReactorCloseChannel` Function

### 6.4.2.2 rsslReactorClose Example

```
RsslErrorInfo rsslErrorInfo;
/* Can be used inside or outside of a callback */
ret = rsslReactorCloseChannel(pReactor, pReactorChannel, &rsslErrorInfo);
```

Code Example 5: **rsslReactorClose** Example

## 6.5 Reporting on Channel Statistics

You can use the **rsslReactorRetrieveChannelStatistic()** method to report on channel statistics. To use this method, you must first activate channel statistics reporting in **RsslReactorConnectOptions** by setting the **statisticFlags** member (for details on this member and the types of statistics on which you can report, refer to Section 6.4.1.2).

To get statistics, create an **RsslReactorChannelStatistic** structure and pass it in with the method. The Transport API responds with the data for which the **statisticFlags** expressed interest.

## 6.6 Dispatching Data

Once an application has an **RsslReactor**, it can begin dispatching messages. Until there is at least one associated **RsslReactorChannel**, there is nothing to dispatch. When **RsslReactorChannels** are available for dispatching, each channel begins seeing its user-defined per-channel callbacks being invoked. For more information about available callbacks and their specifications, refer to Section 6.6.2.

An application can choose to dispatch across all associated **RsslReactorChannels** or to dispatch on a particular **RsslReactorChannel**. If dispatching on a single **RsslReactorChannel**, only this channel's data is processed and returned via the channel's callback. If dispatching across multiple **RsslReactorChannels**, the **RsslReactor** attempts to fairly dispatch over all channels. In either case, the application can use the dispatch call to specify the maximum number of messages that will be processed and returned via callback.

Typically, an application registers both the **RsslReactor.eventFd** and each **RsslReactorChannel**'s **socketId** with an I/O notifier (e.g., **select**, **poll**). The I/O notifier can help inform the application when data is available on particular **RsslReactorChannels** or when channel information is available from the **RsslReactor**. An application can also forgo the use of notifiers and instead periodically call the dispatch function to process data as described in Section 6.6.1.

### 6.6.1 rsslReactorDispatch Function

**Note:** Applications should not call **rsslDestroyReactor** or **rsslReactorDispatch** from within a callback function. All other **RsslReactor** functionality is safe to use from within a callback.

Events received in callback functions should be assumed to be invalid when the callback function returns. For callbacks that provide **RsslMsg** or **RsslRDMMsg** structures, a deep copy of the object should be made if the application wishes to preserve it. To copy an **RsslMsg**, refer to the **rsslCopyMsg** function in the *Transport API C Edition Developers Guide*; for copying an **RsslRDMMsg**, refer to the copy utility function for the appropriate **RsslRDMMsg** structure.

FUNCTION NAME	DESCRIPTION
<code>rsslReactorDispatch</code>	<p>This function processes events and messages across the provided <code>RsslReactor</code> and all of its associated <code>RsslReactorChannels</code>. When channel information or data is available for an <code>RsslReactorChannel</code>, the channel's user-defined callback function is invoked.</p> <p>The application can dispatch on a specified channel or over all channels associated with the <code>RsslReactor</code>. The application can also control the maximum number of messages dispatched with a single call to <code>rsslReactorDispatch</code>. This can be controlled through passed-in <code>RsslReactorDispatchOptions</code>, as described in Section 6.6.1.1.</p>

Table 31: `rsslReactorDispatch` Function

### 6.6.1.1 Reactor Dispatch Options

An application can use `RsslReactorDispatchOptions` to control various aspects of the call to `rsslReactorDispatch`.

STRUCTURE MEMBER	DESCRIPTION
<code>pReactorChannel</code>	The specific <code>RsslReactorChannel</code> to dispatch on in this call. If <code>NULL</code> , <code>rsslReactorDispatch</code> will process across all <code>RsslReactorChannels</code> associated with the passed in <code>RsslReactor</code> .
<code>maxMessages</code>	Controls the maximum number of events or messages processed in this call. If this is larger than the number of available messages, <code>rsslReactorDispatch</code> will return when there is no more data to process. This value is initialized to allow up to 100 messages to be returned with a single call to <code>rsslReactorDispatch</code> .

Table 32: `RsslReactorDispatchOptions` Structure Members

### 6.6.1.2 RsslReactorDispatchOptions Utility Function

The Transport API provides the following utility Function for use with `RsslReactorDispatchOptions`.

FUNCTION NAME	DESCRIPTION
<code>rsslClearReactorDispatchOptions</code>	Clears the <code>RsslReactorDispatchOptions</code> structure. Useful for structure reuse.

Table 33: `RsslReactorDispatchOptions` Utility Function

### 6.6.1.3 rsslReactorDispatch Example

```
RsslReactorDispatchOptions dispatchOpts;

/* Set dispatching options. */
rsslClearReactorDispatchOptions(&dispatchOpts);
dispatchOpts.maxMessages = 200;

/* Call rsslReactorDispatch(). It will keep dispatching events until there is nothing to read or
 * maxMessages is reached. */
ret = rsslReactorDispatch(pReactor, &dispatchOpts, &rsslErrorInfo);
```

Code Example 6: `rsslReactorDispatch` Example



## 6.6.2 Reactor Callback Functions

A series of callback functions returns (to the application) any state information about the `RsslReactorChannel` connection as well as messages for that channel. Each `RsslReactorChannel` can define its own unique callback functions or specify callback functions that can be shared across channels.

There are several values that can be returned from a callback function implementation. These can trigger specific `RsslReactor` behaviors based on the outcome of the callback function. Callback return values are as follows:

RETURN CODE	DESCRIPTION
RSSL_RC_CRET_SUCCESS	Indicates that the callback function was successful and the message or event has been handled.
RSSL_RC_CRET_FAILURE	Indicates that the message or event has failed to be handled. Returning this code from any callback function will cause the <code>RsslReactor</code> to shutdown.
RSSL_RC_CRET_RAISE	Can be returned from any domain-specific callback (e.g., <code>RsslRDMLoginMsgCallback</code> ). This will cause the <code>RsslReactor</code> to invoke the <code>RsslDefaultMsgCallback</code> for this message upon the domain-specific callbacks return.

Table 34: `RsslReactorCallbackRet` Callback Return Codes

## 6.6.3 Reactor Callback: Channel Event

The `RsslReactor` channel event callback communicates `RsslReactorChannel` and connection state information to the application. This callback function has the following prototype:

```
RsslReactorChannelEventCallback(RsslReactor*, RsslReactorChannel*, RsslReactorChannelEvent*)
```

When invoked, this returns the `RsslReactor` and the `RsslReactorChannel` on which the event occurred. In addition, an `RsslReactorChannelEvent` structure is returned, containing more information about the event.

### 6.6.3.1 Reactor Channel Event

The `RsslReactorChannelEvent` is returned to the application via the `RsslReactorChannelEventCallback`.

STRUCTURE MEMBER	DESCRIPTION
channelEventType	The type of event that has occurred on the <code>RsslReactorChannel</code> . For a list of enumeration values, refer to Section 6.6.3.2.
pReactorChannel	The <code>RsslReactorChannel</code> on which the event occurred.
pError	An <code>RsslErrorInfo</code> structure that is populated with error and warning information that occurred. This is only populated for <code>RSSL_RC_CET_CHANNEL_DOWN</code> and <code>RSSL_RC_CET_WARNING</code> event types.

Table 35: `RsslReactorChannelEvent` Structure Members

### 6.6.3.2 Reactor Channel Event Type Enumeration Values

FLAG ENUMERATION	MEANING
RSSL_RC_CET_CHANNEL_DOWN	<p>Indicates that the <code>RsslReactorChannel</code> is not available for use. This could be a result of an initialization failure, a ping timeout, or some other kind of connection-related issue. <code>RsslErrorInfo</code> will contain more detailed information about what occurred.</p> <p>To clean up the failed <code>RsslReactorChannel</code>, the application should call <code>rsslReactorCloseChannel</code>.</p>
RSSL_RC_CET_CHANNEL_DOWN_RECONNECTING	<p>Indicates that the <code>RsslReactorChannel</code> is temporarily unavailable for use. The Reactor will attempt to reconnect the channel according to the values specified in <code>RsslReactorConnectOptionsS</code> when <code>rsslReactorConnect</code> was called.</p> <p>If the watchlist is enabled, requests are recovered as appropriate when the channel successfully reconnects.</p> <p>Before exiting the <code>channelEventCallback</code>, the application should release any resources associated with the channel, such as <code>RsslBufferS</code>, and remove its file-descriptor, if valid, from any notification sets.</p>
RSSL_RC_CET_CHANNEL_OPEN	<p>This event occurs only when the watchlist is enabled and only via the optional <code>channelOpenCallback</code> function.</p> <p>Indicates that a channel has been created via <code>rsslReactorConnect</code>. Though the channel is still not ready for dispatch, the application can begin submitting request messages, which are sent after the channel successfully initializes.</p>
RSSL_RC_CET_CHANNEL_READY	<p>Indicates that the <code>RsslReactorChannel</code> has successfully completed any necessary initialization processes. Where applicable, this includes exchanging any provided Login, Directory, or Dictionary content.</p> <p>The application should now be able to consume or provide content.</p>
RSSL_RC_CET_CHANNEL_UP	<p>Indicates that the <code>RsslReactorChannel</code> is successfully initialized and available for dispatching. Where applicable, any specified Login, Directory, or Dictionary messages are exchanged by the <code>RsslReactor</code>.</p>
RSSL_RC_CET_FD_CHANGE	<p>Indicates that a file-descriptor change occurred on the <code>RsslReactorChannel</code>. If the application is using its own I/O notification mechanism, it should replace the <code>oldSocketId</code> with the <code>socketId</code>, both of which can be found on the <code>RsslReactorChannel</code>.</p>
RSSL_RC_CET_INIT	<p>Channel event initialization value. This should not be used by nor returned to the application.</p>
RSSL_RC_CET_WARNING	<p>Indicates that the <code>RsslReactorChannel</code> has experienced an event that did not result in connection failure, but may require the attention of the application.</p> <p><code>RsslErrorInfo</code> contains more detailed information about what occurred.</p>

**Table 36: `RsslReactorChannelEventType` Enumeration Values**

### 6.6.3.3 Reactor Channel Event Utility Functions

FUNCTION NAME	DESCRIPTION
<code>rsslClearReactorChannelEvent</code>	Clears an <code>RsslReactorChannelEvent</code> structure.

**Table 37: `RsslReactorChannelEvent` Utility Functions**

### 6.6.3.4 Reactor Channel Event Callback Example

```

RsslReactorCallbackRet channelEventCallback(RsslReactor *pReactor, RsslReactorChannel
    *pReactorChannel, RsslReactorChannelEvent *pChannelEvent)
{
    switch (pChannelEvent->channelEventType)
    {
        case RSSL_RC_CET_CHANNEL_UP:
            /* Channel has successfully initialized, add its descriptors to our notification
               mechanism. */
            FD_SET(pReactorChannel->socketId, &readFds);
            FD_SET(pReactorChannel->socketId, &exceptFds);
            break;
        case RSSL_RC_CET_CHANNEL_DOWN:
            /* Channel has failed. Clean up all references and close the channel. */
            FD_CLR(pReactorChannel->socketId, &readFds);
            FD_CLR(pReactorChannel->socketId, &exceptFds);

            /* If all references are already clean up, channel can be closed now. Otherwise the
               * application can wait for a more appropriate time. */
            ret = rsslReactorCloseChannel(pReactor, pReactorChannel, &rsslErrorInfo);
            break;

        case RSSL_RC_CET_CHANNEL_READY:
            /* Channel has exchanged its initial messages (if any were provided on the role object)
               * and is ready for use. */
            sendItemRequests(pReactorChannel);
            break;

        case RSSL_RC_CET_FD_CHANGE:
            /* The descriptor representing this channel has changed. Normally the application only needs
               * to update its notification mechanism in response to this event. */
            FD_CLR(pReactorChannel->oldSocketId, &readFds);
            FD_CLR(pReactorChannel->oldSocketId, &exceptFds);
            FD_SET(pReactorChannel->socketId, &readFds);
            FD_SET(pReactorChannel->socketId, &exceptFds);
            break;

        case RSSL_RC_CET_WARNING:
            /* Received a warning about the channel. The channel is still active, but the event may
               * require the application's attention. */
            printf("Received channel warning event: %d(%s) ",

```

```

        pChannelEvent->pError->rsslError.rsslErrorId,
        pChannelEvent->pError->rsslError.text);

    break;

}

return RSSL_RC_CRET_SUCCESS;
}

```

### Code Example 7: Reactor Channel Event Callback Example

## 6.6.4 Reactor Callback: Default Message

The **RsslReactor** default message callback communicates all received content that is not handled directly by a domain-specific callback function. This callback is also invoked after any domain-specific callback that returns the **RSSL\_RC\_CET\_RAISE** value. This callback function has the following prototype:

```
RsslDefaultMsgCallback(RsslReactor*, RsslReactorChannel*, RsslMsgEvent*)
```

When invoked, this returns the **RsslReactor** and the **RsslReactorChannel** on which the event occurred. In addition, an **RsslMsgEvent** structure is returned, containing more information about the event information.

### 6.6.4.1 Reactor Message Event

The **RsslMsgEvent** is returned to the application via the **RsslDefaultMsgCallback**.

STRUCTURE MEMBER	DESCRIPTION
pRsslMsgBuffer	<p>An <b>RsslBuffer</b> containing the raw, undecoded message that was read and processed by the callback.</p> <p><b>Note:</b> When the consumer watchlist is enabled, an <b>RsslBuffer</b> is not provided, because the message might not match this buffer, or the message might be internally generated.</p>
pRsslMsg	<p>An <b>RsslMsg</b> structure populated with message content by calling <b>rsslDecodeMsg</b>. If not present, an error was encountered while processing the information.</p> <p><b>Note:</b> When the consumer watchlist is enabled, <b>pRsslMsg</b> is not provided to callback functions that provide RDM messages.</p>
pError	An <b>RsslErrorInfo</b> structure that is populated with error and warning information that occurred, likely related to message decoding or processing.
pStreamInfo	Any information associated with a stream (only when the watchlist is enabled).
pSeqNum	The sequence number associated with a message, if present (only when using multicast).
pFTGroupId	The fault-tolerant group associated with a message, if present (only when using multicast).

**Table 38: RsslMsgEvent Structure Members**

### 6.6.4.2 Reactor Message Event Utility Functions

FUNCTION NAME	DESCRIPTION
<code>rsslClearMsgEvent</code>	Clears an <code>RsslMsgEvent</code> structure.

Table 39: `RsslMsgEvent` Utility Function

### 6.6.4.3 Reactor Message Event Callback Example

```
RsslReactorCallbackRet defaultMsgCallback(RsslReactor *pReactor, RsslReactorChannel *pReactorChannel,
    RsslMsgEvent *pMsgEvent)
{
    RsslMsg *pRsslMsg = pMsgEvent->pRsslMsg;

    /* Received an RsslMsg --- or, if the decode failed, an error. */
    /* The RsslMsg will have already been passed through rsslDecodeMsg. Only the payload requires
       additional decoding */
    if (pRsslMsg)
        processRsslMsg(pRsslMsg);
    else
        printf("Error: %s(%s)\n", pMsgEvent->pErrorInfo->rsslError.text,
            pMsgEvent->pErrorInfo->errorLocation);
}
```

Code Example 8: Reactor Message Event Callback Example

## 6.6.5 Reactor Callback: RDM Login Message

The `RsslReactor` RDM Login Message callback is used to communicate all received RDM Login messages. This callback function has the following prototype:

```
RsslRDMLoginMsgCallback(RsslReactor*, RsslReactorChannel*, RsslRDMLoginMsgEvent*)
```

When invoked, this will return the `RsslReactor` and the `RsslReactorChannel` on which the event occurred. In addition, an `RsslRDMLoginMsgEvent` structure is returned, containing more information about the event information.

### 6.6.5.1 Reactor RDM Login Message Event

The `RsslRDMLoginMsgEvent` is returned to the application via the `RsslRDMLoginMsgCallback`.

STRUCTURE MEMBER	DESCRIPTION
<code>baseMsgEvent</code>	An <code>RsslMsgEvent</code> populated with the raw buffer ( <code>RsslMsg</code> ) and any error information. This structure is defined in Section 6.6.4.1.

Table 40: `RsslRDMLoginMsgEvent` Structure Members

STRUCTURE MEMBER	DESCRIPTION
pRDMLoginMsg	The RDM representation of the decoded Login message. If not present, an error was encountered while processing the information. This message is presented as the <b>RsslRDMLoginMsg</b> , described in Section 8.3.

Table 40: **RsslRDMLoginMsgEvent** Structure Members (Continued)

### 6.6.5.2 Reactor RDM Login Message Event Utility Function

FUNCTION NAME	DESCRIPTION
rsslClearRDMLoginMsgEvent	Clears an <b>RsslRDMLoginMsgEvent</b> structure.

Table 41: **RsslRDMLoginMsgEvent** Utility Function

### 6.6.5.3 Reactor RDM Login Message Event Callback Example

```

RsslReactorCallbackRet loginMsgCallback(RsslReactor *pReactor, RsslReactorChannel *pReactorChannel,
    RsslRDMLoginMsgEvent *pLoginMsgEvent)
{
    RsslRDMLoginMsg *pLoginMsg = pLoginMsgEvent->pRDMLoginMsg;

    /* Received an RsslRDMLoginMsg --- or, if the decode failed, an error. */
    /* The login message will already be fully decoded */
    if (pLoginMsg)
    {
        switch(pLoginMsg->rdmMsgBase.rdmMsgType)
        {
            case RDM_LG_MT_REFRESH:
                RsslRDMLoginRefresh *pRefresh = &pLoginMsg->refresh;
                break;
            case RDM_LG_MT_STATUS:
                RsslRDMLoginStatus *pStatus = &pLoginMsg->status;
                break;
            default:
                printf("Received unhandled login message.\n"); break;
        }
    }
    else
        printf("Error: %s(%s)\n", pLoginMsgEvent->baseMsgEvent.pErrorInfo->rsslError.text,
            pLoginMsgEvent->baseMsgEvent.pErrorInfo->errorLocation);
}

```

Code Example 9: Reactor RDM Login Message Event Callback Example

## 6.6.6 Reactor Callback: RDM Directory Message

The **RsslReactor** RDM Directory Message callback is used to communicate all received RDM Directory messages. This callback function has the following prototype:

```
RsslRDMDirectoryMsgCallback(RsslReactor*, RsslReactorChannel*, RsslRDMDirectoryMsgEvent*)
```

When invoked, this will return the **RsslReactor** and the **RsslReactorChannel** on which the event occurred. In addition, an **RsslRDMDirectoryMsgEvent** structure is returned, containing more information about the event information.

### 6.6.6.1 Reactor RDM Directory Message Event

The **RsslRDMDirectoryMsgEvent** is returned to the application via the **RsslRDMDirectoryMsgCallback**.

STRUCTURE MEMBER	DESCRIPTION
baseMsgEvent	An <b>RsslMsgEvent</b> populated with the raw buffer ( <b>RsslMsg</b> ) and any error information. This structure is defined in Section 6.6.4.1.
pRDMDirectoryMsg	The RDM representation of the decoded Source Directory message. If not present, an error was encountered while processing the information. This message is presented as the <b>RsslRDMDirectoryMsg</b> , described in Section 8.4.

Table 42: **RsslRDMDirectoryMsgEvent** Structure Members

### 6.6.6.2 Reactor RDM Directory Message Event Utility Function

FUNCTION NAME	DESCRIPTION
rsslClearRDMDirectoryMsgEvent	Clears an <b>RsslRDMDirectoryMsgEvent</b> structure.

Table 43: **RsslRDMDirectoryMsgEvent** Utility Function

### 6.6.6.3 Reactor RDM Directory Message Event Callback Example

```
RsslReactorCallbackRet directoryMsgCallback(RsslReactor *pReactor, RsslReactorChannel
    *pReactorChannel, RsslRDMDirectoryMsgEvent *pDirectoryMsgEvent)
{
    RsslRDMDirectoryMsg *pDirectoryMsg = pDirectoryMsgEvent->pRDMDirectoryMsg;

    /* Received an RsslRDMDirectoryMsg --- or, if the decode failed, an error. */
    /* The directory message will already be fully decoded */
    if (pDirectoryMsg)
    {
        switch(pDirectoryMsg->rdmMsgBase.rdmMsgType)
        {
            case RDM_DR_MT_REFRESH:
                RsslRDMDirectoryRefresh *pRefresh = &pDirectoryMsg->refresh;
                break;
            case RDM_DR_MT_UPDATE:
```

```

        RsslRDMDirectoryUpdate *pUpdate = &pDirectoryMsg->update;
        break;
    case RDM_DR_MT_STATUS:
        RsslRDMDirectoryStatus *pStatus = &pDirectoryMsg->status;
        break;
    default:
        printf("Received unhandled directory message.\n");
    }
}
else
    printf("Error: %s(%s)\n", pDirectoryMsgEvent->baseMsgEvent.pErrorInfo->rsslError.text,
        pDirectoryMsgEvent->baseMsgEvent.pErrorInfo->errorLocation);
}

```

Code Example 10: Reactor RDM Directory Message Event Callback Example

## 6.6.7 Reactor Callback: RDM Dictionary Message

The **RsslReactor** RDM Dictionary Message callback is used to communicate all received RDM Dictionary messages. This callback function has the following prototype:

```
RsslRDMDictionaryMsgCallback(RsslReactor*, RsslReactorChannel*, RsslRDMDictionaryMsgEvent*)
```

When invoked, this will return the **RsslReactor** and the **RsslReactorChannel** on which the event occurred. In addition, an **RsslRDMDictionaryMsgEvent** structure is returned, containing more information about the event information.

### 6.6.7.1 Reactor RDM Dictionary Message Event

The **RsslRDMDictionaryMsgEvent** is returned to the application via the **RsslRDMDictionaryMsgCallback**.

STRUCTURE MEMBER	DESCRIPTION
baseMsgEvent	An <b>RsslMsgEvent</b> populated with the raw buffer ( <b>RsslMsg</b> ) and any error information. This structure is defined in Section 6.6.4.1.
pRDMDictionaryMsg	The RDM representation of the decoded Dictionary message. If not present, an error was encountered while processing the information. This message is presented as the <b>RsslRDMDictionaryMsg</b> , described in Section 8.5.

Table 44: **RsslRDMDictionaryMsgEvent** Structure Members

### 6.6.7.2 Reactor RDM Dictionary Message Event Utility Function

FUNCTION NAME	DESCRIPTION
rsslClearRDMDictionaryMsgEvent	Clears an <b>RsslRDMDictionaryMsgEvent</b> structure.

Table 45: **RsslRDMDictionaryMsgEvent** Utility Function



### 6.6.7.3 Reactor RDM Dictionary Message Event Callback Example

```
RsslReactorCallbackRet dictionaryMsgCallback(RsslReactor *pReactor, RsslReactorChannel
    *pReactorChannel, RsslRDMDictionaryMsgEvent *pDictionaryMsgEvent)
{
    RsslRDMDictionaryMsg *pDictionaryMsg = pDictionaryMsgEvent->pRDMDictionaryMsg;

    /* Received an RsslRDMDictionaryMsg --- or, if the decode failed, an error. */
    if (pDictionaryMsg)
    {
        switch(pDictionaryMsg->rdmMsgBase.rdmMsgType)
        {
            case RDM_DC_MT_REFRESH:
                RsslRDMDictionaryRefresh *pRefresh = &pDictionaryMsg->refresh;
                break;
            case RDM_DC_MT_STATUS:
                RsslRDMDictionaryStatus *pStatus = &pDictionaryMsg->status;
                break;
            default:
                printf("Received unhandled dictionary message.\n");
        }
    }
    else
        printf("Error: %s(%s)\n", pDictionaryMsgEvent->baseMsgEvent.pErrorInfo->rsslError.text,
            pDictionaryMsgEvent->baseMsgEvent.pErrorInfo->errorLocation);
}
```

Code Example 11: Reactor RDM Dictionary Message Event Callback Example

## 6.7 Writing Data

The Transport API Reactor helps streamline the high performance writing of content. The **RsslReactor** flushes content to the network so the application does not need to. The **RsslReactor** does so through the use of a separate worker thread that becomes active whenever there is queued content that needs to be passed to the connection.

The Transport API Reactor offers two methods for writing content: **rsslReactorSubmitMsg** and **rsslReactorSubmit**. When writing applications to the Reactor, consider which is most appropriate for your needs:

#### **rsslReactorSubmitMsg**

- Takes an **RsslMsg** structure as part of its options; does not require retrieval of an **RsslBuffer** from the channel.
- Must be used when the consumer watchlist is enabled.

#### **rsslReactorSubmit**

- Takes an **RsslBuffer** which the application retrieves from the channel.
- More efficient: the application encodes directly into the buffer, and can use buffer packing.
- Cannot be used when the consumer watchlist is enabled.

## 6.7.1 Writing Data using `rsslReactorSubmitMsg()`

`rsslReactorSubmitMsg` provides a simple interface for writing `RsslMsg`s. To send a message, the application populates an `RsslMsg` structure, sets it (along with any other desired options) on an `RsslReactorSubmitMsgOptions` structure, and calls `rsslReactorSubmitMsg` with the structure.

A buffer is not needed to use `rsslReactorSubmitMsg`. If the application needs to include any encoded content, it can encode the content into any available memory, and set the appropriate member of the `RsslMsg` to point to the memory (as well as set the length of the encoded content).

### 6.7.1.1 `rsslReactorSubmitMsg` Function

FUNCTION NAME	DESCRIPTION
<code>rsslReactorSubmitMsg</code>	Encodes and submits an <code>RsslMsg</code> to the Reactor. This function expects a properly populated <code>RsslMsg</code> .  This function allows for several modifications and additional parameters to be specified via the <code>RsslReactorSubmitMsgOptions</code> structure.

Table 46: `rsslReactorSubmitMsg` Function

### 6.7.1.2 Reactor Submit Message Options

An application can use `RsslReactorSubmitMsgOptions` to control various aspects of the call to `rsslReactorSubmitMsg`.

STRUCTURE MEMBER	DESCRIPTION
<code>majorVersion</code>	The RWF major version of any encoded content in the message.
<code>minorVersion</code>	The RWF minor version of any encoded content in the message.
<code>pRsslMsg</code>	The <code>RsslMsg</code> structure to submit. Use only one instance of either <code>pRsslMsg</code> or <code>pRDMMMsg</code> .
<code>pRDMMMsg</code>	The <code>RsslRDMMMsg</code> structure to submit. Use only one instance of either <code>pRsslMsg</code> or <code>pRDMMMsg</code> .
<code>pServiceName</code>	The application can use this instead of the <code>serviceId</code> member specified on the <code>RsslMsgKey</code> of an <code>RsslMsg</code> .  When used to open streams via request messages, the <code>RsslReactor</code> will recover using this service name.  When used for other message types such as <code>RsslPostMsg</code> or <code>RsslGenericMsg</code> , the <code>RsslReactor</code> converts the name to its corresponding ID before writing the message.  <b>Note:</b> This option is supported only when the consumer watchlist is enabled.
<code>requestMsgOptions</code>	Provides additional functionality that may be used when using <code>RsslRequestMsgs</code> to send requests.

Table 47: `RsslReactorSubmitMsgOptions` Structure Members

### 6.7.1.3 `RsslReactorRequestMsgOptions`

`RsslReactorRequestMsgOptions` provide additional functionality when requesting items. These options are available only when the watchlist is enabled.

STRUCTURE MEMBER	DESCRIPTION
pUserSpec	A user-specified pointer that will be associated with the stream. This pointer will be provided in responses to this stream via the <code>RsslStreamInfo</code> provided with each message event.

Table 48: `RsslReactorRequestMsgOptions` Structure Members

#### 6.7.1.4 RsslReactorSubmitMsgOptions Utility Function

The Transport API provides the following utility function for use with `RsslReactorSubmitMsgOptions`.

FUNCTION NAME	DESCRIPTION
<code>rsslClearReactorSubmitMsgOptions</code>	Clears the <code>RsslReactorSubmitMsgOptions</code> structure. Useful for structure reuse.

Table 49: `RsslReactorSubmitMsgOptions` Utility Function

#### 6.7.1.5 rsslReactorSubmitMsg Return Codes

The following table defines the return codes that can occur when using `rsslReactorSubmitMsg`.

RETURN CODE	DESCRIPTION
<code>RSSL_RET_SUCCESS</code>	Indicates that the <code>rsslReactorSubmitMsg</code> function has succeeded.
<code>RSSL_RET_BUFFER_NO_BUFFERS</code>	Indicates that not enough pool buffers are available to write the message. The application can try to submit the message later, or it can use <code>rsslReactorChannelIoctl</code> to increase the number of available pool buffers and try again.
<code>RSSL_RET_FAILURE</code>	Indicates that a general failure has occurred and the message was not submitted. The <code>RsslErrorInfo</code> structure passed to the function will contain more details.

Table 50: `rsslReactorSubmitMsg` Return Codes

#### 6.7.1.6 rsslReactorSubmitMsg Example

The following example shows typical use of `rsslReactorSubmitMsg`.

```
RsslMsg requestMsg;
RsslReactorSubmitMsgOptions opts;
RsslErrorInfo errorInfo;
RsslRet ret;

rsslClearRequestMsg(&requestMsg);
requestMsg.msgBase.streamId = 2;
requestMsg.msgBase.domainType = RSSL_DMT_MARKET_PRICE;
requestMsg.msgBase.containerType = RSSL_DT_NO_DATA;
requestMsg.flags = RSSL_RQMF_STREAMING | RSSL_RQMF_HAS_QOS;
requestMsg.qos.timeliness = RSSL_QOS_TIME_REALTIME;
requestMsg.qos.rate = RSSL_QOS_RATE_TICK_BY_TICK;
```

```

requestMsg.msgBase.msgKey.flags = RSSL_MKF_HAS_NAME | RSSL_MKF_HAS_SERVICE_ID;
requestMsg.msgBase.msgKey.name.data = "TRI.N";
requestMsg.msgBase.msgKey.name.length = 5;
requestMsg.msgBase.msgKey.serviceId = 1;


rsslClearReactorSubmitMsgOptions(&opts);
opts.pRsslMsg = (RsslMsg*)&requestMsg;
ret = rsslReactorSubmitMsg(pReactor, pReactorChannel, &opts, &errorInfo);

```

### Code Example 12: `rsslReactorSubmitMsg` Example

#### 6.7.2 Writing data using `rsslReactorSubmit()`

The `rsslReactorSubmit` function offers efficient writing of data by using buffers retrieved directly from the Transport API transport buffer pool. It also provides additional features not normally available from `rsslReactorSubmitMsg`, such as buffer packing or the Transport API priority queue. When ready to send data, the application acquires a buffer from the Transport API pool. This allows the content to be encoded directly into the output buffer, reducing the number of times the content needs to be copied. Once content is encoded and the buffer is properly populated, the application can submit the data to the reactor. The Transport API will ensure that successfully submitted buffers reach the network. Applications can also pack multiple messages into a single buffer by following a similar process as described above, however instead of getting a new buffer for each message the application uses the reactor's pack function instead. The following flow chart depicts the typical write process.

Figure 8. Flow Chart for writing data via `rsslReactorSubmit`

### 6.7.2.1 Obtaining a Buffer: Overview

Before you can submit information, you must obtain a buffer from the internal Transport API buffer pool, as described in the *Transport API C Edition Developers Guide*. After acquiring the buffer, you can populate the `RsslBuffer.data` and set the `RsslBuffer.length` to the number of bytes referred to by `data`. If the buffer is not used or the `rsslReactorSubmit` function call fails, the buffer must be released back into the pool to ensure proper reuse and cleanup. If the buffer is successfully passed to `rsslReactorSubmit`, the reactor will return the buffer to the pool.

The number of buffers made available to an `RsslReactorChannel` is configurable through the `RsslReactorConnectOptions` or `RsslReactorAcceptOptions`. For more information about available `rsslReactorConnect` and `rsslReactorAccept` options, refer to Section 6.4.1.2 and Section 6.4.1.8.

### 6.7.2.2 Obtaining a Buffer: Buffer Management Functions

FUNCTION NAME	DESCRIPTION
<code>rsslReactorGetBuffer</code>	<p>Obtains a buffer of the requested size from the buffer pool. When the <code>RsslBuffer</code> is returned, the <code>length</code> member indicates the number of bytes available in the buffer (which should match the amount the application requested). When populating, <code>length</code> must be set to the number of bytes actually used. This ensures that only the required bytes are written to the network.</p> <p>If the requested size is larger than the <code>maxFragmentSize</code>, the transport will create and return the buffer to the user. When written, this buffer will be fragmented by the <code>rsslReactorSubmit</code> function (for further details, refer to Section 6.7.2.4).</p> <p>Because of some additional book keeping required when packing, the application must specify whether a buffer should be 'packable' when calling <code>rsslReactorGetBuffer</code>. For more information on packing, refer to Section 6.7.2.8.</p> <p>For performance purposes, an application is not permitted to request a buffer larger than <code>maxFragmentSize</code> and have the buffer be 'packable.'</p> <p>If the buffer is not used or the <code>rsslReactorSubmit</code> call fails, the buffer must be returned to the pool using <code>rsslReactorReleaseBuffer</code>. If the <code>rsslReactorSubmit</code> call is successful, the buffer will be returned to the correct pool by the transport.</p> <p>This function calls the <code>rsslGetBuffer</code> function which has its use and return values described in the <i>Transport API C Edition Developers Guide</i>.</p>
<code>rsslReactorReleaseBuffer</code>	<p>Releases a buffer back to the correct pool. This should only be called with buffers that originate from <code>rsslReactorGetBuffer</code> and are not successfully passed to <code>rsslReactorSubmit</code>.</p> <p>This function calls the Transport API <code>rsslReleaseBuffer</code> function which has its use and return values described in the <i>Transport API C Edition Developers Guide</i>.</p>
<code>rsslReactorChannelBufferUsage</code>	<p>Returns the number of buffers currently in use by the <code>RsslReactorChannel</code>, this includes buffers that the application holds and buffers internally queued and waiting to be flushed to the connection by the <code>RsslReactor</code>.</p> <p>This function calls the <code>rsslBufferUsage</code> function which has its use and return values described in the <i>Transport API C Edition Developers Guide</i>.</p>

**Table 51: Reactor Buffer Management Functions**

### 6.7.2.3 Obtaining a Buffer: `rsslReactorGetBuffer` Return Values

The following table defines return and error code values that can occur while using `rsslReactorGetBuffer`.

RETURN CODE	DESCRIPTION
Valid buffer returned Success Case	An <code>RsslBuffer</code> is returned to the user. The <code>RsslBuffer.length</code> indicates the number of bytes available to populate and the <code>RsslBuffer.data</code> provides a starting location for population.

**Table 52: `rsslReactorGetBuffer` Return Values**

RETURN CODE	DESCRIPTION
NULL buffer returned Error Code: <code>RSSL_RET_BUFFER_NO_BUFFERS</code>	NULL is returned to the user. This value indicates that there are no buffers available to the user. See <code>RsslErrorInfo</code> content for more details.  This typically occurs because all available buffers are queued and pending flushing to the connection. The <code>rsslReactorChannelIoctl</code> function can be used to increase the number of <code>guaranteedOutputBuffers</code> (for details, refer to Section 6.10).
NULL buffer returned Error Code: <code>RSSL_RET_FAILURE</code>	NULL is returned to the user. This value indicates that some type of general failure has occurred. The <code>RsslReactorChannel</code> should be closed.
NULL buffer returned Error Code: <code>RSSL_RET_INIT_NOT_INITIALIZED</code>	Indicates that the underlying RSSL Transport has not been initialized. See the <code>RsslErrorInfo</code> content for more details.

Table 52: `rsslReactorGetBuffer` Return Values (Continued)

#### 6.7.2.4 Writing Data: Overview

After an `RsslBuffer` is obtained from `rsslReactorGetBuffer` and populated with the user's data, the buffer can be passed to the `rsslReactorSubmit` function. This function manages queuing and flushing of user content. It will also perform any fragmentation or compression. If an unrecoverable error occurs, any `RsslBuffer` that has not been successfully passed to `rsslReactorSubmit` should be released to the pool using `rsslReactorReleaseBuffer`. Section 6.7.2.5 describes the `rsslReactorSubmit` function and its associated parameters.

#### 6.7.2.5 Writing Data: `rsslReactorSubmit` Function

**Note:** Before passing a buffer to `rsslReactorSubmit`, it is required that the application set `length` to the number of bytes actually used. This ensures that only the required bytes are written to the network.

FUNCTION NAME	DESCRIPTION
<code>rsslReactorSubmit</code>	Writes data. This function expects the buffer to be properly populated, where <code>length</code> reflects the actual number of bytes used. This function calls the Transport API <code>rsslWrite</code> function and also triggers the <code>rsslFlush</code> function (described in the <i>Transport API C Edition Developers Guide</i> ).  This function allows for several modifications and additional parameters to be specified via the <code>RsslReactorSubmitOptions</code> structure, defined in Section 6.7.2.6. For a list of return codes, refer to Section 6.7.2.7.

Table 53: `rsslReactorSubmit` Function

#### 6.7.2.6 Writing Data: Reactor Submit Options

The application uses `RsslReactorSubmitOptions` to control various aspects of the call to `rsslReactorSubmit`.

STRUCTURE MEMBER	DESCRIPTION
Priority	Controls the priority at which the data will be written. Valid priorities are <ul style="list-style-type: none"> <li><b>RSSL_HIGH_PRIORITY</b></li> <li><b>RSSL_MEDIUM_PRIORITY</b></li> <li><b>RSSL_LOW_PRIORITY</b></li> </ul> More information about write priorities, including an example scenario, are available in the <i>Transport API C Edition Developers Guide</i> .
writeFlags	Flag values that allow the application to modify the behavior of this <b>rsslReactorSubmit</b> call. This includes options to bypass queuing or compression. <p>More information about the specific flag values are available in the <i>Transport API C Edition Developers Guide</i>.</p>
pBytesWritten	If specified, will return the number of bytes to be written, including any transport header overhead and taking into account any savings from compression.
pUncompressedBytesWritten	If specified, will return the number of bytes to be written, including any transport header overhead but not taking into account any compression savings.

Table 54: **rsslReactorSubmitOptions** Structure Members

#### 6.7.2.7 Writing Data: rsslReactorSubmit Return Codes

The following table defines the return codes that can occur when using **rsslReactorSubmit**.

RETURN CODE	DESCRIPTION
RSSL_RET_SUCCESS	Indicates that the <b>rsslReactorSubmit</b> function has succeeded. The <b>RsslBuffer</b> will be released by the Transport API Reactor.
RSSL_RET_WRITE_CALL_AGAIN	Indicates that a large buffer could not be fully written with this <b>rsslReactorSubmit</b> call. This is typically due to all pool buffers being unavailable. The <b>RsslReactor</b> will flush for the user to free up buffers. The application can optionally use <b>rsslReactorChannelIoctl</b> to increase the number of available pool buffers. After pool buffers become available again, the same buffer should be used to call <b>rsslReactorSubmit</b> an additional time (using the same priority level for proper ordering of each fragment). This will continue the fragmentation process from where it left off. <p>If the application does not subsequently pass the buffer to <b>rsslReactorSubmit</b>, the application should release it by calling <b>rsslReactorReleaseBuffer</b>.</p>
RSSL_RET_FAILURE	Indicates that a general write failure has occurred. The <b>RsslReactorChannel</b> should be closed. <p>The application should release the <b>RsslBuffer</b> by calling <b>rsslReactorReleaseBuffer</b>.</p>

Table 55: **rsslReactorSubmit** Return Codes

#### 6.7.2.8 Writing Data: RsslReactorSubmitOptions Utility Function

The Transport API provides the following utility function for use with the **RsslReactorDispatchOptions**.



FUNCTION NAME	DESCRIPTION
<code>rsslClearReactorSubmitOptions</code>	Clears the <code>RsslReactorSubmitOptions</code> structure. Useful for structure reuse.

Table 56: `RsslReactorSubmitOptions` Utility Function

### 6.7.2.9 Example: `rsslReactorGetBuffer` and `rsslReactorSubmit` Example

The following example shows typical use of `rsslReactorGetBuffer` and `rsslReactorSubmit`.

```

RsslBuffer *pMsgBuffer;
RsslEncodeIterator encodeIter;
RsslReactorSubmitOptions submitOpts;

pMsgBuffer = rsslReactorGetBuffer(pReactorChannel, 1024, RSSL_FALSE, &rsslErrorInfo);

rsslClearEncodeIterator(&encodeIter);
rsslSetEncodeIteratorRWFVersion(&encodeIter, pReactorChannel->majorVersion, pReactorChannel-
    >minorVersion);
rsslSetEncodeIteratorBuffer(&encodeIter, pMsgBuffer);
encodeMsgIntoBuffer(&encodeIter, pMsgBuffer);

pMsgBuffer->length = rsslGetEncodedBufferLength(&encodeIter);
rsslClearReactorSubmitOptions(&submitOpts);
ret = rsslReactorSubmit(pReactor, pReactorChannel, pMsgBuffer, &submitOpts, &rsslErrorInfo);
/* check return code */
switch (ret)
{
    case RSSL_RET_SUCCESS:
        /* successful write, nothing left to do */
        return 0;
    break;
    case RSSL_RET_FAILURE:
        /* an error occurred, need to release buffer */
        rsslReactorReleaseBuffer(pReactorChannel, pMsgBuffer, &rsslErrorInfo);
    break;
    case RSSL_RET_WRITE_CALL_AGAIN:
        /* large message couldn't be fully written with one call, pass it to submit again */
        ret = rsslReactorSubmit(pReactor, pReactorChannel, pMsgBuffer, &rsslErrorInfo);
    break;
}

```

**Code Example 13: Writing Data Using `rsslReactorSubmit`, `rsslReactorGetBuffer`, and `rsslReactorReleaseBuffer`**

### 6.7.2.10 Packing Additional Data into a Buffer

If an application is writing many small buffers, it may be advantageous to combine the small buffers into one larger buffer. This can increase efficiency of the transport layer by reducing the overhead associated with each write operation, although it may add to the latency associated with each smaller buffer.

It is up to the writing application to determine when to stop packing, and the mechanism used can vary greatly. A simple algorithm can pack a fixed number of messages each time. A slightly more complex technique could use the returned `RsslBuffer.length` to determine the amount of space remaining and pack until the buffer is nearly full. Both of these mechanisms can introduce a variable amount of latency as they both depend on the rate of arrival of data (e.g., the packed buffer will not be written until enough data arrives to fill it). One way of balancing this is to employ a timer, used to limit the amount of time a packed buffer is held. If the buffer is full prior to the timer expiring, the data is written. However, when the timer expires the buffer will be written regardless of the amount of data it contains. This can help limit latency by specifying a limit to the time data is held (via use of the timer).

FUNCTION NAME	DESCRIPTION
<code>rsslReactorPackBuffer</code>	<p>Packs the contents of a passed-in <code>RsslBuffer</code> and returns a new <code>RsslBuffer</code> to continue packing new data into. For a buffer to allow packing, it must be requested from <code>rsslReactorGetBuffer</code> as 'packable' and cannot exceed the <code>maxFragmentSize</code>. The returned buffer provides a <code>data</code> pointer for populating and the <code>length</code> conveys number of bytes available in the buffer.</p> <p>An application can use the <code>RsslBuffer.length</code> to determine the amount of space available to continue packing buffers into. After each buffer is populated, the length should be set to reflect the actual number of bytes contained in the buffer. This will ensure that only the necessary space is reserved while packing.</p> <p><code>rsslReactorPackBuffer</code> return values are defined in Section 6.7.2.11.</p> <p>This function calls the <code>rsslPackBuffer</code> function as described in the <i>Transport API C Edition Developers Guide</i>.</p>

**Table 57: `rsslReactorPackBuffer` Function**

### 6.7.2.11 rsslReactorPackBuffer Return Values

The following table defines return and error code values that can occur when using `rsslReactorPackBuffer`.

RETURN CODE	DESCRIPTION
Valid buffer returned Success Case	An <code>RsslBuffer</code> is returned to the user. The <code>RsslBuffer.length</code> indicates the number of bytes available to populate and the <code>RsslBuffer.data</code> provides a starting location for population.
NULL buffer returned Error Code: <code>RSSL_RET_FAILURE</code>	NULL is returned to the user. This value indicates that some type of general failure has occurred. The <code>RsslReactorChannel</code> should be closed.
NULL buffer returned Error Code: <code>RSSL_RET_INIT_NOT_INITIALIZED</code>	Indicates that the underlying RSSL Transport has not been initialized. See the <code>RsslErrorInfo</code> content for more details.

Table 58: `rsslReactorPackBuffer` Return Values

### 6.7.2.12 Example: `rsslReactorGetBuffer`, `rsslReactorPackBuffer`, and `rsslReactorSubmit`

The following example shows typical use of `rsslReactorGetBuffer`, `rsslReactorPackBuffer`, and `rsslReactorSubmit`.

```
RsslBuffer *pMsgBuffer;
RsslReactorSubmitOptions submitOpts;
RsslEncodeIterator encodeIter;

/* get a packable buffer */
pMsgBuffer = rsslReactorGetBuffer(pReactorChannel, 1024, RSSL_TRUE, &rsslErrorInfo);

rsslClearEncodeIterator(&encodeIter);
rsslSetEncodeIteratorRWFVersion(&encodeIter, pReactorChannel->majorVersion, pReactorChannel-
    >minorVersion);
rsslSetEncodeIteratorBuffer(&encodeIter, pMsgBuffer);
encodeMsgIntoBuffer(&encodeIter, pMsgBuffer);

/* pack first encoded message into buffer */
pMsgBuffer->length = rsslGetEncodedBufferLength(&encodeIter);
pMsgBuffer = rsslReactorPackBuffer(pReactorChannel, pMsgBuffer, &rsslErrorInfo);

rsslClearEncodeIterator(&encodeIter);
rsslSetEncodeIteratorRWFVersion(&encodeIter, pReactorChannel->majorVersion, pReactorChannel-
    >minorVersion);
rsslSetEncodeIteratorBuffer(&encodeIter, pMsgBuffer);
encodeMsgIntoBuffer(&encodeIter, pMsgBuffer);

/* pack second encoded message into buffer */
pMsgBuffer->length = rsslGetEncodedBufferLength(&encodeIter);
pMsgBuffer = rsslReactorPackBuffer(pReactorChannel, pMsgBuffer, &rsslErrorInfo);

rsslClearEncodeIterator(&encodeIter);
rsslSetEncodeIteratorRWFVersion(&encodeIter, pReactorChannel->majorVersion, pReactorChannel-
```

```

        >minorVersion);
rsslSetEncodeIteratorBuffer(&encodeIter, pMsgBuffer);

/* now write packed buffer by passing third buffer to rsslSubmit */
encodeMsgIntoBuffer(&encodeIter, pMsgBuffer);
pMsgBuffer->length = rsslGetEncodedBufferLength(&encodeIter);

rsslClearReactorSubmitOptions(&submitOpts);
ret = rsslReactorSubmit(pReactor, pReactorChannel, pMsgBuffer, &submitOpts, &rsslErrorInfo);

```

**Code Example 14: Message Packing using `rsslReactorPackBuffer`**

## 6.8 Creating and Using Tunnel Streams

The Reactor allows users to create and use special tunnel streams. A tunnel stream is a private stream with additional behaviors, such as end-to-end line of sight for authentication and guaranteed delivery. Tunnel streams are founded on the private streams concept, and the Transport API establishes them between consumer and provider endpoints (passing through any intermediate components, such as TREP or EED).

When creating a tunnel, the consumer indicates any additional behaviors to enforce, which is exchanged with the provider application end point. The provider end-point acknowledges creation of the stream as well as the behaviors that it will enforce on the stream. After the stream is established, the consumer can exchange any content it wants, though the tunnel stream will enforce behaviors on the transmitted content as negotiated with the provider.

A tunnel stream allows for multiple substreams to exist, where substreams follow from the same general stream concept, except that they flow and coexist within the confines of a tunnel stream.

In the following diagram, the orange cylinder represents a tunnel stream that connects the consumer application to the provider application. Notice that the tunnel stream passes directly through intermediate components: the tunnel stream has end-to-end line of sight so that the provider and consumer effectively talk to one another directly, though they traverse multiple devices in the system. Each black line flowing through the cylinder represents a different substream, where each substream transmits its own independent stream of information. Each substream could communicate different market content; for example one could be a Time Series request while another could be a request for Market Price content. A substream can also connect to a special provider application called a Queue Provider. A Queue Provider allows for persistence of content exchanged over the tunnel stream and substream, and helps provide content beyond the end-point visible to the consumer. To interact with a Queue Provider, additional addressing information is required, described in more detail in Section 8.6.




Figure 9. Tunnel Stream Illustration

### 6.8.1 Authenticating a Tunnel Stream

Providers might require the consumer to authenticate itself when establishing the tunnel stream. The type of authentication, if any, is given by the `RsslClassOfService.authentication.type`. For more information on class or service, refer to Section 6.8.3.

The `RsslClassOfService.authentication.type` may be set to `RDM_COS_AU_OMM_LOGIN`. When an OMM consumer expects this type of authentication, it should set an `RsslRDMLoginRequest` message on the `RsslTunnelStreamOpenOptions.pAuthLoginRequest` member. If the OMM consumer application does not provide it, the API will use the login request provided on the `RsslReactorOMMConsumerRole.pLoginRequest` when the consumer connected (refer to Section 6.3.2). The consumer must provide one of these for authentication of this type.

The login request will be sent to the provider. When the provider sends a Login response to complete the authentication, the `RsslTunnelStreamStatusEvent` event given to the consumer will include an `RsslTunnelStreamAuthInfo` structure with more details. OMM provider applications will see the login request as a normal message within the `RsslTunnelStream` and should respond with a login response message via `rsslTunnelStreamSubmit` or `rsslTunnelStreamSubmitMsg`.

Other types of authentication might be specified, but must be performed by both the provider and consumer applications by submitting normal `RsslTunnelStream` messages via `rsslTunnelStreamSubmit` or `rsslTunnelStreamSubmitMsg`.

The `RsslTunnelStreamAuthInfo` structure contains the following member:

MEMBER	DESCRIPTION
pLoginMsg	The Login message sent by the tunnel stream's provider application, which resulted in this event.

Table 59: `RsslTunnelStreamAuthInfo` Structure Members

## 6.8.2 Opening a Tunnel Stream

The user can create one or more tunnel streams and associate them with any `RsslReactorChannel`, which opens the private stream connection and negotiates any specified behaviors. Prior to opening a tunnel stream, you must implement the `RsslTunnelStreamStatusEventCallback`, which is described in Section 6.8.4.

### 6.8.2.1 rsslReactorOpenTunnelStream Method

METHOD NAME	DESCRIPTION
rsslReactorOpenTunnelStream	Begins the establishment of a tunnel stream. The <code>RsslTunnelStream</code> is returned via the <code>RsslTunnelStreamStatusEventCallback</code> as specified on the <code>RsslTunnelStreamOpenOptions</code> . For more details, refer to Section 6.8.2.2.

Table 60: `rsslReactorOpenTunnelStream` Method

### 6.8.2.2 RsslTunnelStreamOpenOptions

The `RsslTunnelStreamOpenOptions` contain event handler associations and options for use in creating a tunnel stream.

CLASS MEMBER	DESCRIPTION
domainType	Indicates the domain for which the tunnel stream is established. Set this to the domain specified on the service on which the Transport API opens the tunnel stream.
streamId	Indicates the stream ID to use for the tunnel stream. Though substreams will flow within this stream ID, each will have their own independent stream ID. For example, a tunnel stream can have an ID of 10. If a substream is opened to retrieve TRI data, the substream can have a stream ID of 5, though it is encapsulated in the tunnel stream whose stream ID is 10.
serviceId	Indicates the service ID of the service on which you open the tunnel stream.
userSpecPtr	Indicates a user-specified object passed in via these options and then associated with the <code>RsslTunnelStream</code> .
statusEventCallback	Specifies an instance of the callback for <code>RsslTunnelStreamStatusEvents</code> , which provides the <code>RsslTunnelStream</code> on initial connection, and after the tunnel stream is established, communicates the tunnel stream's state information. For further details, refer to Section 6.8.4.
queueMsgCallback	Specifies the instance of the callback used to handle Queue Messages received on this <code>RsslTunnelStream</code> . <ul style="list-style-type: none"> <li>For details on the <code>RsslTunnelStreamMsgCallback</code>, refer to Section 6.8.4.</li> <li>For details on various Queue Messages, refer to Section 8.6.</li> </ul>

Table 61: `RsslTunnelStreamOpenOptions`

CLASS MEMBER	DESCRIPTION
defaultMsgCallback	Specifies the instance of the callback that handles all other content received on this <code>RsslTunnelStream</code> . For further details, refer to Section 6.8.4.
name	Specifies the tunnel stream name, which is provided to the remote application. <code>name</code> cannot be longer than 255 characters.
responseTimeout	Sets the duration (in seconds) to wait for a provider to respond to a tunnel stream open request. If the provider does not respond in time, an <code>RsslTunnelStreamStatusEvent</code> is sent to the application to indicate that the tunnel stream was not opened.
guaranteedOutputBuffers	Sets the number of guaranteed output buffers available for the tunnel stream.
pAuthLoginRequest	Specifies the <code>RsslRDMLLoginRequest</code> to send if <code>RsslClassOfService.authentication.type</code> is set to <code>RDM_COS_AU_OMM_LOGIN</code> . If absent, the API uses the login request provided on the <code>RsslReactorOMMConsumerRole.pLoginRequest</code> .
classOfService	The class of service of the tunnel stream to be opened. For further details on <code>RsslClassOfService</code> , refer to Section 6.8.3.

Table 61: `RsslTunnelStreamOpenOptions` (Continued)

### 6.8.3 Negotiating Stream Behaviors: Class of Service

`RsslClassOfService` is used to negotiate `RsslTunnelStream` behaviors. Negotiated behaviors are divided into five categories: common, authentication, flow control, data integrity, and guarantee.

- When an OMM consumer application calls `rsslReactorOpenTunnelStream`, it sets the `RsslTunnelStreamOpenOptions.classOfService` members to manage and control tunnel stream behaviors. The consumer passes these settings to the connected OMM provider.
- When the OMM provider application receives an `RsslTunnelStreamRequestEvent`, the provider calls `rsslTunnelStreamRequestGetCos` to retrieve the behaviors requested by the consumer.

After tunnel stream negotiation is complete, the provider and consumer each receive an `RsslTunnelStreamStatusEvent` where each can view the negotiated behaviors on the `RsslTunnelStream` structure.

**Note:** Do not modify the `RsslClassOfService` member of the `RsslTunnelStream`.

The enumerations given for members described in this section can be found in `rsslRDM.h`.

#### 6.8.3.1 ClassOfService Common Member

Common elements describe options related to the exchange of messages, such as the maximum message size and desired exchange protocol.

MEMBER	DEFAULT	RANGE/ ENUMERATIONS	DESCRIPTION
maxFragmentSize	6144	1 – 2,147,483,647	The maximum size of message fragments exchanged on the tunnel stream. This value is set only by providers when accepting a tunnel stream.
maxMsgSize	614400	1 – 2,147,483,647	The maximum size of messages exchanged on the tunnel stream. This value is set only by providers when accepting a tunnel stream.
protocolMajorVersion	RSSL_RWF_MAJOR_VERSION	0 – 255	The major version of the protocol specified by <code>protocolType</code> .
protocolMinorVersion	RSSL_RWF_MINOR_VERSION	0 – 255	The minor version of the protocol specified by <code>protocolType</code> .
protocolType	RSSL_RWF_PROTOCOL_TYPE	0 – 255	Identifies the protocol of the messages exchanged on the tunnel stream.

Table 62: `RsslClassOfService.common` Structure Members

### 6.8.3.2 ClassOfService Authentication Member

The authentication member contains options to authenticate a consumer to the corresponding provider.

MEMBER	DEFAULT	RANGE/ ENUMERATIONS	DESCRIPTION
type	RDM_COS_AU_NOT_REQUIRED	RDM_COS_AU_NOT_REQUIRED == 0, RDM_COS_AU_OMM_LOGIN == 1	Indicates the type of authentication, if any, to perform on the tunnel stream. For further details on authentication, refer to Section 6.8.1.

Table 63: `RsslClassOfService.authentication` Structure Members

### 6.8.3.3 ClassOfService Flow Control Members

The flow control member contains options related to flow control, such as the type and the allowed window of outstanding data.

MEMBER	DEFAULT	RANGE/ ENUMERATIONS	DESCRIPTION
type	RDM_COS_FC_NONE	RDM_COS_FC_NONE == 0, RDM_COS_FC_BIDIRECTIONAL == 1	Indicates the type of flow control (if any) to apply to the tunnel stream.

Table 64: `RsslClassOfService.flowControl` Structure Members



MEMBER	DEFAULT	RANGE/ ENUMERATIONS	DESCRIPTION
recvWindowSize	-1	0 – 2,147,483,647	<p>Sets the amount of data (in bytes) that the remote peer can send to the application over a reliable tunnel stream.</p> <p>If <b>type</b> is set to <b>RDM_COS_FC_NONE</b>, this parameter has no effect.</p> <p>-1 indicates that the application wants to use the default value for the negotiated flow control type. In this case, if <b>type</b> is set to <b>RDM_COS_FC_BIDIRECTIONAL</b>, the default is <b>12288</b>.</p>
sendWindowSize	None	0 – 2,147,483,647	<p>Indicates the amount of data (in bytes) the application can send to the remote peer on a reliable tunnel stream.</p> <p>This value is provided on the <b>RsslTunnelStream</b> object and does not need to be set when opening or accepting a tunnel stream.</p> <p>This value is retrieved from the remote end and is informational, as flow control is performed by the API. When room is available in the window, the API transmits more content as submitted by the application.</p> <p>If <b>type</b> is set to <b>RDM_COS_FC_NONE</b>, this parameter has no effect.</p>

Table 64: **RsslClassOfService.flowControl** Structure Members (Continued)

#### 6.8.3.4 ClassOfService Data Integrity Member

The data integrity member contains options related to the reliability of content exchanged over the tunnel stream.

MEMBER	DEFAULT	RANGE	DESCRIPTION
type	RDM_COS_DI_BEST_EFFORT	RDM_COS_DI_BEST_EFFORT == 0, RDM_COS_DI_RELIABLE == 1	<p>Sets the level of reliability for message transmission on the tunnel stream. If set to <b>RDM_COS_DI_RELIABLE</b>, data is retransmitted as needed over the tunnel stream to ensure that all messages are delivered in the correct order.</p> <p><b>Note:</b> At this time, <b>RDM_COS_DI_RELIABLE</b> is the only supported option.</p>

Table 65: `RsslClassOfService.dataIntegrity` Structure Members

### 6.8.3.5 ClassOfService Guarantee Members

The guarantee member contains options related to the guarantee of content submitted over the tunnel stream.

OMM Consumer applications performing Queue Messaging to a Queue Provider should set the `ClassOfService.guarantee.type` to **RDM\_COS\_GU\_PERSISTENT\_QUEUE**.

MEMBER	DEFAULT	RANGE	DESCRIPTION
type	RDM_COS_GU_NONE	RDM_COS_GU_NONE == 0, RDM_COS_GU_PERSISTENT_QUEUE == 1	<p>Indicates the level of guarantee that will be performed on this stream.</p> <p><b>RDM_COS_GU_PERSISTENT_QUEUE</b> is not supported for provider applications.</p> <p><b>Note:</b> If <code>type</code> is set to <b>RDM_COS_GU_PERSISTENT_QUEUE</b> for a consumer application, the data integrity <code>type</code> must also be set to <b>RDM_COS_DI_RELIABLE</b> and the flow control <code>type</code> to <b>RDM_COS_FC_BIDIRECTIONAL</b>.</p>
persistLocally	RSSL_TRUE	RSSL_FALSE, RSSL_TRUE	<p>Indicates whether messages are persisted locally on the tunnel stream.</p> <p>When <code>type</code> is <b>RDM_COS_GU_NONE</b>, this member has no effect.</p>
persistenceFilePath	NULL	n/a	<p>File path where files containing persistent messages may be stored.</p> <p>If set to NULL, the current working directory is used.</p> <p>When <code>type</code> is <b>RDM_COS_GU_NONE</b>, or when <code>persistLocally</code> is set to <b>RSSL_FALSE</b>, this member has no effect.</p>

Table 66: `RsslClassOfService.guarantee` Structure Members

## 6.8.4 Tunnel Stream Callback Functions and Event Types

Various tunnel stream callbacks return their information via specific event objects. The following table defines these events.

EVENT	EVENT DESCRIPTION	CLASS MEMBER	CLASS MEMBER DESCRIPTION
RsslTunnelStreamStatusEvent	This event presents the tunnel stream and its status.	pReactorChannel	A pointer to the <b>RsslReactorChannelTunnelStream</b> with which this tunnel stream is associated.
		pState	Indicates status information associated with the <b>RsslTunnelStream</b> . For example: <ul style="list-style-type: none"> <li>A state of <b>OPEN</b> and <b>OK</b> indicates that the tunnel stream is established and content should be flowing as expected.</li> <li>A state of <b>CLOSED_RECOVER</b> or <b>SUSPECT</b> indicates that the connection or tunnel stream might be lost. However, if performing guaranteed messaging, content might be persisted by the reactor and communicated upon recovery of the tunnel stream.</li> </ul>
		pRsslMsg	A pointer to an <b>RsslMsg</b> structure.
		pAuthInfo	If the event was produced by an authentication message, <b>pAuthInfo</b> is populated by an <b>RsslTunnelStreamAuthInfo</b> structure. For more information, refer to Section 6.8.1.
RsslTunnelStreamMsgEvent	This event presents content received on the <b>RsslTunnelStream</b> . If a more specific handler (i.e., <b>RsslTunnelStreamQueueMsgCallback</b> ) is also configured, messages of that type will go to their specific handler.	pReactorChannel	A pointer to the <b>RsslReactorChannelTunnelStream</b> with which this tunnel stream is associated.
		pRsslMsg	A pointer to an <b>RsslMsg</b> structure, used to deliver any OMM content or opaque content.
		pErrorInfo	Used to convey error information, when applicable.

**Table 67: Tunnel Stream Callback Event Types**

EVENT	EVENT DESCRIPTION	CLASS MEMBER	CLASS MEMBER DESCRIPTION
RsslTunnelStreamQueueMsgEvent	This event presents any queue message content received on the <b>RsslTunnelStream</b> .	base	An <b>RsslTunnelStreamMsgEvent</b> . Refer to Section 6.8.4.2.
		pQueueMsg	A pointer to a Queue Message containing OMM content or opaque content exchanged with a Queue Provider. Refer to subsequent chapters for information about Queue Messages.

Table 67: Tunnel Stream Callback Event Types (Continued)

#### 6.8.4.1 Tunnel Stream Callback Functions

The **RsslTunnelStream** delivers events via the following user-implemented callback functions. These callback functions return event objects as defined in Section 6.8.4.2. Each callback returns the **RsslTunnelStream** on which the event occurred along with the event itself.

CALLBACK FUNCTION	DESCRIPTION
RsslTunnelStreamStatusEventCallback	Communicates status information about the tunnel stream. Additionally, this callback delivers the <b>RsslTunnelStream</b> object after the enhanced private stream is established.  This callback provides an <b>RsslTunnelStreamStatusEvent</b> to the application. Details about this event are available in Section 6.8.4.2.
RsslTunnelStreamDefaultMsgCallback	Similar to the <b>ReactorChannel</b> 's <b>defaultMsgCallback</b> , content received by the tunnel stream are returned via this callback if it is not handled by a more specific content handler, such as the <b>RsslTunnelStreamQueueMsgCallback</b> .  This callback provides an <b>RsslTunnelStreamMsgEvent</b> to the application. Details about this event are available in Section 6.8.4.2.
RsslTunnelStreamQueueMsgCallback	Any queue messages are delivered via this callback and presented to the user in their native queue message formats. If unspecified, queue messages are delivered via the <b>RsslTunnelStreamDefaultMsgCallback</b> ; however they are not presented in a queue message format.  This callback provides a <b>RsslTunnelStreamQueueMsgEvent</b> to the application. Details about this event are available in Section 6.8.4.2.

Table 68: Tunnel Stream Callback Functions

### 6.8.4.2 Tunnel Stream Callback Event Types

Various tunnel stream callbacks return their information via specific event objects. The following table defines these events.

EVENT	EVENT DESCRIPTION	CLASS MEMBER	CLASS MEMBER DESCRIPTION
RsslTunnelStreamStatusEvent	This event presents the tunnel stream and its status.	pReactorChannel	A pointer to the <b>RsslReactorChannelTunnelStream</b> with which this tunnel stream is associated.
		pState	Indicates status information associated with the <b>RsslTunnelStream</b> . For example: <ul style="list-style-type: none"> <li>A state of <b>OPEN</b> and <b>OK</b> indicates that the tunnel stream is established and content should be flowing as expected.</li> <li>A state of <b>CLOSED_RECOVER</b> or <b>SUSPECT</b> indicates that the connection or tunnel stream might be lost. However, if performing guaranteed messaging, content might be persisted by the reactor and communicated upon recovery of the tunnel stream.</li> </ul>
		pRsslMsg	A pointer to an <b>RsslMsg</b> structure.
		pAuthInfo	If the event was produced by an authentication message, <b>pAuthInfo</b> is populated by an <b>RsslTunnelStreamAuthInfo</b> structure. For more information, refer to Section 6.8.1.
RsslTunnelStreamMsgEvent	This event presents content received on the <b>RsslTunnelStream</b> . If a more specific handler (i.e., <b>RsslTunnelStreamQueueMsgCallback</b> ) is also configured, messages of that type will go to their specific handler.	pReactorChannel	A pointer to the <b>RsslReactorChannelTunnelStream</b> with which this tunnel stream is associated.
		pRsslMsg	A pointer to an <b>RsslMsg</b> structure, used to deliver any OMM content or opaque content.
		pErrorInfo	Used to convey error information, when applicable.

**Table 69: Tunnel Stream Callback Event Types**

EVENT	EVENT DESCRIPTION	CLASS MEMBER	CLASS MEMBER DESCRIPTION
RsslTunnelStreamQueueMsgEvent	This event presents any queue message content received on the <b>RsslTunnelStream</b> .	base	An <b>RsslTunnelStreamMsgEvent</b> . Refer to Section 6.8.4.2.
		pQueueMsg	A pointer to a Queue Message containing OMM content or opaque content exchanged with a Queue Provider. Refer to subsequent chapters for information about Queue Messages.

Table 69: Tunnel Stream Callback Event Types (Continued)

### 6.8.5 Opening a Tunnel Stream Code Sample

The following code sample illustrates how to open a tunnel stream. The example assumes that a Reactor and ReactorChannel are already open and properly established.

```
// Basic sample for event handlers

// RsslTunnelStreamStatusEventCallback
RsslReactorCallbackRet tunnelStreamStatusEventCallback(RsslTunnelStream
    *pTunnelStream, RsslTunnelStreamStatusEvent *pEvent)
{
    printf("Status of Tunnel Stream %d is %d:%d\n", pTunnelStream->streamId, pEvent->pState-
        >streamState, pEvent->pState->dataState);
    return RSSL_RC_CRET_SUCCESS;
}

// RsslTunnelStreamDefaultMsgCallback
RsslReactorCallbackRet tunnelStreamDefaultMsgCallback(RsslTunnelStream *pTunnelStream,
    RsslTunnelStreamMsgEvent *pEvent)
{
    printf("Received content on Tunnel Stream %d\n", pTunnelStream->streamId);
    return RSSL_RC_CRET_SUCCESS;
}

// RsslTunnelStreamQueueMsgCallback
RsslReactorCallbackRet tunnelStreamQueueMsgCallback(RsslTunnelStream *pTunnelStream,
    RsslTunnelStreamQueueMsgEvent *pEvent)
{
    printf("Received Queue Message on Tunnel Stream %d\n", pTunnelStream->streamId);
    return RSSL_RC_CRET_SUCCESS;
}

int openTunnelStream()
{
    RsslTunnelStreamOpenOptions _openOptions;
    RsslErrorInfo _errorInfo;
```

```

rsslClearTunnelStreamOpenOptions(&_openOptions);

// populate the options and enable guaranteed delivery for communication with a Queue Provider
_openOptions.classOfService.guarantee.type = RDM_COS_GU_PERSISTENT_QUEUE;
_openOptions.classOfService.dataIntegrity = RDM_COS_DI_RELIABLE;
_openOptions.classOfService.flowControl = RDM_COS_FC_BIDIRECTIONAL;
_openOptions.classOfService.guarantee.persistLocally = RSSL_TRUE;
_openOptions.streamId = TUNNEL_STREAM_ID;
_openOptions.domainType = RSSL_DMT_QUEUE_MESSAGING;
_openOptions.serviceId = QUEUE_MESSAGING_SERVICE_ID;
// specify the event handlers
_openOptions.statusEventCallback = tunnelStreamStatusEventCallback;
_openOptions.defaultMsgCallback = tunnelStreamDefaultMsgCallback;
_openOptions.queueMsgCallback = tunnelStreamQueueMsgCallback;

if ((rsslReactorOpenTunnelStream(_pReactorChannel, &_openOptions, &_errorInfo)) !=
    RSSL_RET_SUCCESS)
{
    printf("rsslReactorOpenTunnelStream failed!");
    return RSSL_RET_FAILURE;
}

printf("rsslReactorOpenTunnelStream succeeded!");
return RSSL_RET_SUCCESS;
}

```

Code Example 15: Opening a Tunnel Stream

### 6.8.6 Accepting Tunnel Streams

OMM provider applications can accept tunnel streams provided on an **RsslReactorChannel** (enabled by specifying a **RsslTunnelStreamListenerCallback** on the **RsslReactorOMMProviderRole**).

When a consumer opens a tunnel stream, the **RsslTunnelStreamListenerCallback** receives an **RsslTunnelStreamRequestEvent**. At this point, the provider should call **rsslTunnelStreamRequestGetCos** to retrieve the **RsslClassOfService** requested by the tunnel stream and ensure that the parameters indicated by the members of that class of service match what the provider allows. The provider can also check the **RsslTunnelStreamRequestEvent.classOfServiceFilter** to determine which behaviors the consumer supports. For more information on this filter, refer to Section 6.8.6.1.

- To accept a tunnel stream, the provider must call **rsslReactorAcceptTunnelStream** with the given **RsslTunnelStreamRequestEvent**. Further events regarding the accepted stream are provided in the specified **RsslReactorAcceptTunnelStreamOptions.statusEventCallback**.
- To reject a tunnel stream, the provider calls **rsslReactorRejectTunnelStream** with the given **RsslTunnelStreamRequestEvent**. No further events are received for that tunnel stream.

Queue messaging (an **RsslClassOfService.guarantee.type** setting of **RDM\_COS\_GU\_PERSISTENT\_QUEUE**) is not supported for provider applications.

The API automatically rejects tunnel streams that contain invalid information. When this happens, the provider application receives warnings via an **RsslReactorChannelEvent**. The type will be set to **RSSL\_RC\_CET\_WARNING** and the **RsslErrorInfo** in the event will contain text describing the reason for the rejection.



**Warning!** Ensure that the provider application calls `rsslReactorAcceptTunnelStream` or `rsslReactorRejectTunnelStream` before returning from the `RsslTunnelStreamListenerCallback`. If not, the provider application will receive a warning via an `RsslReactorChannelEvent` similar to the above, and the stream will be automatically rejected.

### 6.8.6.1 Reactor Tunnel Stream Listener Callback and Tunnel Stream Request Event

OMM providers that want to handle tunnel streams from connected consumers can specify a `RsslTunnelStreamListenerCallback`. This callback informs the provider application of any consumer tunnel stream requests.

The provider can specify this callback on the `RsslReactorOMMProviderRole`, which has the following signature:

```
RsslTunnelStreamListenerCallback(RsslTunnelStreamRequestEvent*, RsslErrorInfo*)
```

For more information on the `RsslReactorOMMProviderRole`, refer to Section 6.3.3.

An `RsslTunnelStreamRequestEvent` is returned to the application via the `RsslTunnelStreamListenerCallback`.

STRUCTURE MEMBER	DESCRIPTION
pReactorChannel	Specifies the <code>RsslReactorChannel</code> on which the event was received.
streamId	Specifies the stream ID of the requested tunnel stream.
domainType	Specifies the domain type of the requested tunnel stream.
serviceId	Specifies the service ID of the requested tunnel stream.
name	Specifies the name of the requested tunnel stream.
classOfServiceFilter	Sets a filter that indicates which <code>RsslClassOfService</code> members are present. The provider can use this filter to determine whether behaviors are supported by the consumer and if needed, reject the tunnel stream before calling <code>rsslTunnelStreamRequestGetCos</code> to get the full <code>RsslClassOfService</code> . For enumerations of the flags present in this filter, refer to <code>RsslTunnelStreamCoSFilterFlags</code> in <code>rsslIRDM.h</code> .

Table 70: `RsslTunnelStreamRequestEvent` Structure Members

### 6.8.6.2 rsslReactorAcceptTunnelStream Function

FUNCTION NAME	DESCRIPTION
<code>rsslReactorAcceptTunnelStream</code>	Accepts a tunnel stream requested by a consumer. The <code>RsslTunnelStream</code> is returned in the <code>RsslTunnelStreamStatusEventCallback</code> specified on the <code>RsslReactorAcceptTunnelStreamOptions</code> . For more information, refer to Section 6.8.6.3.

Table 71: `rsslReactorAcceptTunnelStream` Function



### 6.8.6.3 RsslReactorAcceptTunnelStreamOptions

OPTION	DESCRIPTION
statusEventCallback	Specifies the instance of the callback for <code>RsslTunnelStreamStatusEvents</code> , which provides the <code>RsslTunnelStream</code> on initial connection and then communicates state information about the tunnel afterwards. For details on the <code>RsslTunnelStreamStatusEventCallback</code> , refer to Section 6.8.4.1.
defaultMsgCallback	Specifies the instance of the callback used to handle all other content received on this <code>RsslTunnelStream</code> . For details on <code>RsslTunnelStreamDefaultMsgCallback</code> , refer to Section 6.8.4.1.
userSpecPtr	Specifies a user-defined pointer passed in via these options and then associated with the <code>RsslTunnelStream</code> .
classOfService	Specifies an <code>RsslClassOfService</code> with members indicating behaviors that the application wants to apply to the <code>RsslTunnelStream</code> . For more information on class of service, refer to Section 6.8.3.
guaranteedOutputBuffers	Sets the number of pooled buffers available to the application when writing content to <code>RsslTunnelStream</code> .

Table 72: `RsslReactorAcceptTunnelStreamOptions` Options

### 6.8.6.4 rsslReactorRejectTunnelStream Function

FUNCTION NAME	DESCRIPTION
<code>rsslReactorRejectTunnelStream</code>	Rejects a tunnel stream requested by a consumer. No further events will be received for this tunnel stream. For more information, refer to Section 6.8.6.5.

Table 73: `rsslReactorRejectTunnelStream` Function

### 6.8.6.5 RsslReactorRejectTunnelStreamOptions

OPTION	DESCRIPTION
state	An <code>RsslState</code> to send to the consumer. The application can use the <code>state.streamState</code> , <code>state.dataState</code> , and <code>state.text</code> to indicate the nature of the rejection.
pCos	An optional <code>RsslClassOfService</code> to send to the consumer. If rejecting the stream due to a problem with the <code>RsslClassOfService</code> parameters from the <code>RsslTunnelStreamRequestEvent</code> , the provider application should populate this with the associated parameters.

Table 74: `RsslReactorRejectTunnelStreamOptions` Options

### 6.8.6.6 Accepting a Tunnel Stream Code Sample

The following code illustrates how to accept a tunnel stream requested by a consumer. The example presumes that a Reactor and Reactor Channel are already open and properly established.

```
RsslReactorCallbackRet tunnelStreamListenerCallback(RsslTunnelStreamRequestEvent *pEvent,
    RsslErrorInfo *pErrorInfo)
{
    RsslErrorInfo errorInfo;
    RsslRet ret;
    RsslClassOfService cos;
    RsslReactorAcceptTunnelStreamOptions acceptOpts;
    ret = rsslTunnelStreamRequestGetCos(pEvent, &cos, &errorInfo);

    /* Now presuming that the application wishes to accept the tunnel stream. */
    rsslClearReactorAcceptTunnelStreamOptions(&acceptOpts);
    acceptOpts.statusEventCallback = tunnelStreamStatusEventCallback;
    acceptOpts.defaultMsgCallback = tunnelStreamDefaultMsgCallback;

    /* Set desired ClassOfService options. */
    /* For this sample, set authentication to match consumer. */
    acceptOpts.classOfService.authentication.type = cos.authentication.type;
    acceptOpts.classOfService.flowControl.type = RDM_COS_FC_BIDIRECTIONAL;
    acceptOpts.classOfService.dataIntegrity.type = RDM_COS_DI_RELIABLE;
    /* ... (set additional members, based on what is desired by the provider) */

    ret = rsslReactorAcceptTunnelStream(pEvent, &acceptOpts, &errorInfo);

    return RSSL_RC_CRET_SUCCESS;
}
```

#### Code Example 16: Accepting a Tunnel Stream Code Example

### 6.8.6.7 Rejecting a Tunnel Stream Code Sample

The following code illustrates how to reject a tunnel stream requested by a consumer. The example presumes that a Reactor and Reactor Channel are already open and properly established.

```
RsslReactorCallbackRet tunnelStreamListenerCallback(RsslTunnelStreamRequestEvent *pEvent,
    RsslErrorInfo *pErrorInfo)
{
    RsslErrorInfo errorInfo;
    RsslRet ret;
    RsslClassOfService cos;

    ret = rsslTunnelStreamRequestGetCos(pEvent, &cos, &errorInfo);

    /* Now presuming that the application wishes to reject the tunnel stream
    * Because it only communicates using the RWF protocol type. */
}
```

```

if (cos.common.protocolType != RSSL_RWF_PROTOCOL_TYPE)
{
    RsslReactorRejectTunnelStreamOptions rejectOpts;
    RsslClassOfService expectedCos;
    rsslClearReactorRejectTunnelStreamOptions(&rejectOpts);

    rejectOpts.state.streamState = RSSL_STREAM_CLOSED;
    rejectOpts.state.dataState = RSSL_DATA_SUSPECT;
    rejectOpts.state.text.data = "This provider only communicates using the RWF protocol.";
    rejectOpts.state.text.length = (RsslUInt32)strlen(rejectOpts.state.text.data);

    /* Set what the class of service is expected to be. */
    rsslClearClassOfService(&expectedCos);
    expectedCos.common.protocolType = RSSL_RWF_PROTOCOL_TYPE;
    expectedCos.common.protocolMajorVersion = RSSL_RWF_MAJOR_VERSION;
    expectedCos.common.protocolMinorVersion = RSSL_RWF_MINOR_VERSION;
    expectedCos.authentication.type = RDM_COS_AU_NOT_REQUIRED;
    expectedCos.flowControl.type = RDM_COS_FC_BIDIRECTIONAL;
    expectedCos.dataIntegrity.type = RDM_COS_DI_RELIABLE;
    /* ... (set additional members, based on what is desired by the provider) */

    rejectOpts.pCos = &expectedCos;

    ret = rsslReactorRejectTunnelStream(pEvent, &rejectOpts, &errorInfo);
}

return RSSL_RC_CRET_SUCCESS;
}

```

### Code Example 17: Rejecting a Tunnel Stream Code Example

## 6.8.7 Receiving Content on a TunnelStream

Invoking the `RsslReactorChannel.dispatch` method reads and processes inbound content, where any information received on this `RsslTunnelStream` will be delivered to the application via the tunnel stream callback methods specified via `rsslReactorOpenTunnelStream` or `rsslReactorAcceptTunnelStream`.

Dispatching this content works in the same manner as dispatching any other content on the reactor.

- Tunnel stream callback methods are described in Section 6.8.4.
- Tunnel stream callback methods deliver the events described in Section 6.8.4.2.

## 6.8.8 Sending Content on a TunnelStream

When you send content on an `RsslTunnelStream`, get a buffer from the `RsslTunnelStream`, encode your content into the buffer, and then use the `rsslTunnelStreamSubmitMsg` method to push the content out over the `RsslTunnelStream`. By obtaining a buffer from the `RsslTunnelStream`, the reactor can then properly handle any negotiated behaviors, making this functionality nearly transparent.

### 6.8.8.1 Tunnel Stream Buffer Methods

METHOD NAME	DESCRIPTION
<code>rsslTunnelStreamGetBuffer</code>	Obtains a buffer from the <code>RsslTunnelStream</code> . To properly enforce negotiated behaviors on content in the buffer, the Transport API associates the buffer with the tunnel stream from which it is obtained.
<code>rsslTunnelStreamReleaseBuffer</code>	Releases a buffer back to the <code>RsslTunnelStream</code> from which it came. You should release any buffer that you do not submit. Releasing the buffer ensures it is properly recycled and can be reused.
	<b>Note:</b> If you submit a buffer properly, you do not need to release it, because the submit method automatically releases it after sending the content on the <code>RsslTunnelStream</code> .

Table 75: Tunnel Stream Buffer Methods

### 6.8.8.2 Tunnel Stream Submit

The submit method is used to write content to the `RsslTunnelStream`. This method also enforces any specified behaviors on submitted content (e.g., if guaranteed messaging is specified, this content follows all configured persistence options).

METHOD NAME	DESCRIPTION
<code>rsslTunnelStreamSubmitMsg</code>	Allows the user to pass in RDM Message content, including Queue Messages, that will be processed and sent over the <code>RsslTunnelStream</code> . This method has additional options that can be specified via the <code>RsslTunnelStreamSubmitOptions</code> . Currently, the only available members of the option structure allow the user to pass in an RDM Message or an <code>RsslMsg</code> structure containing their content.
<code>rsslTunnelStreamSubmit</code>	Allows the user to pass in a buffer populated with content that will be processed and sent over the <code>RsslTunnelStream</code> .

Table 76: Tunnel Stream Submit Method

### 6.8.8.3 RsslTunnelStreamSubmitOptions

When calling `rsslTunnelStreamSubmitMsg`, you can use `RsslTunnelStreamSubmitOptions` to provide the `containerType` option.

MEMBER	DESCRIPTION
<code>containerType</code>	<p>Specifies the type of data in the buffer being submitted.</p> <p>For example:</p> <ul style="list-style-type: none"> <li>If the submitted buffer contains an <code>RsslMsg</code>, set <code>containerType</code> <b>RSSL_DT_MSG</b>.</li> <li>If sending non-RWF data, set <code>containerType</code> to a non-RWF type, such as <b>RSSL_DT_OPAQUE</b>.</li> </ul> <p>For more information on possible container types, refer to the <i>Transport API C Edition Developers Guide</i>.</p>

Table 77: `RsslTunnelStreamSubmitOptions` Structure Members

### 6.8.8.4 RsslTunnelStreamSubmitMsgOptions

When calling `rsslTunnelStreamSubmitMsg`, you can use `RsslTunnelStreamSubmitMsgOptions` to provide options the following options:

MEMBER	DESCRIPTION
<code>pRsslMsg</code>	Specifies an <code>RsslMsg</code> populated by the application, which the API encodes and sends over the <code>RsslTunnelStream</code> ; mutually exclusive with <code>pRDMMsg</code> .
<code>pRDMMsg</code>	Specifies an <code>RsslRDMMsg</code> populated by the application, which the API encodes and sends over the <code>RsslTunnelStream</code> ; mutually exclusive with <code>pRsslMsg</code> .

Table 78: `RsslTunnelStreamSubmitMsgOptions` Structure Members

### 6.8.8.5 Submitting Content on a Tunnel Stream Code Sample

The following code sample is a basic example of writing opaque content to a tunnel stream. This can be combined with the `QueueData` message samples in subsequent chapters to send content to a Queue Provider.

```
int submitMessage()
{
    RsslErrorInfo _errorInfo;
    RsslBuffer *pBuffer;
    RsslTunnelStreamGetBufferOptions _getBufferOpts;
    RsslTunnelStreamSubmitOptions _submitOpts;

    // gets a buffer of 50 bytes to put content into.
    rsslClearTunnelStreamGetBufferOptions(&_getBufferOpts);
    _getBufferOpts.size = 50;
    pBuffer = rsslTunnelStreamGetBuffer(pTunnelStream, &_getBufferOpts, _errorInfo);

    // put generic content into the buffer
    pBuffer->data = "Hello World!";
    pBuffer->length = 12;
}
```

```

rsslClearTunnelStreamSubmitOptions(&_submitOpts);
_submitOpts.containerType = RSSL_DT_OPAQUE;
if ((rsslTunnelStreamSubmit(pTunnelStream, pBuffer, &_submitOpts, &_errorInfo)) !=
    RSSL_RET_SUCCESS)
{
    printf("Content submission failed!");
    // Because submission failed, we need to return the buffer to the tunnel stream
    rsslTunnelStreamReleaseBuffer(&_buffer, &_errorInfo);

    return RSSL_RET_FAILURE;
}

printf("Content submission succeeded!");
// Thanks to successful submission, we do not need to release the buffer because the Reactor will.
return RSSL_RET_SUCCESS;
}

```

Code Example 18: Submitting Content on a Tunnel Stream

#### 6.8.8.6 Closing a Tunnel Stream

When an application has completed its use of an `RsslTunnelStream`, it can be closed.

METHOD NAME	DESCRIPTION
<code>rsslReactorCloseTunnelStream</code>	Closes a tunnel stream. Once closed, any content stored for guaranteed messaging or reliable delivery will be cleaned up.

Table 79: `rsslReactorCloseTunnelStream` Method

#### 6.8.8.7 RsslTunnelStreamCloseOptions

When calling `rsslTunnelStreamClose`, you can use `RsslTunnelStreamCloseOptions` to provide the `finalStatusEvent` option.

MEMBER	DESCRIPTION
<code>finalStatusEvent</code>	Indicates that the application wants to receive a final <code>RsslTunnelStreamStatusEvent</code> whenever the tunnel stream closes. If set to <code>RSSL_TRUE</code> , the tunnel stream is cleaned up after the application receives the final <code>RsslTunnelStreamStatusEvent</code> .

Table 80: `RsslTunnelStreamCloseOptions` Structure Members

### 6.8.8.8 Closing a Tunnel Stream Code Sample

The following code sample illustrates how to close a tunnel stream.

```
int closeTunnelStream()
{
    RsslTunnelStreamCloseOptions _closeOpts;

    rsslClearTunnelStreamCloseOptions(&_closeOpts);
    _closeOpts.finalStatusEvent = RSSL_TRUE;

    if ((rsslReactorCloseTunnelStream(pTunnelStream, &_closeOpts, &_errorInfo)) != RSSL_RET_SUCCESS)
    {
        printf("Closing tunnel stream failed!");
        return RSSL_RET_FAILURE;
    }

    printf("Tunnel Stream closed successfully.");
    return RSSL_RET_SUCCESS;
}
```

**Code Example 19: Closing a Tunnel Stream**

## 6.9 Cloud Connectivity

For details on workflows and routines associated with connecting to the cloud, refer to Chapter 7.

### 6.9.1 `rsslReactorQueryServiceDiscovery`

You use the `rsslReactorQueryServiceDiscovery` method to query service endpoints from the EDP-RT service discovery.

#### 6.9.1.1 `rsslReactorQueryServiceDiscovery` Method

METHOD	DESCRIPTION
<code>rsslReactorQueryServiceDiscovery</code>	Uses the passed-in <code>RsslReactor</code> to query service endpoints from the EDP-RT service according to the <code>rsslReactorQueryServiceDiscoveryOptions</code> that you specify (listed in Section 6.9.1.2). Error handling is managed by the <code>RsslErrorInfo</code> structure.

Table 81: `rsslReactorQueryServiceDiscovery` Method

#### 6.9.1.2 `RsslReactorServiceDiscoveryOptions`

MEMBER	DESCRIPTION
<code>clientId</code>	An <code>RsslBuffer</code> that specifies a unique ID defined for an application making a request to the token service. If <code>clientId</code> is not specified, the ETA Value Added C uses <code>userName</code> instead.
<code>clientSecret</code>	An <code>RsslBuffer</code> that specifies the client secret (if one exists) used by the OAuth client to authenticate to the authorization Server.
<code>dataFormat</code>	Optional. An enumeration that specifies the desired data format to use when retrieving service endpoints from the service discovery. For available values, refer to Section 6.9.1.4.
<code>password</code>	An <code>RsslBuffer</code> that specifies a password for authorization with the token service.
<code>proxyHostName</code>	Optional. An <code>RsslBuffer</code> that specifies a proxy server hostname.
<code>proxyPort</code>	Optional. An <code>RsslBuffer</code> that specifies a proxy server port.
<code>proxyUserName</code>	Optional. An <code>RsslBuffer</code> that specifies a username to perform authorization with a proxy server.
<code>proxyPasswd</code>	Optional. An <code>RsslBuffer</code> that specifies a password to perform authorization with a proxy server.
<code>proxyDomain</code>	Optional. An <code>RsslBuffer</code> that specifies the proxy domain of the user to authenticate. <b>Required</b> for NTLM or for Negotiate/Kerberos or for Kerberos authentication protocols.
<code>pServiceEndpointEventCallback</code>	A callback function that receives <code>RsslReactorServiceEndpointEvents</code> . Applications can take service endpoint information from the callback to get an endpoint and establish a connection to the service.

Table 82: `RsslReactorServiceDiscoveryOptions` Structure Members



MEMBER	DESCRIPTION
transport	Optional. An enumeration that specifies the desired transport protocol to retrieve service endpoints from the service discovery. For available values, refer to Section 6.9.1.3.
userName	An <code>RsslBuffer</code> that specifies a user name for authorization with the token service.
userSpecPtr	Optional. A user-specified pointer which is set on the <code>RsslReactorServiceEndpointEvent</code> .

Table 82: `RsslReactorServiceDiscoveryOptions` Structure Members (Continued)

### 6.9.1.3 RsslReactorDiscoveryTransportProtocol Enumerations

ENUMERATED NAME	DESCRIPTION
RSSL_RD_TP_INIT = 0	Specifies that the transport's protocol is unknown.
RSSL_RD_TP_TCP = 1	Specifies that the service discovery should use the TCP transport protocol.
RSSL_RD_TP_WEBSOCKET = 2	Specifies that the service discovery should use the Websocket transport protocol.

Table 83: `RsslReactorDiscoveryTransportProtocol` Enumerations

### 6.9.1.4 RsslReactorDiscoveryDataFormatProtocol Enumerations

ENUMERATED NAME	DESCRIPTION
RSSL_RD_DP_INIT = 0	Specifies that the transport's data format is unknown.
RSSL_RD_DP_RWF = 1	Specifies that the service discovery should use the RWF data format.
RSSL_RD_DP_JSON2 = 2	Specifies that the service discovery should use the tr_json2 data format.

Table 84: `RsslReactorDiscoveryDataFormatProtocol` Enumerations

### 6.9.1.5 RsslReactorServiceEndpointEvent

MEMBER	DESCRIPTION
pErrorInfo	Returns any information about the error that occurred with the EDP token service and service discovery. Error information includes its location in the source code.
serviceEndpointInfoCount	Specifies the number of service endpoints in <code>serviceEndpointInfoList</code> .
serviceEndpointInfoList	Lists the service endpoints associated with this event.
userSpecPtr	Optional. A user-specified pointer associated with this <code>RsslReactorServiceEndpointEvent</code> .

Table 85: `RsslReactorServiceEndpointEvent` Structure Members

### 6.9.1.6 RsslReactorServiceEndpointInfo

**RsslReactorServiceEndpointEvent** represents service endpoint information.

MEMBER	DESCRIPTION
dataFormatList	An <b>RsslBuffer</b> that contains a list of data formats used by the transport.
dataFormatCount	Specifies the number of data formats in <b>dataFormatList</b> .
endPoint	An <b>RsslBuffer</b> that specifies the domain name of the service access endpoint.
locationList	An <b>RsslBuffer</b> that specifies a list of service locations.
locationCount	Specifies the number of locations in <b>locationList</b> .
port	An <b>RsslBuffer</b> that specifies the port number used to establish connection.
provider	An <b>RsslBuffer</b> that specifies a public cloud provider.
transport	An <b>RsslBuffer</b> that specifies the transport type used to access the service.

Table 86: **RsslReactorServiceEndpointEvent** Structure Members

## 6.9.2 OAuth Credential Management

### 6.9.2.1 RsslReactorOAuthCredential Structure

You use the **RsslReactorOAuthCredential** structure to certify OAuth user credentials when connecting to the cloud.

**RsslReactorOAuthCredential** includes the following members:

MEMBER	DESCRIPTION
clientId	<b>Required.</b> An <b>RsslBuffer</b> that specifies a unique ID defined for the application that makes the request. For further details on the Client ID, refer to Section 7.3.1.
clientSecret	An <b>RsslBuffer</b> that specifies a the Client ID 'secret' that OAuth clients can use to authenticate. For details on how OAuth uses a Client Secret with a Client ID and their relationship, refer to OAuth documentation at: the following URL: <a href="https://www.oauth.com/oauth2-servers/client-registration/client-id-secret/">https://www.oauth.com/oauth2-servers/client-registration/client-id-secret/</a> .
password	<b>Required.</b> An <b>RsslBuffer</b> that specifies the password used in tandem with the <b>userName</b> to obtain the access token.
pOAuthCredentialEventCallback	A callback function that receives the <b>RsslReactorOAuthCredentialEvent</b> to specify the <b>password</b> and/or <b>clientSecret</b> .  If <b>pOAuthCredentialEventCallback</b> is specified, the VAC Reactor does not store the <b>password</b> or <b>clientSecret</b> . In which case, the application must supply the <b>password</b> whenever receiving a new refresh token. For details on this process, refer to Section 7.3.2.

Table 87: **RsslReactorOAuthCredential** structure Members

MEMBER	DESCRIPTION
tokenScope	An <b>RsslBuffer</b> that specifies the user's resource scope that defines the type of data the user accesses in the cloud. For further details on token scopes, refer to the EDP APIs tutorial <a href="#">Authorization - All about tokens</a> in the Developer Community Portal. By default, the Transport API uses the scope: <b>trapi.streaming.pricing.read</b> .
userName	<b>Required.</b> An <b>RsslBuffer</b> that specifies the user name used to obtain the access token from the EDP Gateway.

Table 87: **RsslReactorOAuthCredential** structure Members (Continued)

### 6.9.2.2 RsslReactorOAuthCredentialEvent

Whenever the Transport API needs a new refresh token, it needs to again supply the username, Client ID, and password. But the Transport API stores only the username and Client ID, not the password. To obtain the password (and if available, the client secret), the Transport API sends the **RsslReactorOAuthCredentialEvent** callback to the application.

MEMBER	DESCRIPTION
RsslReactorChannel	Returns the channel associated with the event.
RsslReactorOAuthCredentialRenewal	Returns a structure with OAuth credentials for renewal authentication with the EDP Gateway.

Table 88: **RsslReactorOAuthCredentialEvent** Structure Members

### 6.9.2.3 RsslReactorOAuthCredentialRenewal

MEMBER	DESCRIPTION
userName	Conditional. An <b>RsslBuffer</b> that specifies the user name that the Transport API sends to the EDP token service. The <b>RsslReactorOAuthCredentialEventCallback</b> also uses <b>userName</b> when returning sensitive information. <b>Required</b> except when specifying sensitive information in the <b>RsslReactorOAuthCredentialEventCallback</b> .
password	<b>Required.</b> An <b>RsslBuffer</b> that specifies the password, which is sent with the <b>userName</b> to get an access token and a refresh token.
newPassword	Conditional. An <b>RsslBuffer</b> that specifies the new password when changing the password associated with the specified <b>userName</b> . Include <b>newPassword</b> only when the application wants to change its password, in which case both the current ( <b>password</b> ) and new password ( <b>newPassword</b> ) are <b>required</b> .
clientId	An <b>RsslBuffer</b> that specifies the unique Client ID for the application that makes the request.
clientSecret	An <b>RsslBuffer</b> that specifies the client secret (if one exists) used by the OAuth client to authenticate to the authorization Server.

Table 89:

MEMBER	DESCRIPTION
tokenScope	An <b>RsslBuffer</b> that specifies the scope of the generated token.

Table 89: (Continued)

#### 6.9.2.4 rsslReactorSubmitOAuthCredentialRenewal Method

MEMBERS	DESCRIPTION
rsslReactorSubmitOAuthCredentialRenewal	<p>Uses the passed-in <b>RsslReactor</b> and <b>RsslReactorOAuthCredentialRenewal</b> to submit the application's password (and client secret if available) to the EDP Gateway token service. An application can also use this method to change its password.</p> <p>For a list of options you can use with <b>rsslReactorSubmitOAuthCredentialRenewal</b>, refer to Section 6.9.2.5.</p> <p>If you call this method outside of the <b>RsslReactorOAuthCredentialEventCallback</b>, you should also include <b>pAuthTokenEventCallback</b> to receive a result response.</p> <p>Error handling is managed by the <b>RsslErrorInfo</b> structure.</p>

Table 90: rsslReactorSubmitOAuthCredentialRenewal

#### 6.9.2.5 rsslReactorSubmitOAuthCredentialRenewal Options

OPTION	DESCRIPTION
pAuthTokenEventCallback	<p>A callback function (<b>RsslReactorAuthTokenEventCallback</b>) that receives <b>RsslReactorAuthTokenEvents</b>. The Reactor requests a token for the Consumer (i.e., disabling watchlist) and NiProvider applications to send login requests and reissues with the token.</p> <p><b>pAuthTokenEventCallback</b> is needed only when changing a password without a channel in order to get a response from the request. The application does not have to send a login reissue in this case.</p>
proxyDomain	An <b>RsslBuffer</b> that specifies the domain for authenticated proxies.
proxyHostName	An <b>RsslBuffer</b> that specifies the proxy's host name.
proxyPasswd	An <b>RsslBuffer</b> that specifies the password for authenticated proxies.
proxyPort	An <b>RsslBuffer</b> that specifies the proxy's port.
proxyUserName	An <b>RsslBuffer</b> that specifies the username for authenticated proxies.
renewalMode	A <b>RsslReactorOAuthCredentialRenewalMode</b> that specifies the mode in which the Transport API submits OAuth credential renewals. For available ENUMs and their descriptions, refer to Section 6.9.2.6.

Table 91: rsslReactorSubmitOAuthCredentialRenewal Options

### 6.9.2.6 RsslReactorOAuthCredentialRenewalMode Enums

MODE	DESCRIPTION
RSSL_ROC_RT_RENEW_TOKEN_WITH_PASSWORD	Use this renewal mode when normally submitting a password to obtain an access and refresh token.
RSSL_ROC_RT_RENEW_TOKEN_WITH_PASSWORD_CHANGE	Use this renewal mode only when changing the application's password.

Table 92: RsslReactorOAuthCredentialRenewalMode Enums

## 6.10 Reactor Utility Functions

The Transport API Reactor provides several additional utility functions. These functions can be used to query more detailed information for a specific connection or change certain **RsslReactorChannel** parameters during run-time. These functions are described in Section 6.10.1 - Section 6.10.3.

### 6.10.1 General Reactor Utility Functions

FUNCTION NAME	DESCRIPTION
rsslReactorGetChannelInfo	Allows the application to query <b>RsslReactorChannel</b> negotiated parameters and settings and retrieve all current settings. This includes <b>maxFragmentSize</b> and negotiated compression information as well as many other values. For a full list of available settings, refer to the <b>RsslReactorChannelInfo</b> structure defined in Section 6.10.2.  This function calls the Transport API <b>rsslGetChannelInfo</b> function which has its use and return values described in the <i>Transport API C Edition Developers Guide</i> .
rsslReactorIoctl	Allows the application to change various settings associated with the <b>RsslReactorChannel</b> . The available options are defined in Section 6.10.3.  This function calls the Transport API <b>rsslIoctl</b> function which has its use and return values described in the <i>Transport API C Edition Developers Guide</i> .

Table 93: Reactor Utility Functions

### 6.10.2 RsslReactorChannelInfo Structure Members

The following table describes the values available to the user through using the **rsslReactorGetChannelInfo** function. This information is returned as part of the **RsslReactorChannelInfo** structure.

STRUCTURE MEMBER	DESCRIPTION
rsslChannelInfo	Returns the underlying <b>RsslChannel</b> information. This includes <b>maxFragmentSize</b> , number of output buffers, compression information, and more.  The <b>RsslChannelInfo</b> function structure is fully described in the <i>Transport API C Edition Developers Guide</i> .

Table 94: **RsslReactorChannelInfo** Structure Members

### 6.10.3 rsslReactorIoctl Option Values

There are currently no `RsslReactor` or `RsslReactorChannel` specific codes for use with the `rsslReactorIoctl`. Reactor-specific codes may be added in the future. The application can still use any of the codes allowed with `rsslIoctl`, which are documented in the *Transport API C Edition Developers Guide*.

## Chapter 7 Consuming Data from the Cloud

---

### 7.1 Overview

You can use the Transport API to consume data from a cloud-based ADS server. The API interacts with cloud-based servers using the following work flows:

- Authentication Token Management (for details, refer to Section 7.3)
- Service Discovery (for details, refer to Section 7.4)
- Consuming Market Data (for details, refer to Section 7.5)
- Login Reissue (for details, refer to Section 7.3.3)

By default, for cloud connections the Transport API connects to a server in the **us-east** cloud location.

For further details on Elektron as it functions within the cloud, refer to the *Elektron Real Time in Cloud: Installation and Configuration for Client Use*.

### 7.2 Encrypted Connections

When connecting to an ADS in the cloud, you must use an encrypted connection type (for details on connection types, refer to the *ETA C Developer Guide*).

Encrypted connections to the cloud must use an OpenSSL-based connection type (on both Windows and Linux). WinINet is not supported for cloud connectivity.

## 7.3 Authentication Token Management

### 7.3.1 Client\_ID (AppKey)

To connect to Elektron infrastructure in the cloud (i.e., for ERT in the Cloud), the Transport API requires a **Client\_ID**, and optionally can include a client secret. **Client\_IDs** are generated using **AppGenerator**, which refers to the **Client\_ID** as an AppKey. Each user must obtain their unique **Client\_ID** using the machine account email sent by Refinitiv, which includes a link to **AppGenerator**. Keep your **Client\_ID** private: do not share **Client\_IDs**.

- For further details on generating this ID, refer to the *Elektron Real Time in Cloud: Installation and Configuration for Client Use* document. Each **Client\_ID** is unique: do not share it with others.
- *EMA C++ Edition Reference Manual* [EMA C++ Edition Reference Manual](../../refman/ema/Index.html) For details on how OAuth uses a Client Secret with a Client ID and their relationship, refer to OAuth documentation at: the following URL: <https://www.oauth.com/oauth2-servers/client-registration/client-id-secret/>.

### 7.3.2 Obtaining Initial Access and Refresh Tokens

To obtain an access token, the ESDK API sends its username, **Client\_ID** (from **RsslReactorOAuthCredential** as described in Section 6.9.2.1), and password (defined in the Login Domain, as described in Section 8.3) in a single message to the EDP Gateway. You must configure these details before executing a connect (for details on the **rsslReactorConnect** function, refer to Section 6.4.1.1).

In response, the EDP sends an access token, its expiration timeout (by default: 300 seconds), and a refresh token for use in the login reissue process (for details on the expiration timeout and login reissue process, refer to Section 7.3.3). The API must obtain an Access token before executing a service discovery or obtaining market data.

The following diagram illustrates the process by which the ESDK API obtains its tokens:




Figure 10. Obtaining an Authentication Token



### 7.3.3 Refreshing the Access Token and Sending a Login Reissue

In response to the API's token request, the EDP sends an access token and a refresh token, both with associated expiration timeouts which set the length of time for which the token is valid. If the ADS does not receive a new access token before the end of the expiration timeout, the ADS sends a login close status message and closes the connection.

To create a seamless experience for API users, the API sends the refresh token to proactively obtain a new access token prior to the published expiration timeout. The Transport API calculates the time at which it requests a new access token by multiplying the token's published timeout by 4/5 (i.e., **0.8**). Thus, if the default is 300 seconds, the API requests a new access token after 240 seconds. You can configure this reissue ratio using `RsslCreateReactorOptions.tokenReissueRatio` (for details, refer to Section 6.2.1.2).

In response to receiving a refresh token, the EDP Gateway sends a new access token with an associated timeout to the API. After receiving the new access token from the EDP Gateway, the API renews its connection by sending a Login Reissue with the new access token to the ADS. The process of renewing the access token and refreshing the ADS connection via a Login Reissue continues until the refresh token itself expires (which can take several hours or days). Whenever a refresh token expires, the EDP rejects it when the API attempts to get a new access token. After a refresh token is rejected, the API will obtain a new set of both refresh and access tokens as described in Section 7.3.2.

The login reissue process is illustrated in the following diagram:




Figure 11. Login Reissue

### 7.3.4 Managing the Password and Client Secret

For security purposes, you can now configure whether the Transport API reactor stores the password and client secret (used with username and Client ID to obtain the access and refresh tokens). By default, the Transport API stores them both.

If you configure the Transport API reactor to not store the password and client secret, whenever the Transport API needs these credentials (i.e., when obtaining an initial access token or new refresh token), the API sends the `RsslReactorOAuthCredentialEvent` callback to the application. For details on the `RsslReactorOAuthCredentialEvent` callback, refer to Section 6.9.2.2.

After receiving the `RsslReactorOAuthCredentialEvent` callback, the application should send an `RsslReactorOAuthCredentialRenewal`, with the needed information, using the `rsslReactorSubmitOAuthCredentialRenewal` method.

- For details on `RsslReactorOAuthCredentialRenewal`, refer to Section 6.9.2.3.
- For details on the `rsslReactorSubmitOAuthCredentialRenewal` method, refer to Section 6.9.2.4.



**Tip:** The application can use the `rsslReactorSubmitOAuthCredentialRenewal` method to change its password on the fly.

### 7.3.5 Session Management per User Credential

Prior to Version 3.3.1, the Transport API would manage tokens separately across each channel, even when using the same Username, Client ID, and password credentials. So that each channel had a unique pair of access and refresh tokens. API would manage each channel distinct from the others.

Now, in 3.3.1, the Transport API connects to the EDP Gateway once and reuses the same access and refresh tokens for all channels. The Transport API supports up to, but no more than, 5 channels per OAuth credential set.

## 7.4 Service Discovery

After obtaining a token (for details, refer to Section 7.3.2), the Transport API can perform a service discovery against the EDP Gateway to obtain connection details for the ADS in the cloud. Transport API C Edition uses the `rsslReactorQueryServiceDiscovery` function (refer to Section 6.2.1 for a description of this reactor method) to submit a service discovery.

In response to a service discovery, the EDP returns transport and data format protocols and a list of hosts and associated ports for the requested service(s) (i.e., an ADS running in the cloud). Refinitiv provides multiple cloud locations based on region, which is significant in how an Transport API chooses the IP address and port to use when connecting to the cloud.

From the list sent by the EDP Gateway, the Transport API identifies an ADS (i.e., an endpoint) set up for failover and whose regional location matches the API's location setting in `RsslReactorConnectInfo` (for details, refer to Section 6.4.1.3). If you do not specify a location, the Transport API defaults to the **us-east** cloud location. An endpoint setup for failover lists multiple locations in its location field (e.g., `location: [us-east-1a, us-east-1b]`). If multiple endpoints are set up for failover, the Transport API chooses to connect to the first endpoint listed.





Figure 12. Service Discovery

## 7.5 Consuming Market Data

After obtaining its login token (for details, refer to Section 7.3.2) and running a service discovery (for details, refer to Section 7.4), the API can connect to the ADS in the cloud and obtain market data. While consuming market data, the API must periodically renew its token via the login reissue workflow (for details, refer to Section 7.3.3).



## 7.6 HTTP Error Handling for Reactor Token Reissues

The Transport API supports handling for the following HTTP error codes from the API gateway:

- 300 Errors:
  - Perform URL redirect for 301, 302, 307 and 308 error codes.
  - Retry the request to the API gateway for all other error codes
- 400 Errors:
  - Retry with username and password for error codes 400 and 401
  - Stop retry the request for error codes 403 and 451
  - Retry the request to the API gateway for all other error codes
- 500 Errors: Retry the request to the API gateway for all error codes

## 7.7 Cloud Connection Use Cases

You can connect to the cloud and consume data according to the following use cases:

- Start to finish session management (for details, refer to Section 7.7.1)
- Disabling the watchlist (for details, refer to Section 7.7.2)
- Query service discovery (for details, refer to Section 7.7.3)

### 7.7.1 Session Management Use Case

In the session management use case, the Transport API manages the entire connection from start to finish. To use session management, you need to configure the API to enable the watchlist and session management (i.e., in the `RsslReactorConnectInfo` object, set **enableSessionManagement**).

The API exhibits the following behavior (listed in order) when operating in a session management use case:

- Obtains a token (according to the details in Section 7.3.2)
- Queries service discovery (according to the details in Section 7.4)
- Consumes market data (according to the details in Section 7.5)
- Manages login reissues when needed on a cyclical basis (according to the details in Section 7.3.3)

A special use case exists for connecting to a specific (i.e., non-default) host. As described in Section 7.4, by default the Transport API connects to whichever host is setup for failover in the location specified by the API. If you want to connect to a specific, non-default host, you must set this in the `RsslConnectOptions.connectionInfo` options. In this case, the Transport API exhibits the same behavior listed above, but ignores the endpoints it receives from the service discovery.

### 7.7.2 Disabling the Watchlist

When connecting to an ADS in the cloud with the watchlist disabled (the default), the API:

- Obtains a token (according to the details in Section 7.3.2)
- If needed, queries service discovery (according to the details in Section 7.4)

If using `poAuthCredential`, the application manually logs in with the token and manages the login reissues, otherwise the Reactor initially handles the RDM Login request, with the application handling subsequent Login Reissues using renewed access tokens. For details on `poAuthCredential`, refer to Section 6.3.2.1.

To support this use case, you must configure session management (i.e., in `RsslReactorConnectInfo` objects, set **enableSessionManagement**).

### 7.7.3 Query Service Discovery

In the query service discovery use case, the API user wants to connect to the EDP Gateway only for a service discovery, and does not necessarily want to consume market data. The API exhibits the following behavior (listed in order) when operating in a query service discovery use case:

- Obtains a token (according to the details in Section 7.3.2)
- Queries service discovery (according to the details in Section 7.4)



## Chapter 8 Administration Domain Models Detailed View

### 8.1 Concepts

**Administration Domain Model Representations** are RDM-specific representations of OMM administrative domain models. This Value Added Component contains structures that represent messages within the Login, Source Directory, and Dictionary domains (discussed in Table 95). All structures follow the formatting and naming specified in the *Transport API C Edition RDM Usage Guide*, so access to content is logical and specific to the content being represented. This component also handles all encoding and decoding functionality for these domain models, so the application needs only to manipulate the message's structure members to send or receive content. Such functionality significantly reduces the amount of code an application needs to interact with OMM devices (i.e., TREP infrastructure), and also ensures that encoding/decoding for these domain models follow OMM-specified formatting rules. Applications can use this Value Added Component directly to help with encoding, decoding, and representation of these domain models. When using the Transport API Reactor, this component is embedded to manage and present callbacks with a domain-specific representation of content.

Where possible, the members of an Administration Domain Model Representation structure are represented in the structure with the same **RsslDataType** that is specified for the element by the Domain Model. In cases where multiple elements are part of a more complex container such as an **RsslMap** or **RsslElementList**, the elements are represented with a C-style array with an associated count indicating the number of structures in the array.

The *Transport API C Edition RDM Usage Guide* defines and describes all domain-specific behaviors, usage, and details.

DOMAIN	PURPOSE
Dictionary	<p>Provides dictionaries that may be needed when decoding data. Though use of the Dictionary domain is optional, Thomson Reuters recommends that provider applications support the domain's use.</p> <p>The Dictionary domain is considered an administrative domain. Many Thomson Reuters components require this content and expect it to follow the domain model definition.</p> <p>For further details refer to Section 8.5.</p>
Login	<p>Authenticates users and advertises/requests features that are not specific to a particular domain. Use of and support for this domain is required for all OMM applications.</p> <p>Login is considered an administrative domain. Many Thomson Reuters components require this content and expect it to conform to the domain model definition.</p> <p>For further details refer to Section 8.3.</p>
Source Directory	<p>Advertises information about available services and their state, QoS, and capabilities. This domain also conveys any group status and group merge information.</p> <p>Interactive and Non-Interactive OMM Provider applications require support for this domain. Thomson Reuters strongly recommends that OMM Consumers request this domain.</p> <p>Source Directory is considered an administrative domain, and many Thomson Reuters components expect this content and require it to conform to the domain model definition.</p> <p>For further details, refer to Section 8.4.</p>

**Table 95: Domains Representations in the Administration Domain Model Value Added Component**

## 8.2 RDM Message Base

All Administration Domain Model Representation structures contain a common base structure that provides members common to all representations and identifies the specific message.

### 8.2.1 RSSL RDM Message Base Structure Members

All domain representation structures have several common members used for stream and domain identification. These are available in the `RsslRDMMsgBase` structure, as described in the following table.

STRUCTURE MEMBER	DESCRIPTION
streamId	<p><b>Required.</b> A unique signed-integer identifier associated with all messages flowing in the stream.</p> <ul style="list-style-type: none"> <li>Positive values indicate a consumer-instantiated stream, typically via a request message.</li> <li>Negative values indicate a provider-instantiated stream, often associated with Non-Interactive Providers.</li> </ul> <p><code>streamId</code> is required on all messages.</p>
domainType	<p><b>Required.</b> Identifies the specific domain message model type. If value is less than <b>128</b>, domain is a Thomson Reuters defined domain model. If value is <b>128 - 255</b>, domain is a user defined domain model. Domain model definition is decoupled from the API and domain models are typically defined in some type of specification document. Thomson Reuters defined domain models are specified in the <i>Transport API C Edition RDM Usage Guide</i>. This is required on all messages.</p>
rdmMsgType	<p><b>Required.</b> Identifies the specific representation for a given domain. The currently supported <code>rdmMsgTypes</code> are defined in Section 8.2.2.</p>

**Table 96: `RsslRDMMsgBase` Structure Members**

### 8.2.2 RSSL RDM Message Types

The following table provides a reference mapping between the administrative domain type and the structural representations provided in this component.

DOMAIN TYPE	RDM MESSAGE TYPE	RDM MESSAGE STRUCTURE
RSSL_DMT_LOGIN ( <code>RsslRDMLLoginMsg</code> )  Refer to Section 8.3	RDM_LG_MT_REQUEST	RsslRDMLLoginRequest
	RDM_LG_MT_REFRESH	RsslRDMLLoginRefresh
	RDM_LG_MT_STATUS	RsslRDMLLoginStatus
	RDM_LG_MT_CLOSE	RsslRDMLLoginClose
	RDM_LG_MT_CONSUMER_CONNECTION_STATUS	RsslRDMLLoginConsumerConnectionStatus

**Table 97: `RsslRDMLMsg`**



DOMAIN TYPE	RDM MESSAGE TYPE	RDM MESSAGE STRUCTURE
RSSL_DMT_SOURCE ( <i>RsslRDMDirectoryMsg</i> )  Refer to Section 8.4	RDM_DR_MT_REQUEST	RsslRDMDirectoryRequest
	RDM_DR_MT_REFRESH	RsslRDMDirectoryRefresh
	RDM_DR_MT_UPDATE	RsslRDMDirectoryUpdate
	RDM_DR_MT_STATUS	RsslRDMDirectoryStatus
	RDM_DR_MT_CLOSE	RsslRDMDirectoryClose
	RDM_DR_MT_CONSUMER_STATUS	RsslRDMDirectoryConsumerStatus
RSSL_DMT_DICTIONARY ( <i>RsslRDMDictionaryMsg</i> )  Refer to Section 8.5	RDM_DC_MT_REQUEST	RsslRDMDictionaryRequest
	RDM_DC_MT_REFRESH	RsslRDMDictionaryRefresh
	RDM_DC_MT_STATUS	RsslRDMDictionaryStatus
	RDM_DC_MT_CLOSE	RsslRDMDictionaryClose

Table 97: *RsslRDMMsg* (Continued)

### 8.2.3 RSSL RDM Encoding and Decoding Functions

Encode and decode functionality is provided that can take the *RsslRDMMsg* union. This allows users to encode or decode from a general type that can represent any of the domain messages. Encode and decode functions are also provided for each specific domain type, as documented in the following chapters.

FUNCTION NAME	DESCRIPTION
<i>rsslEncodeRDMMsg</i>	Used to encode any message that the <i>RsslRDMMsg</i> can represent. This function takes the <i>RsslRDMMsg</i> as a parameter.
<i>rsslDecodeRDMMsg</i>	Used to decode any message that the <i>RsslRDMMsg</i> can represent. This function populates the <i>RsslRDMMsg</i> and leverages the Value Added Utility message buffer (refer to Section 9.2).
	<b>Note:</b> The decoded message may refer to encoded data from the original <i>RsslMsg</i> . If the message is to be stored, the appropriate copy function for the decoded <i>RsslRDMMsg</i> should be used to create a full copy.

Table 98: RDM Encoding and Decoding Functions

## 8.3 RDM Login Domain

The Login domain registers a user with the system, after which the user can request<sup>1</sup>, post<sup>2</sup>, or provide<sup>3</sup> OMM content.

- A consumer application must log into the system before it can request or post content.
- A non-interactive provider (NIP) application must log into the system before providing content. An interactive provider application must handle login requests and provide login response messages, possibly using DACS to authenticate users.

Section 8.3.1 - Section 8.3.9 detail the layout and use of each message structure in the Login portion of the Administration Domain Message Component.

1. Consumer applications can request content after logging into the system.
2. Consumer applications can post content (similar to contributions or unmanaged publications) after logging into the system.
3. Non-interactive provider applications.

### 8.3.1 RSSL RDM Login Request

A **Login Request** message is encoded and sent by OMM consumer and OMM non-interactive provider applications. This message registers a user with the system. After receiving a successful login response, applications can then begin consuming or providing additional content. An OMM provider can use the login request information to authenticate users with DACS.

The **RsslRDMLLoginRequest** represents all members of a login request message and allows for simplified use in OMM applications that leverage RDM. This structure follows the behavior and layout that is defined in the *Transport API C Edition RDM Usage Guide*.

#### 8.3.1.1 RSSL RDM Login Request Structure Members

STRUCTURE MEMBER	DESCRIPTION
allowSuspectData	<p><b>Optional.</b> If present, a <b>flags</b> value of <b>RDM_LG_RQF_HAS_ALLOW_SUSPECT_DATA</b> should be specified. If absent, a default value of <b>1</b> is assumed.</p> <ul style="list-style-type: none"> <li><b>1:</b> Indicates that the consumer application allows for suspect <b>streamState</b> information.</li> <li><b>0:</b> Indicates that the consumer application prefers any suspect data to result in the stream being closed with an <b>RSSL_STREAM_CLOSED_RECOVER</b> state.</li> </ul>
applicationId	<p><b>Optional.</b> If present, a <b>flags</b> value of <b>RDM_LG_RQF_HAS_APPLICATION_ID</b> should be specified.</p> <p>When populated, should contain the DACS <b>applicationId</b>. If the server authenticates with DACS, the consumer application may be required to pass in a valid application id. If initializing <b>RsslRDMLLoginRequest</b> using <b>rsslInitDefaultRDMLLoginRequest</b>, an <b>applicationId</b> of <b>256</b> will be used.</p>
applicationName	<p><b>Optional.</b> If present, a <b>flags</b> value of <b>RDM_LG_RQF_HAS_APPLICATION_NAME</b> should be specified.</p> <p>When present, the <b>applicationName</b> in the login request identifies the OMM consumer or OMM non-interactive provider.</p> <p>If initializing <b>RsslRDMLLoginRequest</b> using <b>rsslInitDefaultRDMLLoginRequest</b>, the name <b>upa</b> will be used.</p>
authenticationExtended	<p><b>Optional.</b> If present, a <b>flags</b> value of <b>RDM_LG_RQF_HAS_AUTHN_EXTENDED</b> should be specified.</p> <p>When populated, <b>authenticationExtended</b> contains additional content that will be passed to the token authenticator as an additional means to verifying a user's identity.</p>
downloadConnectionConfig	<p><b>Optional.</b> If present, a <b>flags</b> value of <b>RDM_LG_RQF_HAS_DOWNLOAD_CONN_CONFIG</b> should be specified. If absent, a default value of <b>0</b> is assumed.</p> <p>Enabling this option allows the application to download information about other providers on the network. You can use such downloaded information to load balance connections across multiple providers.</p> <ul style="list-style-type: none"> <li><b>1:</b> Indicates that the user wants to download connection configuration information.</li> <li><b>0:</b> Indicates that the user does not want to download connection information.</li> </ul>
flags	<p><b>Required.</b> Indicate presence of optional login request members. For details, refer to Section 8.3.1.2.</p>

**Table 99: RsslRDMLLoginRequest Structure Members**

STRUCTURE MEMBER	DESCRIPTION
instanceId	<p><b>Optional.</b> If present, a <b>flags</b> value of <b>RDM_LG_RQF_HAS_INSTANCE_ID</b> should be specified.</p> <p>You can use the <b>instanceId</b> to differentiate applications running on the same machine. However, because <b>instanceId</b> is set by the user logging into the system, it does not guarantee uniqueness across different applications on the same machine.</p>
password	<p><b>Optional.</b> If present, a <b>flags</b> value of <b>RDM_LG_RQF_HAS_PASSWORD</b> should be specified.</p> <p>When necessary, this should be set to the <b>password</b> for logging into the system. See specific component documentation to determine password requirements and how to obtain one.</p>
position	<p><b>Optional.</b> If present, a <b>flags</b> value of <b>RDM_LG_RQF_HAS_POSITION</b> should be specified.</p> <p>When populated, should contain the DACS <b>position</b>. If the server is authenticating with DACS, the consumer application might be required to pass in a valid position.</p> <p>If initializing <b>RsslRDMLLoginRequest</b> using <b>rsslInitDefaultRDMLLoginRequest</b>, the IP address of the system the application is running on will be used.</p>
providePermissionExpressions	<p><b>Optional.</b> If present, a <b>flags</b> value of <b>RDM_LG_RQF_HAS_PROVIDE_PERM_EXPR</b> should be specified. If absent, a default value of <b>1</b> is assumed.</p> <p>When <b>1</b>, this indicates a consumer wants permission expression information to be sent with responses. Permission expressions allow for items to be proxy permissioned by a consumer via content-based entitlements.</p>
providePermissionProfile	<p><b>Optional.</b> If present, a <b>flags</b> value of <b>RDM_LG_RQF_HAS_PROVIDE_PERM_PROFILE</b> should be specified. If not present, a default value of <b>1</b> is assumed.</p> <p>When <b>1</b>, this indicates that a consumer desires the permission profile. The permission profile can be used by an application to perform proxy permissioning.</p>
rdmMsgBase	<p><b>Required.</b> Contains general message information like <b>streamId</b> and <b>domainType</b>. For more information, refer to Section 8.2.</p>
role	<p><b>Optional.</b> If present, a <b>flags</b> value of <b>RDM_LG_RQF_HAS_ROLE</b> should be specified. If absent, a default value of <b>RDM_LOGIN_ROLE_CONS</b> is assumed.</p> <p>Indicates the role of the application logging onto the system.</p> <ul style="list-style-type: none"> <li>• <b>0: RDM_LOGIN_ROLE_CONS</b>, indicates application is a consumer.</li> <li>• <b>1: RDM_LOGIN_ROLE_PROV</b>, indicates application is a provider.</li> </ul>
singleOpen	<p><b>Optional.</b> If present, a <b>flags</b> value of <b>RDM_LG_RQF_HAS_SINGLE_OPEN</b> should be specified. If absent, a default value of <b>1</b> is assumed.</p> <ul style="list-style-type: none"> <li>• <b>1:</b> Indicates the consumer application wants the provider to drive stream recovery.</li> <li>• <b>0:</b> Indicates that the consumer application will drive stream recovery.</li> </ul>

Table 99: **RsslRDMLLoginRequest** Structure Members (Continued)

STRUCTURE MEMBER	DESCRIPTION
supportProviderDictionaryDownload	<p><b>Optional.</b> If present, a <b>flags</b> value of <b>RDM_LG_RQF_HAS_SUPPORT_PROV_DIC_DOWNLOAD</b> should be specified. If absent, a default value of <b>0</b> is assumed.</p> <p>Indicates whether the ADH supports the Provider Dictionary Download feature, which allows the application to request RWFFId and RFFEnum dictionaries from ADH.</p> <ul style="list-style-type: none"> <li>• <b>1</b>: The ADH supports the Provider Dictionary Download feature.</li> <li>• <b>0</b>: The ADH does not support the Provider Dictionary Download feature.</li> </ul> <p>For details on the Provider Dictionary Download feature, refer to the <i>Transport API C Edition Developers Guide</i>.</p>
userName	<p><b>Required.</b> Populate this member with the username, email address, or user token based on the <b>userNameType</b> specification.</p> <p>If you initialize <b>RsslRDMLLoginRequest</b> using <b>rsslInitDefaultRDMLLoginRequest</b>, it uses the name of the user currently logged into the system on which the application runs.</p>
userNameType	<p><b>Optional.</b> If present, a <b>flags</b> value of <b>RDM_LG_RQF_HAS_USERNAME_TYPE</b> should be specified. If absent, a default value of <b>RDM_LOGIN_USER_NAME</b> is assumed.</p> <p>Possible values:</p> <ul style="list-style-type: none"> <li>• <b>RDM_LOGIN_USER_NAME == 1</b></li> <li>• <b>RDM_LOGIN_USER_EMAIL_ADDRESS == 2</b></li> <li>• <b>RDM_LOGIN_USER_TOKEN == 3</b></li> <li>• <b>RDM_LOGIN_USER_COOKIE == 4</b></li> <li>• <b>RDM_LOGIN_USER_AUTHN_TOKEN==5</b></li> </ul> <p>A type of <b>RDM_LOGIN_USER_NAME</b> typically corresponds to a DACS user name and can to authenticate and permission a user.</p> <p><b>RDM_LOGIN_USER_TOKEN</b> is specified when using the AAA ('triple A') API. The user token is retrieved from the Authentication Manager application. To validate users, a provider application passes this user token to the AAA Gateway. This type of token periodically changes: when it changes, an application can send a login reissue to pass information upstream. For more information, refer to documentation specific to the AAA API.</p> <p><b>RDM_LOGIN_USER_AUTHN_TOKEN</b> is specified when using TREP Authentication. The authentication token should be specified in the <b>userName</b> member. This type of token can periodically change: when it changes, an application can send a login reissue to pass information upstream. For more information, refer to the <i>TREP Authentication User Manual</i>.<sup>a</sup></p>

Table 99: **RsslRDMLLoginRequest** Structure Members (Continued)

a. For further details on TREP Authentication, refer to the *TREP Authentication User Manual*, accessible on [Thomson Reuters MyAccount](#) in the DACS product documentation set.

## 8.3.1.2 RSSL RDM Login Request Flag Enumeration Values

FLAG ENUMERATION	MEANING
RDM_LG_RQF_HAS_ALLOW_SUSPECT_DATA	Indicates the presence of <b>allowSuspectData</b> . If not present, a value of <b>1</b> should be assumed.
RDM_LG_RQF_HAS_APPLICATION_ID	Indicates the presence of <b>applicationId</b> .
RDM_LG_RQF_HAS_APPLICATION_NAME	Indicates the presence of <b>applicationName</b> .
RDM_LG_RQF_HAS_AUTHN_EXTENDED	Indicates the presence of <b>authenticationExtended</b> .
RDM_LG_RQF_HAS_DOWNLOAD_CONN_CONFIG	Indicates the presence of <b>downloadConnectionConfig</b> . If absent, a value of <b>0</b> should be assumed.
RDM_LG_RQF_HAS_INSTANCE_ID	Indicates the presence of <b>instanceId</b> .
RDM_LG_RQF_HAS_PASSWORD	Indicates the presence of <b>password</b> .
RDM_LG_RQF_HAS_POSITION	Indicates the presence of <b>position</b> .
RDM_LG_RQF_HAS_PROVIDE_PERM_EXPR	Indicates the presence of <b>providePermissionExpressions</b> . If not present, a value of <b>1</b> should be assumed.
RDM_LG_RQF_HAS_PROVIDE_PERM_PROFILE	Indicates the presence of <b>providePermissionProfile</b> . If not present, a value of <b>1</b> should be assumed.
RDM_LG_RQF_HAS_ROLE	Indicates the presence of <b>role</b> . If absent, a role of <b>RDM_LOGIN_ROLE_CONS</b> is assumed.
RDM_LG_RQF_HAS_SINGLE_OPEN	Indicates the presence of <b>singleOpen</b> . If not present, a value of <b>1</b> should be assumed.
RDM_LG_RQF_HAS_USERNAME_TYPE	Indicates the presence of <b>userNameType</b> . If not present, a <b>userNameType</b> of <b>RDM_LOGIN_USER_NAME</b> should be assumed.
RDM_LG_RQF_PAUSE_ALL	Indicates that the consumer wants to pause all streams associated with the logged in user. For more information on pause and resume behavior, refer to the <i>Transport API C Edition Developers Guide</i> .
RDM_LG_RQF_NO_REFRESH	Indicates that the consumer application does not require a login refresh for this request. This typically occurs when resuming a stream or changing a AAA token. In some instances, a provider can still deliver a refresh message, however if such a message is not explicitly asked for by the consumer, it is considered unsolicited.
RDM_LG_RQF_HAS_SUPPORT_PROV_DIC_DOWNLOAD	Indicates the presence of <b>supportProviderDictionaryDownload</b> . If absent, a value of <b>0</b> should be assumed. For more information on Provider Dictionary Download, refer to the <i>Transport API C Edition Developers Guide</i> .

Table 100: **RsslRDMLoginRequest** Flags

### 8.3.1.3 RSSL RDM Login Request Utility Functions

FUNCTION NAME	DESCRIPTION
<code>rsslClearRDMLLoginRequest</code>	Clears an <code>RsslRDMLLoginRequest</code> structure. Useful for structure reuse.
<code>rsslInitDefaultRDMLLoginRequest</code>	Clears an <code>RsslRDMLLoginRequest</code> structure and populates <code>userName</code> , <code>position</code> , <code>applicationId</code> , and <code>applicationName</code> with default values.
<code>rsslCopyRDMLLoginRequest</code>	Performs a deep copy of an <code>RsslRDMLLoginRequest</code> structure.

Table 101: `RsslRDMLLoginRequest` Utility Functions

### 8.3.2 RSSL RDM Login Refresh

A **Login Refresh** message is encoded and sent by an OMM interactive provider application and responds to a Login Request message. A login refresh message indicates that the user's Login is accepted. An OMM Provider can use information from the login request to authenticate users with DACS. After authentication, a refresh message is sent to convey that the login was accepted. If the login is rejected, a login status message should be sent as described in Section 8.3.3.

The `RsslRDMLLoginRefresh` represents all members of a login refresh message and allows for simplified use in OMM applications that leverage RDM. This structure follows the behavior and layout that is defined in the *Transport API C Edition RDM Usage Guide*.

#### 8.3.2.1 RSSL RDM Login Refresh Structure Members

STRUCTURE MEMBER	DESCRIPTION
<code>allowSuspectData</code>	<p><b>Optional.</b> If present, <code>flags</code> value of <code>RDM_LG_RFF_HAS_ALLOW_SUSPECT_DATA</code> should be specified. If absent, a default value of 1 is assumed.</p> <ul style="list-style-type: none"> <li><b>1:</b> Indicates that the consumer application allows for suspect <code>streamState</code> information.</li> <li><b>0:</b> Indicates that the consumer application prefers any suspect data to result in the stream being closed with an <code>RSSL_STREAM_CLOSED_RECOVER</code> state.</li> </ul>
<code>applicationId</code>	<p><b>Optional.</b> If present, <code>flags</code> value of <code>RDM_LG_RFF_HAS_APPLICATION_ID</code> should be specified.</p> <p>When populated, this should match the <code>applicationId</code> contained in the login request.</p>
<code>applicationName</code>	<p><b>Optional.</b> If present, <code>flags</code> value of <code>RDM_LG_RFF_HAS_APPLICATION_NAME</code> should be specified.</p> <p>When populated, the <code>applicationName</code> in the login refresh identifies the OMM provider.</p>
<code>authenticationErrorCode</code>	<p><b>Optional.</b> If present, a <code>flags</code> value of <code>RDM_LG_RFF_HAS_AUTHN_ERROR_CODE</code> should be specified.</p> <p><code>authenticationErrorCode</code> is specific to a TREP Authentication environment, where <b>0</b> indicates an error-free condition. For further information, refer to the <i>TREP Authentication User Manual</i>.<sup>a</sup></p>

Table 102: `RsslRDMLLoginRefresh` Structure Members

STRUCTURE MEMBER	DESCRIPTION
authenticationErrorText	<b>Optional.</b> If present, a <b>flags</b> value of <b>RDM_LG_RFF_HAS_AUTHN_ERROR_TEXT</b> should be specified. <b>authenticationErrorText</b> specifies any error text that accompanies an <b>authenticationErrorCode</b> . For further information, refer to the <i>TREP Authentication User Manual</i> . <sup>a</sup>
authenticationExtendedResp	<b>Optional.</b> If present, a <b>flags</b> value of <b>RDM_LG_RFF_HAS_AUTHN_EXTENDED_RESP</b> should be specified. <b>authenticationExtendedResp</b> contains additional, customer-defined data associated with the authentication token sent in the original request. For further information, refer to the <i>TREP Authentication User Manual</i> . <sup>a</sup>
authenticationTTReissue	<b>Optional.</b> If present, a <b>flags</b> value of <b>RDM_LG_RFF_HAS_AUTHN_TT_REISSUE</b> should be specified. Indicates when a new authentication token needs to be reissued (in UNIX Epoch time). For more information, refer to the <i>TREP Authentication User Manual</i> . <sup>a</sup>
flags	<b>Required.</b> Indicate the presence of optional login refresh members. For details, see Section 8.3.2.2.
numStandbyServers	<b>Optional.</b> If present, <b>flags</b> value of <b>RDM_LG_RFF_HAS_CONN_CONFIG</b> should be specified and the <b>serverList</b> member should also be specified. If not present, a default value of <b>0</b> is assumed. Indicates the number of servers in the <b>serverList</b> that the consumer is expected to use as standby servers when using Warm Standby functionality.
position	<b>Optional.</b> If present, <b>flags</b> value of <b>RDM_LG_RFF_HAS_POSITION</b> should be specified. When populated, this should match the <b>position</b> contained in the login request.
providePermissionProfile	<b>Optional.</b> If present, <b>flags</b> value of <b>RDM_LG_RFF_HAS_PROVIDE_PERM_PROFILE</b> should be specified. If absent, a default value of <b>1</b> is assumed. When <b>1</b> , this indicates that the permission profile is provided. The permission profile can be used by an application to perform proxy permissioning.
providePermissionExpressions	<b>Optional.</b> If present, <b>flags</b> value of <b>RDM_LG_RFF_HAS_PROVIDE_PERM_EXPR</b> should be specified. If absent, a default value of <b>1</b> is assumed. When <b>1</b> , this indicates a provider will provide permission expression information with responses. Permission expressions allow for items to be proxy permissioned by a consumer via content-based entitlements.
rdmMsgBase	<b>Required.</b> Contains general message information like streamId and domainType. (i.e.,
sequenceNumber	<b>Optional.</b> A user-specified, item-level sequence number which can be used by the application for sequencing messages within this stream.
serverCount	<b>Optional.</b> If present, <b>flags</b> value of <b>RDM_LG_RFF_HAS_CONN_CONFIG</b> should be specified and the <b>serverList</b> member should also be specified. If not present, a default value of <b>0</b> is assumed. Indicates the number of servers present in the <b>serverList</b> parameter.

Table 102: **Rss1RDMLginRefresh** Structure Members (Continued)



STRUCTURE MEMBER	DESCRIPTION
serverList	<p><b>Optional.</b> If present, <b>flags</b> value of <b>RDM_LG_RFF_HAS_CONN_CONFIG</b> should be specified and the <b>serverCount</b> and <b>numStandbyServers</b> members should also be specified.</p> <p>An array of servers that the consumer may connect to when using Warm Standby functionality.</p>
singleOpen	<p><b>Optional.</b> If present, <b>flags</b> value of <b>RDM_LG_RFF_HAS_SINGLE_OPEN</b> should be specified. If absent, a default value of <b>1</b> is assumed.</p> <ul style="list-style-type: none"> <li>• <b>1</b>: Indicates the consumer application wants the provider to drive stream recovery.</li> <li>• <b>0</b>: Indicates that the consumer application will drive stream recovery.</li> </ul>
state	<p><b>Required.</b> Indicates the state of the login stream.</p> <p>Defaults to a <b>streamState</b> of <b>RSSL_STREAM_OPEN</b> and a <b>dataState</b> of <b>RSSL_DATA_OK</b>.</p> <p>For more information on <b>RsslState</b>, refer to the <i>Transport API C Edition Developers Guide</i>.</p>
supportBatchRequests	<p><b>Optional.</b> If present, <b>flags</b> value of <b>RDM_LG_RFF_HAS_SUPP_BATCH</b> should be specified. If absent, a default value of <b>0</b> is assumed.</p> <p>Indicates whether the provider supports batch functionality. Batch functionality allows a consumer to specify multiple items, all with matching attributes, in the same request message.</p> <ul style="list-style-type: none"> <li>• <b>1</b>: The provider supports batch requesting.</li> <li>• <b>0</b>: The provider does not support batch requesting.</li> </ul> <p>For more information on batch requesting, refer to the <i>Transport API C Edition Developers Guide</i>.</p>
supportEnhancedSymbolList	<p><b>Optional.</b> If present, a <b>flags</b> value of <b>RDM_LG_RFF_HAS_SUPPORT_ENH_SL</b> should be specified. If absent, a default value of <b>0x0</b> is assumed.</p> <p>Advertises, via flags, additional features that the provider supports for the <b>Symbol List</b> domain, such as providing data streams for the items present in a requested <b>Symbol List</b> item.</p> <ul style="list-style-type: none"> <li>• <b>0x0</b>: The provider does not support any Symbol List enhancements.</li> <li>• <b>0x1</b>: The provider supports providing Symbol List data streams.</li> </ul> <p>For more information on <b>Symbol List</b> requestable behaviors, refer to the <i>Transport API C Edition RDM Usage Guide</i>.</p>
supportOMMPost	<p><b>Optional.</b> If present, <b>flags</b> value of <b>RDM_LG_RFF_HAS_SUPP_POST</b> should be specified. If absent, a default value of <b>0</b> is assumed.</p> <p>Indicates whether the provider supports OMM Posting:</p> <ul style="list-style-type: none"> <li>• <b>1</b>: The provider supports OMM Posting and the user is permissioned.</li> <li>• <b>0</b>: The provider supports the OMM Post feature, but the user is not permissioned.</li> <li>• If this element is not present, then the server does not support OMM Post feature.</li> </ul> <p>For more information on Posting, refer to the <i>Transport API C Edition Developers Guide</i>.</p>

Table 102: **RsslRDMLoginRefresh** Structure Members (Continued)



STRUCTURE MEMBER	DESCRIPTION
supportOptimizedPauseResume	<p><b>Optional.</b> If present, <b>flags</b> value of <b>RDM_LG_RFF_HAS_SUPP_OPT_PAR</b> should be specified. If not present, a default value of <b>0</b> is assumed.</p> <p>Indicates whether the provider supports Optimized Pause and Resume. Optimized Pause and Resume allows for pausing/resuming of individual item streams or pausing all item streams via a pause of the login stream.</p> <ul style="list-style-type: none"> <li>• <b>1</b>: The server supports optimized pause and resume.</li> <li>• <b>0</b>: The server does not support optimized pause and resume.</li> </ul> <p>For more information on Pause and Resume, refer to the <i>Transport API C Edition Developers Guide</i>.</p>
supportProviderDictionaryDownload	<p><b>Optional.</b> If present, a <b>flags</b> value of <b>RDM_LG_RFF_HAS_SUPPORT_PROV_DIC_DOWNLOAD</b> should be specified. If absent, a default value of <b>0</b> is assumed.</p> <p>Indicates whether the ADH supports the Provider Dictionary Download feature, which allows a user to request RWFFId and RFFEnum dictionaries from ADH.</p> <ul style="list-style-type: none"> <li>• <b>1</b>: The ADH supports the Provider Dictionary Download feature.</li> <li>• <b>0</b>: The ADH does not support the Provider Dictionary Download feature.</li> </ul> <p>For more information on Provider Dictionary Download, refer to the <i>Transport API C Edition Developers Guide</i>.</p>
supportStandby	<p><b>Optional.</b> If present, <b>flags</b> value of <b>RDM_LG_RFF_HAS_SUPP_STANDBY</b> should be specified. If absent, a default value of <b>0</b> is assumed.</p> <p>Indicates whether the provider supports Warm Standby functionality. If supported, a provider can be told to run as an Active or a Standby server, where the Active will behave as usual. The Standby will respond to item requests only with the message header and will forward any state changing information. When informed of an Active's failure, the Standby begins sending responses and assumes Active functionality.</p> <ul style="list-style-type: none"> <li>• <b>1</b>: The provider can support a role of Active or Standby in a Warm Standby group.</li> <li>• <b>0</b>: The provider does not support warm standby functionality.</li> </ul>
supportViewRequests	<p><b>Optional.</b> If present, <b>flags</b> value of <b>RDM_LG_RFF_HAS_SUPP_VIEW</b> should be specified. If absent, a default value of <b>0</b> is assumed.</p> <p>Indicates whether the provider supports Dynamic View functionality. A Dynamic View allows a user to request only the specific contents of the response information in which they are interested.</p> <ul style="list-style-type: none"> <li>• <b>1</b>: The provider supports Dynamic View functionality.</li> <li>• <b>0</b>: The provider does not support Dynamic View functionality.</li> </ul> <p>For more information on Dynamic View use, refer to the <i>Transport API C Edition Developers Guide</i>.</p>
userName	<p><b>Optional.</b> If present, a <b>flags</b> value of <b>RDM_LG_RFF_HAS_USERNAME</b> should be specified.</p> <p>If populated, this should match the <b>userName</b> contained in the login request.</p>

Table 102: **Rss1RDMLginRefresh** Structure Members (Continued)

STRUCTURE MEMBER	DESCRIPTION
userNameType	<p><b>Optional.</b> If present, a <b>flags</b> value of <b>RDM_LG_RFF_HAS_USERNAME_TYPE</b> should be specified. If absent, a default value of <b>RDM_LOGIN_USER_NAME</b> is assumed.</p> <p>Possible values:</p> <ul style="list-style-type: none"> <li>• <b>RDM_LOGIN_USER_NAME == 1</b></li> <li>• <b>RDM_LOGIN_USER_EMAIL_ADDRESS == 2</b></li> <li>• <b>RDM_LOGIN_USER_TOKEN == 3</b></li> <li>• <b>RDM_LOGIN_USER_COOKIE==4</b></li> <li>• <b>RDM_LOGIN_USER_AUTHN_TOKEN==5</b></li> </ul> <p>A type of <b>RDM_LOGIN_USER_NAME</b> typically corresponds to a DACS user name and can be used to authenticate and permission a user.</p> <p><b>RDM_LOGIN_USER_TOKEN</b> is specified when using the AAA ('triple A') API. The user token is retrieved from the Authentication Manager application. To validate users, a provider application passes this user token to the AAA Gateway. This type of token periodically changes: when it changes, an application can send a login reissue to pass information upstream. For more information, refer to documentation specific to the AAAAPI.</p> <p><b>RDM_LOGIN_USER_AUTHN_TOKEN</b> is specified when using TREP Authentication. The authentication token should be specified in the <b>userName</b> member. This type of token can periodically change: when it changes, an application can send a login reissue to pass information upstream. For more information, refer to the <i>TREP Authentication User Manual</i>.<sup>a</sup></p>

Table 102: **Rss1RDMLLoginRefresh** Structure Members (Continued)

a. For further details on TREP Authentication, refer to the *TREP Authentication User Manual*, accessible on [Thomson Reuters MyAccount](#) in the DACS product documentation set.

### 8.3.2.2 RSSL RDM Login Refresh Flag Enumeration Values

FLAG ENUMERATION	DESCRIPTION
RDM_LG_RFF_CLEAR_CACHE	Indicates to clear stored payload information associated with the login stream. This might occur if some portion of data is known to be invalid.
RDM_LG_RFF_HAS_ALLOW_SUSPECT_DATA	Indicates the presence of <b>allowSuspectData</b> . If absent, a value of <b>1</b> should be assumed.
RDM_LG_RFF_HAS_APPLICATION_ID	Indicates the presence of <b>applicationId</b> .
RDM_LG_RFF_HAS_APPLICATION_NAME	Indicates the presence of <b>applicationName</b> .
RDM_LG_RFF_HAS_AUTHN_ERROR_CODE	Indicates the presence of <b>authenticationErrorCode</b> .
RDM_LG_RFF_HAS_AUTHN_ERROR_TEXT	Indicates the presence of <b>authenticationErrorText</b> .
RDM_LG_RFF_HAS_AUTHN_EXTENDED_RESP	Indicates the presence of <b>authenticationExtendedResp</b> .
RDM_LG_RFF_HAS_AUTHN_TT_REISSUE	Indicates the presence of <b>authenticationTTReissue</b> .

Table 103: **Rss1RDMLLoginRefresh** Flags

FLAG ENUMERATION	DESCRIPTION
RDM_LG_RFF_HAS_CONN_CONFIG	Indicates the presence of connection configuration information.
RDM_LG_RFF_HAS_POSITION	Indicates the presence of <b>position</b> .
RDM_LG_RFF_HAS_PROVIDE_PERM_EXPR	Indicates the presence of <b>providePermissionExpressions</b> . If absent, a value of <b>1</b> should be assumed.
RDM_LG_RFF_HAS_PROVIDE_PERM_PROFILE	Indicates the presence of <b>providePermissionProfile</b> . If absent, a value of <b>1</b> should be assumed.
RDM_LG_RFF_HAS_SEQ_NUM	Indicates the presence of <b>numStandbyServers</b> , <b>serverCount</b> , and <b>serverList</b> .
RDM_LG_RFF_HAS_SINGLE_OPEN	Indicates the presence of <b>singleOpen</b> . If absent, a value of <b>1</b> should be assumed.
RDM_LG_RFF_HAS_SUPP_BATCH	Indicates the presence of <b>supportBatchRequests</b> . If absent, a value of <b>0</b> should be assumed. For more information on Batch functionality, refer to the <i>Transport API C Edition Developers Guide</i> .
RDM_LG_RFF_HAS_SUPP_POST	Indicates the presence of <b>supportOMMPost</b> . If absent, a value of <b>0</b> should be assumed. For more information on Posting, refer to the <i>Transport API C Edition Developers Guide</i> .
RDM_LG_RFF_HAS_SUPPORT_PROV_DIC_DOWNLOAD	Indicates the presence of <b>supportProviderDictionaryDownload</b> . If absent, a value of <b>0</b> should be assumed. For more information on Provider Dictionary Download, refer to the <i>Transport API C Edition Developers Guide</i> .
RDM_LG_RFF_HAS_SUPP_OPT_PAR	Indicates the presence of <b>supportOptimizedPauseResume</b> . If absent, a value of <b>0</b> should be assumed. For more information on Pause and Resume, refer to the <i>Transport API C Edition Developers Guide</i> .
RDM_LG_RFF_HAS_SUPP_VIEW	Indicates the presence of <b>supportViewRequests</b> . If absent, a value of <b>0</b> should be assumed. For more information on View functionality, refer to the <i>Transport API C Edition Developers Guide</i> .
RDM_LG_RFF_HAS_SUPP_STANDBY	Indicates the presence of <b>supportStandby</b> . If absent, a value of <b>0</b> should be assumed.
RDM_LG_RFF_HAS_USERNAME	Indicates the presence of <b>userName</b> .
RDM_LG_RFF_HAS_USERNAME_TYPE	Indicates the presence of <b>userNameType</b> . If absent, a <b>userNameType</b> of <b>RDM_LOGIN_USER_NAME</b> should be assumed.

Table 103: **Rss1RDMLoginRefresh** Flags (Continued)

FLAG ENUMERATION	DESCRIPTION
RDM_LG_RFF_SOLICITED	<ul style="list-style-type: none"> <li>If present, this flag indicates that the login refresh is solicited (e.g., it is in response to a request).</li> <li>If this flag is absent, this refresh is unsolicited.</li> </ul>

Table 103: **RsslRDMLoginRefresh** Flags (Continued)

### 8.3.2.3 RSSL RDM Login Refresh Utility Functions

FUNCTION NAME	DESCRIPTION
rsslClearRDMLLoginRefresh	Clears an <b>RsslRDMLoginRefresh</b> structure. Useful for structure reuse.
rsslCopyRDMLLoginRefresh	Performs a deep copy of an <b>RsslRDMLoginRefresh</b> structure.

Table 104: **RsslRDMLoginRefresh** Utility Functions

### 8.3.2.4 RSSL RDM Server Info Structure Members

STRUCTURE MEMBER	DESCRIPTION
flags	<b>Required.</b> Indicates the presence of optional server information members. For details, refer to Section 8.3.2.5.
hostname	<b>Required.</b> Indicates the server's <b>hostname</b> .
loadFactor	<b>Optional.</b> Indicates the load information for this server. If present, a <b>flags</b> value of <b>RDM_LG_SIF_HAS_LOAD_FACTOR</b> should be specified.
port	<b>Required.</b> Indicates the server's port number for connections.
serverIndex	<b>Required.</b> Provides the index value to this server.
serverType	<b>Optional.</b> Indicates whether this server is an active or standby server. If present, a <b>flags</b> value of <b>RDM_LG_SIF_HAS_TYPE</b> should be specified, populated by <b>RDMLoginServerTypes</b> .

Table 105: **RsslRDMServerInfo** Structure Members

### 8.3.2.5 RSSL RDM Server Info Flag Enumeration Values

FLAG ENUMERATION	DESCRIPTION
RDM_LG_SIF_HAS_LOAD_FACTOR	Indicates presence of <b>loadFactor</b> information.
RDM_LG_SIF_HAS_TYPE	Indicates presence of <b>serverType</b> .

Table 106: **RsslRDMServerInfo** Flags

### 8.3.2.6 RSSL RDM Server Info Utility Functions

FUNCTION NAME	DESCRIPTION
<code>rsslClearRDMServerInfo</code>	Clears an <code>RsslRDMServerInfo</code> structure. Useful for structure reuse.

**Table 107: `RsslRDMServerInfo` Utility Functions**

### 8.3.3 RSSL RDM Login Status

OMM Provider and OMM non-interactive provider applications use the **Login Status** message to convey state information associated with the login stream. Such state information can indicate that a login stream cannot be established or to inform a consumer of a state change associated with an open login stream.

The login status message can also reject a login request or close an existing login stream. When a status message closes a login stream, any other open streams associated with the user are also closed.

The **RsslRDMLoginStatus** represents all members of a login status message and allows for simplified use in OMM applications that leverage RDM. This structure follows the behavior and layout defined in the *Transport API C Edition RDM Usage Guide*.

#### 8.3.3.1 RSSL RDM Login Status Structure Members

STRUCTURE MEMBER	DESCRIPTION
authenticationErrorCode	<b>Optional.</b> If present, a <b>flags</b> value of <b>RDM_LG_STF_HAS_AUTHN_ERROR_CODE</b> should be specified. <b>authenticationErrorCode</b> is specific to deployments using TREP Authentication, and specifies an error code. A code of <b>0</b> indicates no error condition. For further information, refer to the <i>TREP Authentication User Manual</i> . <sup>a</sup>
authenticationErrorText	<b>Optional.</b> If present, a <b>flags</b> value of <b>RDM_LG_STF_HAS_AUTHN_ERROR_TEXT</b> should be specified. Specifies any text associated with the specified <b>authenticationErrorCode</b> . For further information, refer to the <i>TREP Authentication User Manual</i> . <sup>a</sup>
flags	<b>Required.</b> Indicates the presence of optional login status members. For details, refer to Section 8.3.3.2.
rdmMsgBase	<b>Required.</b> Contains general message information, such as <b>streamId</b> and <b>domainType</b> .
state	<b>Optional.</b> If present, a flags value of <b>RDM_LG_STF_HAS_STATE</b> should be specified. Indicates the state of the login stream. When rejecting a login the state should be: <ul style="list-style-type: none"> <li>• <b>streamState</b> = <b>RSSL_STREAM_CLOSED</b> or <b>RSSL_STREAM_CLOSED_RECOVER</b></li> <li>• <b>dataState</b> = <b>RSSL_DATA_SUSPECT</b></li> <li>• <b>stateCode</b> = <b>RSSL_SC_NOT_ENTITLED</b></li> </ul> For more information on <b>RsslState</b> , refer to the <i>Transport API C Edition Developers Guide</i> .

Table 108: **RsslRDMLoginStatus** Structure Members

STRUCTURE MEMBER	DESCRIPTION
userNameType	<p><b>Optional.</b> If present, a <b>flags</b> value of <b>RDM_LG_STF_HAS_USERNAME_TYPE</b> should be specified. If absent, a default value of <b>RDM_LOGIN_USER_NAME</b> is assumed.</p> <p>Possible values:</p> <ul style="list-style-type: none"> <li>• <b>RDM_LOGIN_USER_NAME == 1</b></li> <li>• <b>RDM_LOGIN_USER_EMAIL_ADDRESS == 2</b></li> <li>• <b>RDM_LOGIN_USER_TOKEN == 3</b></li> <li>• <b>RDM_LOGIN_USER_COOKIE == 4</b></li> <li>• <b>RDM_LOGIN_USER_AUTHN_TOKEN == 5</b></li> </ul> <p>A type of <b>RDM_LOGIN_USER_NAME</b> typically corresponds to a DACS user name and can be used to authenticate and permission a user.</p> <p><b>RDM_LOGIN_USER_TOKEN</b> is specified when using the AAA ('triple A') API. The user token is retrieved from the Authentication Manager application. To validate users, a provider application passes this user token to the AAA Gateway. This type of token periodically changes: when it changes, an application can send a login reissue to pass information upstream. For more information, refer to documentation specific to the AAA API.</p> <p><b>RDM_LOGIN_USER_AUTHN_TOKEN</b> is specified when using TREP Authentication. The authentication token should be specified in the <b>userName</b> member. This type of token can periodically change: when it changes, an application can send a login reissue to pass information upstream. For more information, refer to the <i>TREP Authentication User Manual</i>.<sup>a</sup></p>
userName	<p><b>Optional.</b> If present, a <b>flags</b> value of <b>RDM_LG_STF_HAS_USERNAME</b> should be specified.</p> <p>When populated, this should match the <b>userName</b> in the login request.</p>

**Table 108: Rss1RDMLginStatus Structure Members (Continued)**

a. For further details on TREP Authentication, refer to the *TREP Authentication User Manual*, accessible on [Thomson Reuters MyAccount](#) in the DACS product documentation set.

### 8.3.3.2 RSSL RDM Login Status Flag Enumeration Values

FLAG ENUMERATION	MEANING
RDM_LG_STF_CLEAR_CACHE	Indicates whether the receiver of the login status should clear any associated cache information.
RDM_LG_STF_HAS_AUTHN_ERROR_CODE	Indicates the presence of <b>authenticationErrorCode</b> .
RDM_LG_STF_HAS_AUTHN_ERROR_TEXT	Indicates the presence of <b>authenticationErrorText</b> .
RDM_LG_STF_HAS_STATE	Indicates the presence of <b>state</b> . If absent, any previously conveyed state continues to apply.
RDM_LG_STF_HAS_USERNAME	Indicates the presence of <b>userName</b> .

**Table 109: Rss1RDMLginStatus Flags**

FLAG ENUMERATION	MEANING
RDM_LG_STF_HAS_USERNAME_TYPE	Indicates the presence of <code>userNameType</code> . If absent a <code>userNameType</code> of <code>RDM_LOGIN_USER_NAME</code> is assumed.

Table 109: `RsslRDMLoginStatus` Flags (Continued)

### 8.3.3.3 RSSL RDM Login Status Utility Functions

FUNCTION NAME	DESCRIPTION
<code>rsslClearRDMLoginStatus</code>	Clears an <code>RsslRDMLoginStatus</code> structure. Useful for structure reuse.
<code>rsslCopyRDMLoginStatus</code>	Performs a deep copy of an <code>RsslRDMLoginStatus</code> structure.

Table 110: `RsslRDMLoginStatus` Utility Functions

### 8.3.4 RSSL RDM Login Close

A **Login Close** message is encoded and sent by OMM consumer applications. This message allows a consumer to log out of the system. Closing a login stream is equivalent to a **Close All** type of message, where all open streams are closed (i.e., all streams associated with the user). A provider can log off a user and close all of that user's streams via a login status message, see Section 8.3.3.

#### 8.3.4.1 RSSL RDM Login Close Structure Member

STRUCTURE MEMBER	DESCRIPTION
<code>rdmMsgBase</code>	Contains general message information like <code>streamId</code> and <code>domainType</code> .

Table 111: `RsslRDMLoginClose` Structure Member

#### 8.3.4.2 RSSL RDM Login Close Utility Functions

FUNCTION NAME	DESCRIPTION
<code>rsslClearRDMLoginClose</code>	Clears an <code>RsslRDMLoginClose</code> structure. Useful for structure reuse.
<code>rsslCopyRDMLoginClose</code>	Performs a deep copy of an <code>RsslRDMLoginClose</code> structure.

Table 112: `RsslRDMLoginClose` Utility Functions

### 8.3.5 RSSL RDM Consumer Connection Status

The **Login Consumer Connection Status** informs an interactive provider of its role in a **Warm Standby** group, either as an **Active** or **Standby** provider. An active provider behaves normally; however a standby provider responds to requests only with a message header (allowing a consumer application to confirm the availability of requested data across active and standby servers), and forwards any state-related messages (i.e., unsolicited refresh messages, status messages). A standby provider aggregates changes to item streams whenever possible. If a provider changes from Standby to Active via this message, all aggregated update messages are passed along. If aggregation is not possible, a full, unsolicited refresh message is passed along.

The consumer application is responsible for ensuring that items are available and equivalent across all providers in a warm standby group. This includes managing state and availability differences as well as item group differences.



The `RsslRDMLLoginConsumerConnectionStatus` relies on the `RsslGenericMsg` and represents all members necessary for applications that leverage RDM. This structure follows the behavior and layout that is defined in the *Transport API C Edition RDM Usage Guide*.

### 8.3.5.1 RSSL RDM Login Consumer Connection Status Structure Members

STRUCTURE MEMBER	DESCRIPTION
flags	<b>Required.</b> Indicate the presence of optional login consumer connection status members. For details, refer to Section 8.3.5.2.
rdmMsgBase	<b>Required.</b> Contains general message information like <code>streamId</code> and <code>domainType</code> . Indicates the Login Message type (for login connection status, set to <code>LoginMsgType.CONSUMER_CONNECTION_STATUS</code> ).
warmStandbyInfo	<b>Optional.</b> Includes <code>RsslRDMLLoginWarmStandbyInfo</code> to convey the state of the upstream provider. For details, refer to Section 8.3.5.3. If present, a flags value of <code>RDM_LG_CCSF_HAS_WARM_STANDBY_INFO</code> should be specified.

Table 113: `RsslRDMLLoginConsumerConnectionStatus` Structure Members

### 8.3.5.2 RSSL RDM Login Consumer Connection Status Flag Enumeration Value

FLAG ENUMERATION	DESCRIPTION
<code>RDM_LG_CCSF_HAS_WARM_STANDBY_INFO</code>	Indicates presence of <code>warmStandbyInfo</code> .

Table 114: `RsslRDMLLoginConsumerConnectionStatus` Flags

### 8.3.5.3 RSSL RDM Login Warm Standby Info Structure Members

STRUCTURE MEMBER	DESCRIPTION
action	<b>Required.</b> Indicates how a cache of Warm Standby content should apply this information. For information on <code>RsslMapEntry</code> actions, refer to the <i>Transport API C Edition Developers Guide</i> .
warmStandbyMode	<b>Required.</b> Indicates the presence of optional login consumer connection status members. For details, refer to Section 8.3.5.4.

Table 115: `RsslRDMLLoginWarmStandbyInfo` Structure Members

### 8.3.5.4 RSSL RDM Login Warm Standby Mode Enumeration Values

ENUMERATION	DESCRIPTION
<code>RDM_LOGIN_SERVER_TYPE_ACTIVE</code>	Indicates that the server is acting as the <b>active</b> or primary server in a warm standby configuration.
<code>RDM_LOGIN_SERVER_TYPE_STANDBY</code>	Indicates that the server is acting as the <b>standby</b> or backup server in a warm standby configuration.

Table 116: `RDMLLoginServerTypes` Enumeration Values

### 8.3.5.5 RSSL RDM Login Consumer Connection Status Utility Functions

FUNCTION NAME	DESCRIPTION
<code>rsslClearRDMLLoginConsumerConnectionStatus</code>	Clears an <code>RsslRDMLLoginConsumerConnectionStatus</code> structure. Useful for structure reuse.
<code>rsslClearRDMLLoginWarmStandbyInfo</code>	Clears the <code>RsslRDMLLoginWarmStandbyInfo</code> structure.
<code>rsslCopyRDMLLoginConsumerConnectionStatus</code>	Performs a deep copy of an <code>RsslRDMLLoginConsumerConnectionStatus</code> structure.

Table 117: `RsslRDMLLoginConsumerConnectionStatus` Utility Functions

### 8.3.6 Login Post Message Use

OMM consumer applications can encode and send data for any item via Post messages on the item's login stream. This is known as **off-stream posting** because items are posted without using that item's dedicated stream. Posting an item on its own dedicated stream is referred to as **on-stream posting**.

When an application is off-stream posting, `msgKey` information is required on the `RsslPostMsg`. For more details on posting, refer to the *Transport API C Edition Developers Guide*.

### 8.3.7 Login Ack Message Use

OMM Provider applications encode and send Ack messages to acknowledge the receipt of Post messages. An Ack message is used whenever a consumer posts and asks for acknowledgments. For more details on posting, see the *Transport API C Edition Developers Guide*.

### 8.3.8 RSSL RDM Login Message Union

This union can contain any of the RDM Login message types. This is provided for use with Login specific functionality.

#### 8.3.8.1 RSSL RDM Login Union

UNION MEMBERS	DESCRIPTION
<code>rdmMsgBase</code>	The message base information.
<code>request</code>	The <code>RsslRDMLLoginRequest</code> as described in Section 8.3.1.
<code>close</code>	The <code>RsslRDMLLoginClose</code> as described in Section 8.3.4.
<code>refresh</code>	The <code>RsslRDMLLoginRefresh</code> as described in Section 8.3.2.
<code>status</code>	The <code>RsslRDMLLoginStatus</code> as described in Section 8.3.3.
<code>consumerConnectionStatus</code>	The <code>RsslRDMLLoginConsumerConnectionStatus</code> as described in Section 8.3.5.

Table 118: `RsslRDMLLoginMsg` Union Members

### 8.3.8.2 RSSL RDM Login Message Utility Functions

FUNCTION NAME	DESCRIPTION
<code>rsslClearRDMLLoginMsg</code>	Clears an <code>RsslRDMLLoginMsg</code> union. Useful for reuse.
<code>rsslCopyRDMLLoginMsg</code>	Performs a deep copy of an <code>RsslRDMLLoginMsg</code> structure.

**Table 119: `RsslRDMLLoginMsg` Utility Functions**

### 8.3.9 Login Encoding and Decoding

#### 8.3.9.1 RSSL RDM Directory Login Encoding and Decoding Functions

FUNCTION NAME	DESCRIPTION
<code>rsslDecodeRDMLLoginMsg</code>	Decodes an RDM Login message. This function populates the <code>RsslRDMLLoginMsg</code> and leverages the Value Added Utility message buffer (refer to Section 9.2). Alternatively, <code>rsslDecodeRDMMsg</code> can be used to decode into an <code>RsslRDMMsg</code> .
<code>rsslEncodeRDMLLoginMsg</code>	Encodes an RDM Login message. This function takes the <code>RsslRDMLLoginMsg</code> as a parameter. Alternately, <code>rsslEncodeRDMMsg</code> can be used if encoding from an <code>RsslRDMMsg</code> .

**Table 120: RDM Login Encoding and Decoding Functions**

#### 8.3.9.2 Encoding a Login Request

```

RsslEncodeIterator encodeIter;
RsslRDMLLoginRequest loginRequest;

/* Clear the Login Request structure. */
rsslClearRDMLLoginRequest(&loginRequest);

/* Set flags indicating presence of optional members. */
loginRequest.flags =
    RDM_LG_RQF_HAS_APPLICATION_NAME
    | RDM_LG_RQF_HAS_APPLICATION_ID
    | RDM_LG_RQF_HAS_POSITION;

/* Set UserName. */
loginRequest.userName.data = "username";
loginRequest.userName.length = 8;

/* Set ApplicationName */
loginRequest.applicationName.data = "upa";
loginRequest.applicationName.length = 3;

/* Set ApplicationId */
loginRequest.applicationId.data = "256";
loginRequest.applicationId.length = 3;

```

```

/* Set Position */
loginRequest.position.data = "127.0.0.1/net";
loginRequest.position.length = 13;

/* Clear the encode iterator, set its RWF Version, and set it to a buffer for encoding into. */
rsslClearEncodeIterator(&encodeIter);
ret = rsslSetEncodeIteratorRWFVersion(&encodeIter, channelMajorVersion, channelMinorVersion);
ret = rsslSetEncodeIteratorBuffer(&encodeIter, &msgBuffer);

/* Encode the message. */
ret = rsslEncodeRDMMsg(&encodeIter, (RsslRDMMsg*)&loginRequest, &msgBuffer.length, &rsslErrorInfo);

```

### Code Example 20: Login Request Encoding Example

#### 8.3.9.3 Decoding a Login Request

```

/* The decoder may require additional space to store things such as lists. */
char memoryArray[1024];
RsslBuffer memoryBuffer = { 1024, memoryArray };

RsslDecodeIterator decodeIter;
RsslMsg msg;
RsslRDMMsg rdmmMsg;
RsslRDMLLoginRequest *pLoginRequest;

/* Clear the decode iterator, set its RWF Version, and set it to the encoded buffer. */
rsslClearDecodeIterator(&decodeIter);
ret = rsslSetDecodeIteratorRWFVersion(&decodeIter, channelMajorVersion, channelMinorVersion);
ret = rsslSetDecodeIteratorBuffer(&decodeIter, &msgBuffer);

/* Decode the message to an RsslMsg structure and RsslRDMMsg structure. */
ret = rsslDecodeRDMMsg(&decodeIter, &msg, &rdmmMsg, &memoryBuffer, &rsslErrorInfo);

if (ret == RSSL_RET_SUCCESS
    && rdmmMsg.rdmMsgBase.domainType == RSSL_DMT_LOGIN && rdmmMsg.rdmMsgBase.rdmMsgType ==
    RDM_LG_MT_REQUEST)
{
    /* The message we decoded is an RsslRDMLLoginRequest. */
    pLoginRequest = &rdmmMsg.loginMsg.request;

    /* Print username. */
    printf("Username: %.*s\n", pLoginRequest->userName.length, pLoginRequest->userName.data);

    /* Print ApplicationName if present. */
    if (pLoginRequest->flags & RDM_LG_RQF_HAS_APPLICATION_NAME)
        printf("ApplicationName: %.*s\n", pLoginRequest->applicationName.length, pLoginRequest->
            applicationName.data);
}

```

```

/* Print ApplicationId if present. */
if (pLoginRequest->flags & RDM_LG_RQF_HAS_APPLICATION_ID)
    printf("ApplicationId: %.*s\n", pLoginRequest->applicationId.length, pLoginRequest->applicationId.data);

/* Print Position if present. */
if (pLoginRequest->flags & RDM_LG_RQF_HAS_POSITION)
    printf("Position: %.*s\n", pLoginRequest->position.length, pLoginRequest->position.data);
}

```

### Code Example 21: Login Request Decoding Example

#### 8.3.9.4 Encoding a Login Refresh

```

RsslEncodeIterator encodeIter;
RsslRDMLLoginRefresh loginRefresh;

/* Clear the Login Refresh structure. */
rsslClearRDMLLoginRefresh(&loginRefresh);

/* Set flags indicating presence of optional members. */
loginRefresh.flags =
    RDM_LG_RFF_HAS_USERNAME
    | RDM_LG_RFF_HAS_APPLICATION_NAME
    | RDM_LG_RFF_HAS_APPLICATION_ID
    | RDM_LG_RFF_HAS_POSITION;

/* Set UserName(should match request). */
loginRefresh.userName.data = "username";
loginRefresh.userName.length = 8;

/* Set ApplicationName(should match request). */
loginRefresh.applicationName.data = "upa";
loginRefresh.applicationName.length = 3;

/* Set ApplicationId(should match request). */
loginRefresh.applicationId.data = "256";
loginRefresh.applicationId.length = 3;

/* Set Position(should match request). */
loginRefresh.position.data = "127.0.0.1/net";
loginRefresh.position.length = 13;

/* Clear the encode iterator, set its RWF Version, and set it to a buffer for encoding into. */
rsslClearEncodeIterator(&encodeIter);
ret = rsslSetEncodeIteratorRWFVersion(&encodeIter, channelMajorVersion, channelMinorVersion);
ret = rsslSetEncodeIteratorBuffer(&encodeIter, &msgBuffer);

```

```

/* Encode the message. */
ret = rsslEncodeRDMMsg(&encodeIter, (RsslRDMMsg*)&loginRefresh, &msgBuffer.length, &rsslErrorInfo);

```

### Code Example 22: Login Refresh Encoding Example

#### 8.3.9.5 Decoding a Login Refresh

```

/* The decoder may require additional space to store things such as lists. */
char memoryArray[1024];
RsslBuffer memoryBuffer = { 1024, memoryArray };

RsslDecodeIterator decodeIter;
RsslMsg msg;
RsslRDMMsg rdmMsg;
RsslRDMLginRefresh *pLoginRefresh;

/* Clear the decode iterator, set its RWF Version, and set it to the encoded buffer. */
rsslClearDecodeIterator(&decodeIter);
ret = rsslSetDecodeIteratorRWFVersion(&decodeIter, channelMajorVersion, channelMinorVersion);
ret = rsslSetDecodeIteratorBuffer(&decodeIter, &msgBuffer);

/* Decode the message to an RsslMsg structure and RsslRDMMsg structure. */
ret = rsslDecodeRDMMsg(&decodeIter, &msg, &rdmMsg, &memoryBuffer, &rsslErrorInfo);

if (ret == RSSL_RET_SUCCESS
    && rdmMsg.rdmMsgBase.domainType == RSSL_DMT_LOGIN && rdmMsg.rdmMsgBase.rdmMsgType ==
    RDM_LG_MT_REFRESH)
{
    /* The message we decoded is an RsslRDMLginRefresh. */
    pLoginRefresh = &rdmMsg.loginMsg.refresh;

    /* Print username if present. */
    if (pLoginRefresh->flags & RDM_LG_RFF_HAS_APPLICATION_NAME)
        printf("Username: %.*s\n", pLoginRefresh->userName.length, pLoginRefresh->userName.data);

    /* Print ApplicationName if present. */
    if (pLoginRefresh->flags & RDM_LG_RFF_HAS_APPLICATION_NAME)
        printf("ApplicationName: %.*s\n", pLoginRefresh->applicationName.length, pLoginRefresh->
            >applicationName.data);

    /* Print ApplicationId if present. */
    if (pLoginRefresh->flags & RDM_LG_RFF_HAS_APPLICATION_ID)
        printf("ApplicationId: %.*s\n", pLoginRefresh->applicationId.length, pLoginRefresh->
            >applicationId.data);

    /* Print Position if present. */
    if (pLoginRefresh->flags & RDM_LG_RFF_HAS_POSITION)
        printf("Position: %.*s\n", pLoginRefresh->position.length, pLoginRefresh->position.data);
}

```

```
}
```

### Code Example 23: Login Refresh Decoding Example

## 8.4 Source Directory Domain

The Source Directory domain model conveys information about:

- All available services and their capabilities, their supported domain types, services' states, QoS, and item group information (associated with any particular service). Each service is associated with a unique **serviceId**.
- Item group status, allowing a single message to change the state of all associated items. Thus, using the Source Directory domain an application can send a mass update for multiple items instead of sending a status message for each individual item. The consumer is responsible for applying any changes to its open items. For details, refer to Section 8.4.10.
- Source Mirroring between an ADH and OMM interactive provider applications. The Source Directory exchanges this information via a specifically-formatted generic message as described in Section 8.4.6.

### 8.4.1 RSSL RDM Directory Request

An OMM consumer application encodes and sends **Directory Request** messages to request information from an OMM provider about available services. A consumer may request information about all services by omitting the **serviceId** member, or request information about a specific service by setting it to the ID of the desired service.

The **RsslRDMDirectoryRequest** represents all members of a directory request message and is easily used in OMM applications that leverage RDM. This structure follows the behavior and layout that is defined in the *Transport API C Edition RDM Usage Guide*.

#### 8.4.1.1 RSSL RDM Directory Request Structure Members

STRUCTURE MEMBER	DESCRIPTION
filter	<b>Required.</b> Indicates the service information in which the consumer is interested. The available flags are: <ul style="list-style-type: none"> <li>• <b>RDM_DIRECTORY_SERVICE_INFO_FILTER == 0x01</b></li> <li>• <b>RDM_DIRECTORY_SERVICE_STATE_FILTER == 0x02</b></li> <li>• <b>RDM_DIRECTORY_SERVICE_GROUP_FILTER == 0x04</b></li> <li>• <b>RDM_DIRECTORY_SERVICE_LOAD_FILTER == 0x08</b></li> <li>• <b>RDM_DIRECTORY_SERVICE_DATA_FILTER == 0x10</b></li> <li>• <b>RDM_DIRECTORY_SERVICE_LINK_FILTER == 0x20</b></li> </ul> In most cases, you should set the <b>RDM_DIRECTORY_SERVICE_INFO_FILTER</b> , <b>RDM_DIRECTORY_SERVICE_STATE_FILTER</b> , and <b>RDM_DIRECTORY_SERVICE_GROUP_FILTER</b> .
flags	<b>Required.</b> Indicates the presence of optional directory request members. For details, refer to Section 8.4.1.2.
rdmMsgBase	<b>Required.</b> Contains general message information like <b>streamId</b> and <b>domainType</b> .
serviceId	<b>Optional.</b> <ul style="list-style-type: none"> <li>• If not present, this indicates the consumer wants information about all available services.</li> <li>• If present, this indicates the ID of the service about which the consumer wants information. Additionally, a <b>flags</b> value of <b>RDM_DR_RQF_HAS_SERVICE_ID</b> should be specified.</li> </ul>

**Table 121: RsslRDMDirectoryRequest Structure Members**



### 8.4.1.2 RSSL RDM Directory Request Flag Enumeration Values

FLAG ENUMERATION	DESCRIPTION
RDM_DR_RQF_HAS_SERVICE_ID	Indicates the presence of <code>serviceId</code> .
RDM_DR_RQF_STREAMING	Indicates that the consumer wants to receive updates about directory information after the initial refresh.

Table 122: `RsslRDMDirectoryRequest` Flags

### 8.4.1.3 RSSL RDM Directory Request Utility Functions

FUNCTION NAME	DESCRIPTION
<code>rsslClearRDMDirectoryRequest</code>	Clears an <code>RsslRDMDirectoryRequest</code> structure. Useful for structure reuse.
<code>rsslInitDefaultRDMDirectoryRequest</code>	Clears an <code>RsslRDMDirectoryRequest</code> , sets the structure to request all services and receive updates for them, and populates <code>filter</code> with default values.
<code>rsslCopyRDMDirectoryRequest</code>	Performs a deep copy of an <code>RsslRDMDirectoryRequest</code> structure.

Table 123: `RsslRDMDirectoryRequest` Utility Functions

## 8.4.2 RSSL RDM Directory Refresh

A **Directory Refresh** message is encoded and sent by OMM provider and non-interactive provider applications. This message can provide information about the services supported by the provider application.

The `RsslRDMDirectoryRefresh` represents all members of a directory refresh message and is easily used in OMM applications that leverage RDM. This structure follows the behavior and layout that is defined in the *Transport API C Edition RDM Usage Guide*.

### 8.4.2.1 RSSL RDM Directory Refresh Structure Members

STRUCTURE MEMBER	DESCRIPTION
<code>filter</code>	<b>Required.</b> Indicates the information being provided about supported services. This should match the <code>filter</code> of the consumer's <code>RsslRDMDirectoryRequest</code> . The available flags are: <ul style="list-style-type: none"> <li><code>RDM_DIRECTORY_SERVICE_INFO_FILTER == 0x01</code></li> <li><code>RDM_DIRECTORY_SERVICE_STATE_FILTER == 0x02</code></li> <li><code>RDM_DIRECTORY_SERVICE_GROUP_FILTER == 0x04</code></li> <li><code>RDM_DIRECTORY_SERVICE_LOAD_FILTER == 0x08</code></li> <li><code>RDM_DIRECTORY_SERVICE_DATA_FILTER == 0x10</code></li> <li><code>RDM_DIRECTORY_SERVICE_LINK_FILTER == 0x20</code></li> </ul>
<code>flags</code>	<b>Required.</b> Indicates the presence of optional directory refresh members. Refer to Section 8.4.2.2.
<code>rdmMsgBase</code>	<b>Required.</b> Contains general message information, such as <code>streamId</code> and <code>domainType</code> .

Table 124: `RsslRDMDirectoryRefresh` Structure Members

STRUCTURE MEMBER	DESCRIPTION
sequenceNumber	<b>Optional.</b> If present, a <b>flags</b> value of <b>RDM_DR_RFF_HAS_SEQ_NUM</b> should be specified. <b>sequenceNumber</b> is a user-specified, item-level sequence number that the application can use to sequence messages in the stream.
serviceCount	<b>Required.</b> Indicates the number of services present in the <b>serviceList</b> .
serviceId	<b>Optional.</b> If present, a <b>flags</b> value of <b>RDM_DR_RFF_HAS_SERVICE_ID</b> should be specified, which should match the <b>serviceId</b> of the consumer's <b>RsslRDMDirectoryRequest</b> .
serviceList	<b>Optional.</b> Presence indicated by <b>serviceCount</b> . Contains an array of information about available services.
state	<b>Required.</b> Indicates stream and data state information. For further details on <b>RsslState</b> , refer to the <i>Transport API C Edition Developers Guide</i> .

Table 124: **RsslRDMDirectoryRefresh** Structure Members (Continued)

#### 8.4.2.2 RSSL RDM Directory Refresh Flag Enumeration Values

FLAG ENUMERATION	DESCRIPTION
RDM_DR_RFF_CLEAR_CACHE	Indicates that any stored payload information associated with the directory stream should be cleared. This might happen if some portion of data is known to be invalid.
RDM_DR_RFF_HAS_SEQ_NUM	Indicates the presence of <b>sequenceNumber</b> .
RDM_DR_RFF_HAS_SERVICE_ID	Indicates the presence of <b>serviceId</b> .
RDM_DR_RFF_SOLICITED	If present, this flag indicates that the directory refresh is solicited (i.e., it is in response to a request). The absence of this flag indicates that the refresh is unsolicited.

Table 125: **RsslRDMDirectoryRefresh** Flags

#### 8.4.2.3 RSSL RDM Directory Refresh Utility Functions

FUNCTION NAME	DESCRIPTION
rsslClearRDMDirectoryRefresh	Clears an <b>RsslRDMDirectoryRefresh</b> structure. Useful for structure reuse.
rsslCopyRDMDirectoryRefresh	Performs a deep copy of an <b>RsslRDMDirectoryRefresh</b> structure.

Table 126: **RsslRDMDirectoryRefresh** Utility Functions

### 8.4.3 RSSL RDM Directory Update

A **Directory Update** message is encoded and sent by OMM provider and non-interactive provider applications. This message can provide information about new or removed services, or changes to existing services.

The **RsslRDMDirectoryUpdate** represents all members of a directory update message and allows for simplified use in OMM applications that leverage RDM. This structure follows the behavior and layout that is defined in the *Transport API C Edition RDM Usage Guide*.

### 8.4.3.1 RSSL RDM Directory Update Structure Members

STRUCTURE MEMBER	DESCRIPTION
filter	<p><b>Optional.</b> Indicates what information is provided about supported services. This should match the <b>filter</b> of the consumer's <b>RsslRDMDirectoryRequest</b>.</p> <p>If present, a <b>flags</b> value of <b>RDM_DR_UPF_HAS_FILTER</b> should be specified.</p> <p>Available flags are:</p> <ul style="list-style-type: none"> <li>• <b>RDM_DIRECTORY_SERVICE_INFO_FILTER == 0x01</b></li> <li>• <b>RDM_DIRECTORY_SERVICE_STATE_FILTER == 0x02</b></li> <li>• <b>RDM_DIRECTORY_SERVICE_GROUP_FILTER == 0x04</b></li> <li>• <b>RDM_DIRECTORY_SERVICE_LOAD_FILTER == 0x08</b></li> <li>• <b>RDM_DIRECTORY_SERVICE_DATA_FILTER == 0x10</b></li> <li>• <b>RDM_DIRECTORY_SERVICE_LINK_FILTER == 0x20</b></li> </ul>
flags	<p><b>Required.</b> Indicates the presence of optional directory update members. For details refer to Section 8.4.3.2.</p>
sequenceNumber	<p><b>Optional.</b> A user-specified, item-level sequence number which the application can use to sequence messages in this stream.</p> <p>If present, a <b>flags</b> value of <b>RDM_DR_UPF_HAS_SEQ_NUM</b> should be specified.</p>
serviceCount	<p><b>Required.</b> Indicates the number of services present in the <b>serviceList</b>.</p>
serviceId	<p><b>Optional.</b> This member's value must match the <b>serviceId</b> of the consumer's <b>RsslRDMDirectoryRequest</b>.</p> <p>If present, a <b>flags</b> value of <b>RDM_DR_UPF_HAS_SERVICE_ID</b> should be specified.</p>
serviceList	<p><b>Optional.</b> Presence indicated by <b>serviceCount</b>. Contains an array of information about available services.</p>
rdmMsgBase	<p><b>Required.</b> Contains general message information like <b>streamId</b> and <b>domainType</b>.</p>

Table 127: **RsslRDMDirectoryUpdate** Structure Members

### 8.4.3.2 RSSL RDM Directory Update Flag Enumeration Values

FLAG ENUMERATION	DESCRIPTION
RDM_DR_UPF_HAS_FILTER	Indicates the presence of <b>filter</b> .
RDM_DR_UPF_HAS_SEQ_NUM	Indicates the presence of <b>sequenceNumber</b> .
RDM_DR_UPF_HAS_SERVICE_ID	Indicates the presence of <b>serviceId</b> .

Table 128: **RsslRDMDirectoryUpdate** Flags

### 8.4.3.3 RSSL RDM Directory Update Utility Functions

FUNCTION NAME	DESCRIPTION
<code>rsslClearRDMDirectoryUpdate</code>	Clears an <code>RsslRDMDirectoryUpdate</code> structure. Useful for structure reuse.
<code>rsslCopyRDMDirectoryUpdate</code>	Performs a deep copy of an <code>RsslRDMDirectoryUpdate</code> structure.

**Table 129: `RsslRDMDirectoryUpdate` Utility Functions**

### 8.4.4 RSSL RDM Directory Status

OMM provider and OMM non-interactive provider applications use the **Directory Status** message to convey state information associated with the directory stream. Such state information can indicate that a directory stream cannot be established or to inform a consumer of a state change associated with an open directory stream. An application can also use the Directory Status message to close an existing directory stream.

The `RsslRDMDirectoryStatus` represents all members of a directory status message and allows for simplified use in OMM applications that leverage RDM. This structure follows the behavior and layout that is defined in the *Transport API C Edition RDM Usage Guide*.

#### 8.4.4.1 RSSL RDM Directory Status Structure Members

STRUCTURE MEMBER	DESCRIPTION
<code>filter</code>	<b>Optional.</b> If present, a <code>flags</code> value of <code>RDM_DR_STF_HAS_FILTER</code> should be specified. Indicates what information is being provided about supported services. This should match the <code>filter</code> of the consumer's <code>RsslRDMDirectoryRequest</code> . The available flags are: <ul style="list-style-type: none"> <li>• <code>RDM_DIRECTORY_SERVICE_INFO_FILTER == 0x01</code></li> <li>• <code>RDM_DIRECTORY_SERVICE_STATE_FILTER == 0x02</code></li> <li>• <code>RDM_DIRECTORY_SERVICE_GROUP_FILTER == 0x04</code></li> <li>• <code>RDM_DIRECTORY_SERVICE_LOAD_FILTER == 0x08</code></li> <li>• <code>RDM_DIRECTORY_SERVICE_DATA_FILTER == 0x10</code></li> <li>• <code>RDM_DIRECTORY_SERVICE_LINK_FILTER == 0x20</code></li> </ul>
<code>flags</code>	<b>Required.</b> Indicates the presence of optional directory status members. For details, refer to Section 8.4.4.2.
<code>serviceId</code>	<b>Optional.</b> If present, a <code>flags</code> value of <code>RDM_DR_STF_HAS_SERVICE_ID</code> should be specified. This member should match the <code>serviceId</code> of the consumer's <code>RsslRDMDirectoryRequest</code> .
<code>state</code>	<b>Optional.</b> Indicates the state of the directory stream. If present, a <code>flags</code> value of <code>RDM_DR_STF_HAS_STATE</code> should be specified. For more information on <code>RsslState</code> , refer to the <i>Transport API C Edition Developers Guide</i> .
<code>rdmMsgBase</code>	<b>Required.</b> Contains general message information like <code>streamId</code> and <code>domainType</code> .

**Table 130: `RsslRDMDirectoryStatus` Structure Members**

#### 8.4.4.2 RSSL RDM Directory Status Flag Enumeration Values

FLAG ENUMERATION	DESCRIPTION
RDM_DR_STF_CLEAR_CACHE	Indicates that any stored payload data associated with the directory stream should be cleared. This might happen if some portion of data is known to be invalid.
RDM_DR_STF_HAS_FILTER	Indicates the presence of <b>filter</b> .
RDM_DR_STF_HAS_SERVICE_ID	Indicates the presence of <b>serviceId</b> .
RDM_DR_STF_HAS_STATE	Indicates the presence of <b>state</b> . If not present, any previously conveyed state should continue to apply.

Table 131: **RsslRDMDirectoryStatus** Flags

#### 8.4.4.3 RSSL RDM Directory Status Utility Functions

FUNCTION NAME	DESCRIPTION
rsslClearRDMDirectoryStatus	Clears an <b>RsslRDMDirectoryStatus</b> structure. Useful for structure reuse.
rsslCopyRDMDirectoryStatus	Performs a deep copy of an <b>RsslRDMDirectoryStatus</b> structure.

Table 132: **RsslRDMDirectoryStatus** Utility Functions

### 8.4.5 RSSL RDM Directory Close

#### 8.4.5.1 RSSL RDM Directory Close Structure Member

STRUCTURE MEMBER	DESCRIPTION
rdmMsgBase	<b>Required.</b> Contains general message information like streamId and domainType.

Table 133: **RsslRDMDirectoryClose** Structure Member

#### 8.4.5.2 RSSL RDM Directory Close Utility Functions

FUNCTION NAME	DESCRIPTION
rsslClearRDMDirectoryClose	Clears an <b>RsslRDMDirectoryClose</b> structure. Useful for structure reuse.
rsslCopyRDMDirectoryClose	Performs a deep copy of an <b>RsslRDMDirectoryClose</b> structure.

Table 134: **RsslRDMDirectoryClose** Utility Functions

### 8.4.6 RSSL RDM Consumer Status

The **Directory Consumer Status** is sent by OMM consumer applications to inform a service of how the consumer is used for **Source Mirroring**. This message is primarily informational.

The **RsslRDMDirectoryConsumerStatus** relies on the **RsslGenericMsg** and represents all members necessary for applications that leverage RDM. This structure follows the behavior and layout that is defined in the *Transport API C Edition RDM Usage Guide*.

#### 8.4.6.1 RSSL RDM Directory Consumer Status Structure Members

STRUCTURE MEMBER	DESCRIPTION
consumerServiceStatusCount	<b>Required.</b> Indicates the number of services present in the <code>serviceList</code> .
consumerServiceStatusList	<b>Optional.</b> Presence indicated by <code>consumerServiceStatusCount</code> . Contains an array of <code>RsslRDMConsumerStatusService</code> structures.
rdmMsgBase	<b>Required.</b> Contains general message information like <code>streamId</code> and <code>domainType</code> .

Table 135: `RsslRDMDirectoryConsumerStatus` Structure Members

#### 8.4.6.2 RSSL RDM Directory Consumer Status Service Structure Members

STRUCTURE MEMBER	DESCRIPTION
action	<b>Required.</b> Indicates how a cache of Source Mirroring content should apply this information. For information on <code>RsslMapEntry</code> actions, refer to the <i>Transport API C Edition Developers Guide</i> .
serviceId	<b>Required.</b> Indicates the service associated with this status.
sourceMirroringMode	<b>Required.</b> Indicates how the consumer is using the service. Available enumerations are: <ul style="list-style-type: none"> <li><code>RDM_DIRECTORY_SOURCE_MIRROR_MODE_ACTIVE_NO_STANDBY == 0</code>,</li> <li><code>RDM_DIRECTORY_SOURCE_MIRROR_MODE_ACTIVE_WITH_STANDBY == 1</code>,</li> <li><code>RDM_DIRECTORY_SOURCE_MIRROR_MODE_STANDBY == 2</code></li> </ul>

Table 136: `RsslRDMConsumerStatusService` Structure Members

#### 8.4.6.3 RSSL RDM Directory Consumer Status Utility Functions

FUNCTION NAME	DESCRIPTION
<code>rsslClearRDMDirectoryConsumerStatus</code>	Clears an <code>RsslRDMDirectoryConsumerStatus</code> structure. Useful for structure reuse.
<code>rsslClearRDMConsumerStatusService</code>	Clears the <code>RsslRDMConsumerStatusService</code> structure.
<code>rsslCopyRDMDirectoryConsumerStatus</code>	Performs a deep copy of an <code>RsslRDMDirectoryConsumerStatus</code> structure.

Table 137: `RsslRDMDirectoryConsumerStatus` Utility Functions

### 8.4.7 Source Directory RDM Service

An `RsslRDMService` structure conveys information about a service. An array of `RsslRDMServices` forms the `serviceList` member of the `RsslRDMDirectoryRefresh` and `RsslRDMDirectoryUpdate` messages.

The members of an `RsslRDMService` represent the different filters used to categorize service information.

### 8.4.7.1 RSSL RDM Service Structure Members

STRUCTURE MEMBER	DESCRIPTION
action	<b>Required.</b> Indicates how a cache of the service should apply this information. For information on <b>RsslMapEntry</b> actions, refer to the <i>Transport API C Edition Developers Guide</i> .
data	<b>Optional.</b> Contains data that applies to the items requested from the service and represents the Source Directory Data Filter. If present, a <b>flags</b> value of <b>RDM_SVCF_HAS_DATA</b> should be specified.
flags	<b>Required.</b> Indicates the presence of optional service members. For details, refer to Section 8.4.7.2.
groupStateCount	<b>Required.</b> Indicates the number of elements present in <b>groupStateList</b> .
groupStateList	<b>Optional.</b> Presence indicated by <b>groupStateCount</b> . Contains an array of elements indicating changes to item groups and represents the Source Directory Group filter.
info	<b>Optional.</b> Contains information related to the Source Directory Info Filter. If present, a <b>flags</b> value of <b>RDM_SVCF_HAS_INFO</b> should be specified.
linkInfo	<b>Optional.</b> Contains information about upstream sources that provide data to this service and represents the Source Directory Link Filter. If present, a <b>flags</b> value of <b>RDM_SVCF_HAS_LINK</b> should be specified.
load	<b>Optional.</b> Contains information about the service's operating workload and represents the Source Directory Load Filter. If present, a <b>flags</b> value of <b>RDM_SVCF_HAS_LOAD</b> should be specified.
serviceId	<b>Required.</b> Indicates the service associated with this <b>RsslRDMSservice</b> .
state	<b>Optional.</b> Contains information related to the Source Directory State Filter. If present, a <b>flags</b> value of <b>RDM_SVCF_HAS_STATE</b> should be specified.

Table 138: **RsslRDMSservice** Structure Members

### 8.4.7.2 RSSL RDM Service Flag Enumeration Values

FLAG ENUMERATION	DESCRIPTION
RDM_SVCF_HAS_DATA	Indicates the presence of <b>data</b> .
RDM_SVCF_HAS_INFO	Indicates the presence of <b>info</b> .
RDM_SVCF_HAS_LINK	Indicates the presence of <b>linkInfo</b> .
RDM_SVCF_HAS_LOAD	Indicates the presence of <b>load</b> .
RDM_SVCF_HAS_STATE	Indicates the presence of <b>state</b> .

Table 139: **RsslRDMSservice** Flags

### 8.4.7.3 RSSL RDM Service Utility Functions

FUNCTION NAME	DESCRIPTION
<code>rsslClearRDMService</code>	Clears an <code>RsslRDMService</code> structure. Useful for structure reuse.

Table 140: `RsslRDMService` Utility Function

### 8.4.8 Source Directory RDM Service Info

An `RsslRDMServiceInfo` structure conveys information that identifies the service and the content it provides. The `RsslRDMServiceInfo` structure represents the Source Directory Info filter. More information about the Info filter is available in the *Transport API C Edition RDM Usage Guide*.

#### 8.4.8.1 RSSL RDM Service Info Members

STRUCTURE MEMBER	DESCRIPTION
<code>acceptingConsumerStatus</code>	<b>Optional.</b> Indicates whether this service supports accepting <code>RsslRDMDirectoryConsumerStatus</code> messages for Source Mirroring. Available values are: <ul style="list-style-type: none"> <li><b>1:</b> The service will accept Consumer Status messages. If not present, a value of 1 is assumed.</li> <li><b>0:</b> The service will not accept Consumer Status messages.</li> </ul> If present, a <code>flags</code> value of <code>RDM_SVC_IFF_HAS_ACCEPTING_CONS_STATUS</code> should be specified.
<code>action</code>	<b>Required.</b> Indicates how a service info cache should apply this information. For information on <code>RsslFilterEntry</code> actions, refer to the <i>Transport API C Edition Developers Guide</i> .
<code>capabilitiesCount</code>	<b>Required.</b> Indicates the number of capabilities present in the <code>capabilitiesList</code> .
<code>capabilitiesList</code>	<b>Required.</b> Contains a list of capabilities that the service supports. Populated by domain types.
<code>dictionariesProvidedCount</code>	<b>Optional.</b> Indicates the number of elements present in <code>dictionariesProvided</code> . If present, a <code>flags</code> value of <code>RDM_SVC_IFF_HAS_DICTS_PROVIDED</code> should be specified.
<code>dictionariesProvidedList</code>	<b>Optional.</b> Contains an array of elements that identify dictionaries that can be requested from this service. If present, a <code>flags</code> value of <code>RDM_SVC_IFF_HAS_DICTS_PROVIDED</code> and <code>dictionariesProvidedCount</code> should be specified.
<code>dictionariesUsedCount</code>	<b>Optional.</b> Indicates the number of elements present in <code>dictionariesUsed</code> . If present, a <code>flags</code> value of <code>RDM_SVC_IFF_HAS_DICTS_USED</code> should be specified.

Table 141: `RsslRDMServiceInfo` Structure Members



STRUCTURE MEMBER	DESCRIPTION
dictionariesUsedList	<b>Optional.</b> Contains an array of elements that identify dictionaries used to decode data from this service. If present, a <b>flags</b> value of <b>RDM_SVC_IFF_HAS_DICTS_USED</b> and <b>dictionariesUsedCount</b> should be specified.
flags	<b>Required.</b> Indicates the presence of optional service info members. For details, refer to Section 8.4.8.2.
isSource	<b>Optional.</b> Indicates whether the service is provided directly by a source or represents a group of sources. <ul style="list-style-type: none"> <li>• <b>1</b>: The service is provided directly by a source</li> <li>• <b>0</b>: The service represents a group of sources. If absent, a value of <b>0</b> is assumed.</li> </ul> If present, a <b>flags</b> value of <b>RDM_SVC_IFF_HAS_IS_SOURCE</b> should be specified.
itemList	<b>Optional.</b> Specifies a name that can be requested on the <b>RSSL_DMT_SYMBOL_LIST</b> domain to get a list of all items available from this service. If present, a <b>flags</b> value of <b>RDM_SVC_IFF_HAS_ITEM_LIST</b> should be specified.
qosCount	<b>Optional.</b> Indicates the number of elements present in <b>qosList</b> . If present, a <b>flags</b> value of <b>RDM_SVC_IFF_HAS_QOS</b> should be specified.
qosList	<b>Optional.</b> Contains an array of elements that identify the available Qualities of Service. If present, a <b>flags</b> value of <b>RDM_SVC_IFF_HAS_QOS</b> and the <b>qosCount</b> should be specified.
serviceName	<b>Required.</b> Indicates the name of the service.
supportsOutOfBandSnapshots	<b>Optional.</b> Indicates whether this service supports making snapshot requests even when the <b>OpenLimit</b> is reached. Available values are: <ul style="list-style-type: none"> <li>• <b>1</b>: Snapshot requests are allowed. If not present, a value of <b>1</b> is assumed.</li> <li>• <b>0</b>: Snapshot requests are not allowed.</li> </ul> If present, a <b>flags</b> value of <b>RDM_SVC_IFF_HAS_SUPPORT_OOB_SNAPSHOTS</b> should be specified.
supportsQosRange	<b>Optional.</b> Indicates whether this service supports specifying a range of Qualities of Service when requesting an item. For further information, refer to the <b>qos</b> and <b>worstQos</b> members of the <b>RsslRequestMsg</b> in the <i>Transport API C Edition Developers Guide</i> . Available values are: <ul style="list-style-type: none"> <li>• <b>1</b>: QoS Range requests are supported.</li> <li>• <b>0</b>: QoS Range requests are not supported. If not present, a value of <b>0</b> is assumed.</li> </ul> If present, a <b>flags</b> value of <b>RDM_SVC_IFF_HAS_SUPPORT_QOS_RANGE</b> should be specified.
vendor	<b>Optional.</b> Identifies the vendor of the data. If present, a <b>flags</b> value of <b>RDM_SVC_IFF_HAS_VENDOR</b> should be specified.

Table 141: **RsslRDMServiceInfo** Structure Members (Continued)

### 8.4.8.2 RSSL RDM Service Info Flag Enumeration Values

FLAG ENUMERATION	DESCRIPTION
RDM_SVC_IFF_HAS_ACCEPTING_CONS_STATUS	Indicates the presence of <code>acceptingConsumerStatus</code> .
RDM_SVC_IFF_HAS_DICTS_PROVIDED	Indicates the presence of <code>dictionariesProvidedList</code> and <code>dictionariesProvidedCount</code> .
RDM_SVC_IFF_HAS_DICTS_USED	Indicates the presence of <code>dictionariesUsedList</code> and <code>dictionariesUsedCount</code> .
RDM_SVC_IFF_HAS_IS_SOURCE	Indicates the presence of <code>isSource</code> .
RDM_SVC_IFF_HAS_ITEM_LIST	Indicates the presence of <code>itemList</code> .
RDM_SVC_IFF_HAS_QOS	Indicates the presence of <code>qosList</code> and <code>qosCount</code> .
RDM_SVC_IFF_HAS_SUPPORT_OOB_SNAPSHOTS	Indicates the presence of <code>supportsOutOfBandSnapshots</code> .
RDM_SVC_IFF_HAS_SUPPORT_QOS_RANGE	Indicates the presence of <code>supportsQosRange</code> .
RDM_SVC_IFF_HAS_VENDOR	Indicates the presence of <code>vendor</code> .

Table 142: `RsslRDMServiceInfo` Flags

### 8.4.8.3 RSSL RDM Service Info Utility Functions

FUNCTION NAME	DESCRIPTION
<code>rsslClearRDMServiceInfo</code>	Clears an <code>RsslRDMServiceInfo</code> structure. Useful for structure reuse.

Table 143: `RsslRDMServiceInfo` Utility Functions

### 8.4.9 Source Directory RDM Service State

An `RsslRDMServiceState` structure conveys information about service's current state. It represents the Source Directory State filter. For more information about the State filter, refer to the *Transport API C Edition RDM Usage Guide*.

#### 8.4.9.1 RSSL RDM Service State Members

STRUCTURE MEMBER	DESCRIPTION
<code>acceptingRequests</code>	Indicates whether the immediate provider (to which the consumer is directly connected) can handle the request. Available values are: <ul style="list-style-type: none"> <li><b>1</b>: The service will accept new requests.</li> <li><b>0</b>: The service does not currently accept new requests.</li> </ul> If present, <code>flags</code> value of <code>RDM_SVC_STF_HAS_ACCEPTING_REQS</code> should be specified.
<code>action</code>	<b>Required.</b> Indicates how a cache of the service state should apply this information. For details on <code>RsslFilterEntry</code> actions, refer to the <i>Transport API C Edition Developers Guide</i> .

Table 144: `RsslRDMServiceState` Structure Members

STRUCTURE MEMBER	DESCRIPTION
flags	<b>Required.</b> Indicates the presence of optional service state members. For details refer to Section 8.4.9.2.
serviceState	<b>Required.</b> Indicates whether the original provider of the data can respond to new requests. Requests can still be made if so indicated by <b>acceptingRequests</b> . Available values are: <ul style="list-style-type: none"> <li>• <b>1</b>: The original provider of the data is available.</li> <li>• <b>0</b>: The original provider of the data is not currently available.</li> </ul>
status	This status should be applied to all open items associated with this service. If present, <b>flags</b> value of <b>RDM_SVC_STF_HAS_STATUS</b> should be specified.

Table 144: **RsslRDMServiceState** Structure Members (Continued)

#### 8.4.9.2 RSSL RDM Service State Flag Enumeration Values

FLAG ENUMERATION	DESCRIPTION
RDM_SVC_STF_HAS_ACCEPTING_REQS	Indicates the presence of <b>acceptingRequests</b> .
RDM_SVC_STF_HAS_STATUS	Indicates the presence of <b>status</b> .

Table 145: **RsslRDMServiceState** Flags

#### 8.4.9.3 RSSL RDM Service State Utility Functions

FUNCTION NAME	DESCRIPTION
rsslClearRDMServiceState	Clears an <b>RsslRDMServiceState</b> structure. Useful for structure reuse.

Table 146: **RsslRDMServiceState** Utility Functions

### 8.4.10 Source Directory RDM Service Group State

An **RsslRDMServiceGroupState** structure is used to convey status and name changes for an item group. It represents the Source Directory Group filter. For further details about the Group State filter, refer to the *Transport API C Edition RDM Usage Guide*.

#### 8.4.10.1 RSSL RDM Service Group State Members

STRUCTURE MEMBER	DESCRIPTION
action	<b>Required.</b> Indicates how a cache of the service group state should apply this information. For further details on <b>RsslFilterEntry</b> actions, refer to the <i>Transport API C Edition Developers Guide</i> .
flags	<b>Required.</b> Indicates the presence of optional service group members. For details, refer to Section 8.4.10.2.

Table 147: **RsslRDMServiceGroupState** Structure Members

STRUCTURE MEMBER	DESCRIPTION
group	<b>Required.</b> Identifies the name of the item group being changed.
mergedToGroup	<b>Optional.</b> Specifies the new group name. All items of the specified <b>group</b> are put into this new group. If present, a <b>flags</b> value of <b>RDM_SVC_GRP_HAS_MERGED_TO_GROUP</b> should be specified.
status	<b>Optional.</b> Specifies the status to apply to all open items associated with the group specified by <b>group</b> . If present, a <b>flags</b> value of <b>RDM_SVC_GRP_HAS_STATUS</b> should be specified.

Table 147: **RsslRDMServiceGroupState** Structure Members (Continued)

#### 8.4.10.2 RSSL RDM Service Group State Flag Enumeration Values

FLAG ENUMERATION	DESCRIPTION
RDM_SVC_GRP_HAS_MERGED_TO_GROUP	Indicates the presence of <b>mergedToGroup</b> .
RDM_SVC_GRP_HAS_STATUS	Indicates the presence of <b>status</b> .

Table 148: **RsslRDMServiceGroupState** Flags

#### 8.4.10.3 RSSL RDM Service Group State Utility Functions

FUNCTION NAME	DESCRIPTION
rsslClearRDMServiceGroupState	Clears an <b>RsslRDMServiceGroupState</b> structure. Useful for structure reuse.

Table 149: **RsslRDMServiceGroupState** Utility Functions

### 8.4.11 Source Directory RDM Service Load

An **RsslRDMServiceLoad** structure conveys the workload of a service. It represents the Source Directory Load filter. For further details on the Service Load filter, refer to the *Transport API C Edition RDM Usage Guide*.

#### 8.4.11.1 RSSL RDM Service Load Members

STRUCTURE MEMBER	DESCRIPTION
action	<b>Required.</b> Indicates how a cache of the service load should apply this information. For information on <b>RsslFilterEntry</b> actions, refer to the <i>Transport API C Edition Developers Guide</i> .
flags	<b>Required.</b> Indicates presence of optional service load members. For details, refer to Section 8.4.11.2.

Table 150: **RsslRDMServiceLoad** Structure Members

STRUCTURE MEMBER	DESCRIPTION
loadFactor	If present, <b>flags</b> value of <b>RDM_SVC_LDF_HAS_LOAD_FACTOR</b> should be specified. Indicates the current workload on the source that provides data. A higher load factor indicates a higher workload. For more information, refer to the <i>Transport API C Edition RDM Usage Guide</i> .
openLimit	Specifies the maximum number of streaming requests that the service allows. If present, <b>flags</b> value of <b>RDM_SVC_LDF_HAS_OPEN_LIMIT</b> should be specified.
openWindow	Specifies the maximum number of outstanding requests (i.e., requests awaiting a refresh) that the service allows. If present, <b>flags</b> value of <b>RDM_SVC_LDF_HAS_OPEN_WINDOW</b> should be specified.

Table 150: **RsslRDMServiceLoad** Structure Members (Continued)

#### 8.4.11.2 RSSL RDM Service Load Flag Enumeration Values

FLAG ENUMERATION	DESCRIPTION
RDM_SVC_LDF_HAS_LOAD_FACTOR	Indicates the presence of <b>loadFactor</b> .
RDM_SVC_LDF_HAS_OPEN_LIMIT	Indicates the presence of <b>openLimit</b> .
RDM_SVC_LDF_HAS_OPEN_WINDOW	Indicates the presence of <b>openWindow</b> .

Table 151: **RsslRDMServiceLoad** Flags

#### 8.4.11.3 RSSL RDM Service Load Utility Functions

FUNCTION NAME	DESCRIPTION
rsslClearRDMServiceLoad	Clears an <b>RsslRDMServiceLoad</b> structure. Useful for structure reuse.

Table 152: **RsslRDMServiceLoad** Utility Functions

### 8.4.12 Source Directory RDM Service Data

An **RsslRDMServiceData** structure conveys the data to apply to all items of a service. It represents the Source Directory Data filter. For further details on the Data filter, refer to the *Transport API C Edition RDM Usage Guide*.

#### 8.4.12.1 RSSL RDM Service Data Members

STRUCTURE MEMBER	DESCRIPTION
action	<b>Required.</b> Indicates how a cache of the service data should apply this information. For further details on <b>RsslFilterEntry</b> actions, refer to the <i>Transport API C Edition Developers Guide</i> .

Table 153: **RsslRDMServiceData** Structure Members

STRUCTURE MEMBER	DESCRIPTION
data	<b>Optional.</b> Contains the encoded <b>RsslBuffer</b> representing the data. The type of the data is given by <b>dataType</b> . If present, a <b>flags</b> value of <b>RDM_SVC_DTF_HAS_DATA</b> should be specified.
dataType	<b>Optional.</b> Specifies the <b>RsslDataType</b> of the data. For information on <b>RsslDataTypes</b> , refer to the <i>Transport API C Edition Developers Guide</i> . If present, a <b>flags</b> value of <b>RDM_SVC_DTF_HAS_DATA</b> should be specified.
flags	<b>Required.</b> Indicates the presence of optional service data members. For details, refer to Section 8.4.12.2.
type	<b>Optional.</b> Indicates the type of content present in <b>data</b> . Available enumerations are: <ul style="list-style-type: none"> <li><b>RDM_DIRECTORY_DATA_TYPE_TIME == 1</b></li> <li><b>RDM_DIRECTORY_DATA_TYPE_ALERT == 2</b></li> <li><b>RDM_DIRECTORY_DATA_TYPE_HEADLINE == 3</b></li> <li><b>RDM_DIRECTORY_DATA_TYPE_STATUS == 4</b></li> </ul> If present, <b>flags</b> value of <b>RDM_SVC_DTF_HAS_DATA</b> should be specified.

Table 153: **RsslRDMSERVICEData** Structure Members (Continued)

#### 8.4.12.2 RSSL RDM Service Load Data Enumeration Values

FLAG ENUMERATION	DESCRIPTION
RDM_SVC_DTF_HAS_DATA	Indicates the presence of <b>type</b> , <b>dataType</b> , and <b>data</b> .

Table 154: **RsslRDMSERVICEData** Flags

#### 8.4.12.3 RSSL RDM Service Data Utility Functions

FUNCTION NAME	DESCRIPTION
rsslClearRDMSERVICEData	Clears an <b>RsslRDMSERVICEData</b> structure. Useful for structure reuse.

Table 155: **RsslRDMSERVICEData** Utility Functions

### 8.4.13 Source Directory RDM Service Link Information

An **RsslRDMSERVICELinkInfo** structure conveys information about upstream sources that form a service. It represents the Source Directory Link filter. More information about the Service Link filter content is available in the *Transport API C Edition RDM Usage Guide*.

The **RsslRDMSERVICELinkInfo** structure contains an array of **RsslRDMSERVICELink** structures that each represents an upstream source.

### 8.4.13.1 RSSL RDM Service Link Info Members

STRUCTURE MEMBER	DESCRIPTION
action	<b>Required.</b> Indicates how a cache of the service link information should apply this information. For further information on <code>RsslFilterEntry</code> actions, refer to the <i>Transport API C Edition Developers Guide</i> .
linkCount	<b>Required.</b> Indicates the number of link elements present in <code>linkList</code> .
linkList	<b>Optional.</b> Presence indicated by <code>linkCount</code> . Contains an array of <code>RsslRDMServiceLink</code> structures, each representing a source.

Table 156: `RsslRDMServiceLinkInfo` Structure Members

### 8.4.13.2 RSSL RDM Service Link Info Utility Functions

FUNCTION NAME	DESCRIPTION
<code>rsslClearRDMServiceLinkInfo</code>	Clears an <code>RsslRDMServiceLinkInfo</code> structure. Useful for structure reuse.

Table 157: `RsslRDMServiceLinkInfo` Utility Functions

### 8.4.14 Source Directory RDM Service Link

An `RsslRDMServiceLink` structure conveys information about an upstream source. It represents an entry in the Source Directory Link filter and is used by the `linkList` member of the `RsslRDMServiceLinkInfo` structure. For further details on Service Link filter content, refer to the *Transport API C Edition RDM Usage Guide*.

#### 8.4.14.1 RSSL RDM Service Link Members

STRUCTURE MEMBER	DESCRIPTION
action	<b>Required.</b> Indicates how a cache of the service link should apply this information. For information on <code>RsslMapEntry</code> actions, refer to the <i>Transport API C Edition Developers Guide</i> .
flags	<b>Required.</b> Indicates the presence of optional service link members. For details, refer to Section 8.4.14.2.
linkCode	<b>Optional.</b> Indicates additional information about the status of a source. Available enumerations are: <ul style="list-style-type: none"> <li><code>RDM_DIRECTORY_LINK_CODE_NONE == 0</code></li> <li><code>RDM_DIRECTORY_LINK_CODE_OK == 1</code></li> <li><code>RDM_DIRECTORY_LINK_CODE_RECOVERY_STARTED == 2</code></li> <li><code>RDM_DIRECTORY_LINK_CODE_RECOVERY_COMPLETED == 3</code></li> </ul> If present, a <code>flags</code> value of <code>RDM_SVC_LKF_HAS_CODE</code> should be specified.
linkState	<ul style="list-style-type: none"> <li><b>Required.</b> Indicates whether the source is up or down.</li> </ul>

Table 158: `RsslRDMServiceLink` Structure Members

STRUCTURE MEMBER	DESCRIPTION
name	<b>Required.</b> Specifies the name of the source. Sources with identical names are typically load-balanced sources.
text	<b>Optional.</b> Gives additional status details regarding the source. If present, a <b>flags</b> value of <b>RDM_SVC_LKF_HAS_TEXT</b> should be specified.
type	<b>Optional.</b> Specifies whether the source is interactive or broadcast. Available enumerations are: <ul style="list-style-type: none"> <li>• <b>RDM_DIRECTORY_LINK_TYPE_INTERACTIVE == 1</b></li> <li>• <b>RDM_DIRECTORY_LINK_TYPE_BROADCAST == 2</b></li> </ul> If present, a <b>flags</b> value of <b>RDM_SVC_LKF_HAS_TYPE</b> should be specified.

Table 158: **RsslRDMSERVICELink** Structure Members (Continued)

#### 8.4.14.2 RSSL RDM Service Link Enumeration Values

FLAG ENUMERATION	DESCRIPTION
RDM_SVC_LKF_HAS_CODE	Indicates the presence of <b>code</b> .
RDM_SVC_LKF_HAS_TEXT	Indicates the presence of <b>text</b> .
RDM_SVC_LKF_HAS_TYPE	Indicates the presence of <b>type</b> .

Table 159: **RsslRDMSERVICELink** Flags

#### 8.4.14.3 RSSL RDM Service Link Utility Functions

FUNCTION NAME	DESCRIPTION
rsslClearRDMSERVICELink	Clears an <b>RsslRDMSERVICELink</b> structure. Useful for structure reuse.

Table 160: **RsslRDMSERVICELink** Utility Functions

### 8.4.15 Source Directory RDM Sequenced Multicast Information

An **RsslRDMSERVICESeqMcastInfo** structure is included in the services advertised by the Reference Data Server component of an Elektron Direct Feed (EDF) system. It identifies components in the system to which an OMM Consumer application connects for content.

- For further information on the service sequenced multicast information filter, refer to the *Transport API C Edition RDM Usage Guide*.
- For further information on Elektron Direct Feed, refer to the *EDF Developers Guide*.

#### 8.4.15.1 RSSL RDM Service Sequenced Multicast Information Structure

STRUCTURE MEMBER	DESCRIPTION
flags	<b>Required.</b> Sets any optional members. For details, refer to Section 8.4.15.2.

Table 161: **RsslRDMSERVICESeqMcastInfo** Structure Members



STRUCTURE MEMBER	DESCRIPTION
action	<b>Required.</b> Sets how a cache should apply this information. For details, refer to the <i>Transport API C Edition Developers Guide</i> .
snapshotServer	Sets the network address/port information for the Snapshot Server, if one is present.
gapRecoveryServer	Sets the network address/port information for the Gap Recovery Server, if one is present.
refDataServer	Sets the network address/port information for the Reference Data Server, if one is present.
StreamingMCastChanServerCount	The number of real time stream components in <b>StreamingMCastChanServerList</b> .
StreamingMCastChanServerList	Sets the network address/port information for real time stream components.
GapMCastChanServerCount	Number of Gap Fill Server components in <b>GapMCastServerList</b> .
GapMCastChanServerList	Sets the network address/port information for Gap Fill Server components.

Table 161: **RsslRDMSERVICESEQMCASTINFO** Structure Members (Continued)

#### 8.4.15.2 RSSL RDM Service Sequenced Multicast Info Enumeration Values

FLAG ENUMERATION	DESCRIPTION
RDM_SVC_SMF_HAS_SNAPSHOT_SERV	Indicates the presence of <b>snapshotServer</b> .
RDM_SVC_SMF_HAS_GAP_REC_SERV	Indicates the presence of <b>gapRecoveryServer</b> .
RDM_SVC_SMF_HAS_REF_DATA_SERV	Indicates the presence of <b>refDataServer</b> .
RDM_SVC_SMF_HAS_SMC_SERV	Indicates the presence of <b>StreamingMCastChanServerList</b> .
RDM_SVC_SMF_HAS_GMC_SERV	Indicates the presence of <b>GapMCastChanServerList</b> .

Table 162: RSSL RDM Service Sequenced Multicast Info Enumeration Values

#### 8.4.15.3 RSSL RDM Address/Port Information

STRUCTURE MEMBER	DESCRIPTION
address	The network address of the component.
port	The network port of the component.
domain	The item domain associated with this component (e.g.: 6 (MarketPrice)).

Table 163: RSSL RDM Address/Port Information Structure Members

#### 8.4.15.4 RSSL RDM Sequenced Multicast Info Utility Functions

UTILITY	DESCRIPTION
rsslClearRDMMCAAddressPortInfo	Clears an <b>RsslRDMAAddressPortInfo</b> structure.

Table 164: **RsslRDMSERVICESEQMCASTINFO** Utility Functions

UTILITY	DESCRIPTION
<code>rsslClearRDMSERVICESeqMcastInfo</code>	Clears an <code>RsslRDMSERVICESeqMcastInfo</code> structure.

Table 164: `RsslRDMSERVICESeqMcastInfo` Utility Functions (Continued)

### 8.4.16 RSSL RDM Directory Message Union

This union can contain any of the RDM Directory message types. This is provided for use with directory-specific functionality.

#### 8.4.16.1 RSSL RDM Directory Union

UNION MEMBERS	DESCRIPTION
<code>rdmMsgBase</code>	The message base information.
<code>request</code>	The <code>RsslRDMDirectoryRequest</code> as described in Section 8.4.1.
<code>close</code>	The <code>RsslRDMDirectoryClose</code> as described in Section 8.4.5.
<code>refresh</code>	The <code>RsslRDMDirectoryRefresh</code> as described in Section 8.4.2.
<code>status</code>	The <code>RsslRDMDirectoryStatus</code> as described in Section 8.4.4.
<code>update</code>	The <code>RsslRDMDirectoryUpdate</code> as described in Section 8.4.3.
<code>consumerStatus</code>	The <code>RsslRDMDirectoryConsumerStatus</code> as described in Section 8.4.6.

Table 165: `RsslRDMDirectoryMsg` Union Members

#### 8.4.16.2 RSSL RDM Directory Message Utility Functions

FUNCTION NAME	DESCRIPTION
<code>rsslClearRDMDirectoryMsg</code>	Clears an <code>RsslRDMDirectoryMsg</code> union. Useful for reuse.
<code>rsslCopyRDMDirectoryMsg</code>	Performs a deep copy of an <code>RsslRDMDirectoryMsg</code> structure.

Table 166: `RsslRDMDirectoryMsg` Utility Functions

### 8.4.17 Source Directory Encoding and Decoding

#### 8.4.17.1 RSSL RDM Directory Encoding and Decoding Functions

FUNCTION NAME	DESCRIPTION
<code>rsslEncodeRDMDirectoryMsg</code>	Used to encode an RDM Directory message. This function takes the <code>RsslRDMDirectoryMsg</code> as a parameter. Alternately, <code>rsslEncodeRDMMsg</code> can be used if encoding from an <code>RsslRDMMsg</code> .
<code>rsslDecodeRDMDirectoryMsg</code>	Used to decode an RDM Directory message. This function populates the <code>RsslRDMDirectoryMsg</code> and leverages the Value Added Utility message buffer (refer to Section 9.2). Alternately, <code>rsslDecodeRDMMsg</code> can be used to decode into an <code>RsslRDMMsg</code> .

Table 167: RDM Directory Encoding and Decoding Functions

### 8.4.17.2 Encoding a Source Directory Request

```

RsslEncodeIterator encodeIter;
RsslRDMDirectoryRequest directoryRequest;

/* Clear the Directory Request structure. */
rsslClearRDMDirectoryRequest(&directoryRequest);

/* Set flags indicating presence of optional members. */
directoryRequest.flags =
    RDM_DR_RQF_HAS_SERVICE_ID
    | RDM_DR_RQF_STREAMING;

/* Set Service ID. */
directoryRequest.serviceId = 273;

/* Set ApplicationName. */
directoryRequest.filter =
    RDM_DIRECTORY_SERVICE_INFO_FILTER
    | RDM_DIRECTORY_SERVICE_STATE_FILTER
    | RDM_DIRECTORY_SERVICE_GROUP_FILTER;

/* Clear the encode iterator, set its RWF Version, and set it to a buffer for encoding into. */
rsslClearEncodeIterator(&encodeIter);
ret = rsslSetEncodeIteratorRWFVersion(&encodeIter, channelMajorVersion, channelMinorVersion);
ret = rsslSetEncodeIteratorBuffer(&encodeIter, &msgBuffer);

/* Encode the message. */
ret = rsslEncodeRDMMsg(&encodeIter, (RsslRDMMsg*)&directoryRequest, &msgBuffer.length,
    &rsslErrorInfo);

```

#### Code Example 24: Directory Request Encoding Example

### 8.4.17.3 Decoding a Source Directory Request

```

/* The decoder may require additional space to store things such as lists. */
char memoryArray[1024];
RsslBuffer memoryBuffer = { 1024, memoryArray };

RsslDecodeIterator decodeIter;
RsslMsg msg;
RsslRDMMsg rdmMsg;
RsslRDMDirectoryRequest *pDirectoryRequest;

/* Clear the decode iterator, set its RWF Version, and set it to the encoded buffer. */
rsslClearDecodeIterator(&decodeIter);
ret = rsslSetDecodeIteratorRWFVersion(&decodeIter, channelMajorVersion, channelMinorVersion);
ret = rsslSetDecodeIteratorBuffer(&decodeIter, &msgBuffer);

```

```

/* Decode the message to an RsslMsg structure and RsslRDMMsg structure. */
ret = rsslDecodeRDMMsg(&decodeIter, &msg, &rdmMsg, &memoryBuffer, &rsslErrorInfo);

if (ret == RSSL_RET_SUCCESS
    && rdmMsg.rdmMsgBase.domainType == RSSL_DMT_SOURCE && rdmMsg.rdmMsgBase.rdmMsgType ==
    RDM_DR_MT_REQUEST)
{
    /* The message we decoded is an RsslRDMDirectoryRequest. */
    pDirectoryRequest = &rdmMsg.directoryMsg.request;

    /* Print if Info filter was requested. */
    if (pDirectoryRequest->filter & RDM_DIRECTORY_SERVICE_INFO_FILTER)
        printf("Info filter requested.\n");

    /* Print if State filter was requested. */
    if (pDirectoryRequest->filter & RDM_DIRECTORY_SERVICE_STATE_FILTER)
        printf("State filter requested.\n");

    /* Print if Group filter was requested. */
    if (pDirectoryRequest->filter & RDM_DIRECTORY_SERVICE_GROUP_FILTER)
        printf("Group filter requested.\n");

    /* Print service ID if present. */
    if (pDirectoryRequest->flags & RDM_DR_RQF_HAS_SERVICE_ID)
        printf("Service ID: %u\n", pDirectoryRequest->serviceId);
}

```

### Code Example 25: Directory Request Decoding Example

#### 8.4.17.4 Encoding a Source Directory Refresh

```

RsslEncodeIterator encodeIter;
RsslRDMDirectoryRefresh directoryRefresh;

/* List of services to be used.
 * This example will show encoding of one service. Additional services
 * can be set up using the same method shown below. */

RsslRDMService serviceList[1];
/* Lists to be used with MY_SERVICE. */
RsslUInt capabilitiesList[3];
RsslBuffer dictionariesList[2];
RsslQos qosList[2];

/* Clear the Directory Refresh structure. */
rsslClearRDMDirectoryRefresh(&directoryRefresh);

/* Set flags */

```

```

directoryRefresh.flags = RDM_DR_RFF_SOLICITED;

/* Set state. */
directoryRefresh.state.streamState = RSSL_STREAM_OPEN;
directoryRefresh.state.dataState = RSSL_DATA_OK;
directoryRefresh.state.code = RSSL_SC_NONE;

/* Set filter to say the Info, State, and Group filters are supported. */
directoryRefresh.filter =
    RDM_DIRECTORY_SERVICE_INFO_FILTER
    | RDM_DIRECTORY_SERVICE_STATE_FILTER
    | RDM_DIRECTORY_SERVICE_GROUP_FILTER;

/** Build Service MY_SERVICE. */

rsslClearRDMService(&serviceList[0]);

/* Set flags to indicate Info and State filter are present. */
serviceList[0].flags =
    RDM_SVCF_HAS_INFO
    | RDM_SVCF_HAS_STATE;

/* Set action to indicate adding a new service. */
serviceList[0].info.action = RSSL_MPEA_ADD_ENTRY;

/** Build Info for MY_SERVICE. */

/* Set flags to indicate optional members. */
serviceList[0].info.flags =
    RDM_SVC_IFF_HAS_VENDOR
    | RDM_SVC_IFF_HAS_DICTS_PROVIDED
    | RDM_SVC_IFF_HAS_DICTS_USED
    | RDM_SVC_IFF_HAS_QOS;

/* Set service name. */
serviceList[0].info.serviceName.data = "MY_SERVICE";
serviceList[0].info.serviceName.length = 10;

/* Set vendor name. */
serviceList[0].info.vendor.data = "Thomson Reuters";
serviceList[0].info.vendor.length = 15;

/* Build capabilities list. */
capabilitiesList[0] = RSSL_DMT_DICTIONARY;
capabilitiesList[1] = RSSL_DMT_MARKET_PRICE;
capabilitiesList[2] = RSSL_DMT_MARKET_BY_ORDER;

/* Set capabilities list. */
serviceList[0].info.capabilitiesList = capabilitiesList;
serviceList[0].info.capabilitiesCount = 3;

```

```

/* Build dictionary list to use with dictionariesProvidedList and dictionariesUsedList. */
dictionariesList[0].data = "RWFFld";
dictionariesList[0].length = 6;
dictionariesList[1].data = "RWFEnum";
dictionariesList[1].length = 7;

/* Set dictionaries provided. */
serviceList[0].info.dictionariesProvidedList = dictionariesList;
serviceList[0].info.dictionariesProvidedCount = 2;

/* Set dictionaries used. */
serviceList[0].info.dictionariesUsedList = dictionariesList;
serviceList[0].info.dictionariesUsedCount = 2;

/* Build QoS list. */
qosList[0].timeliness = RSSL_QOS_TIME_REALTIME;
qosList[0].rate = RSSL_QOS_RATE_TICK_BY_TICK;
qosList[1].timeliness = RSSL_QOS_TIME_REALTIME;
qosList[1].rate = RSSL_QOS_RATE_JIT_CONFLATED;

/* Set QoS list. */
serviceList[0].info.qosList = qosList;
serviceList[0].info.qosCount = 2;

/** Build Service State for MY_SERVICE */
serviceList[0].state.flags = RDM_SVC_STF_HAS_ACCEPTING_REQS;
serviceList[0].state.serviceState = 1;
serviceList[0].state.acceptingRequests = 1;

/** Finish and encode. */

/* Set the array of services on the message. The refresh will information about 2 services*/
directoryRefresh.serviceList = serviceList;
directoryRefresh.serviceCount = 1;

/* Clear the encode iterator, set its RWF Version, and set it to a buffer for encoding into. */
rsslClearEncodeIterator(&encodeIter);
ret = rsslSetEncodeIteratorRWFVersion(&encodeIter, channelMajorVersion, channelMinorVersion);
ret = rsslSetEncodeIteratorBuffer(&encodeIter, &msgBuffer);

/* Encode the message. */
ret = rsslEncodeRDMMsg(&encodeIter, (RsslRDMMsg*)&directoryRefresh, &msgBuffer.length,
    &rsslErrorInfo);

```

### Code Example 26: Directory Refresh Encoding Example

### 8.4.17.5 Decoding a Source Directory Refresh

```

/* The decoder may require additional space to store things such as lists. */
char memoryArray[4096];
RsslBuffer memoryBuffer = { 4096, memoryArray };

RsslDecodeIterator decodeIter;
RsslMsg msg;
RsslRDMMsg rdmMsg;
RsslRDMDirectoryRefresh *pDirectoryRefresh;

/* Clear the decode iterator, set its RWF Version, and set it to the encoded buffer. */
rsslClearDecodeIterator(&decodeIter);
ret = rsslSetDecodeIteratorRWFVersion(&decodeIter, channelMajorVersion, channelMinorVersion);
ret = rsslSetDecodeIteratorBuffer(&decodeIter, &msgBuffer);

/* Decode the message to an RsslMsg structure and RsslRDMMsg structure. */
ret = rsslDecodeRDMMsg(&decodeIter, &msg, &rdmMsg, &memoryBuffer, &rsslErrorInfo);

if (ret == RSSL_RET_SUCCESS && rdmMsg.rdmMsgBase.domainType == RSSL_DMT_SOURCE &&
    rdmMsg.rdmMsgBase.rdmMsgType == RDM_DR_MT_REFRESH)
{
    RsslUInt32 i;

    /* The message we decoded is an RsslRDMDirectoryRefresh. */
    pDirectoryRefresh = &rdmMsg.directoryMsg.refresh;

    /* Print serviceId if present. */
    if (pDirectoryRefresh->flags & RDM_DR_RFF_HAS_SERVICE_ID)
        printf("Service ID: %u\n", pDirectoryRefresh->serviceId);

    /* Print information about each service present in the refresh. */
    for(i = 0; i < pDirectoryRefresh->serviceCount; ++i)
    {
        /* Print Service Info if present */
        if (pDirectoryRefresh->serviceList[i].flags & RDM_SVCF_HAS_INFO)
        {
            RsslUInt32 j;
            RsslRDMServiceInfo *pInfo = &pDirectoryRefresh->serviceList[i].info;

            /* Print service name. */
            printf("Service Name: %.*s\n", pInfo->serviceName.length, pInfo->serviceName.data);

            /* Print vendor name if present. */
            if (pInfo->flags & RDM_SVC_IFF_HAS_VENDOR)
                printf("Vendor: %.*s\n", pInfo->vendor.length, pInfo->vendor.data);

            /* Print supported domains if present. */
            for (j = 0; j < pInfo->capabilitiesCount; ++j)
                printf("Capability: %s\n", rsslDomainTypeToString(pInfo->capabilitiesList[j]));
        }
    }
}

```

```

/* Print dictionaries provided if present. */
if (pInfo->flags & RDM_SVC_IFF_HAS_DICTS_PROVIDED)
{
    for (j = 0; j < pInfo->dictionariesProvidedCount; ++j)
        printf("Dictionary Provided: %.*s\n", pInfo->dictionariesProvidedList[j].length,
            pInfo->dictionariesProvidedList[j].data);
}

/* Print dictionaries used if present. */
if (pInfo->flags & RDM_SVC_IFF_HAS_DICTS_USED)
{
    for (j = 0; j < pInfo->dictionariesUsedCount; ++j)
        printf("Dictionary Used: %.*s\n", pInfo->dictionariesUsedList[j].length,
            pInfo->dictionariesUsedList[j].data);
}

/* Print qualities of service supported if present. */
if (pInfo->flags & RDM_SVC_IFF_HAS_QOS)
{
    for (j = 0; j < pInfo->qosCount; ++j)
        printf("QoS: %s,%s\n", rsslQosTimelinessToString(pInfo->
            qosList[j].timeliness), rsslQosRateToString(pInfo->qosList[j].rate));
}
}

/* Print Service State if present */
if (pDirectoryRefresh->serviceList[i].flags & RDM_SVCF_HAS_STATE)
{
    RsslRDMSERVICE_STATE *pState = &pDirectoryRefresh->serviceList[i].state;

    printf("Service State: %llu\n", pState->serviceState);

    if (pState->flags & RDM_SVC_STF_HAS_ACCEPTING_REQS)
        printf("Accepting Requests: %llu\n", pState->acceptingRequests);
}
}
}

```

**Code Example 27: Directory Refresh Decoding Example**



## 8.5 Dictionary Domain

The Dictionary domain model conveys information needed for parsing published data. Dictionaries provide additional meta-data, such as that necessary to decode the content of an **RsslFieldEntry** or additional content related to its **fieldId**. For more information about the different types of dictionaries and their usage, refer to the *Transport API C Edition RDM Usage Guide*.

The structures provided for this domain make it easier to use the existing utilities for encoding, decoding, and caching dictionary information. For more information on these utilities, see the *Transport API C Edition RDM Usage Guide*.

### 8.5.1 RSSL RDM Dictionary Request

A **Dictionary Request** message is encoded and sent by OMM Consumer applications. This message requests a dictionary from a service.

The **RsslRDMDictionaryRequest** represents all members of a dictionary request message and is easily used in OMM applications that leverage RDM. This structure follows the behavior and layout that is defined in the *Transport API C Edition RDM Usage Guide*.

#### 8.5.1.1 RSSL RDM Dictionary Request Structure Members

STRUCTURE MEMBER	DESCRIPTION
dictionaryName	<b>Required.</b> Indicates the name of the dictionary being requested.
flags	<b>Required.</b> Indicates the presence of optional dictionary request members. For details, refer to Section 8.5.1.2.
rdmMsgBase	<b>Required.</b> Contains general message information like streamId and domainType.
serviceld	<b>Required.</b> Specifies the service from which to request the dictionary.
verbosity	<b>Required.</b> Indicates the amount of information desired from the dictionary. Available enumerations are: <ul style="list-style-type: none"> <li><b>RDM_DICTIONARY_INFO == 0x00:</b> Version information only</li> <li><b>RDM_DICTIONARY_MINIMAL == 0x03:</b> Provides information needed for caching</li> <li><b>RDM_DICTIONARY_NORMAL == 0x07:</b> Provides all information needed for decoding</li> <li><b>RDM_DICTIONARY_VERBOSE == 0x0F:</b> Provides all information (including comments)</li> </ul> Providers are not required to support the <b>MINIMAL</b> and <b>VERBOSE</b> filters.

Table 168: **RsslRDMDictionaryRequest** Structure Members

#### 8.5.1.2 RSSL RDM Dictionary Request Flag Enumeration Value

FLAG ENUMERATION	DESCRIPTION
RDM_DC_RQF_STREAMING	Indicates that the dictionary stream should remain open after the initial refresh. An open stream can listen for status messages that indicate changes to the dictionary version. For more information, see the <i>Transport API C Edition RDM Usage Guide</i> .

Table 169: **RsslRDMDictionaryRequest** Flag

### 8.5.1.3 RSSL RDM Dictionary Request Utility Functions

FUNCTION NAME	DESCRIPTION
<code>rsslClearRDMDictionaryRequest</code>	Clears an <code>RsslRDMDictionaryRequest</code> structure. Useful for structure reuse.
<code>rsslCopyRDMDictionaryRequest</code>	Performs a deep copy of an <code>RsslRDMDictionaryRequest</code> structure.

**Table 170: `RsslRDMDictionaryRequest` Utility Functions**

### 8.5.2 RSSL RDM Dictionary Refresh

A **Dictionary Refresh** message is encoded and sent by OMM provider applications. This message transmits dictionary content in response to a request.

The `RsslRDMDictionaryRefresh` represents all members of a dictionary refresh message and is easy to use in OMM applications that leverage RDM. This structure follows the behavior and layout that is defined in the *Transport API C Edition RDM Usage Guide*.

#### 8.5.2.1 RSSL RDM Dictionary Refresh Structure Members

STRUCTURE MEMBER	DESCRIPTION
<code>dataBody</code>	When decoding, this points to the encoded data buffer with dictionary content. This buffer should be set on an <code>RsslDecodeIterator</code> and passed to the appropriate decode function according to the <code>type</code> . <b>Not used when encoding.</b> The dictionary is retrieved from the <code>RsslDataDictionary</code> structure.
<code>pDictionary</code>	<b>Conditional (required when encoding).</b> Points to an <code>RsslDataDictionary</code> object that contains content to encode. For more information on the <code>RsslDataDictionary</code> structure, refer to the <i>Transport API C Edition RDM Usage Guide</i> . <b>Not used when decoding.</b>
<code>dictionaryId</code>	When decoding, this will be populated with the dictionary's ID. The Dictionary is retrieved from the <code>RsslDataDictionary</code> structure. This structure's presence is indicated by the <code>RDM_DC_RFF_HAS_INFO</code> flag. <b>Not used when encoding.</b>
<code>dictionaryName</code>	<b>Required.</b> Indicates the name of the dictionary being provided.
<code>flags</code>	<b>Required.</b> Indicates the presence of optional dictionary refresh members. For details, refer to Section 8.5.2.2.
<code>rdmMsgBase</code>	<b>Required.</b> Contains general message information like <code>streamId</code> and <code>domainType</code> .
<code>sequenceNumber</code>	<b>Optional.</b> A user-specified, item-level sequence number that the application can use to sequence messages in this stream. If present, a <code>flags</code> value of <code>RDM_DC_RFF_HAS_SEQ_NUM</code> should be specified.
<code>serviceId</code>	<b>Required.</b> Indicates the service ID of the service from which the dictionary is provided.

**Table 171: `RsslRDMDictionaryRefresh` Structure Members**


STRUCTURE MEMBER	DESCRIPTION
startFid	Maintains the state when encoding a dictionary across multiple messages.   <b>Warning!</b> To ensure that all dictionary content is correctly encoded, the application should not modify this.
state	<b>Required.</b> Indicates the state of the dictionary stream. Defaults to a <b>streamState</b> of <b>RSSL_STREAM_OPEN</b> and a <b>dataState</b> of <b>RSSL_DATA_OK</b> . For more information on <b>RsslState</b> , refer to the <i>Transport API C Edition Developers Guide</i> .
type	<b>Required.</b> Indicates the type of dictionary being provided. The dictionary encoder and decoder support the following types: <ul style="list-style-type: none"> <li>• <b>RDM_DICTIONARY_FIELD_DEFINITIONS == 1</b></li> <li>• <b>RDM_DICTIONARY_ENUM_TABLES == 2</b></li> </ul>
verbosity	<b>Required.</b> Indicates the amount of information desired from the dictionary. Available enumerations are: <ul style="list-style-type: none"> <li>• <b>RDM_DICTIONARY_INFO == 0x00</b>: Provides version information only</li> <li>• <b>RDM_DICTIONARY_MINIMAL == 0x03</b>: Provides information needed for caching</li> <li>• <b>RDM_DICTIONARY_NORMAL == 0x07</b>: Provides all information needed for decoding</li> <li>• <b>RDM_DICTIONARY_VERBOSE == 0x0F</b>: Provides all information (including comments)</li> </ul> Providers do not need to support the <b>MINIMAL</b> and <b>VERBOSE</b> filters.
version	When decoding, this will be populated with the dictionary's version string. Presence is indicated by the <b>RDM_DC_RFF_HAS_INFO</b> flag. <b>Not used when encoding.</b> The Dictionary is retrieved from the <b>RsslDataDictionary</b> structure.

Table 171: **RsslRDMDictionaryRefresh** Structure Members (Continued)

## 8.5.2.2 RSSL RDM Dictionary Refresh Flag Enumeration Values

FLAG ENUMERATION	DESCRIPTION
RDM_DC_RFF_CLEAR_CACHE	Indicates that stored payload information associated with the dictionary stream should be cleared. This might happen if some portion of data is known to be invalid.
RDM_DC_RFF_HAS_INFO	Indicates the presence of <b>dictionaryId</b> , <b>version</b> , and <b>type</b> . <b>Not used when encoding.</b> The <b>encode</b> function adds information to the encoded message when appropriate.
RDM_DC_RFF_HAS_SEQ_NUM	Indicates presence of <b>sequenceNumber</b> .
RDM_DC_RFF_IS_COMPLETE	Indicates that this is the final fragment and that the consumer has received all content for this dictionary. <b>Not used when encoding.</b> The <b>encode</b> function adds information to the encoded message when appropriate.

Table 172: **RsslRDMDictionaryRefreshFlags**

FLAG ENUMERATION	DESCRIPTION
RDM_DC_RFF_SOLICITED	Indicates that the directory refresh is solicited (e.g., it is a response to a request). If the flag is not present, this refresh is unsolicited.

Table 172: **RsslRDMDictionaryRefreshFlags** (Continued)

### 8.5.2.3 RSSL RDM Dictionary Refresh Utility Functions

FUNCTION NAME	DESCRIPTION
rsslClearRDMDictionaryRefresh	Clears an <b>RsslRDMDictionaryRefresh</b> structure. Useful for structure reuse.
rsslCopyRDMDictionaryRefresh	Performs a deep copy of an <b>RsslRDMDictionaryRefresh</b> structure.

Table 173: **RsslRDMDictionaryRefresh** Utility Functions

### 8.5.3 RSSL RDM Dictionary Status

OMM provider and non-interactive provider applications use the **Dictionary Status** message to convey state information associated with the dictionary stream. Such state information can indicate that a dictionary stream cannot be established or to inform a consumer of a state change associated with an open login stream. The Dictionary status message can also indicate that a new dictionary should be retrieved. For more information on handling Dictionary versions, see the *Transport API C Edition RDM Usage Guide*.

The **RsslRDMDictionaryStatus** represents all members of a dictionary status message and allows for simplified use in OMM applications that leverage RDM. This structure follows the behavior and layout that is defined in the *Transport API C Edition RDM Usage Guide*.

#### 8.5.3.1 RSSL RDM Dictionary Status Structure Members

STRUCTURE MEMBER	DESCRIPTION
flags	<b>Required.</b> Indicate the presence of optional dictionary status members. For details, refer to Section 8.5.3.2.
rdmMsgBase	<b>Required.</b> Contains general message information like <b>streamId</b> and <b>domainType</b> .
state	<b>Optional.</b> Indicates the state of the dictionary stream. For more information on <b>RsslState</b> , refer to the <i>Transport API C Edition Developers Guide</i> . If present, a <b>flags</b> value of <b>RDM_DC_STF_HAS_STATE</b> should be specified.

Table 174: **RsslRDMDictionaryStatus** Structure Members

#### 8.5.3.2 RSSL RDM Dictionary Status Flag Enumeration Value

FLAG ENUMERATION	DESCRIPTION
RDM_DC_STF_CLEAR_CACHE	Indicates that any stored payload information associated with the dictionary stream should be cleared. This might happen if some portion of data is known to be invalid.

Table 175: **RsslRDMDictionaryStatus** Flags

FLAG ENUMERATION	DESCRIPTION
RDM_DC_STF_HAS_STATE	Indicates the presence of <b>state</b> . If absent, any previously conveyed state continues to apply.

Table 175: **RsslRDMDictionaryStatus** Flags (Continued)

### 8.5.3.3 RSSL RDM Dictionary Status Utility Functions

FUNCTION NAME	DESCRIPTION
rsslClearRDMLoginStatus	Clears an <b>RsslRDMLoginStatus</b> structure. Useful for structure reuse.
rsslCopyRDMLoginStatus	Performs a deep copy of an <b>RsslRDMLoginStatus</b> structure.

Table 176: **RsslRDMDictionaryStatus** Utility Functions

## 8.5.4 RSSL RDM Dictionary Close

A **Dictionary Close** message is encoded and sent by OMM consumer applications. This message allows a consumer to close an open dictionary stream. A provider can close the directory stream via a Dictionary Status message, refer to Section 8.5.3.

### 8.5.4.1 RSSL RDM Dictionary Close Structure Members

STRUCTURE MEMBER	DESCRIPTION
rdmMsgBase	<b>Required</b> . Contains general message information like <b>streamId</b> and <b>domainType</b> .

Table 177: **RsslRDMDictionaryClose** Structure Members

### 8.5.4.2 RSSL RDM Dictionary Close Utility Functions

FUNCTION NAME	DESCRIPTION
rsslClearRDMDictionaryClose	Clears an <b>RsslRDMDictionaryClose</b> structure. Useful for structure reuse.
rsslCopyRDMDictionaryClose	Performs a deep copy of an <b>RsslRDMDictionaryClose</b> structure.

Table 178: **RsslRDMDictionaryClose** Utility Functions

## 8.5.5 RSSL RDM Dictionary Message Union

This union can contain any of the RDM Dictionary message types. This is provided for use with Dictionary specific functionality.

### 8.5.5.1 RSSL RDM Dictionary Union

UNION MEMBERS	DESCRIPTION
rdmMsgBase	The message base information.
request	The <b>RsslRDMDictionaryRequest</b> as described in Section 8.5.1.
close	The <b>RsslRDMDictionaryClose</b> as described in Section 8.5.4.

Table 179: **RsslRDMDictionaryMsg** Union Members

UNION MEMBERS	DESCRIPTION
refresh	The <code>RsslRDMDictionaryRefresh</code> as described in Section 8.5.2.
status	The <code>RsslRDMDictionaryStatus</code> as described in Section 8.5.3.

Table 179: `RsslRDMDictionaryMsg` Union Members (Continued)

### 8.5.5.2 RSSL RDM Dictionary Message Utility Functions

FUNCTION NAME	DESCRIPTION
<code>rsslClearRDMDictionaryMsg</code>	Clears an <code>RsslRDMDictionaryMsg</code> union. Useful for reuse.
<code>rsslCopyRDMDictionaryMsg</code>	Performs a deep copy of an <code>RsslRDMDictionaryMsg</code> structure.

Table 180: `RsslRDMDictionaryMsg` Utility Functions

## 8.5.6 Dictionary Encoding and Decoding

### 8.5.6.1 RSSL RDM Dictionary Encoding and Decoding Functions

FUNCTION NAME	DESCRIPTION
<code>rsslEncodeRDMDictionaryMsg</code>	Used to encode an RDM Dictionary message. This function takes the <code>RsslRDMDictionaryMsg</code> as a parameter. Alternately, <code>rsslEncodeRDMMsg</code> can be used if encoding from an <code>RsslRDMMsg</code> .
<code>rsslDecodeRDMDictionaryMsg</code>	Used to decode an RDM Directory message. This function populates the <code>RsslRDMDictionaryMsg</code> and leverages the Value Added Utility message buffer (refer to Section 9.2). Alternately, <code>rsslDecodeRDMMsg</code> can be used to decode into an <code>RsslRDMMsg</code> .

Table 181: RDM Dictionary Encoding and Decoding Functions

### 8.5.6.2 Encoding a Dictionary Request

```

RsslEncodeIterator encodeIter;
RsslRDMDictionaryRequest dictionaryRequest;

/* Clear the Dictionary Request structure. */
rsslClearRDMDictionaryRequest(&dictionaryRequest);

/* Set flags. */
dictionaryRequest.flags = RDM_DC_RQF_STREAMING;

/* Set serviceId. */
dictionaryRequest.serviceId = 273;

/* Set verbosity. */
dictionaryRequest.verbosity = RDM_DICTIONARY_NORMAL;

/* Set dictionary name. */

```

```

dictionaryRequest.dictionaryName.data = "RWFFld";
dictionaryRequest.dictionaryName.length = 6;

/* Clear the encode iterator, set its RWF Version, and set it to a buffer for encoding into. */
rsslClearEncodeIterator(&encodeIter);
ret = rsslSetEncodeIteratorRWFVersion(&encodeIter, channelMajorVersion, channelMinorVersion);
ret = rsslSetEncodeIteratorBuffer(&encodeIter, &msgBuffer);

/* Encode the message. */
ret = rsslEncodeRDMMsg(&encodeIter, (RsslRDMMsg*)&dictionaryRequest, &msgBuffer.length,
    &rsslErrorInfo);

```

### Code Example 28: Dictionary Request Encoding Example

#### 8.5.6.3 Decoding a Dictionary Request

```

/* The decoder may require additional space to store things such as lists. */
char memoryArray[1024];
RsslBuffer memoryBuffer = { 1024, memoryArray };

RsslDecodeIterator decodeIter;
RsslMsg msg;
RsslRDMMsg rdmmMsg;
RsslRDMDictionaryRequest *pDictionaryRequest;

/* Clear the decode iterator, set its RWF Version, and set it to the encoded buffer. */
rsslClearDecodeIterator(&decodeIter);
ret = rsslSetDecodeIteratorRWFVersion(&decodeIter, channelMajorVersion, channelMinorVersion);
ret = rsslSetDecodeIteratorBuffer(&decodeIter, &msgBuffer);

/* Decode the message to an RsslMsg structure and RsslRDMMsg structure. */
ret = rsslDecodeRDMMsg(&decodeIter, &msg, &rdmmMsg, &memoryBuffer, &rsslErrorInfo);

if (ret == RSSL_RET_SUCCESS && rdmmMsg.rdmMsgBase.domainType == RSSL_DMT_DICTIONARY &&
    rdmmMsg.rdmMsgBase.rdmMsgType == RDM_DC_MT_REQUEST)
{
    /* The message we decoded is an RsslRDMDictionaryRequest. */
    pDictionaryRequest = &rdmmMsg.dictionaryMsg.request;

    /* Print if streaming. */
    if (pDictionaryRequest->flags & RDM_DC_RQF_STREAMING)
        printf("Request is streaming.\n");

    /* Print serviceId. */
    printf("Service ID: %u\n", pDictionaryRequest->serviceId);

    /* Print verbosity. */
    printf("Verbosity: %u\n", pDictionaryRequest->verbosity);
}

```

```

    /* Print dictionary name. */
    printf("Dictionary Name: %.*s\n", pDictionaryRequest->dictionaryName.length, pDictionaryRequest->
        dictionaryName.data);
}

```

### Code Example 29: Dictionary Request Decoding Example

#### 8.5.6.4 Encoding a Dictionary Refresh

```

RsslEncodeIterator encodeIter;
RsslRDMDictionaryRefresh dictionaryRefresh;
RsslDataDictionary dataDictionary;

rsslClearDataDictionary(&dataDictionary);
ret = rsslLoadFieldDictionary("RDMFieldDictionary", &dataDictionary, &errorText);

/* Clear the Dictionary Refresh structure. */
rsslClearRDMDictionaryRefresh(&dictionaryRefresh);

/* Set flags. */
dictionaryRefresh.flags = RDM_DC_RFF_SOLICITED;

/* Set dictionary name. */
dictionaryRefresh.dictionaryName.data = "RWFFld";
dictionaryRefresh.dictionaryName.length = 6;

/* Set type. */
dictionaryRefresh.type = RDM_DICTIONARY_FIELD_DEFINITIONS;

/* Set the dictionary. */
dictionaryRefresh.pDictionary = &dataDictionary;

/* Set serviceId. */
dictionaryRefresh.serviceId = 273;

/* Set verbosity. */
dictionaryRefresh.verbosity = RDM_DICTIONARY_NORMAL;

do
{
    /* (Represents the application getting a new buffer to encode the message into.) */
    getNextEncodeBuffer(&msgBuffer);

    /* Clear the encode iterator, set its RWF Version, and set it to a buffer for encoding into. */
    rsslClearEncodeIterator(&encodeIter);
    ret = rsslSetEncodeIteratorRWFVersion(&encodeIter, channelMajorVersion, channelMinorVersion);
    ret = rsslSetEncodeIteratorBuffer(&encodeIter, &msgBuffer);
}

```



```

/* Encode the message. This will return RSSL_RET_DICT_PART_ENCODED if it only a part
 * was encoded. We must keep encoding the message until RSSL_RET_SUCCESS is returned. */
ret = rsslEncodeRDMMsg(&encodeIter, (RsslRDMMsg*)&dictionaryRefresh, &msgBuffer.length,
    &rsslErrorInfo);
} while (ret == RSSL_RET_DICT_PART_ENCODED);

```

### Code Example 30: Dictionary Refresh Encoding Example

#### 8.5.6.5 Decoding a Dictionary Refresh

```

/* The decoder may require additional space to store things such as lists. */
char memoryArray[4096];
RsslBuffer memoryBuffer = { 4096, memoryArray };

RsslDecodeIterator decodeIter;
RsslMsg msg;
RsslRDMMsg rdmMsg;
RsslRDMDictionaryRefresh *pDictionaryRefresh;
RsslInt32 dictionaryTypeForThisStreamId = 0;

RsslDataDictionary dataDictionary;

rsslClearDataDictionary(&dataDictionary);

do
{
    /* (Represents the application getting the next buffer to decode.) */
    getNextDecodeBuffer(&msgBuffer);

    /* Reset our memory buffer. */
    memoryBuffer.length = 4096;
    memoryBuffer.data = memoryArray;

    /* Clear the decode iterator, set its RWF Version, and set it to the encoded buffer. */
    rsslClearDecodeIterator(&decodeIter);
    ret = rsslSetDecodeIteratorRWFVersion(&decodeIter, channelMajorVersion, channelMinorVersion);
    ret = rsslSetDecodeIteratorBuffer(&decodeIter, &msgBuffer);

    /* Decode the message to an RsslMsg structure and RsslRDMMsg structure. */
    ret = rsslDecodeRDMMsg(&decodeIter, &msg, &rdmMsg, &memoryBuffer, &rsslErrorInfo);

    if (ret == RSSL_RET_SUCCESS && rdmMsg.rdmMsgBase.domainType == RSSL_DMT_DICTIONARY &&
        rdmMsg.rdmMsgBase.rdmMsgType == RDM_DC_MT_REFRESH)
    {
        /* The message we decoded is an RsslRDMDictionaryRefresh. */
        pDictionaryRefresh = &rdmMsg.dictionaryMsg.refresh;
    }
}

```

```

/* Print if request is streaming. */
if (pDictionaryRefresh->flags & RDM_DC_RFF_SOLICITED)
    printf("Refresh is solicited.\n");

/* Print info if present. If the dictionary is split into parts, this is normally only present
 * on the first part. */
if (pDictionaryRefresh->flags & RDM_DC_RFF_HAS_INFO)
{
    /* Remember the dictionary type for this stream since subsequent parts will not indicate it.
     */
    dictionaryTypeForThisStreamId = pDictionaryRefresh->type;

    /* Print version. */
    printf("Version: %.*s\n", pDictionaryRefresh->version.length, pDictionaryRefresh->
        version.data);

    /* Print dictionary ID. */
    printf("Dictionary ID: %lld\n", pDictionaryRefresh->dictionaryId);
}

/* Print serviceId. */
printf("Service ID: %u\n", pDictionaryRefresh->serviceId);

/* Print verbosity. */
printf("Verbosity: %u\n", pDictionaryRefresh->verbosity);

/* Print dictionary name. */
printf("Dictionary Name: %.*s\n", pDictionaryRefresh->dictionaryName.length,
    pDictionaryRefresh->dictionaryName.data);

if (dictionaryTypeForThisStreamId == RDM_DICTIONARY_FIELD_DEFINITIONS)
{
    /* Decode the dictionary content into the RsslDataDictionary structure. */
    rsslClearDecodeIterator(&decodeIter);
    ret = rsslSetDecodeIteratorRWFVersion(&decodeIter, channelMajorVersion,
        channelMinorVersion);
    ret = rsslSetDecodeIteratorBuffer(&decodeIter, &pDictionaryRefresh->dataBody);
    ret = rsslDecodeFieldDictionary(&decodeIter, &dataDictionary, RDM_DICTIONARY_NORMAL,
        &errorText);
}
}
} while(!(pDictionaryRefresh->flags & RDM_DC_RFF_IS_COMPLETE));

```

### Code Example 31: Dictionary Refresh Decoding Example

## 8.6 RDM Queue Messages

The Queue Messaging domain model is a series of message constructs that you use to interact with a Queue Provider. A Queue Provider can persist content for which users want to have guaranteed delivery and can also help send content to destinations with which users cannot directly communicate.

### 8.6.1 Queue Data Message Persistence

When opening a queue messaging stream with a queue provider, using a persistence file can guarantee delivery of messages sent by the OMM consumer on that queue stream. The queue file will be named after the name of the queue stream (as specified in the `RsslRDMQueueRequest` message that opened the stream). When the consumer submits `RsslRDMQueueData` messages, the consumer stores these messages in the persistence file in case the tunnel stream to the queue provider is lost and reconnected. As `RsslRDMQueueAck` messages are received from the queue provider, space in the persistence file is freed for additional messages. If at any time the application submits an `RsslRDMQueueData` message but the persistence file has no room for it, the application receives the `RSSL_RET_PERSISTENCE_FULL` return code.

The `RsslClassOfService.guarantee.persistLocally` option (set when opening the tunnel stream) specifies whether to create and maintain persistence files. The location for storage of persistent files is specified by the `RsslClassOfService.guarantee.persistenceFilePath` option. For more information on these options, refer to Section 6.8.3

**Note:** Thomson Reuters recommends that the `RsslClassOfService.guarantee.persistenceFilePath` be set to a local storage device.

If a particular queue stream is no longer needed, the user may delete the persistence file that carries the associated queue stream's name.



**Warning!** If you delete a persistence file that stores messages that were not successfully transmitted, the messages will be lost.

### 8.6.2 Queue Request

The OMM application encodes and sends a **Queue Request** message to a Queue Provider to open a user queue. By opening a queue with an `RsslRDMQueueRequest`, the user receives any content previously sent to and persisted on a Queue Provider. To send content to another user's queue, a user must first open their own queue.

MEMBER	DESCRIPTION
<code>rdmMsgBase</code>	<b>Required.</b> Specifies the message type (i.e., <code>RDM_QMSG_MT_REQUEST</code> ) and contains general message information, including the stream's ID ( <code>streamId</code> ) and domain type ( <code>domainType</code> ).
<code>sourceName</code>	<b>Required.</b> Specifies the name of the queue you want to open.

Table 182: `RsslRDMQueueRequest` Members

### 8.6.3 Queue Refresh

A Queue Provider encodes and sends a **Queue Refresh** message to OMM applications to inform users about queue open requests and give state information pertaining to specific queue refresh request attempts.

MEMBER	DESCRIPTION
rdmMsgBase	<b>Required.</b> Sets the message type (i.e., <b>RDM_QMSG_MT_REFRESH</b> ) and contains general message information, including the stream's ID ( <b>streamId</b> ) and domain type ( <b>domainType</b> ).
sourceName	<b>Required.</b> Specifies the name of a queue you want to open, which should match the <b>sourceName</b> specified in the initial queue request.
state	<b>Required.</b> Indicates the state of the queue. <ul style="list-style-type: none"> <li>States of <b>Open</b> and <b>Ok</b> indicate the queue was successfully opened.</li> <li>Other state combinations indicate an issue, for which additional code and text provide supplemental information.</li> </ul> For more information on <b>RsslState</b> , refer to the <i>Transport API C Edition Developers Guide</i> .
queueDepth	<b>Required.</b> Indicates how many Queue Data or Queue Data Expired messages are inbound on this Queue Stream.

Table 183: **RsslRDMQueueRefresh** Members

### 8.6.4 Queue Status

A Queue Provider encodes and sends **Queue Status** messages to OMM applications, conveying state information about a user's queue.

MEMBER	DESCRIPTION
flags	<b>Required.</b> Indicates the presence of optional queue status members. <b>flags</b> has only one enumeration: <b>HAS_STATE</b> , which indicates the presence of the <b>state</b> member. If <b>flags</b> is absent (or has no value), any previously conveyed state continues to apply.
rdmMsgBase	<b>Required.</b> Sets the message type (i.e., <b>RDM_QMSG_MT_STATUS</b> ) and contains general message information, including the stream's ID ( <b>streamId</b> ) and domain type ( <b>domainType</b> ).
state	Indicates the state of the queue: <ul style="list-style-type: none"> <li>States of <b>Open</b> and <b>Ok</b> indicate the queue is in a good state.</li> <li>Other state combinations indicate an issue, for which additional code and text provide supplemental information.</li> </ul> For more information on <b>RsslState</b> , refer to the <i>Transport API C Edition Developers Guide</i> .

Table 184: **RsslRDMQueueStatus** Members

### 8.6.5 Queue Close

An OMM application encodes and sends a **Queue Close** message to a Queue Provider, closing the user's queue.

MEMBER	DESCRIPTION
rdmMsgBase	<b>Required.</b> Sets the message type (i.e., <b>RDM_QMSG_MT_CLOSE</b> ) and contains general message information, including the stream's ID ( <b>streamId</b> ) and domain type ( <b>domainType</b> ).

Table 185: **RsslRDMQueueClose** Members

### 8.6.6 Queue Data

Both OMM applications and queue providers can send and receive **Queue Data** messages, which exchange data content between queue users and also communicate whether content was undeliverable.

#### 8.6.6.1 Queue Data Members

MEMBER	DESCRIPTION
containerType	<b>Required.</b> Indicates the type of contents in this queue data message.
destName	<b>Required.</b> Specifies the name of the queue to which content is sent.
encDataBody	<b>Optional.</b> <ul style="list-style-type: none"> <li>If sending a message, populate <b>encDataBody</b> with pre-encoded content. If sending a message without pre-encoded contents, you can use the encoding methods described in Section 8.6.6.4.</li> <li>If receiving a message, <b>encDataBody</b> can be used to access payload contents for decoding.</li> </ul>
flags	<b>Required.</b> Specifies any flags that indicate more information about this message. For further details on available flags, refer to Section 8.6.6.2. <b>flags</b> is only for decoding, and OMM Consumer applications do not need to set it.
identifier	<b>Required.</b> A user-specified unique identifier for the message being sent. <b>identifier</b> is used when acknowledging this content via a Queue Ack message.
queueDepth	<b>Required.</b> Indicates the number of Queue Data or Queue Data Expired messages still inbound on this queue stream, following this message. <b>queueDepth</b> is only for reading, and OMM Consumer applications do not need to set it.
rdmMsgBase	<b>Required.</b> Sets the message type (i.e., <b>RDM_QMSG_MT_DATA</b> ) and contains general message information, including the stream ID ( <b>streamId</b> ) and domain type ( <b>domainType</b> ).
sourceName	<b>Required.</b> Specifies the name of the queue from which content is sourced, which should match the <b>sourceName</b> specified in the Queue Request for this substream.
timeout	<b>Optional.</b> Specifies the desired timeout for this content (which can be any of the <b>RsslRDMQueueTimeCodes</b> in Section 8.6.6.3 or a specific time interval in milliseconds). If a timeout value expires during the course of delivery, the content is returned as an <b>RsslRDMQueueDataExpired</b> message. If not specified, this defaults to <b>QueueMsgTimeoutCodes.INFINITE</b> (i.e., the content never times out).

Table 186: **RsslRDMQueueData** Members

#### 8.6.6.2 Queue Data Flag

**RsslRDMQueueData** messages and **RsslRDMQueueDataExpired** messages use the following flag:

FLAG	DESCRIPTION
RDM_QMSG_DF_POSSIBLE_DUPLICATE== 0x1	Indicates that the message was retransmitted and that the application might have already received it.

Table 187: Queue Data Flag

### 8.6.6.3 Queue Message Timeout Codes

Queue message timeout codes are special codes that can be set on the `RsslRDMQueueData.timeout` member to specify timeout behavior.

ENUMERATION	DESCRIPTION
RDM_QMSG_TC_INFINITE	This message persists in the system for an infinite amount of time.
RDM_QMSG_TC_IMMEDIATE	This message immediately times out if any portion of its delivery path is unavailable.
RDM_QMSG_TC_PROVIDER_DEFAULT	This message persists in the system for a duration set by the provider.

**Table 188: `RsslRDMQueueTimeoutCodes`**

### 8.6.6.4 Queue Data Encoding

The `RsslRDMQueueData` message allows users to encode both OMM and non-OMM/opaque content. There are several methods available to help with encoding.

FUNCTION NAME	DESCRIPTION
<code>rsslEncodeRDMQueueMsg</code>	When sending no payload or payload content is preencoded and specified on the <code>RsslRDMQueueData.encDataBody</code> buffer, this method encodes the <code>RsslRDMQueueData</code> message in a single call.
<code>rsslEncodeRDMQueueMsgComplete</code>	Completes the content encoding into this <code>RsslRDMQueueData</code> message.
<code>rsslEncodeRDMQueueMsgInit</code>	<p>Begins the process of encoding content into this <code>RsslRDMQueueData</code> message. This method takes an <code>EncodeIterator</code> as a parameter, where the <code>EncodeIterator</code> is associated with the buffer into which content is encoded.</p> <p>When this method returns, users should call additional methods required to encode the content. After all remaining encoding is completed, call the <code>encodeComplete</code> method.</p>

**Table 189: Queue Data Message Encoding Methods**

### 8.6.6.5 Queue Data Message Encoding Code Sample

```
RsslEncodeIterator _msgEncIter;
RsslRDMQueueData _queueData;

// initialize the QueueData encoding
rsslClearRDMQueueData(&_queueData);
_queueData.rdmMsgBase.streamId = QUEUE_MSG_STREAM_ID;
_queueData.identifier= 124;
_queueData.sourceName.data = "MY_QUEUE";
_queueData.sourceName.length = 8;
_queueData.destName.data = "DESTINATION_QUEUE";
_queueData.destName.length = 17;
_queueData.timeout = RDM_QMSG_TC_INFINITE;
_queueData.containerType = RSSL_DT_FIELD_LIST;
```

```

_msgEncIter.clear();
rsslClearEncodeIterator(&_msgEncIter);
rsslSetEncodeIteratorRWFVersion(&_msgEncIter, pTunnelStream-
    >classOfService.common.protocolMajorVersion, pTunnelStream-
    >classOfService.common.protocolMinorVersion);
rsslSetEncodeIteratorBuffer(&_msgEncIter, buffer);

// begin encoding content into RsslRDMQueueData message
if ((ret = rsslEncodeRDMQueueMsgInit(&_msgEncIter, &_queueData, &error)) < RSSL_RET_SUCCESS)
{
    printf("rsslEncodeRDMQueueMsgInit() failed");
    return;
}

// Start Content Encoding - follow standard field list encoding as shown in the
// Transport API C Edition Developers Guide examples.
// When content encoding is done, complete the RsslRDMQueueData encoding

if ((ret = rsslEncodeRDMQueueMsgComplete(&_msgEncIter, RSSL_TRUE, &buffer->length &error)) <
    RSSL_RET_SUCCESS)
{
    printf("rsslEncodeRDMQueueMsgComplete() failed");
    return;
}

```

Code Example 32: Queue Data Message Encoding Example

### 8.6.7 QueueDataExpired

If queue data messages sent on a queue stream cannot be successfully delivered, the queue provider sends **RsslRDMQueueDataExpired** messages on the queue stream to OMM consumer applications.

OMM consumer applications do not send this message.

#### 8.6.7.1 RsslRDMQueueDataExpired Structure Members

MEMBER	DESCRIPTION
containerType	<b>Required.</b> Indicates the type of contents in the message.
destName	<b>Required.</b> <b>destName</b> specifies the name of the queue from which content is sourced (i.e., the value of <b>sourceName</b> as set in the original <b>RsslRDMQueueData</b> message).
encDataBody	Optional. Contains the payload contents (if any) of the original Queue Data message.
flags	<b>Required.</b> <b>flags</b> indicate more information about this message. For details, refer to Section 8.6.6.2.
identifier	<b>Required.</b> A user-specified, unique identifier for the message (which is the same as the <b>identifier</b> from the original <b>RsslRDMQueueData</b> message).

Table 190: RsslRDMQueueDataExpired Structure Members

MEMBER	DESCRIPTION
queueDepth	<b>Required.</b> Indicates how many Queue Data or Queue Data Expired messages are still inbound on this queue stream (following this message).
rdmMsgBase	<b>Required.</b> Specifies the queue message type (i.e., <b>RDM_QMSG_MT_DATA_EXPIRED</b> ) and contains general message information, including the stream's ID ( <b>streamId</b> ) and domain type ( <b>domainType</b> ).
sourceName	<b>Required.</b> <b>sourceName</b> specifies the name of the queue to which content was sent (i.e., the value of <b>destName</b> as set in the original <b>RssIRDMQueueData</b> message).
undeliverableCode	<b>Required.</b> Specifies a code explaining why the content was undeliverable. For more information on undeliverable codes and their meanings, refer to Section 8.6.7.2.

Table 190: RssIRDMQueueDataExpired Structure Members (Continued)

### 8.6.7.2 Queue Message Undeliverable Codes

Undeliverable codes are used in the **QueueDataExpired.undeliverable** member, and specify why the message could not be delivered.

ENUMERATION	REASON FOR DELIVERY FAILURE
RDM_QMSG_UC_EXPIRED	Indicates that the timeout value specified for this message has expired.
RDM_QMSG_UC_INVALID_SENDER	Indicates that the sender of this message has now become invalid.
RDM_QMSG_UC_INVALID_TARGET	Indicates that the specified destination of this message does not exist.
RDM_QMSG_UC_MAX_MSG_SIZE	Indicates that the message was too large.
RDM_QMSG_UC_NO_PERMISSION	Indicates that the source/sender of this message is not permitted to send or is not permitted to send to the specified destination.
RDM_QMSG_UC_QUEUE_DISABLED	Indicates that the specified destination of this message has a disabled queue.
RDM_QMSG_UC_QUEUE_FULL	Indicates that the specified destination of this message has a full queue and cannot receive any additional content.
RDM_QMSG_UC_TARGET_DELETED	Indicates that the target queue was deleted before the message was delivered.
RDM_QMSG_UC_UNSPECIFIED	Indicates that the delivery failed for unspecified reasons.

Table 191: RssIRDMQueueDataUndeliverableCodes

### 8.6.8 Queue Ack

A Queue Provider encodes and sends a **Queue Ack** message to OMM applications, acknowledging that a Queue Data message is persisted on the Queue Provider. After a Queue Provider acknowledges persistence, the OMM application no longer needs to persist the acknowledged content.

MEMBER	DESCRIPTION
destName	Optional. Specifies the name of the queue from which content is sourced (i.e., the value of <b>sourceName</b> as set in the original Queue Data message).

Table 192: RssIRDMQueueAck



MEMBER	DESCRIPTION
identifier	<b>Required.</b> The identifier of the message being acknowledged. This should match the <code>RsslRDMQueueData.identifier</code> for the message being acknowledged.
sourceName	<b>Required.</b> Specifies the name of the queue to which content was originally sent (i.e., the value of <code>destName</code> as set in the original Queue Data message).
rdmMsgBase	<b>Required.</b> Sets the message type (i.e., <code>RDM_QMSG_MT_ACK</code> ) and contains general message information, including the stream's ID ( <code>streamId</code> ) and domain type ( <code>domainType</code> ).

Table 192: `RsslRDMQueueAck` (Continued)

## Chapter 9 Value Added Utilities

### 9.1 Utility Overview

The Value Added Utilities are a collection of helper constructs, mainly used by the Transport API Reactor. Included is a multi-purpose memory buffer type that can help with flexible, reusable memory - this is leveraged by the Administration Domain Model Representations when encoding or decoding messages. Other Value Added Utilities include a simple queue, mutex locks, thread helper functionality, and a simple event alerting component.

Only the Memory Buffer utility is described in this document as it is leveraged by the provided example applications. The other Value Added Utilities are internally leveraged by the Transport API Reactor so applications need not be familiar with their use.

### 9.2 Memory Buffer

The Memory Buffer utilities provide a simple method to apportion space from a block of memory space. This allows for the creation of complex objects without expensively requesting and releasing memory from the operating system. This also allows for easy reuse of the memory block. The memory is provided to the functions via an **RsslBuffer** that has its **data** member set to the memory block and **length** member indicating the byte length of the memory.

FUNCTION NAME	DESCRIPTION
<code>rsslReserveBufferMemory</code>	Reserves memory from an <b>RsslBuffer</b> . The buffer passed in is modified to point to the unused portion of the memory block. Subsequent calls reserve adjacent memory, so this can be called multiple times to generate a C-style array of objects without knowing the full length in advance.
<code>rsslReserveAlignedBufferMemory</code>	Reserves memory from an <b>RsslBuffer</b> . Similar to <code>rsslReserveBufferMemory</code> , but will ensure that the memory is aligned on an appropriate word boundary. Subsequent calls to the non-aligned <code>rsslReserveBufferMemory</code> will reserve adjacent memory, so this can be called multiple times to generate a C-style array of objects without knowing the full length in advance.
<code>rsslCopyBufferMemory</code>	Requires an input <b>RsslBuffer</b> , output <b>RsslBuffer</b> , and an <b>RsslBuffer</b> pointing to an available memory block. Sets the output buffer to a deep copy of the input <b>RsslBuffer</b> , using the space provided by the memory block.

Table 193: Memory Buffer Functions

### 9.3 Using the Memory Buffer

The following example reserves an aligned block of memory to represent an array of five user-defined **MyStruct** structures. The memory for the first structure is reserved and aligned. Each subsequent member of the array is then reserved in a loop, wherein memory is reserved based on the initial aligned offset. The memory associated with each **MyStruct** is initialized after it is reserved. Once completed, **myStructArray** can be accessed like an array of **MyStructs** (`myStructArray[index]`, etc.).

```
/* Represents some complex user-defined struct.
 * This example will create an array of these structs. */
typedef struct
{
    int number;
```

```

    char letter;
} MyStruct;

int i = 0;

/* The block of memory that we will use as storage of the array. */
char memoryBlock[128];
RsslBuffer memoryBuffer;

MyStruct *myStructArray, *myStructElem;

memoryBuffer.data = memoryBlock;
memoryBuffer.length = 128;

/* Create first element on a word boundary, then initialize */
myStructArray = (MyStruct*)rsslReserveAlignedBufferMemory(&memoryBuffer, 1, sizeof(MyStruct));
myStructArray->number = i;
myStructArray->letter = 'a';

for(i = 1; i < 5; ++i)
{
    /* Reserve space for subsequent elements and initialize them in. */
    myStructElem = (MyStruct*)rsslReserveBufferMemory(&memoryBuffer, 1, sizeof(MyStruct));

    myStructElem->number = i;
    myStructElem->letter = 'a';
}

/* Change the letter of MyStruct in position 2, can access just like an array */
myStructArray[2]->letter = 'b';

```

### Code Example 33: Memory Buffer Example

## Chapter 10 Payload Cache Detailed View

### 10.1 Concepts

The Value Added Payload Cache component provides a facility for storing OMM containers (the data payload of OMM messages). Typical use of a payload cache is to store the current image of OMM data streams, where each entry in the cache corresponds to a single data stream. The initial content of a cache entry is defined by the payload of a refresh message. The current (or last) value of the entry is defined by the cumulative application of all refresh and update messages applied to the cache entry container. Values are stored in and retrieved from the cache as encoded OMM containers.

A cache is defined as a collection of OMM data containers. An application may create multiple cache collections, or instances, depending on how it wants to organize the data. The only restriction on cache organization is that all entries in a cache must use the same RDM Field Dictionary to define the set of field definitions it will use. At minimum, a separate cache would be required for each field dictionary in use by the application. However, because cache instances can also share the same field dictionary, partitioning is not restricted to dictionary usage. Some examples of how cache instances can be organized in an application include: all item streams on an RSSL connection; all items belonging to a particular service; all items across the entire application.

The application is responsible for organizing cache instances, managing the lifecycle of all entries in each cache, and applying and retrieving data from the cache. Figure 13 shows an example consumer type application which has created two cache instances to store data from two services on an OMM provider.




Figure 13. Consumer Application using Cache to Store Payload Data for Item Streams

### 10.2 Payload Cache

This section describes how the payload cache is managed (initialization and uninitialization), and how instances of cache (collections of payload entries) are created and destroyed.

## 10.2.1 Managing the Payload Cache

To use the Value Added Payload Cache, the application must first call the `rsslPayloadCacheInitialize` function for global static resource initialization. When the payload cache is no longer needed, the application should call `rsslPayloadCacheUninitialize` to cleanup and release all resources used by the cache.

Use the following functions to manage the cache:

FUNCTION NAME	DESCRIPTION
<code>rsslPayloadCacheInitialize</code>	The first function the application must call prior to using the payload cache. The method only needs to be called one time by the application, but may be called more than once. A reference count is incremented for each call to this function. An equal number of calls to <code>rsslPayloadCacheUninitialize</code> must be made before the component is uninitialized.
<code>rsslPayloadCacheUninitialize</code>	The last call an application should make when it is finished using the payload cache interface. The initialization reference count is decremented for each call to this function. Uninitialization only occurs if the initialization reference count is zero. During uninitialization, all remaining cache instances, entries, and resources will be destroyed.
<code>rsslPayloadCacheIsInitialized</code>	This function can be used by an application to determine if the payload cache component has already been initialized (by a call to <code>rsslPayloadCacheInitialize</code> ).

**Table 194: Payload Cache Management Functions**

## 10.2.2 Cache Error Handling

Some of the functions on the payload cache interface use the `RsslCacheError` structure to return error information. This structure will be populated with additional information if an error occurs during the function call. The application should check the return value from functions. The application can optionally provide the `RsslCacheError` structure to obtain additional information.

### 10.2.2.1 Cache Error Structure Members

The `RsslCacheError` has the following structure members:

STRUCTURE MEMBER	DESCRIPTION
<code>rsslErrorId</code>	Specifies an error ID. The range of values is defined by the set of Transport API return codes (from the <code>RsslReturnCodes</code> enumeration).
<code>text</code>	This <code>char[]</code> will contain text with additional information when a function call returns a failed result. The size of the buffer is fixed to <code>MAX_OMM_CACHE_ERROR_TEXT</code> as defined on the cache interface.

**Table 195: `RsslCacheError` Structure Members**

### 10.2.2.2 Clearing a Cache Error

The following function clears the `RsslCacheError`.

STRUCTURE MEMBER	DESCRIPTION
<code>rsslCacheErrorClear</code>	Clears the <code>RsslCacheError</code> structure. Use this function prior to passing the structure to a cache interface function.

**Table 196: Function for Cache Error Handling**

## 10.2.3 Payload Cache Instances

A payload cache instance is a collection of payload data containers. An empty cache instance must be created before any data can be stored in the cache. When a cache or its entries are no longer needed, it can be destroyed. For functions used to create and destroy a cache, refer to Section 10.2.3.1. Before using payload caches, you must first have initialized this function using `rsslPayloadCacheInitialize` as described in Section 10.2.1.

### 10.2.3.1 Managing Payload Instances

FUNCTION NAME	DESCRIPTION
<code>rsslPayloadCacheCreate</code>	Creates a payload cache instance, and returns the <code>RsslPayloadCacheHandle</code> . All operations on the cache require this handle. Options are passed in via the <code>RsslPayloadCacheConfigOptions</code> defined in Section 10.2.3.2.
<code>rsslPayloadCacheDestroy</code>	Destroys a payload cache instance. Any entries remaining in the cache are also destroyed at this time.

Table 197: Functions for Managing Cache Instances

### 10.2.3.2 Payload Cache Structure Member

STRUCTURE MEMBER	DESCRIPTION
<code>maxItems</code>	Sets the maximum number of entries allowed in the cache. When the maximum number of items is reached, the cache refuses new entries until existing entries are removed. The <code>rsslPayloadEntryCreate</code> function will return a null <code>RsslPayloadEntryHandle</code> when the maximum number of items is reached.  When set to zero, the cache allows an unlimited number of items.  Refer to Section 10.3.1.

Table 198: `RsslPayloadCacheConfigOptions` Structure Members

## 10.2.4 Managing RDM Field Dictionaries for Payload Cache

Each cache instance requires an RDM Field Dictionary, to define the set of fields that may be encoded in the OMM containers stored in the cache.

A cache is associated with a field dictionary through a binding process, which requires an `RsslDataDictionary` structure loaded with the field dictionary. The dictionary structure can be loaded from a file (using the `rsslLoadFieldDictionary` function) or from an encoded dictionary message from a provider (using the `rsslDecodeFieldDictionary` function). The cache does not use the enumerated dictionary content, so loading the enumeration dictionary is not required. For more information on using `RsslDataDictionary`, refer to the *Transport API Reference Manual*.

After the `RsslDataDictionary` loads, it is bound to a cache instance using a key (an arbitrary string identifier assigned by the application to name the dictionary). The key allows multiple cache instances to share the same dictionary. After the first binding of a dictionary, it can be bound to additional cache instances by simply providing the same key on additional bindings. For a list of functions used in binding a dictionary to a cache, refer to Section 10.2.4.1.

The cache builds its own field definition database from the `RsslDataDictionary` definitions. After binding, the application does not need to retain the dictionary structure, because the cache does not refer to the `RsslDataDictionary` used during the binding. In typical usage, the application will likely retain the dictionary for use with other encoding and decoding operations.

**Note:** A cache can be bound to a dictionary only once during its lifetime. While a cache cannot be switched to a new dictionary, the dictionary in use can be extended with new definitions. Refer to Section 10.2.4.3.

### 10.2.4.1 Setting Functions

FUNCTION NAME	DESCRIPTION
<code>rsslPayloadCacheBindDictionary</code>	<b>Deprecated.</b> For details on using this function, refer to the <i>Transport API C Edition Developers Guide</i> . Otherwise, for equivalent functionality, refer to <code>rsslPayloadCacheSetDictionary</code> in this table.
<code>rsslPayloadCacheBindSharedDictionaryKey</code>	<b>Deprecated.</b> For details on using this function, refer to the <i>Transport API C Edition Developers Guide</i> . Otherwise, for equivalent functionality, refer to <code>rsslPayloadCacheSetSharedDictionaryKey</code> in this table.
<code>rsslPayloadCacheSetDictionary</code>	<p>This function sets an <code>RsslDataDictionary</code> to a cache instance (identified by <code>RsslPayloadCacheHandle</code>). Use this function the first time a dictionary is set to a cache. The application must provide a key parameter to this function to name the dictionary for future reference. This key is used in future setting operations when the application wants to share a dictionary between cache instances or to extend the definitions in the dictionary.</p> <p>The first time a particular key is used with this function will be the initial setting of that dictionary to a cache. The second time the same key is used in this function; it will reload the field definitions from the given <code>RsslDataDictionary</code> structure, enabling the dictionary to be extended. Refer to Section 10.2.4.3.</p>
<code>rsslPayloadCacheSetSharedDictionaryKey</code>	<p>Use this function when sharing a dictionary among multiple caches. This function sets a cache (identified by the <code>RsslPayloadCacheHandle</code>) to a previously set dictionary (identified by the dictionary key name). To share a dictionary, the dictionary named by the key passed to this function must have previously had an initial setting to another cache using the <code>rsslPayloadCacheSetDictionary</code> function.</p> <p>This function does not require the <code>RsslDataDictionary</code> structure, since that was already loaded during the initial setting with this dictionary key.</p>

**Table 199: Functions for Setting Dictionary to Cache**

### 10.2.4.2 Setting Example

In the following example, two cache instances are created and set to a single shared field dictionary.

```

RsslRet ret;
RsslCacheError cacheError;
RsslPayloadCacheConfigOptions cacheConfig;
const char* dictionaryKey = "SharedKey1";
char errorDataArray[256];
RsslBuffer errorBuffer = {256, &errorDataArray[0]};
RsslPayloadCacheHandle cacheHandle1 = 0;
RsslPayloadCacheHandle cacheHandle2 = 0;
RsslDataDictionary dataDictionary;

/* For simplicity in this code fragment, CHK is assumed to be a macro for error handling
   (performing cleanup and returning from function). */

/* Initialize cache component and create cache instances */
ret = rsslPayloadCacheInitialize(); CHK(ret)

```

```

cacheConfig.maxItems = 0; /* unlimited */
cacheHandle1 = rsslPayloadCacheCreate(&cacheConfig, &cacheError);
if (cacheHandle1 == 0)
{
    printf("rsslPayloadCacheCreate failure: %s\n", cacheError.text);
    CHK(cacheError.rsslErrorId)
}
cacheHandle2 = rsslPayloadCacheCreate(&cacheConfig, &cacheError);
if (cacheHandle2 == 0)
{
    printf("rsslPayloadCacheCreate failure: %s\n", cacheError.text);
    CHK(cacheError.rsslErrorId)
}

/* Load an RDM Field Dictionary structure from file: set to each cache. */
rsslClearDataDictionary(&dataDictionary);
ret = rsslLoadFieldDictionary("RDMFieldDictionary", &dataDictionary, &errorBuffer); CHK(ret)
/* Initial setting of the dictionary to the first cache */
ret = rsslPayloadCacheSetDictionary(cacheHandle1, &dataDictionary, dictionaryKey, &cacheError);
    CHK(ret)
/* Shared setting of the same dictionary to the second cache */
ret = rsslPayloadCacheSetSharedDictionaryKey(cacheHandle2, dictionaryKey, &cacheError); CHK(ret)
/* The dataDictionary can be destroyed after setting, but is typically retained by the application
    for encoding and decoding. */

/* Two cache instances are now ready for applying and retrieving data */
/* ... */

/* Cleanup */
rsslPayloadCacheDestroy(cacheHandle1); /* destroys all entries and the cache instance */
rsslPayloadCacheDestroy(cacheHandle2);
/* After all cache instances bound to a dictionary are destroyed, the cache API will clean up the
    internal field dictionary database used by the cache. */
rsslPayloadCacheUninitialize(); /* final call to cache interface */
rsslDeleteDataDictionary(&dataDictionary);

```

### Code Example 34: Creating Cache and Setting to Dictionary

#### 10.2.4.3 Extending the Cache Field Dictionary

While a cache can only be set to a single dictionary during its lifetime, the set of field definitions defined by the dictionary can be extended. This is accomplished by reloading the cache field definition database with another call to the **rsslPayloadCacheSetDictionary** function. When extending the field dictionary, the **RsslDataDictionary** must contain the original field definitions and any new definitions the application wishes to use. Changes or deletions to the original field definitions are not supported; only additions are allowed. Using the same **RsslPayloadCacheHandle** and dictionary key that were previously set, call the **rsslPayloadCacheSetDictionary** function again with extended dictionary structure.

**Note:** When extending a field dictionary that is shared, all caches sharing that same dictionary key will see the extension with only a single call to **rsslPayloadCacheSetDictionary**. There is no need to set the shared dictionary key again to each cache after a dictionary is extended.



## 10.2.5 Payload Cache Utilities

Use the following functions for managing cache instances. These utilities provide a count of the cache entries and a list of handles to each cache entry.

FUNCTION NAME	DESCRIPTION
<code>rsslPayloadCacheGetEntryCount</code>	Returns the number of item payload entries in this cache instance ( <code>RsslPayloadCacheHandle</code> ).
<code>rsslPayloadCacheGetEntryList</code>	Populates an array provided by the caller with entry handles ( <code>RsslPayloadEntryHandle</code> ) for this cache instance ( <code>RsslPayloadCacheHandle</code> ). Because each cache entry is likely associated with an entry in the application's item list, an application would typically manage the set of entry handles. This utility provides access to the entire entry handle list if needed.
<code>rsslPayloadCacheClearAll</code>	Destroys all entries in the cache instance ( <code>RsslPayloadCacheHandle</code> ). The empty cache can be reused and remains bound to its data dictionary.

Table 200: Payload Cache Utility Functions

## 10.3 Payload Cache Entries

A payload cache entry stores a single OMM container (whose data types are defined by `RsslContainerType`). While a cache entry can store any arbitrary OMM data, the primary use case is to maintain the last known value of an item data stream by applying the sequence of refresh and update messages in the stream to the cache entry. Initial data applied to a container must be a refresh message payload, which will define the container type to be stored (e.g. Map). As refresh and update messages from the item stream are applied to the cache entry, the cache decodes the OMM data and sets the current value by following the OMM rules for the container (e.g., adding, deleting, or updating map entries in a Map, or updating fields in a field list). The last value of the data stream can be retrieved from cache at any time as an encoded OMM container.

### 10.3.1 Managing Payload Cache Entries

Payload cache entries are created within a cache instance. A cache entry is defined by the `RsslPayloadEntryHandle` returned from the `rsslPayloadEntryCreate` function. You cannot move entries between different cache instances, due to their dependency on the field dictionary bound to the cache where they are created.

Cache entries only store the payload container of an item. Maintain other item data (e.g. message key attributes, domain, state) as needed in an item list managed by the application, which will identify the source or sink associated with the cache entry data. This item list will likely include the `RsslPayloadEntryHandle` if the payload of the item is cached.

For a list of basic utilities provided by the payload cache to manage the collection of entries in the cache, refer to Section 10.2.5.

Use the following functions to manage cache entries:

FUNCTION NAME	DESCRIPTION
<code>rsslPayloadEntryCreate</code>	<p>This method returns a <code>RsslPayloadEntryHandle</code> to the newly created entry in the cache defined by the given <code>RsslPayloadCacheHandle</code>. The <code>RsslPayloadEntryHandle</code> is required for all operations on this entry.</p> <p>This function will return a null handle if it cannot create the entry (e.g., if the maximum number of entries as defined in <code>RsslPayloadCacheConfigOptions</code> would be exceeded).</p>

Table 201: Payload Cache Entry Management Functions

FUNCTION NAME	DESCRIPTION
<code>rsslPayloadEntryDestroy</code>	This method destroys the cache entry defined by <code>RsslPayloadEntryHandle</code> and removes it from its cache.
<code>rsslPayloadEntryClear</code>	This method deletes any data in the cache entry <code>RsslPayloadEntryHandle</code> and returns the entry to its initial state. The entry itself remains in the cache and can be re-used.

Table 201: Payload Cache Entry Management Functions (Continued)

### 10.3.2 Applying Data

Data is applied to a cache entry from the payload of an OMM message by using the `rsslPayloadEntryApply` function. The decoded `RsslMsg` and an `RsslDecodeIterator` are passed to the apply function. The iterator (positioned at the start of the encoded payload data `RsslMsgBase.encDataBody`) will be used to decode the OMM data so that the cache entry data can be set or updated.

Some caching behaviors are controlled by flags in the `RsslMsg`. When an `RsslRefreshMsg` is applied to the cache entry, the following `RsslRefreshFlags` take effect:

- **RSSL\_RFMF\_CLEAR\_CACHE**: Cache entry data will be cleared prior to applying this message.
- **RSSL\_RFMF\_DO\_NOT\_CACHE**: The payload will not be applied to the cache entry.

When an `RsslUpdateMsg` is applied to cache, the following `RsslUpdateFlags` take effect:

- **RSSL\_UPMF\_DO\_NOT\_CACHE**: The payload data will not be applied to the cache entry.
- **RSSL\_UPMF\_DO\_NOT\_RIPPLE**: When applying the data, entry rippling is not performed.

The following example demonstrates how to create a payload entry in a cache instance and apply the payload of an `RsslMsg` to the cache entry.

```
/* Apply buffer containing an encoded RsslMsg to cache entry */
RsslRet applyBufferToCache(RsslChannel *pChannel, RsslBuffer *pBuffer, RsslPayloadCacheHandle
    cacheHandle, RsslPayloadEntryHandle *pEntryHandle)
{
    RsslDecodeIterator dIter;
    RsslMsg msg;
    RsslRet ret;
    RsslCacheError cacheError;

    /* If the caller did not provide a cache entry handle, create a new entry */
    if (*pEntryHandle == 0)
    {
        rsslCacheErrorClear(&cacheError);
        *pEntryHandle = rsslPayloadEntryCreate(cacheHandle, &cacheError);
        if (*pEntryHandle == 0)
        {
            printf("Error (%d) creating cache entry: %s\n", cacheError.rsslErrorId, cacheError.text);
            return cacheError.rsslErrorId;
        }
    }

    /* Perform message decoding. */
}
```

```

rsslClearDecodeIterator(&dIter);
rsslSetDecodeIteratorRwfVersion(&dIter, pChannel->majorVersion, pChannel->minorVersion);
rsslSetDecodeIteratorBuffer(&dIter, pBuffer);
rsslClearMsg(&msg);
ret = rsslDecodeMsg(&dIter, &msg);
if (ret < RSSL_RET_SUCCESS)
{
    printf("Failure (%d) decoding message from buffer\n");
    return ret;
}

/* Apply the decoded RsslMsg to cache, with iterator positioned at the start of the payload */
rsslCacheErrorClear(&cacheError);
ret = rsslPayloadEntryApply(*pEntryHandle, &dIter, &msg, &cacheError);
if (ret < RSSL_RET_SUCCESS)
{
    printf("Error (%d) applying data to cache entry: %s\n", cacheError.rsslErrorId,
           cacheError.text);
    return ret;
}

return ret;
}

```

Code Example 35: Applying Data to a Payload Cache Entry

### 10.3.3 Retrieving Data

Data is retrieved from a cache entry as an encoded OMM container by using the `rsslPayloadEntryRetrieve` function. The application provides the data buffer (via an `RsslEncodeIterator`) where the container will be encoded. The retrieve function supports both encoding scenarios. When using `rsslEncodeMsg`, the encoded content retrieved from the cache entry can be set on the `RsslMsgBase.encDataBody`. If using `rsslEncodeMsgInit` and `rsslEncodeMsgComplete` encoding, the cache retrieve function can encode the message payload prior to `rsslEncodeMsgComplete`.

There are two options for using the `rsslPayloadEntryRetrieve` function. For single-part retrieval, the buffer provided by the application must be large enough to hold the entire encoded container. For multi-part retrieval, the application makes a series of calls to `rsslPayloadEntryRetrieve` to get the OMM container in fragments (e.g., a sequence of maps are retrieved which together contain the entire set of map entries for the OMM container). In this usage, the optional `RsslPayloadCursorHandle` is required to maintain the state of the multi-part retrieval. Container types `FieldList` and `ElementList` cannot be fragmented, so the buffer size must be large enough to retrieve the entire container.

The following functions describe data-related operations on a cache entry.

FUNCTION NAME	DESCRIPTION
<code>rsslPayloadEntryGetDataType</code>	Returns the <code>RsslContainerType</code> stored in the cache entry ( <code>RsslPayloadEntryHandle</code> ). When initially created (or after the entry is cleared), the data type will be <b>RSSL_DT_UNKNOWN</b> . The data type is defined by the container type of the first refresh message applied to the entry.

Table 202: Functions for Applying and Retrieving Cache Entry Data

FUNCTION NAME	DESCRIPTION
<code>rsslPayloadEntryApply</code>	Applies the OMM data in the payload of the <code>RsslMsg</code> to the cache entry ( <code>RsslPayloadEntryHandle</code> ). The first message applied must be a refresh message (class <code>RSSL_MC_REFRESH</code> ).
<code>rsslPayloadEntryRetrieve</code>	Retrieves data from the cache entry by encoding the OMM container into the buffer provided with the <code>RsslEncodeIterator</code> given by the application. For single-part retrieval, the <code>RsslPayloadCursorHandle</code> parameter is optional. For details on multi-part retrieval, refer to Section 10.3.3.1.

Table 202: Functions for Applying and Retrieving Cache Entry Data (Continued)

### 10.3.3.1 Multi-Part Retrieval

For data types that support fragmentation, the container can be retrieved in multiple parts by calling `rsslPayloadEntryRetrieve` until the complete container is returned. To support multi-part retrieval, the optional `RsslPayloadCursorHandle` parameter is required when calling `rsslPayloadEntryRetrieve`. The cursor is used to maintain the position where the next retrieval will resume. The application must check the state of the cursor after each call to `rsslPayloadEntryRetrieve` to determine when the retrieval is complete. The following functions are needed when using the payload cursor.

FUNCTION NAME	DESCRIPTION
<code>rsslPayloadCursorCreate</code>	Creates a cursor for optional use in the <code>rsslPayloadEntryRetrieve</code> function (required for multi-part retrieval). Returns the <code>RsslPayloadCursorHandle</code> .
<code>rsslPayloadCursorDestroy</code>	Destroys the cursor referenced by the <code>RsslPayloadCursorHandle</code> .
<code>rsslPayloadCursorClear</code>	Clears the state of the cursor for the given <code>RsslPayloadCursorHandle</code> . Whenever retrieving data from a cache entry, the cursor must be cleared prior to the first call to <code>rsslPayloadEntryRetrieve</code> . Clearing the cursor also allows it to be reused with a retrieval on a different container.
<code>rsslPayloadCursorsIsComplete</code>	Returns the completion state of a retrieval where the <code>RsslPayloadCursorHandle</code> was used. The state must be checked after each call to <code>rsslPayloadEntryRetrieve</code> to determine whether additional data needs to be encoded for the cache entry container. When the cursor state is complete, the entire container of the cache entry has been retrieved.

Table 203: Functions for Using the Payload Cursor

### 10.3.3.2 Buffer Management

In multi-part usage, the size of the buffer used in the calls to `rsslPayloadEntryRetrieve` will affect how many fragments are required to retrieve the entire image of the cache entry. The retrieve function will continue to encode OMM entries from the cache container until it runs out of room in the buffer to encode the next entry. To progress during a multi-part retrieval, the buffer size must be at least large enough to encode a single OMM entry from the payload container. For example, if retrieving a map in multiple parts, the buffer must be large enough to encode at least one `MapEntry` on each retrieval.

There are three general outcomes when using the `rsslPayloadEntryRetrieve` function:

- Full cache container is encoded into the buffer. This can occur with or without the use of the optional `RsslPayloadCursorHandle`. If used in this scenario, the cursor state would indicate the retrieval is complete.
- Partial container encoded into the buffer. This is only possible when using the `RsslPayloadCursorHandle` for container types that support fragmentation. The application must check the cursor to test whether this is the final part.

- No data encoded into container due to insufficient buffer size. This can occur with or without the use of the optional `RsslPayloadCursorHandle`. The application may retrieve again with a larger buffer.

### 10.3.3.3 Example: Cache Retrieval with Multi-Part Support

The following example illustrates data retrieval from a cache entry, which supports multi-part encoding of a container.

```
/* Code fragment showing use of rsslPayloadEntryRetrieve for multi-part retrieval. */

RsslRet ret;
RsslCacheError cacheError;
RsslBuffer buffer;
RsslEncodeIterator eIter;
int arraySize = DEFAULT_BUFFER_SIZE;
unsigned char* bufferArray = (char*) malloc(arraySize);
buffer.data = bufferArray;
buffer.length = arraySize;
RsslPayloadCursorHandle cursorHandle = rsslPayloadCursorCreate();
rsslPayloadCursorClear(cursorHandle);
while (!rsslPayloadCursorIsComplete(cursorHandle))
{
    buffer.length = arraySize;
    rsslClearEncodeIterator(&eIter);
    rsslSetEncodeIteratorBuffer(&eIter, &buffer);
    rsslCacheErrorClear(&cacheError);
    /* _entryHandle created outside the scope of this code fragment */
    ret = rsslPayloadEntryRetrieve(_entryHandle, &eIter, cursorHandle, &cacheError);
    if (ret == RSSL_RET_SUCCESS)
        /* Number of bytes encoded is buffer.length. Application can use encoded data, e.g. set the
           payload on RsslMsgBase.encDataBody and encode a message to be transmitted. */
    else if (ret == RSSL_RET_BUFFER_TOO_SMALL)
        /* Increase arraySize and reallocate bufferArray. */
    else
        /* Handle terminal error condition. See cacheError.text[] for additional information. */
}
rsslPayloadCursorDestroy(cursorHandle);
free(bufferArray);
```

#### Code Example 36: Cache Retrieval with Multi-Part Support

© 2015 - 2019 Thomson Reuters. All rights reserved.

Republication or redistribution of Thomson Reuters content, including by framing or similar means, is prohibited without the prior written consent of Thomson Reuters. 'Thomson Reuters' and the Thomson Reuters logo are registered trademarks and trademarks of Thomson Reuters and its affiliated companies.

Any third party names or marks are the trademarks or registered trademarks of the relevant third party.

Document ID: ETAC331UMVAC.190

Date of issue: 31 July 2019



**THOMSON REUTERS**