

IBM Education Assistance for z/OS V2R2

Item: SLIP ACTION=CMD

Element/Component: BCP Service Aids



Agenda

- Trademarks
- Presentation Objectives
- Overview
- Usage & Invocation
- Migration & Coexistence Considerations
- Miscellaneous
- Presentation Summary
- Appendix



Trademarks

- See URL <http://www.ibm.com/legal/copytrade.shtml> for a list of trademarks.



Presentation Objectives

- Find out what SLIP ACTION=CMD can do for you
- Learn about the DESC parameter to describe wait state and dumps
- Learn about miscellaneous Service Aids (SVA) enhancements
 - IPCS
 - Show the BEAR
 - Allow system symbols in IPCS parmlib members
 - NOALIGN/ALIGN for IP LIST output
 - CBFORMAT model header can now show 64 bit addresses
 - PDUU
 - Greater than 999 files supported
 - NO_FTP option
 - MGMTCLAS option



Overview - Review

- What is SLIP?
 - Serviceability Level Indication Processing
 - System command
 - Intercepts system events and takes requested actions
 - System events:
 - Error events
 - ABENDs, program checks, SVC errors, EOT/ EOM
 - PER (program event recording) events
 - IF – instruction fetch – range of code is executing
 - SBT – successful branch
 - SA - storage alteration
 - ZAD – referencing storage from a zero pointer



Overview - Review

- Actions:
 - SVCD, SYNC SVCD – take a dump
 - WAIT – cause a wait state
 - RECORD – create a logrec
 - RECOVERY – force recovery
 - REFBEFORE, REFAFTER – clear storage
 - NODUMP, NOSVCD, NOSYSA, NOSYSM, NOSYSU
 - do not take a dump
 - NOSUP – ignore dae (and take a dump)
 - STOPGTF – stop gtf recording when trap disabled
 - TRACE, STRACE – issue a trace (gtf or system)
 - TRDUMP, STDUMP – trace and dump when trap disabled
 - SUBTRAP, TARGETID, IGNORE – affect other SLIP traps
 - **COMMAND** – **issue a console command**



Overview - ACTION=CMD

- Problem Statement / Need Addressed
 - For better problem determination and first failure data capture (FFDC), SLIP should be enhanced to allow COMMAND as an ACTION to a slip trap event

- Solution
 - Allow a COMMAND to be issued as the result of a slip trap event in addition to other actions such as SVCD

- Benefit / Value
 - Problem determination and analysis can now include timely issuance of console commands as the result of a SLIP trap being hit



Overview – DESC parameter

- Problem Statement / Need Addressed
 - For better problem determination and FFDC, SLIP should be enhanced to allow a DESC keyword to customize WAIT state descriptions and dump headers (SVCD, SYNC SVCD, STDUMP, TRDUMP)
- Solution
 - Allow a DESC keyword to provide a description that will show up in WAIT state messages or dump header
- Benefit / Value
 - Installations can use DESC to more easily describe WAIT states and dumps initiated by SLIP actions, and understand where and why they occurred



Usage & Invocation – Action=CMD

- ACTION=CMD will allow SLIP to issue a command:

```
SLIP SET, ..., ACTION=CMD, CMD='command1', END
```

- Allowed on all types of traps including PER and error events
- Allowed with other actions except WAIT and IGNORE
- Not allowed as a REMOTE option (however ROUTE can be used as a command)
- Up to 8 commands can be specified as such:

```
SLIP SET, ..., ACTION=CMD, CMD=('command1', 'command2', ...), END
```

- The command can be broken into parts with nested parentheses

```
SLIP SET, C=071, SDATA=(ALLNUC, SQA, CSA, LPA, LSQA, ALLPSA, RGN,  
SUM, TRT), REASON=20, ID=SS71,  
CMD=('command 1', ('command 2 part 1',  
'command 2 part 2'), ('command 3 part 1',  
'command 3 part 2', 'command 3 part 3')), A=(SVCD, CMD), END
```



Usage & Invocation – Action=CMD

- MVS commands can be up to 126 characters long
 - SLIP accepts the commands in the CMD buffer up to 126 characters
- Use the SLIP parmlib to issue longer SLIPs
 - add the SLIP to an IEASLPxx parmlib
 - issue a SET SLIP command
- To use a quote character ('), enter two quotes (")
 - The extra quote does not count against the character limit
- The user issuing the SLIP command must have authority to issue embedded commands
 - SLIP does a MGCRC and passes the SLIP issuers authorization
 - Authorization is copied from the SLIP trap enabler (See Appendix B)



Usage & Invocation – Action=CMD

- There is no guarantee in the order of completion of commands; command processing is asynchronous after a SLIP event
- If multiple matches for a SLIP with A=CMD, commands may not be issued for every match, but will be issued at least once
- There is no default MATCHLIM for A=CMD.
 - IBM strongly recommends using MATCHLIM or PRCNTLIM when using A=CMD
 - If the commands specified can cause the trap to be hit again, the sequence could recursively continue indefinitely. This can have a serious impact on system performance.



Usage & Invocation – DESC

- DESC will allow a description to be set for WAIT or dump actions (SVCD, SYNC SVCD, TRDUMP, STDUMP)

```
SLIP SET, ..., ACTION=SVCD, DESC='dump description', END
```

- DESC is optional
- DESC can be up to 65 characters in length



Usage & Invocation – Messages

- SLIP display message IEE7351 also shows DESC=.... and CMD=.... when specified for the input slip trap

- SLIP message IEE836D has a new *err* description:

```
IEE836D SLIP {ID=xxxx|COMMAND} ERROR - keywd - err , COL nnn.  
ENTER 1 KEYWORD, NULL LINE, OR 'CANCEL'.
```

- When more than 8 commands are entered *err* can now also be
TOO MANY COMMANDS



Usage & Invocation – Example 1

- Example: Set a SLIP and DISPLAY it:
- **SLIP SET**, C=0C1, ID=NRJ1, A=(SVCD, CMD), CMD=('D SLIP', 'D GRS'), DESC='Nicks Command Action and Dump', END

- **D SLIP**=NRJ1

```
IEE735I 15.15.04 SLIP DISPLAY 523
ID=NRJ1, NONPER, ENABLED
ACTION=SVCD, CMD, SET BY CONS CON3E0Y1, RBLEVEL=ERROR
MATCHLIM=1, 0, COMP=0C1
CMD=('D SLIP',
    'D GRS')
DESC=Nicks Command Action and Dump
```



Usage & Invocation – Example 1

▪ Example: Force an OC1

IEA992I SLIP TRAP ID=NRJ1 MATCHED. JOBNAME=*MASTER*, ASID=0001.

IEA411I SLIP TRAP ID=NRJ1 DISABLED FOR MATCHLIM

IEA045I AN SVC DUMP HAS STARTED AT TIME=15.15.41 DATE=06/17/2013
FOR ASID (0001)

QUIESCE = YES

IEE735I 15.15.41 SLIP DISPLAY 545

ID	STATE	ID	STATE	ID	STATE	ID	STATE
----	-------	----	-------	----	-------	----	-------

SQAO	ENABLED	NRJ1	DISABLED				
------	---------	------	----------	--	--	--	--

IEA794I SVC DUMP HAS CAPTURED:

DUMPID=001 REQUESTED BY JOB (*MASTER*)

DUMP TITLE=SLIP DUMP ID=NRJ1, **Nicks Command Action and Dump**

ISG343I 15.15.42 GRS STATUS 550

SYSTEM	STATE	SYSTEM	STATE
--------	-------	--------	-------

SY1	CONNECTED		
-----	-----------	--	--

GRS STAR MODE INFORMATION

LOCK STRUCTURE (ISGLOCK) CONTAINS 1048576 LOCKS.

THE CONTENTION NOTIFYING SYSTEM IS SY1

SYNCHRES: YES

ENQMAXU: 16384

...



Usage & Invocation – Example 2

▪ Example: Set a WAIT DESC SLIP

```
SLIP SET,C=0C1,ID=NRJ1,A=WAIT,DESC='Nicks Test Dump
Description',END
```

▪ Force an 0C1 and show the resulting wait state message:

```
IEE844W SLIP TRAP NRJ1 MATCHED. ACTION=WAIT TYPE=RTM2
```

DESC: Nicks Test Dump Description

```
RTM2WA ADDR: 7F53CCF0
```

BEAR: 00000000_08288EA2

```
PSW: 07042000 80000000 00000000 08288ECE
```

```
CR 3-4: 00C00037 00000037
```

AR/GR 0: 00000000/00000000_01000000	1: 00000001/0A5CD588_01111111
2: 00000001/FFFFFFFF_01222222	3: 00000001/FFFFFFFF_01333333
4: 00000001/FFFFFFFF_01444444	5: 00000001/FFFFFFFF_01555555
6: 00000001/FFFFFFFF_01666666	7: 00000001/FFFFFFFF_01777777
8: 00000001/FFFFFFFF_01888888	9: 00000001/00000000_01999999
A: 00000001/00000000_0A5CD350	B: 00000001/00000000_0A5CD588
C: 00000001/00000000_0828AB78	D: 00000001/00000000_01DDDDDD
E: 00000001/00000000_01EEEEEE	F: 00000001/FFFFFFFF_01FFFFFF

```
RESTART THE SYSTEM TO CONTINUE
```



Migration & Coexistence Considerations

- Keep in mind:
 - SLIP commands that are routed to all consoles containing ACTION=CMD or DESC will fail syntax checking on pre V2R2 systems
 - SLIP commands in IEASLPxx or COMMNDxx with ACTION=CMD or DESC will fail syntax checking when processed on pre V2R2 systems



Miscellaneous - IPCS

- Do a better job of showing the BEAR during IPCS processing
 - BEAR symbol available in IPCS

```
IP LIST BEAR
```

```
BEAR - Breaking Event Address Register
```

```
LIST 0FF0. HEADER LENGTH(X'08') STRUCTURE(Bear)  
+00000 00000FF0. 00000000 08601EA2
```

- Recognize system symbolics in IPCS parmlibs
 - BLSCECT, BLSCUSER, and IPCSPRxx now support system symbols
 - Helpful to use for setting the SYSDDIR statement



Miscellaneous - IPCS

- NOALIGN/ALIGN for IP LIST output
 - ALIGN is now a SETDEF DISPLAY(...) option
 - ALIGN displays the storage for LIST output AREA, STRUCTURE, BIT, and CHAR pointers aligned to the previous double word boundary
 - For example: `IP LIST 3.` generates this:

```
LIST 03. ASID(X'0024') LENGTH(X'1000') AREA
00000003.      00 000130E1 00000000 00000000 | .....|
00000010. 00FD9A48 00000000 7FFFF000 7FFFF000 | .....".0.".0.|
00000020. 7FFFF000 7FFFF000 7FFFF000 7FFFF000 | ".0.".0.".0.".0.|
```

- NOALIGN displays the storage for LIST output aligned to the requested bit boundary

```
LIST 03. ASID(X'0024') LENGTH(X'1000') AREA
00000003. 00000130 E1000000 00000000 0000FD9A | .....|
00000013. 48000000 007FFFF0 007FFFF0 007FFFF0 | .....".0.".0.".0.|
00000023. 007FFFF0 007FFFF0 007FFFF0 00000000 | .".0.".0.".0....|
```



Miscellaneous - IPCS

- CBFORMAT model header can now show 64 bit addresses

```
IP CBFORMAT 0000004800004000. STR(WXYZ)
```

```
WXYZ: 00000048_00004000
```

```
+0000 Id..... ABCD          Length... D48000  Version.. 00  
.....
```



Miscellaneous - PDUU

- >999 files supported
 - PDUU can generate up to 99,999 files instead of up to 999

- MGMTCLAS option
 - PDUU SYSIN allows for MGMTCLAS specification in addition to existing DATACLAS and STORCLAS keywords

 - New message to enforce MGMTCLAS input boundaries
 - AMA763I THE LENGTH OF MGMTCLAS NAME SPECIFIED IS NOT BETWEEN 1 AND 8 CHARACTERS



Miscellaneous – PDUU - NO_FTP

- NO_FTP option to separate and compress but not FTP files (RFE 69536)
 - Clients with closed data centers (with no outside internet access) want to use PDUU to prepare files to be brought to IBM without FTPing the files over the internet
 - NO_FTP(Y) indicates for PDUU to prepare the files and move them to a local USS directory without using FTP transfer
 - PDUU will separate and compress the files to manageable chunks
 - Encryption can be performed
 - PDUU uses TSO services to send the files
 - Options ignored:
 - SYSIN parameters: TARGET_SYS, CC_FTP, USERID, PASSWORD
 - FTPCMDS DD
 - CC_FTP is set 1



Miscellaneous – PDUU - NO_FTP

- Once transferred files can be extracted by the input USS directory depending on the PMR and target DSN input
 - e.x.: PMR.TARGET_DSN.Tdate.MTFTP.F00002 to Fnnnnn.
 - Number of files depends on WORK_DSN_SIZE and how well compression performs
 - A small file with suffix F001 contains info IBM needs to recreate the file
 - Bring all files to IBM as you normally bring service documentation.
- SYSTSPRT DD can be used to debug TSO problems. IF AMA778I shows a return code '4'x and a function code 'C'x the messages may help debug the failure.



Miscellaneous – PDUU - NO_FTP

– Example:

```
//FTP      EXEC  PGM=AMAPDUPL
//SYSPRINT DD   SYSOUT=*
//SYSTSPRT DD   SYSOUT=*
//SYSUT1   DD   DISP=SHR,DSN=H44IPCS.WESSAMP.TRKS055K
//SYSIN     DD   *
NO_FTP=Y
TARGET_DSN=WESSAMP.BIGFILE
WORK_DSN=WES.FTPOUT
WORK_DSN_SIZE=500
DIRECTORY=/u/nickj/pduu/
PMR=12345.123.123
```

– These files are generated in the /u/nickj/pduu/ directory

```
12345.123.123.WESSAMP.BIGFILE.TE3246.MTFTP.F00002
12345.123.123.WESSAMP.BIGFILE.TE3246.MTFTP.F00003
12345.123.123.WESSAMP.BIGFILE.TE3246.MTFTP.F00004
...
12345.123.123.WESSAMP.BIGFILE.TE3246.MTFTP.F001
```



Presentation Summary

- You've now learned
 - about the SLIP ACTION=CMD and what it can do for you
 - about the DESC parameter to describe wait state and dumps
 - about some miscellaneous SVA enhancements
 - IPCS
 - Show the BEAR
 - Allow system symbols in IPCS parmlib members
 - NOALIGN/ALIGN for IP LIST output
 - CBFORMAT model header can now show 64 bit addresses
 - PDUU
 - >999 files supported
 - NO_FTP option to separate and compress but not ftp files
 - MGMTCLAS option



Appendix

- A – Publications
- B – SLIP CMD authorization notes



Appendix A - Publications

▪ Publications:

- z/OS MVS Diagnosis: Tools and Service Aids – GA32-0905
- z/OS MVS System Commands – SA38-0666
- z/OS MVS IPCS Commands – SA23-1382
- z/OS MVS System Messages
 - Vol 1 (ABA-AOM) – SA38-0668
 - Vol 7 (IEB-IEE) – SA38-0674



Appendix B – SLIP CMD authorization notes

- Authorization to issue commands is copied from the SLIP trap enabler
 - USER1 has authority for the SLIP command but not the CHNGDUMP command, and enters:

```
SLIP SET, ID=UAC1, MSGID=IEE852I, DISABLE, ACTION=(CMD),  
      CMD=( 'CHNGDUMP SET, SDUMP=(HCSABYASID, HCSY) ' ), END
```
 - USER2 has authority for the SLIP and CHNGDUMP command and enters:

```
SLIP MOD, ID=UCA1, ENABLE
```
 - When IEE8521I is seen, the CHNGDUMP command is executed (as USER2 has authority to issue CHNGDUMP)

```
IEA992I SLIP TRAP ID=UA1A MATCHED.  JOBNAME=*MASTER*, ASID=0001.  
CHNGDUMP SET, SDUMP=(HCSABYASID, HCSY)  
IEE712I CHNGDUMP PROCESSING COMPLETE
```
 - IF USER1 enabled UCA1, then when IEE8521I is seen, the CHNGDUMP command would not be issued

```
IEA992I SLIP TRAP ID=UAC1 MATCHED.  JOBNAME/ASID NOT AVAILABLE.  
IEE345I CHNGDUMP AUTHORITY INVALID, FAILED BY SECURITY PRODUCT
```

