



# Erk Commands

## Erk IRC Client Commands Documentation

<https://github.com/nutjob-laboratories/erk>  
<https://github.com/nutjob-laboratories/erk-plugins>

**Version 0.830**

Much like other popular IRC clients, users can input commands into the chat input widget to control the Erk IRC client. To use these commands, type the command, followed by any arguments, into the same widget that you enter chat text, and press the enter button.

<b>Connection Scripts and "Callable" Scripts.....</b>	<b>2</b>
<b>IRC Commands.....</b>	<b>2</b>
/away [MESSAGE...]	2
/back	2
/invite CHANNEL NICKNAME	2
/join CHANNEL [KEY]	3
/list [TERMS]	3
/me TEXT	3
/msg TARGET MESSAGE...	3
/nick NICKNAME	3
/notice TARGET MESSAGE...	3
/oper USERNAME PASSWORD	3
/part CHANNEL [MESSAGE]	3
/quit [MESSAGE...]	4
/send MESSAGE	4
/time [SERVER]	4
/topic CHANNEL TEXT...	4
/version SERVER [SERVER...]	4
/who TEXT	4
/whois NICKNAME	4
/whowas NICKNAME [MAXIMUM ENTRIES] [SERVER]	4
<b>Scripting Commands.....</b>	<b>5</b>
/alias NAME MESSAGE...	5
/argcount NUMBER MESSAGE...	5
/connect [SERVER] [PORT]	5
/exit	5
/help	5
/print MESSAGE...	6
/reconnect [SERVER] [PORT]	6
/refresh	6
/ressl [SERVER] [PORT]	6
/script FILENAME [ARGUMENT ...]	6
/settings	6
/ssl [SERVER] [PORT]	7
/style FILENAME	7
/switch [WINDOW NAME]	7
/wait TIME	7

## Connection Scripts and “Callable” Scripts

Ork uses two different kinds of scripts: connection scripts (which can be automatically executed upon connection to a server, and are set in the connection dialog) and “callable” scripts (scripts that are executed by the **/script** command or the “Run Script” button on non-chat windows).

Connection scripts are executed with *no* arguments, and, thus, can’t use the **/argcount** command (if this command is called, it is simply ignored). Other than that, they function just like other scripts.

“Callable” scripts are executed with whatever arguments are passed to the **/script** command; scripts executed with the “Run Script” button are executed with no arguments (calls to **/argcount** *will* be executed, however, any script using the command to look for anything other than zero (0) arguments will stop execution).

## IRC Commands

The majority of the available commands are for controlling the IRC connection (for example, joining and leaving channels, sending chat messages, etc). Three commands (**/invite**, **/part** and **/topic**) will behave differently depending on where the command is entered; it will behave one way if it is entered into a chat window (for private chat or channel chat) or if it’s entered into a console window (the window which displays data sent by the connected IRC server). One command, **/me**, cannot be entered into a non-chat window. These commands should be familiar to users of other IRC clients such as mIRC or HexChat.

Called from any window

**/away [MESSAGE...]**

Sets the client to AWAY. If MESSAGE is included, MESSAGE will be sent to any user that sends a private message to the client.

Called from any window

**/back**

Sets the client to BACK, and disables **/away** functionality.

Called from a chat window

**/invite [CHANNEL] NICKNAME**

Invites NICKNAME to the current channel if CHANNEL is omitted; invites NICKNAME to CHANNEL if a channel is included.

Called from any window

**/invite CHANNEL NICKNAME**

Invites NICKNAME to CHANNEL.

Called from any window

### **/join CHANNEL [KEY]**

Joins CHANNEL. If KEY is included, it will be passed to the server as part of the join request.

Called from any window

### **/list [TERMS]**

Displays a list of all channels on the server if TERMS is omitted; displays a list of channels matching TERMS if TERMS is included. TERMS can contain wildcards such as \* or ?.

Called from a chat window

Called from any window

### **/me TEXT**

Sends TEXT to the current chat as a CTCP action message. The command can *only* be called from a chat window.

Called from any window

### **/msg TARGET MESSAGE...**

Sends a private message to TARGET (which can be a channel or a nickname).

Called from any window

### **/nick NICKNAME**

Changes NICKNAME. If someone is already using NICKNAME, an error is displayed to the client.

Called from any window

### **/notice TARGET MESSAGE...**

Sends a NOTICE to TARGET (which can be a channel or a nickname).

Called from any window

### **/oper USERNAME PASSWORD**

Logs into a server operator account using USERNAME and PASSWORD.

Called from a chat window

Called from any window

### **/part [CHANNEL] [MESSAGE]**

Leaves the current channel if CHANNEL is omitted; leaves CHANNEL if a channel is included. MESSAGE is the message displayed to other users when leaving; MESSAGE is optional.

### **/part CHANNEL [MESSAGE]**

Leaves CHANNEL. MESSAGE is the message displayed to other users when leaving; MESSAGE is optional.

Called from any window

### **/quit [MESSAGE...]**

Disconnects from the current server. If MESSAGE is included, this will be sent to any channels the client is in before it disconnects.

Called from any window

### **/send MESSAGE**

Sends MESSAGE to the server as a raw text; the outgoing message will not be altered. This is to allow the client to send messages to the server that the client doesn't normally support.

Called from any window

### **/time [SERVER]**

Displays local time for the server currently connected to, or the SERVER specified.

Called from a chat window

Called from any window

### **/topic [CHANNEL] TEXT...**

Sets the topic for the current channel if CHANNEL is omitted; sets the topic for another channel if CHANNEL is included.

### **/topic CHANNEL TEXT...**

Sets the topic for CHANNEL.

Called from any window

### **/version SERVER [SERVER...]**

Requests server software version information from one or more SERVERs.

Called from any window

### **/who TEXT**

Displays a list of users who's nickname matches TEXT.

Called from any window

### **/whois NICKNAME**

Displays information about a specific user.

Called from any window

### **/whowas NICKNAME [MAXIMUM ENTRIES] [SERVER]**

Displays information about users with a NICKNAME that no longer exists.

## Scripting Commands

The rest of the commands control the *Θrk* client software itself. All of these commands can be entered into *any* window; however, the **/help** command will display slightly different output depending on what kind of window the command is called from. Three commands, **/argcount**, **/alias**, and **/wait**, can't be called by any window, and can only be called from scripts. If called with no arguments, the **/connect**, **/reconnect**, **/ressl**, and **/ssl** commands will open the "Connect" dialog with the appropriate options pre-selected.

Called only from a script

### **/alias NAME MESSAGE...**

Creates a new alias (called an "alias variable" in this document). Any script or command ran after this one (including the commands that follow the **/alias** command) that contains a dollar sign followed by NAME (\$NAME) will have that instance replaced with MESSAGE. This command is *only* available for use in scripts; however, alias variables are interpolated into *any* input, including the text typed into the text input widget. Alias variables are "global"; once created, they are usable in any script or command input. Alias variables can also be overloaded (or overwritten) by any other script.

Called only from a script

### **/argcount NUMBER MESSAGE...**

Checks to make sure that a script is called with the proper NUMBER of arguments; if not enough or too many arguments are passed to the script, MESSAGE is displayed and script execution stops immediately. This command cannot be called from connection scripts.

Called from any window

### **/connect [SERVER] [PORT]**

Causes the client to connect to an IRC server. If PORT is omitted, a default of 6667 is used. If SERVER and PORT is omitted, the connection dialog is displayed. The client's current nickname, username, and real name is used.

Called from any window

### **/exit**

Disconnects from all servers and exits the client.

Called from a chat window

### **/help**

Displays a list of commands useful in channel and private message sessions.

Called from any window

### **/help**

Displays a list of all commands.

Called from any window

### **/print MESSAGE...**

Displays MESSAGE in the client's current window.

Called from any window

### **/reconnect [SERVER] [PORT]**

Causes the client to connect to an IRC server, with the option to reconnect upon disconnection turned on.. If PORT is omitted, a default of 6667 is used. If SERVER and PORT is omitted, the connection dialog is displayed. The client's current nickname, username, and real name is used.

Called from any window

### **/refresh**

Requests a new list of channels from the server, and stores the new list in an internal cache.

Called from any window

### **/ressl [SERVER] [PORT]**

Causes the client to connect to an IRC server via SSL/TLS, with the option to reconnect upon disconnection turned on.. If PORT is omitted, a default of 6697 is used. If SERVER and PORT is omitted, the connection dialog is displayed. The client's current nickname, username, and real name is used.

Called from any window

### **/script FILENAME [ARGUMENT ...]**

Opens FILENAME, reads its contents into memory, and executes it as a list of commands; each additional ARGUMENT, is passed to the script. Any errors found in the script are displayed to the current window. ARGUMENTs can be used in the script much like **/alias** variables: **#1** is replaced with the first argument, **#2** with the second, and so on. To interpolate all ARGUMENTs as a single string, use **#0**. ARGUMENTs are interpolated into the script before **/alias** variables. If a line in a script doesn't contain a valid command, it will be sent to the current window as chat text, just as if the user entered it as chat text; if the current window is a non-chat window, an error will be displayed rather than the text being sent to the server. If a complete path to FILENAME is not provided, the client will look in the scripts directory (in **settings\scripts**, or set by the **-scripts** command-line flag) for the file.

Called from any window

### **/settings**

Opens the client's settings dialog.

Called from any window

### **/ssl [SERVER] [PORT]**

Causes the client to connect to an IRC server via SSL/TLS. If PORT is omitted, a default of 6697 is used. If SERVER and PORT is omitted, the connection dialog is displayed. The client's current nickname, username, and real name is used.

Called from any window

### **/style FILENAME**

Loads a style file (created with the "Style Editor", accessible from the "Preferences" dialog) into the current chat. If a complete path to FILENAME is not provided, the client will look in the scripts directory (in **settings\scripts**, or set by the **-scripts** command-line flag) for the file.

Called from any window

### **/switch [WINDOW NAME]**

Switches the current displayed channel. If WINDOW NAME is omitted, a list of available channels/private chats is displayed.

Called only from a script

### **/wait TIME**

Causes a script to pause for TIME seconds. This command is *only* available for use in scripts.