




Upgrade Adobe Experience Manager Guides 4.1.3



November 2022

Contents

Upgrade Adobe Experience Manager Guides 1

 Upgrade from version 3.8.5 to version 4.0 1

 Install version 4.0 3

 Upgrade to version 4.1 3

 Install version 4.1 3

 After you install version 4.1 4

 Upgrade to version 4.1.2 or 4.1.3 5

Upgrade Adobe Experience Manager Guides

You can upgrade your current version of AEM Guides to version 4.1.3. If you are using version 4.1 or 4.1.x, then you can directly upgrade to version 4.1.3. If you are using version 4.0.x, then you need to upgrade to version 4.1 or 4.1.x before upgrading to 4.1.3. If you are using AEM Guides version 3.8.5, then you need to upgrade to version 4.0 or any Service Pack of version 4.0 before upgrading to 4.1. If you are on a version prior to 3.8.5, refer to the Upgrade AEM Guides section in the product-specific installation guide.

For more details, refer to the following procedures:

- [Upgrade from 3.8.5 to version 4.0](#)
- [Upgrade to version 4.1](#)
- [Upgrade to version 4.1.2 or 4.1.3](#)

Upgrade from version 3.8.5 to version 4.0

If you are using AEM Guides version 3.8.5, then you can upgrade to version 4.0 of AEM Guides. With the upgrade feature, you don't have to uninstall the previous version of AEM Guides.

Before running the process there are certain tasks that you must complete. The following sub-sections will walk you through the prerequisites, report generation, and migration process. Also, after you install AEM Guides version 4.0 you may customize various configurations, according to the customer settings.

NOTE: This Upgrade process is applicable only from version 3.8.5 to version 4.0. For the process to upgrade from version 3.4 or higher to 3.8.5, refer to the *Upgrade AEM Guides* section in the product-specific installation guide available in the [Help Archival Page](#).

Prerequisites

Before you start the AEM Guides upgrade process, ensure that you have:

- 1) Imported the review comments in topics open for review.
- 2) Closed all active reviews.
- 3) Closed all translation tasks.
- 4) Uninstall any AEM Guides hot fixes installed on the top of the previous version (major or patch release) of AEM Guides.

Before you install version 4.0

Before you install version 4.0, perform the following steps:

- 1) Ensure at this point AEM Guides is on version 3.8.5.
- 2) Download the upgrade script package. To do so, search for "XML Documentation solution 4.0 Upgrade Package" on [Adobe Software Distribution Portal](#) which will download a zip file.
- 3) Upload this package to AEM via Package Manager and install this package.
- 4) Once the upgrade package is installed, run the below given scripts in the same order and follow the given instructions:

Check upgrade compatibility API

This API is designed to assess the current system status and report if the upgrade is possible or not. To run this script, trigger the below given endpoint:

End Point	/bin/dxml/upgrade/3xto4x/report
Request Type	GET You can use a web browser, where you are logged in to the AEM instance as an administrator.
Expected Response	<ul style="list-style-type: none"> In case all required nodes can be moved, you will get a passed check. In case a node is present at the target location, you will get a relevant error. Clean up the repository (delete node <code>/var/dxml</code>) and reinstall the upgrade package and then trigger this endpoint again. <i>NOTE: This is not a common error as the target location is not used earlier by 3.x AEM Guides.</i> If this script does not succeed, do not proceed and report to your customer success team.

System data migration API

This API is designed to migrate the system data as mentioned in the Migration Mapping section.

- 1) Do not execute this script if the Check upgrade compatibility API fails (do not proceed).
- 2) Once the Check upgrade compatibility API returns success, you can run the upgrade script.

End Point	/bin/dxml/upgrade/3xto4x
Request Type	POST This script is a POST request hence should be executed via agents like Postman.
Expected Response	<ul style="list-style-type: none"> Once the migration is successful, you can install XML Documentation solution version 4.0. In case there are errors, restore to the last checkpoint and share the error logs along with API output with your customer success team.

Migration Mapping: The above API migrates all the data under the source location to the target location.

Source	Target
/content/fmdita	/var/dxml

Source	Target
/content/dxml	/var/dxml
/etc/fmdita	/libs/fmdita

Install version 4.0

- 1) Install version 4.0 only if the upgrade steps were successful.
- 2) Download 4.0 version package from [Adobe Software Distribution Portal](#):
 - If you are using UUID version of software, search for "4.0 UUID Release for XML Documentation solution for AEM 6.5."
 - If you are using Non-UUID version of software, search for "4.0 Non-UUID Release for XML Documentation solution for AEM 6.5."
- 3) Upload the package to the existing AEM server instance(s) using CRX Package Manager and install it.
NOTE: Wait for all system components to start.
- 4) Clear the browser cache after installing the package.
- 5) If a dispatcher is configured on AEM Author instance, perform the following steps:
 - Ensure the following are handled in dispatcher rules:
 - The URL pattern `/home/users/*/preferences` is whitelisted.
 - The URL pattern `/libs/cq/security/userinfo.json` is not cached.
- 6) Clear dispatcher cache (to clear any `clientlibs` cached).

Upgrade to version 4.1

Prerequisites

Before you start the AEM Guides 4.1 upgrade process, ensure that you have:

- 1) Upgraded to AEM Guides version 4.0 or any Service Pack of version 4.0.
- 2) Closed all active reviews.
- 3) Uninstall any AEM Guides hot fixes installed on the top of the previous version (major or patch release) of AEM Guides.

NOTE: It is recommended to close all translation tasks.

Install version 4.1

- 1) Download 4.1 version package from [Adobe Software Distribution Portal](#).
- 2) Install version 4.1 package.

- 3) Upgrade Oxygen connector plugin released with version 4.1 (if needed).
- 4) Clear the browser cache after installing the package.
- 5) Continue upgrading the customizations as detailed out in the next section.

After you install version 4.1

After you install AEM Guides version 4.1, you may merge the various configurations applicable from the newly installed version to your setup.

NOTE: The dam-update-asset model may be customized. So, if any customizations have been done, then we need to sync the customizations and AEM Guides into the working copy of the model.

- 1) **DAM Update Asset workflow (Post-processing changes):**
 - a) Open URL:
`http://localhost:4502/libs/cq/workflow/admin/console/content/models.html`
 - b) Select **DAM Update Asset workflow**.
 - c) Click on **Edit**.
 - d) If the **DXML Post Process Initiator** component is present, ensure that the customizations are synced.
 - e) If the **DXML Post Process Initiator** component is absent, perform the following steps to insert it:
 - i) Click **Insert component** (Responsible for AEM Guides post-processing as the final step in the process).
 - ii) Configure the **Process step** with below details:

Common tab

Title: *DXML Post Process Initiator*

Description: *DXML post process initiator step which will trigger a sling job for DXML post-processing of the modified/created asset*

Process tab

 - Select **DXML Post Process Initiator** from the **Process** drop down
 - Select **Handler Advance**
 - Select **Done**
 - iii) Click **Sync** on the top right after completing the changes. You will receive a success notification.

NOTE: : Refresh and verify that customized changes and the AEM Guides post-processing step is present in the final workflow model.
- 2) Once **DAM Update Asset workflow** is validated, check corresponding launcher configurations. To do so, go to AEM Workflow interface and open launchers.
`http://localhost:4502/libs/cq/workflow/content/console.html`
*Find and make changes (if necessary) to the following two launchers (that should be active) corresponding to **DAM Update Asset workflow**:*

- Launcher for "*Node Created*" for **DAM Update Asset workflow**- for condition `"jcr:content/jcr:mimeType!=video"`,
 - the 'Globbing' value should be:


```
/content/dam(/((?!/subassets|/translation_output).)*/)renditions/original
```
 - 'excludeList' should have `"event-user-data:changedByWorkflowProcess"`.
 - Launcher for "*Node Modified*" for **DAM Update Asset workflow** - for condition `"jcr:content/jcr:mimeType!=video"`,
 - the 'Globbing' value should be:


```
"/content/dam(/((?!/subassets|/translation_output).)*/)renditions/original"
```
 - 'excludeList' should have `"event-user-data:changedByWorkflowProcess"`.
- 3) Once the upgrade is complete, ensure any of the customizations/overlays are validated and updated to match the new application code. Some examples are given below:
- Any components overlayed from `/libs/fmdita` or `/libs` should be compared with the new product code and updates should be done in overlayed files under `/apps`.
 - Any clientlib categories used from product, should be reviewed for changes. Any overridden configurations (examples below) should be compared with the latest ones so as to get the latest features:
 - `elementmapping.xml`
 - `ui_config.json`(may have been set in folder profiles)
 - amended `com.adobe.fmdita.config.ConfigManager`
 - Check if any of the custom code was using any old paths (as mentioned in the Migration Mapping section) - should be updated to the new paths so that the customizations also work as expected.
- 4) Read about any new configurations brought in the current release (check [Release Notes](#)) and see if any functionality is impacted then take appropriate action. An example could be to make use of "Improved file and version handling" introduced in version 4.0, for which you need to enable a configuration.

Upgrade to version 4.1.2 or 4.1.3

Upgrading to version 4.1.2 or 4.1.3 depends on the current version of AEM Guides.

If you are using version 4.1 or 4.1.x, then you can directly upgrade to version 4.1.2 or 4.1.3. You need to first upgrade to version 4.1 or 4.1.x before upgrading to 4.1.2 or 4.1.3.