

WeborbClient Class Reference

Overview

Instance Methods

initWithUrl:

Creates an engine for connecting to the application running on the specified web server. Traditionally the application would be accessible via the URL formatted as: `http://hostname[:port]/app`

`-(id)initWithUrl:(NSString *)gatewayURL;`

Parameters

gatewayURL
URL of the server application

initWithUrl:destination:

Creates an engine for connecting to the application running on the specified web server. Traditionally the application would be accessible via the URL formatted as: `http://hostname[:port]/app`

`-(id)initWithUrl:(NSString *)gatewayURL destination:(NSString *)destination;`

Parameters

gatewayURL
URL of the server application
destination
destination of the service (if nil = by default: «GenericDestination»)

setResponder:

Sets a current delegate for remote invocation; this delegate must be the instance conforming IRemoteClientDelegate protocol

`-(void)setResponder:(id <IRemoteClientDelegate>)delegate;`

Parameters

delegate
delegate for remote invocation

invoke:method:args

Invokes the remote service method with arguments; response will be returned to the

current delegate

```
-(void)invoke:(NSString *)className method:(NSString *)methodName args:(NSArray *)args;
```

Parameters

className
service name (or nil)
methodName
method name
args
array of method arguments (or nil)

invoke:method:args:responder

Invokes the remote service method with arguments; response will be returned to the specified delegate (must be the instance conforming IRemoteClientDelegate protocol)

```
-(void)invoke:(NSString *)className method:(NSString *)methodName args:(NSArray *)args  
responder:(id <IRemoteClientDelegate>)delegate;
```

Parameters

className
service name (or nil)
methodName
method name
args
array of method arguments (or nil)
delegate
delegate for remote invocation

IRemoteClientDelegate Protocol Reference

Overview

Instance Methods

responseHandler:headers:

The delegate receives this method when the engine got a response on remote method invocation

```
-(void)responsehandler:(id)result headers:(NSDictionary *)headers;
```

Parameters

result
The result object of remote invocation

headers

The response headers

errorHandler:detailization:

The delegate receives this method when the engine got an error or exception on remote method invocation

```
-(void)errorhandler:(NSString *)message detailization:(NSString *)detail;
```

Parameters

message

The error or exception message

detail

The error or exception detail description

additional

RTMPClient Class Reference

getSharedObject:persistent:owner

Returns a reference to a remote shared object that multiple clients can access. If the remote shared object does not already exist, it is created by the server (if the application the client is connected to allows RSO construction).

```
-(id <IClientSharedObject>)getSharedObject:(NSString *)name persistent:(BOOL)persistent  
owner:(id <ISharedObjectListener>)owner;
```

Parameters

name

The name of the shared object

persistent

If YES – specifies that the shared object is persistent on the server. The value of NO indicates the shared object is not persistent.

owner

delegate for the shared object (must conform the ISharedObjectListener protocol)