

Gruppen

Einbau unter
 <vehicle>
 <dashboards>
 <groups>
 <group ... />
 </groups>
 </dashboards>
 </vehicle>

Elemente	To be implemented within <vehicle> <dashboard> <dashboardLive> <dashboard ... /> </dashboardLive> </dashboard> </vehicle>											trailer: Number of chosen trailer or "S" for currently selected vehicle		partition: Number of chosen fillVolume	max: (optional) Upper limit	min: (optional) Lower limit	factor: (optional) Number the dashboard's value will be multiplied with				
	valueType=	cmd=	option=	joints=	state=	stateText=	trailer=	partition=	max=	min=	factor=	selection=	selectionGroup=	suggested displayTypes	Description						
base	disconnected		all any	1 2 ... n S					optional	optional	optional			VISIBLE, EMITTER	Active if nothing is connected to the given joints						
	connected		all any	1 2 ... n S					optional	optional	optional			VISIBLE, EMITTER	Active if something is connected to the given joints						
	lifted		all any	1 2 ... n S					optional	optional	optional			VISIBLE, EMITTER	Active if given joint is lifted						
	lifting		all any	1 2 ... n S					optional	optional	optional			VISIBLE, EMITTER	Active if given joint is lifting						
	lowering		all any	1 2 ... n S					optional	optional	optional			VISIBLE, EMITTER	Active if given joint is lowering						
	lowered		all any	1 2 ... n S					optional	optional	optional			VISIBLE, EMITTER	Active if given joint is lowered						
	lowerable		all any	1 2 ... n S					optional	optional	optional			VISIBLE, EMITTER	Active if given joint is lowerable						
	pto		all any	1 2 ... n S					optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if PTO/hydraulics corresponding to given joint is/are active						
	ptoRpm		all any	1 2 ... n S					optional	optional	optional			NUMBER, TEXT, ANIMATION, SLIDER	Value of PTO's turn rate in relation to the vehicles RPM. Set min, max and factor for fine tuning						
	foldable		all any	1 2 ... n S					optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if implement at given joint is foldable						
	folded		all any	1 2 ... n S					optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if implement at given joint is folded						
	unfolded		all any	1 2 ... n S					optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if implement at given joint is unfolded						
	folding		all any	1 2 ... n S					optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if implement at given joint is folding						
	unfolding		all any	1 2 ... n S					optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if implement at given joint is unfolding						
	foldingState		all any	1 2 ... n S					optional	optional	optional			NUMBER, TEXT, ANIMATION, SLIDER	Value of current folding process (0 .. 1). Use factor for scaling.						
	unfoldingState		all any	1 2 ... n S					optional	optional	optional			NUMBER, TEXT, ANIMATION, SLIDER	Value of current unfolding process (0 .. 1). Use factor for scaling.						
	tipping		all any	1 2 ... n S					optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if implement at given joint is tipping to the ground/trigger						
	swath		all any	1 2 ... n S	1 2 3 ...				optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if given swath state is active						
	mpConditioner		all any	1 2 ... n S					optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if Conditioner is on (requires Maize+)						
	seedType		all any	1 2 ... n S					optional	optional	optional			TEXT	Returns the current set seed type						
	fillLevel		abs percent max abskg percentkg maxkg		1 2 ... n S			1..n S	1..n	optional	optional	optional			NUMBER, TEXT, ANIMATION, SLIDER	Value of current fillLevel of choosen trailer and partition at given joint. abs: absolute value, percent: fillLevel in percent, max: capacity absKg: absolute fill weight, percentkg: percent from max weight, maxkg: maximum weight					
	hasSpec		all any <specName>		1 2 ... n S					optional	optional	optional			VISIBLE, EMITTER	Active if implement at given joint has the given specialization					
	hasTypedesc		all any <typeDescName>		1 2 ... n S					optional	optional	optional			VISIBLE, EMITTER	Active if implement at given joint has the given type description					
	tippingState		all any		1 2 ... n S					optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Value of current tipping process (0..1). User factor for scaling.					
	ridgeMarker		all any		1 2 ... n S	1 2 3 ...				optional	optional	optional			VISIBLE, EMITTER	Active if ridgeMarker has given state					
	liftState		all any		1 2 ... n S					optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Value of current lifting state (0..1). This only makes sense with 3P-Attachments. Use factor for scaling.					
	tipSide		all any		1 2 ... n S	Front Back Left Right BackGrainDoor				optional	optional	optional			VISIBLE, EMITTER	Active if set tipSide equals given tipSide.					
	tipSideText		all any		1 2 ... n S					optional	optional	optional			TEXT	Returns current set tipSide as plain text.					
	realClock		all any		1 2 ... n S					optional	optional	optional			TEXT	Returns real world clock time as plain text.					
	heading		all any		1 2 ... n S					optional	optional	optional			NUMBER, TEXT	Returns current heading in degree					
	headingText1		all any		1 2 ... n S					optional	optional	optional			TEXT	Returns current heading as N, E, S, W.					
	headingText2		all any		1 2 ... n S					optional	optional	optional			TEXT	Returns current heading as N, NE, E, SE, S, SW, W, NW.					
	fieldNumber		all any		1 2 ... n S					optional	optional	optional			NUMBER, TEXT	Returns current field number					
combine	chopper					enabled active			optional	optional	optional			VISIBLE, EMITTER	Active if chopper of combine is active (no swath): enabled: chopper is activated, active: chopper is currently working						
	swath					enabled active			optional	optional	optional			VISIBLE, EMITTER	Active if combine is producing straw swathes: enabled: swath is activated, active: swath is currently being produced						
	filling								optional	optional	optional			VISIBLE, EMITTER	Active if combine's tank is currently filling						
	hectars								optional	optional	optional			NUMBER, TEXT	Value of worked area						
	cutHeight								optional	optional	optional			NUMBER, TEXT	Value of set cutting height						
	pipeState				1 2 3 ...				optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if current pipe state equals given state						
	pipeFolding								optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if pipe is currently folding or unfolding						
	pipeFoldingState								optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Value of current folding state (0..1). Use factor for scaling.						
overloading				1 2 3 ...				optional	optional	optional			VISIBLE, EMITTER	Active if pipe is currently overloading							
vrs	park								optional	optional	optional			VISIBLE, EMITTER	Active if park break is set						
	diff_front								optional	optional	optional			VISIBLE, EMITTER	Active if front differential is activated						
	diff_back								optional	optional	optional			VISIBLE, EMITTER	Active if back differential is activated						
	diff								optional	optional	optional			VISIBLE, EMITTER	Active if front or back differential is activated						
	diff_4wd								optional	optional	optional			VISIBLE, EMITTER	Active if all-wheel-drive is activated						

vca	diff_awdF							optional	optional	optional			VISIBLE, EMITTER	Active if advance speed of front axle is activated
	ks							optional	optional	optional			VISIBLE, EMITTER	Active if "Keep Speed" is activated
	slip							optional	optional	optional			NUMBER, TEXT	Value of current slip (requires VCA or REA GUI)
	speed2							optional	optional	optional			NUMBER, TEXT	Value of second speed control
	speed3							optional	optional	optional			NUMBER, TEXT	Value of third speed control
hlm								optional	optional	optional			VISIBLE, EMITTER	Active if Headland Management is turned on
	field							optional	optional	optional			VISIBLE, EMITTER	Active if Headland Management is currently in field mode
	headland							optional	optional	optional			VISIBLE, EMITTER	Active if Headland Management is currently in headland mode
gps	contour							optional	optional	optional			VISIBLE, EMITTER	Active if Headland Management is currently in field mode and contour guidance is activated
		on						optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if GPS is turned on (Guidance Steering/GS or VCA)
		active						optional	optional	optional			VISIBLE, EMITTER	Active if GPS is currently active (GS or VCA)
		lane+						optional	optional	optional			VISIBLE, EMITTER	Active if current GPS-Lane is bigger than 0 (GS only)
gpsLane		lane-						optional	optional	optional			VISIBLE, EMITTER	Active if current GPS-Lane is smaller than 0 (GS only)
								optional	optional	optional			NUMBER, TEXT	Value of current GPS-Lane (GS only)
		delta						optional	optional	optional			ALL	Value of necessary course correction (-0.5..+0.5, GS only). Use factor for scaling.
		dir						optional	optional	optional			ANIMATION	Direction of course correction (-1: left, +1: right, GS only.
		dirLeft						optional	optional	optional			ALL	Active if direction of necessary course correction is left
gpsWidth		dirRight						optional	optional	optional			ALL	Active if direction of necessary course correction is right
		headingDelta						optional	optional	optional			ALL	Value of heading delta to gps course (GS or VCA)
proSeed								optional	optional	optional			NUMBER, TEXT	Value of currently set gps width
		mode						optional	optional	optional			TEXT	Value of ProSeed's mode in plain text
		mode			auto semi manual			optional	optional	optional			VISIBLE, EMITTER	Active if proSeed's mode equals given state
		distance						optional	optional	optional			NUMBER, TEXT	Value of tramLine distance
		laneDrive						optional	optional	optional			NUMBER, TEXT	Value of currently set lane
		laneFull						optional	optional	optional			NUMBER, TEXT	Number of lanes set
		tram						optional	optional	optional			VISIBLE, EMITTER	Active if tramLines are created
		fert						optional	optional	optional			VISIBLE, EMITTER	Active if fertilizer is enabled
		areaWork						optional	optional	optional			NUMBER, TEXT	Value of worked area
		areaField						optional	optional	optional			NUMBER, TEXT	Value of field size
		timeUse						optional	optional	optional			NUMBER, TEXT	Value of hectares per hour
		seedUse						optional	optional	optional			NUMBER, TEXT	Value of seed use
		segment			1 2 3 ...			optional	optional	optional			VISIBLE, EMITTER	Active if segment choosen in state is enabled
		tramType						optional	optional	optional			VISIBLE, EMITTER	Active if premarked tramlines are created
selection		audio						optional	optional	optional			VISIBLE, EMITTER	Active if proSeed's audio signals are enabled
								optional	optional	optional	... -2 -1 0 1 2 -2 -1 0 1 2 ...	VISIBLE, EMITTER	Active if currently selected vehicle/implement equals given selection
baler								optional	optional	optional			VISIBLE, EMITTER	Active if currently selected group equals given selectionGroup
	isRoundBale	all any selected current	1 2 ... n S					optional	optional	optional			VISIBLE, EMITTER	Active if bale is a round bale selected: baler setting, current: current bale
	baleSize	all any selected current	1 2 ... n S					optional	optional	optional			NUMBER, TEXT	Value of current bale size selected: baler setting, current: current bale
	baleCountAnz	all any	1 2 ... n S					optional	optional	optional			NUMBER, TEXT	Current value of processed bales (requires Ifko's baleCounter Mod or Göweil DLC or Vermeer DLC)
	baleCountTotal	all any	1 2 ... n S					optional	optional	optional			NUMBER, TEXT	Total value of processed bales (requires Ifko's baleCounter Mod or Göweil DLC or Vermeer DLC)
	wrappedBaleCountAnz	all any	1 2 ... n S					optional	optional	optional			NUMBER, TEXT	Current value of wrapped bales (requires Ifko's baleCounter Mod)
lockSteeringAxle	wrappedBaleCountTotal	all any	1 2 ... n S					optional	optional	optional			NUMBER, TEXT	Total value of wrapped bales (requires Ifko's baleCounter Mod)
													VISIBLE, EMITTER, ANIMATION, SLIDER	Active if steering axle lock is activated (requires Ifkos lockSteeringAxle mod)
combineXP	tonPerHour												NUMBER, TEXT	Value of currently processed tons per hour
	engineLoad												NUMBER, TEXT	Value of engine load
	yield												NUMBER, TEXT	Value of current yield
	highMoisture												VISIBLE, EMITTER, ANIMATION, SLIDER	Active if high crop moisture is detected
frontLoader	toolRotation	all any	1 2 ... n S					optional	optional	optional			NUMBER, TEXT	Value of tool's rotation
	toolRotation	all any	1 2 ... n S			origin		optional	optional	optional			NUMBER, TEXT	Value of tool's rotation normalized
	isToolRotation	all any	1 2 ... n S					optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if tool's rotation is between min and max
	isToolRotation	all any	1 2 ... n S			origin		optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if tool's normalized rotation is between min and max
print	<text>												TEXT	Prints value of <cmd>