

Elemente	To be implemented within <vehicle> <dashboard> <dashboardLive> <dashboard ... /> </dashboardLive> </dashboard> </vehicle>					trailer: Number of chosen trailer or "S" for currently selected vehicle	partition: Number of chosen fillVolume	max: (optional) Upper limit	min: (optional) Lower limit	factor: (optional) Number the dashboard's value will be multiplied with							
	valueType=	cmd=	option=	joints=	state=	stateText=	trailer=	partition=	max=	min=	factor=	selection=	selectionGroup=	suggested displayTypes	Description	Version	
base	disconnected	all   any		1 2 ... n   S					optional	optional	optional			VISIBLE, EMITTER	Active if nothing is connected to the given joints	1.0.0.0	
	connected	all   any		1 2 ... n   S					optional	optional	optional			VISIBLE, EMITTER	Active if something is connected to the given joints	1.0.0.0	
	lifted	all   any		1 2 ... n   S			1..n		optional	optional	optional			VISIBLE, EMITTER	Active if given joint is lifted	1.0.0.0	
	lifting	all   any		1 2 ... n   S			1..n		optional	optional	optional			VISIBLE, EMITTER	Active if given joint is lifting	1.0.0.0	
	lowering	all   any		1 2 ... n   S			1..n		optional	optional	optional			VISIBLE, EMITTER	Active if given joint is lowering	1.0.0.0	
	lowered	all   any		1 2 ... n   S			1..n		optional	optional	optional			VISIBLE, EMITTER	Active if given joint is lowered	1.0.0.0	
	lowerable	all   any		1 2 ... n   S			1..n		optional	optional	optional			VISIBLE, EMITTER	Active if given joint is lowerable	1.0.0.0	
	pto	all   any		1 2 ... n   S					optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if PTO/hydraulics corresponding to given joint is/are active	1.0.0.0	
	ptoRpm	all   any		1 2 ... n   S					optional	optional	optional			NUMBER, TEXT, ANIMATION, SLIDER	Value of PTO's turn rate in relation to the vehicles RPM. Set min, max and factor for fine tuning	1.0.0.0	
	foldable	all   any		1 2 ... n   S			1..n		optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if implement at given joint is foldable	1.0.0.0	
	folded	all   any		1 2 ... n   S			1..n		optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if implement at given joint is folded	1.0.0.0	
	unfolded	all   any		1 2 ... n   S			1..n		optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if implement at given joint is unfolded	1.0.0.0	
	folding	all   any		1 2 ... n   S			1..n		optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if implement at given joint is folding	1.0.0.0	
	unfolding	all   any		1 2 ... n   S			1..n		optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if implement at given joint is unfolding	1.0.0.0	
	foldingState	all   any		1 2 ... n   S			1..n		optional	optional	optional			NUMBER, TEXT, ANIMATION, SLIDER	Value of current folding process (0 .. 1). Use factor for scaling.	1.0.0.0	
	unfoldingState	all   any		1 2 ... n   S			1..n		optional	optional	optional			NUMBER, TEXT, ANIMATION, SLIDER	Value of current unfolding process (0 .. 1). Use factor for scaling.	1.0.0.0	
	tilting	all   any		1 2 ... n   S			1..n		optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if implement at given joint is tipping to the ground/trigger	1.0.0.0	
	swath	all   any		1 2 ... n   S	1 2 3 ...		1..n		optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if given swath state is active	1.0.0.0	
	mpConditioner	all   any		1 2 ... n   S			1..n		optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if Conditioner is on (requires Maize+)	1.0.0.0	
	seedType	all   any		1 2 ... n   S					optional	optional	optional			TEXT	Returns the current set seed type	1.0.0.0	

valueType=	cmd=	option=	joints=	state=	stateText=	trailer=	partition=	max=	min=	factor=	selection=	selectionGroup=	suggested displayTypes	Description	Version
gps		on						optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if GPS is turned on (Guidance Steering/GS or VCA)	1.0.0.0
		active						optional	optional	optional			VISIBLE, EMITTER	Active if GPS is currently active (GS or VCA)	1.0.0.0
		lane+						optional	optional	optional			VISIBLE, EMITTER	Active if current GPS-Lane is bigger than 0 (GS only)	1.0.0.0
		lane-						optional	optional	optional			VISIBLE, EMITTER	Active if current GPS-Lane is smaller than 0 (GS only)	1.0.0.0
gpsLane								optional	optional	optional			NUMBER, TEXT	Value of current GPS-Lane (GS only)	1.0.0.0
		delta						optional	optional	optional			ALL	Value of necessary course correction (-0.5..+0.5, GS only). Use factor for scaling	1.1.0.0
		dir						optional	optional	optional			ANIMATION	Direction of course correction (-1: left, +1: right, GS only).	1.1.0.0
		dirLeft						optional	optional	optional			ALL	Active if direction of necessary course correction is left	1.1.0.0
		dirRight						optional	optional	optional			ALL	Active if direction of necessary course correction is right	1.1.0.0
gpsWidth		headingDelta						optional	optional	optional			ALL	Value of heading delta to gps course (GS or VCA)	1.1.0.0
proSeed								optional	optional	optional			NUMBER, TEXT	Value of currently set gps width	1.0.0.0
		mode						optional	optional	optional			TEXT	Value of ProSeed's mode in plain text	1.0.0.0
		mode		auto   semi   manual				optional	optional	optional			VISIBLE, EMITTER	Active if proSeed's mode equals given state	1.0.0.0
		distance						optional	optional	optional			NUMBER, TEXT	Value of tramLine distance	1.0.0.0
		laneDrive						optional	optional	optional			NUMBER, TEXT	Value of currently set lane	1.0.0.0
		laneFull						optional	optional	optional			NUMBER, TEXT	Number of lanes set	1.0.0.0
		tram						optional	optional	optional			VISIBLE, EMITTER	Active if tramLines are created	1.0.0.0
		fert						optional	optional	optional			VISIBLE, EMITTER	Active if fertilizer is enabled	1.0.0.0
		areaWork						optional	optional	optional			NUMBER, TEXT	Value of worked area	1.0.0.0
		areaField						optional	optional	optional			NUMBER, TEXT	Value of field size	1.0.0.0
		timeUse						optional	optional	optional			NUMBER, TEXT	Value of hectares per hour	1.0.0.0
		seedUse						optional	optional	optional			NUMBER, TEXT	Value of seed use	1.0.0.0
		segment			1 2 3 ...			optional	optional	optional			VISIBLE, EMITTER	Active if segment choosen in state is enabled	1.0.0.0
		tramType						optional	optional	optional			VISIBLE, EMITTER	Active if premarked tramlines are created	1.0.0.0
selection		audio						optional	optional	optional			VISIBLE, EMITTER	Active if proSeed's audio signals are enabled	1.0.0.0
								optional	optional	optional	...-1 2 -1 0 1 2 ...	...-1 2 -1 0 1 2 ...	VISIBLE, EMITTER	Active if currently selected vehicle/implement equals given selection	1.0.0.0
baler	isRoundBale	all   any selected   current	1 2 ... n   S					optional	optional	optional			VISIBLE, EMITTER	Active if bale is a round bale selected: baler setting, current: current bale	1.1.0.0
	baleSize	all   any selected   current	1 2 ... n   S					optional	optional	optional			NUMBER, TEXT	Value of current bale size selected: baler setting, current: current bale	1.1.0.0
	baleCountAnz	all   any	1 2 ... n   S					optional	optional	optional			NUMBER, TEXT	Current value of processed bales (requires Ifko's baleCounter Mod or Göweil DLC or Vermeer DLC)	1.1.0.0
	baleCountTotal	all   any	1 2 ... n   S					optional	optional	optional			NUMBER, TEXT	Total value of processed bales (requires Ifko's baleCounter Mod or Göweil DLC or Vermeer DLC)	1.1.0.0
	wrappedBaleCountAnz	all   any	1 2 ... n   S					optional	optional	optional			NUMBER, TEXT	Current value of wrapped bales (requires Ifko's baleCounter Mod)	1.1.0.0
	wrappedBaleCountTotal	all   any	1 2 ... n   S					optional	optional	optional			NUMBER, TEXT	Total value of wrapped bales (requires Ifko's baleCounter Mod)	1.1.0.0
lockSteeringAxle	found		1 2 ... n   S			1..n							VISIBLE, EMITTER, ANIMATION, SLIDER	Active if steering axle lock is activated (requires Ifkos lockSteeringAxle mod)	1.0.0.0
	locked		1 2 ... n   S			1..n							VISIBLE, EMITTER, ANIMATION, SLIDER	Active if steering axle lock is activated (requires Ifkos lockSteeringAxle mod)	1.0.0.0
combineXP	tonPerHour												NUMBER, TEXT	Value of currently processed tons per hour	1.1.0.0
	engineLoad												NUMBER, TEXT	Value of engine load	1.1.0.0
	yield												NUMBER, TEXT	Value of current yield	1.1.0.0
	highMoisture												VISIBLE, EMITTER, ANIMATION, SLIDER	Active if high crop moisture is detected	1.1.0.0
frontLoader	toolRotation	all   any	1 2 ... n   S					optional	optional	optional			NUMBER, TEXT	Value of tool's rotation	1.1.0.0
	toolRotation	all   any	1 2 ... n   S		origin			optional	optional	optional			NUMBER, TEXT	Value of tool's rotation normalized	1.1.0.0
	isToolRotation	all   any	1 2 ... n   S					optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if tool's rotation is between min and max	1.1.0.0
	isToolRotation	all   any	1 2 ... n   S		origin			optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if tool's normalized rotation is between min and max	1.1.0.0
print	<text>												TEXT	Prints value of <cmd>	1.0.0.0
miniMap	map												VISIBILITY	Displays miniMap on plane at node	1.2.0.0
	posMarker												VISIBILITY	Displays position marker on miniMap	1.2.0.0
cvt	drivinglevel				1 2 3 ...								ALL	CVT drive level	1.3.0.0
	accramp				1 2 3 ...								ALL	CVT acceleration ramp	1.3.0.0
	brakeramp				1 2 3 ...								ALL	CVT brake ramp	1.3.0.0
	neutral												ALL	CVT in neutral	1.3.0.0
	tmspedal												ALL	CVT tms pedal activated	1.3.0.0
	pedalpercent				1 2 3 ...								ALL	CVT pedal percent	1.3.0.0
	digitalhandgasstep				1 2 3 ...								ALL	CVT handgas step	1.3.0.0
	rpmrange												ALL	CVT rpm range	1.3.0.0
	rpmDmin												ALL	CVT rpm min	1.3.0.0
	rpmDmax												ALL	CVT rpm max	1.3.0.0
precfarming	phActual												NUMBER, TEXT	actual PH value	1.3.0.0
	phTarget												NUMBER, TEXT	target PH value	1.3.0.0
	phChanged												NUMBER, TEXT	PH value changed by	1.3.0.0
	nActual												NUMBER, TEXT	actual nitrogen level	1.3.0.0
	nTarget												NUMBER, TEXT	target nitrogen level	1.3.0.0
	nChanged												NUMBER, TEXT	nitrogen level changed by	1.3.0.0
	sprayAmountAutoMode												VISIBLE, EMITTER, ANIMATION, SLIDER	spray amount automode	1.3.0.0
	applicationRate												NUMBER, TEXT	application rate	1.3.0.0
rda	soilType												NUMBER, TEXT	soil type	1.3.0.0
	cropSensor					optional							VISIBLE, EMITTER	crop sensor active	1.3.0.0
	inflating												NUMBER, TEXT	Inflating / deflating is active	1.3.0.0
	pressure												NUMBER, TEXT	actual pressure	1.3.0.0
	pressure	target											NUMBER, TEXT	set pressure (target value)	1.3.0.0
	pressure	max											NUMBER, TEXT	max pressure	1.3.0.0
	pressure	min											NUMBER, TEXT	min pressure	1.3.0.0
	maxSpeed												NUMBER, TEXT	max speed allowed	1.3.0.0