

Elemente	To be implemented within <vehicle> <dashboard> <dashboardLive> <dashboard ... /> </dashboardLive> </dashboard> </vehicle>						trailer: Number of chosen trailer or "S" for currently selected vehicle	partition: Number of chosen fillVolume	max: (optional) Upper limit	min: (optional) Lower limit	factor: (optional) Number the dashboard's value will be multiplied with				
	valueType=	cmd=	option=	joints=	state=	stateText=	trailer=	partition=	max=	min=	factor=	selection=	selectionGroup=	suggested displayTypes	Description
base	disconnected		all any	1 2 ... n S					optional	optional	optional			VISIBLE, EMITTER	Active if nothing is connected to the given joints
	connected		all any	1 2 ... n S					optional	optional	optional			VISIBLE, EMITTER	Active if something is connected to the given joints
	lifted		all any	1 2 ... n S			1..n		optional	optional	optional			VISIBLE, EMITTER	Active if given joint is lifted
	lifting		all any	1 2 ... n S			1..n		optional	optional	optional			VISIBLE, EMITTER	Active if given joint is lifting
	lowering		all any	1 2 ... n S			1..n		optional	optional	optional			VISIBLE, EMITTER	Active if given joint is lowering
	lowered		all any	1 2 ... n S			1..n		optional	optional	optional			VISIBLE, EMITTER	Active if given joint is lowered
	lowerable		all any	1 2 ... n S			1..n		optional	optional	optional			VISIBLE, EMITTER	Active if given joint is lowerable
	pto		all any	1 2 ... n S					optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if PTO/hydraulics corresponding to given joint is/are active
	ptoRpm		all any	1 2 ... n S					optional	optional	optional			NUMBER, TEXT, ANIMATION, SLIDER	Value of PTO's turn rate in relation to the vehicles RPM. Set min, max and factor for fine tuning
	foldable		all any	1 2 ... n S			1..n		optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if implement at given joint is foldable
	folded		all any	1 2 ... n S			1..n		optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if implement at given joint is folded
	unfolded		all any	1 2 ... n S			1..n		optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if implement at given joint is unfolded
	folding		all any	1 2 ... n S			1..n		optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if implement at given joint is folding
	unfolding		all any	1 2 ... n S			1..n		optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if implement at given joint is unfolding
	foldingState		all any	1 2 ... n S			1..n		optional	optional	optional			NUMBER, TEXT, ANIMATION, SLIDER	Value of current folding process (0 .. 1). Use factor for scaling.
	unfoldingState		all any	1 2 ... n S			1..n		optional	optional	optional			NUMBER, TEXT, ANIMATION, SLIDER	Value of current unfolding process (0 .. 1). Use factor for scaling.
	tipping		all any	1 2 ... n S			1..n		optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if implement at given joint is tipping to the ground/trigger
	swath		all any	1 2 ... n S	1 2 3 ...		1..n		optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if given swath state is active
	mpConditioner		all any	1 2 ... n S			1..n		optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if Conditioner is on (requires Maize+)
	seedType		all any	1 2 ... n S					optional	optional	optional			TEXT	Returns the current set seed type
	fillLevel		abs percent max abskg percentkg maxkg	1 2 ... n S			1..n	1..n	optional	optional	optional			NUMBER, TEXT, ANIMATION, SLIDER	Value of current fillLevel of choosen trailer and partition at given joint. abs: absolute value, percent: fillLevel in percent, max: capacity absKg: absolute fill weight, percentkg: percent from max weight, maxkg: maximum weight
	hasSpec		all any <specName>	1 2 ... n S			1..n		optional	optional	optional			VISIBLE, EMITTER	Active if implement at given joint has the given specialization
	hasTypedesc		all any <typeDescName>	1 2 ... n S			1..n		optional	optional	optional			VISIBLE, EMITTER	Active if implement at given joint has the given type description
	tippingState		all any	1 2 ... n S			1..n		optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Value of current tipping process (0..1). User factor for scaling.
	ridgeMarker		all any	1 2 ... n S	1 2 3 ...				optional	optional	optional			VISIBLE, EMITTER	Active if ridgeMarker has given state
	liftState		all any	1 2 ... n S					optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Value of current lifting state (0..1). This only makes sense with 3P-Attachments. Use factor for scaling.
	tipSide		all any	1 2 ... n S	Front Back Left Right BackGrainDoor		1..n		optional	optional	optional			VISIBLE, EMITTER	Active if set tipSide equals given tipSide.
	tipSideText		all any	1 2 ... n S			1..n		optional	optional	optional			TEXT	Returns current set tipSide as plain text.
	realClock		all any	1 2 ... n S					optional	optional	optional			TEXT	Returns real world clock time as plain text.
	heading		all any	1 2 ... n S					optional	optional	optional			NUMBER, TEXT	Returns current heading in degree
	headingText1		all any	1 2 ... n S					optional	optional	optional			TEXT	Returns current heading as N, E, S, W.
	headingText2		all any	1 2 ... n S					optional	optional	optional			TEXT	Returns current heading as N, NE, E, SE, S, SW, W, NW.
	fieldNumber		all any	1 2 ... n S					optional	optional	optional			NUMBER, TEXT	Returns current field number
combine	chopper					enabled active			optional	optional	optional			VISIBLE, EMITTER	Active if chopper of combine is active (no swath): enabled: chopper is activated, active: chopper is currently working
	swath					enabled active			optional	optional	optional			VISIBLE, EMITTER	Active if combine is producing straw swathes: enabled: swath is activated, active: swath is currently being produced
	filling								optional	optional	optional			VISIBLE, EMITTER	Active if combine's tank is currently filling
	hectars								optional	optional	optional			NUMBER, TEXT	Value of worked area
	cutHeight								optional	optional	optional			NUMBER, TEXT	Value of set cutting height
	pipeState				1 2 3 ...				optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if current pipe state equals given state
	pipeFolding								optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if pipe is currently folding or unfolding
	pipeFoldingState								optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Value of current folding state (0..1). Use factor for scaling.
overloading				1 2 3 ...				optional	optional	optional			VISIBLE, EMITTER	Active if pipe is currently overloading	
vca	park								optional	optional	optional			VISIBLE, EMITTER	Active if park break is set
	diff_front								optional	optional	optional			VISIBLE, EMITTER	Active if front differential is activated
	diff_back								optional	optional	optional			VISIBLE, EMITTER	Active if back differential is activated
	diff								optional	optional	optional			VISIBLE, EMITTER	Active if front or back differential is activated
	diff_awd								optional	optional	optional			VISIBLE, EMITTER	Active if all-wheel-drive is activated
	diff_awdF								optional	optional	optional			VISIBLE, EMITTER	Active if advance speed of front axle is activated
	ks								optional	optional	optional			VISIBLE, EMITTER	Active if "Keep Speed" is activated
	slip								optional	optional	optional			NUMBER, TEXT	Value of current slip (requires VCA or REA GUI)
	speed2								optional	optional	optional			NUMBER, TEXT	Value of second speed control
speed3								optional	optional	optional			NUMBER, TEXT	Value of third speed control	
hlm	field								optional	optional	optional			VISIBLE, EMITTER	Active if Headland Managment is turned on
	headland								optional	optional	optional			VISIBLE, EMITTER	Active if Headland Management is currently in field mode
	contour								optional	optional	optional			VISIBLE, EMITTER	Active if Headland Management is currently in headland mode Active if Headland Management is currently in field mode and contour guidance is activated

valueType=	cmd=	option=	joints=	state=	stateText=	trailer=	partition=	max=	min=	factor=	selection=	selectionGroup=	suggested displayTypes	Description
gps		on						optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if GPS is turned on (Guidance Steering/GS or VCA)
		active						optional	optional	optional			VISIBLE, EMITTER	Active if GPS is currently active (GS or VCA)
		lane+						optional	optional	optional			VISIBLE, EMITTER	Active if current GPS-Lane is bigger than 0 (GS only)
		lane-						optional	optional	optional			VISIBLE, EMITTER	Active if current GPS-Lane is smaller than 0 (GS only)
gpsLane								optional	optional	optional			NUMBER, TEXT	Value of current GPS-Lane (GS only)
		delta						optional	optional	optional			ALL	Value of necessary course correction (-0.5..+0.5, GS only). Use factor for scaling.
		dir						optional	optional	optional			ANIMATION	Direction of course correction (-1: left, +1: right, GS only.
		dirLeft						optional	optional	optional			ALL	Active if direction of necessary course correction is left
		dirRight						optional	optional	optional			ALL	Active if direction of necessary course correction is right
gpsWidth		headingDelta						optional	optional	optional			ALL	Value of heading delta to gps course (GS or VCA)
								optional	optional	optional			NUMBER, TEXT	Value of currently set gps width
proSeed		mode						optional	optional	optional			TEXT	Value of ProSeed's mode in plain text
		mode		auto semi manual				optional	optional	optional			VISIBLE, EMITTER	Active if proSeed's mode equals given state
		distance						optional	optional	optional			NUMBER, TEXT	Value of tramLine distance
		laneDrive						optional	optional	optional			NUMBER, TEXT	Value of currently set lane
		laneFull						optional	optional	optional			NUMBER, TEXT	Number of lanes set
		tram						optional	optional	optional			VISIBLE, EMITTER	Active if tramLines are created
		fert						optional	optional	optional			VISIBLE, EMITTER	Active if fertilizer is enabled
		areaWork						optional	optional	optional			NUMBER, TEXT	Value of worked area
		areaField						optional	optional	optional			NUMBER, TEXT	Value of field size
		timeUse						optional	optional	optional			NUMBER, TEXT	Value of hectares per hour
		seedUse						optional	optional	optional			NUMBER, TEXT	Value of seed use
		segment		1 2 3 ...				optional	optional	optional			VISIBLE, EMITTER	Active if segment choosen in state is enabled
		tramType						optional	optional	optional			VISIBLE, EMITTER	Active if premarked tramlines are created
		audio						optional	optional	optional			VISIBLE, EMITTER	Active if proSeed's audio signals are enabled
selection								optional	optional	optional	... -2 -1 0 1 2 ...		VISIBLE, EMITTER	Active if currently selected vehicle/implemment equals given selection
								optional	optional	optional	... -2 -1 0 1 2 -2 -1 0 1 2 ...	VISIBLE, EMITTER	Active if currently selected group equals given selectionGroup
baler	isRoundBale	all any selected current	1 2 ... n S					optional	optional	optional			VISIBLE, EMITTER	Active if bale is a round bale selected: baler setting, current: current bale
	baleSize	all any selected current	1 2 ... n S					optional	optional	optional			NUMBER, TEXT	Value of current bale size selected: baler setting, current: current bale
	baleCountAnz	all any	1 2 ... n S					optional	optional	optional			NUMBER, TEXT	Current value of processed bales (requires Ifko's baleCounter Mod or Göweill DLC or Vermeer DLC)
	baleCountTotal	all any	1 2 ... n S					optional	optional	optional			NUMBER, TEXT	Total value of processed bales (requires Ifko's baleCounter Mod or Göweill DLC or Vermeer DLC)
	wrappedBaleCountAnz	all any	1 2 ... n S					optional	optional	optional			NUMBER, TEXT	Current value of wrapped bales (requires Ifko's baleCounter Mod)
	wrappedBaleCountTotal	all any	1 2 ... n S					optional	optional	optional			NUMBER, TEXT	Total value of wrapped bales (requires Ifko's baleCounter Mod)
lockSteeringAxle	found		1 2 ... n S			1..n							VISIBLE, EMITTER, ANIMATION, SLIDER	Active if steering axle lock is activated (requires Ifkos lockSteeringAxle mod)
	locked		1 2 ... n S			1..n							VISIBLE, EMITTER, ANIMATION, SLIDER	Active if steering axle lock is activated (requires Ifkos lockSteeringAxle mod)
combineXP	tonPerHour												NUMBER, TEXT	Value of currently processed tons per hour
	engineLoad												NUMBER, TEXT	Value of engine load
	yield												NUMBER, TEXT	Value of current yield
	highMoisture												VISIBLE, EMITTER, ANIMATION, SLIDER	Active if high crop moisture is detected
frontLoader	toolRotation	all any	1 2 ... n S					optional	optional	optional			NUMBER, TEXT	Value of tool's rotation
	toolRotation	all any	1 2 ... n S		origin			optional	optional	optional			NUMBER, TEXT	Value of tool's rotation normalized
	isToolRotation	all any	1 2 ... n S					optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if tool's rotation is between min and max
	isToolRotation	all any	1 2 ... n S		origin			optional	optional	optional			VISIBLE, EMITTER, ANIMATION, SLIDER	Active if tool's normalized rotation is between min and max
print	<text>												TEXT	Prints value of <cmd>
miniMap	map												VISIBILITY	Displays miniMap on plane at node
	posMarker												VISIBILITY	Displays position marker on miniMap
cvt	drivinglevel			1 2 3 ...									ALL	CVT drive level
	accramp			1 2 3 ...									ALL	CVT acceleration ramp
	brakeramp			1 2 3 ...									ALL	CVT brake ramp
	neutral												ALL	CVT in neutral
	tmspedal												ALL	CVT tms pedal activated
	pedalpercent			1 2 3 ...									ALL	CVT pedal percent
	digitalhandgasstep			1 2 3 ...									ALL	CVT handgas step
	rpmrange												ALL	CVT rpm range
	rpmDmin												ALL	CVT rpm min
	rpmDmax												ALL	CVT rpm max
precfarming	phActual												NUMBER, TEXT	actual PH value
	phTarget												NUMBER, TEXT	target PH value
	phChanged												NUMBER, TEXT	PH value changed by
	nActual												NUMBER, TEXT	actual nitrogen level
	nTarget												NUMBER, TEXT	target nitrogen level
	nChanged												NUMBER, TEXT	nitrogen level changed by
	sprayAmountAutoMode												VISIBLE, EMITTER, ANIMATION, SLIDER	spray amount automode
	applicationRate												NUMBER, TEXT	application rate
	applicationRateStr												NUMBER, TEXT	application rate
	soilType												NUMBER, TEXT	soil type