

novelWriter

Project File Format 1.5 Specification

This document covers the file format specification for the 1.5 file format for novelWriter project files. See the [documentation](#)¹ for a full description of the app's functionality.

The target audience of this document is developers who intend to write a tool or script that generates valid novelWriter project files from data from other applications, or for templating purposes.

Note that flags are generally written out as yes/no values, but also true/false and on/off are understood by the application. The None value that occasionally occurs is the text representation of the Python None value, and must be used in those cases.

XML Root

Tag: `novelWriterXML`

The root tag of a novelWriter project file must be named “`novelWriterXML`”. This value is case sensitive. The `fileVersion` attribute must also be set to the appropriate format version in order to be parsed correctly.

Attributes

Name	Required	Description
<code>appVersion</code>	No	A string representation of the novelWriter version used to write the file. The value is not required, but is used to report to the user when the file format is converted.
<code>hexVersion</code>	No	A hex representation of the novelWriter version used to write the file. The value is used to check if the project is opened by a lower version than was used to write it, which issues a warning. Defaults to 0x0.
<code>fileVersion</code>	Yes	The file format version used when writing the project file. This determines how the file is parsed, so it is important that it is set correctly.
<code>timeStamp</code>	No	The ISO 8601 timestamp of when the file was saved. This information is not used by the parser, and is purely for debugging.

Example

```
<novelWriterXML appVersion="2.0-rc1" hexVersion="0x020000c1"
fileVersion="1.5" timeStamp="2022-11-05 17:46:51">
```

¹ See: <https://novelwriter.readthedocs.io/>

Project Node

Tag: `project`

The project section is a level one node under the root. It stores the primary settings for the project. The only required values are the `id` attribute and the `name` value. All other entries are set to default values during parsing and can be omitted from the XML.

Attributes

Name	Required	Description
<code>id</code>	Yes	A UUID that is unique for the project and does not change during the lifetime of the project. It is used by novelWriter for to keep track of temporary files and associate cross-project settings with different projects without relying on the project name.
<code>saveCount</code>	No	A number representing the number of times the project file has been written as a result of user interaction with the application.
<code>autoCount</code>	No	A number representing the number of times the project file has been written as a result of internal timed automatic operations of the application.
<code>editTime</code>	No	A number representing the accumulated time in seconds the project has been open.

Values

Name	Required	Description
<code>name</code>	Yes	The name the user has given to the project.
<code>title</code>	No	The title the user has given to the project, which may differ from the project name. The value is used in some places in the user interface, and can be added to manuscript builds.
<code>author</code>	No	The name of a single author of the project. This value can be repeated for multiple authors.

Example

```
<project id="e2be99af-f9bf-4403-857a-c3d1ac25abea"
  saveCount="5" autoCount="10" editTime="1000">
  <name>Sample Project</name>
  <title>Sample Project</title>
  <author>Jane Smith</author>
  <author>Jay Doh</author>
</project>
```

Settings Node

Tag: **settings**

The settings section is a level one node under the root. It stores the various runtime values for the project, and the settings available from the Project Settings panel. None of these settings are required, and if missing, will be set to default values. The entire settings section can thus be omitted.

Attributes

None

Values

Name	Required	Description
doBackup	No	User-controlled setting for whether or not to run backup when the project is closed.
language	No	The language used when building the manuscript. The settings is controlled from the Build Novel Project tool.
spellChecking	No	The spell checking language to use for this project if it differs from the default spell checking language for the application.
		Attribute auto : A flag determining whether the spell checking is automatic or not.
lastHandle	No	An auto-generated list of the last documents open in the editor and viewer, and which novel root folder was last viewed in the Novel Tree and Outline View. These are saved as key/value pairs. See separate section for how they are stored as XML.
autoReplace	No	The entries of the auto-replace feature available from the Project Settings. These are saved as key/value pairs. See separate section for how they are stored as XML.
titleFormat	No	The formatting specifications set by the user in the Build Novel Project tool for formatting headers in the manuscript. These are saved as key/value pairs. See separate section for how they are stored as XML.
status	No	The status labels as defined by the user in Project Settings. These are saved as special key/value pairs. See separate section for how they are stored as XML.
importance	No	The importance labels as defined by the user in Project Settings. These are saved as special key/value pairs. See separate section for how they are stored as XML.

Example

```
<settings>
  <doBackup>yes</doBackup>
  <language>en_GB</language>
  <spellChecking auto="yes">en_GB</spellChecking>
  <lastHandle />
  <autoReplace />
  <titleFormat />
  <status />
  <importance />
</settings>
```

Key/Value Nodes

The key/value nodes are used for **lastHandle**, **autoReplace** and **titleFormat** settings. The lookup key is stored as an attribute, and the value is the text of the node.

Attributes

Name	Required	Description
key	Yes	The lookup key.

Example

```
<lastHandle>
  <entry key="editor">636b6aa9b697b</entry>
  <entry key="viewer">636b6aa9b697b</entry>
  <entry key="novelTree">7031beac91f75</entry>
  <entry key="outline">7031beac91f75</entry>
</lastHandle>
```

Status/Importance Key/Value Nodes

The status and importance settings are stored as key/value nodes with additional data attributes.

Attributes

Name	Required	Description
key	Yes	The lookup key. For status labels, it must consist of an “s” followed by six hexadecimal numbers. These must be unique for each entry. For importance labels it must consist of an “i” followed by six hexadecimal numbers.
count	No	A record of the number of times each label is used in the project content.
red	Yes	A number between 0 and 255 representing the red component of the label colour.
green	Yes	A number between 0 and 255 representing the green component of the label colour.
blue	Yes	A number between 0 and 255 representing the blue component of the label colour.

Example

```
<status>
  <entry key="sf12341" count="4"
    red="100" green="100" blue="100">New</entry>
  <entry key="sd51c5b" count="0"
    red="193" green="129" blue="0">Draft</entry>
  <entry key="s78ea90" count="1"
    red="58" green="180" blue="58">Finished</entry>
</status>
<importance>
  <entry key="ia857f0" count="5"
    red="100" green="100" blue="100">None</entry>
  <entry key="icfb3a5" count="2"
    red="0" green="122" blue="188">Minor</entry>
  <entry key="i2d7a54" count="2"
    red="21" green="0" blue="180">Major</entry>
</importance>
```

Content Node

Tag: **content**

The content section is a level one node under the root. It stores all the project items of the project. The items are stored in the order in which they appear in the project tree, so altering the order will affect the structure. The attribute with the order number is not used when processing the data. It is mainly written to the XML for debugging purposes.

Attributes

Name	Required	Description
items	No	The number of project items in the content section.
novelWords	No	The number of words in total for all document nodes layout DOCUMENT. The value defaults to 0, but this number forms the basis of computing writing statistics during a session, so the number should be properly set in order to ensure correct statistics.
notesWords	No	The number of words in total for all document nodes layout NOTE. The value defaults to 0, but this number forms the basis of computing writing statistics during a session, so the number should be properly set in order to ensure correct statistics.

Values

Name	Required	Description
item	No	A node representing a project item.

Example

```
<content items="27" novelWords="954" notesWords="409">
  <item handle="7031beac91f75" parent="None" root="7031beac91f75"
    order="0" type="ROOT" class="NOVEL">
    <meta expanded="yes"/>
    <name status="sc24b8f" import="ia857f0">Novel</name>
  </item>
  ...
</content>
```

Item Nodes

The item nodes make up the actual project content of the project. Each node represents either a root folder, a regular folder, or a document. Each node has a type, class and layout setting that determine its category. Each item is given a handle that is a random hexadecimal string of length 13. For the items that are document files, this handle corresponds to its filename. It is therefore important that these match. Each document node is expected to correspond to a file in the contents folder of the project named “content/7031beac91f75.nwd” for the item handle “7031beac91f75”.

Each item node has a meta data node and a name node. The meta data node contains only collected information, and is thus not strictly required. However, an accurate word count and the correct icon in the project tree depend on these values. These values are set by the indexer class, so rebuilding the index should restore the data.

The name node contains the primary user defined settings for an item, and is required.

Attributes

Name	Required	Description
handle	Yes	The 13 value hexadecimal string that represents the item in the project. This is the primary identifier of a project item, and is required.
parent	Yes	The handle of the parent item in the tree. This value should only be None for root

folders. All other items must have a parent handle set. If the parent handle is None for an item that isn't a root folder, the item will be treated as orphaned during project loading.

root	No	The handle of the top of its hierarchy of parent items. That is, the root folder which it ultimately sits under. If the attribute is not set, it will be computed during loading. It is primarily saved to the XML file for efficiency reasons.
order	No	The numerical order of the item under its parent item. This value is not used during the loading process as the physical item order in the content node is used instead. It is primarily saved to the XML for debugging purposes.
type	Yes	The item type of the item node. Allowed values are ROOT, FOLDER and FILE.
class	Yes	The item class of the item node. There are a number of item classes available in the app, all corresponding to a specific type of root folder. Each item in a root folder should have the same class set as the root folder itself. The attribute is not strictly required for items that aren't root folders as it will be automatically set to match during loading.
layout	Yes	The item layout of the item node. Allowed values are DOCUMENT and NOTE. This is the attribute that determines if a FILE type item is a Novel Document or a Project Note.

Values

Name	Required	Description
meta	No	A node of meta data attributes for the item.
name	Yes	A node of user settings for the item.

Meta Nodes

The meta data collected for the current item. This data is collected primarily by the indexer class. It can be restored by rebuilding the index, so the data is not essential.

Attributes

Name	Required	Description
expanded	No	Whether the tree node in the project tree was expanded or collapsed during the last session. Applies to all item types.
heading	No	The heading level of the first heading of the text of the item. Only applies to FILE item types. Allowed values are H0, H1, H2, H3, and H4. Other values are reset to H0.
charCount	No	The number of characters in the text of the item. Only applies to FILE item types.
wordCount	No	The number of words in the text of the item. Only applies to FILE item types.
paraCount	No	The number of paragraphs in the text of the item. Only applies to FILE item types.
cursorPos	No	The last cursor position in the text of the item from the last session. Only applies to FILE item types. The value is used to restore the cursor position when the document is opened in the editor.

Name Nodes

The name node contains information about an item that is set by the user. Including its label, which is the text value of the node. This is the label that is displayed in the project tree.

Attributes

Name	Required	Description
status	No	The ID of the status label that has been set for this item. Defaults to the first status item defined in the status section of the settings node.
import	No	The ID of the importance label that has been set for this item. Defaults to the first importance item defined in the importance section of the settings node.

active

No

The active/inactive status of the document. Only applies to FILE item types.

Example

```
<item handle="53b69b83cdafc" parent="7031beac91f75" root="7031beac91f75"
  order="0" type="FILE" class="NOVEL" layout="DOCUMENT">
  <meta expanded="no" heading="H1" charCount="93" wordCount="19"
    paraCount="2" cursorPos="119"/>
  <name status="sc24b8f" import="ia857f0" active="yes">Title Page</name>
</item>
```