

z/OS V2R3 SDSF Product Update



SHARE St. Louis, Session 23530

August 16, 2018

Ken Jonas

kjonas@rocketsoftware.com

Agenda

- Recent V2R1 and V2R2 Enhancements
- Usability enhancements in V2R3
- New tabular panels in V2R3
- z/OSMF SDSF V2R3 plug-in enhancements
- Installation
- Toleration
- Security
- Documentation and help
 - SDSF User's Guide – **New !!**



RECENT UPDATES (SDSF SPES)

SDSF Recent Updates

- SDSF V2R1 and V2R2 new function (via SPEs)

APAR	V2R1 PTF (HGX7790)	V2R2 PTF (HGX77A0)	Implements
PI43902 (Base)	UI90031	UI90032	APF, LNK, LPA, PARM, PAG, SRCH, SYS
PI56007 (Base)	UI90045	UI90046	ENQ, SYM
PI60412 (Base)	UI90050	UI90051	Support for SDSF z/OSMF plug-in
PI60831 (z/OSMF plug-in)	UI38656	UI38655	APF, LNK, LPA, PAG, PARM, SYS
PI64206 (Base)	UI41033	UI41032	AS, DYNX, PROC
PI68831 (Base)	UI90061	UI90062	Support for SDSF z/OSMF plug-in
PI64210 (z/OSMF plug-in)	UI42812	UI42811	AS, PS, SP

SDSF Recent Updates

- New Panels
 - AS – Address space memory
 - APF – APF list **
 - JS – Job Step (V2R2 and higher)
 - LNK – Link list **
 - LPA – LPA list **
 - PAG – Page data sets
 - PARM – Parmlib data sets **
 - PROC – Proclib data sets (V2R2 JES2 only) **
- SRCH – Search for member pattern

** SRCH command applies

SDSF Recent Updates

- SYS – System information panel
- DYNX – Dynamic exits
- ENQ – Enqueues (ENQC for contention)

SDSF Recent Updates

- z/OSMF SDSF/UI new panels
 - Address Space Storage
 - APF list
 - Link list
 - LPA list
 - Page Data Sets
 - Parmlib data sets
 - Unix Processes
 - Spool Data Sets
 - System Information

Address Space Storage (AS) Panel

Display Filter View Print Options Search Help										
SDSF AS DISPLAY RS86			RS86		LINE 1-24 (71)					
COMMAND INPUT ==>			SCROLL ==> HALF							
PREFIX=* DEST=(ALL) OWNER=*			SORT=CSA/D		SYSNAME=					
ACTION=+-Extend,-/-Show,-/-Block,-/-RunExec,-/-Repeat,-/-JobModule,-/-JobDevices,										
ACTION=JM-JobMemory,JT-JobTasks										
NP	JOBNAME	ASIDX	Real	Fixed	CSA	CSA%	ECSA	ECSA%	SQA	SQA%
	MXIMAST	005E	14556	366	207184	6.04	1222776	0.68	0	0.00
	MASTER	0001	3552	2468	127304	3.71	2681392	1.49	30848	1.86
	RACF	0029	849	87	35424	1.03	736	0.00	64	0.00
	VTAM	0025	2963	134	25160	0.73	2418472	1.34	0	0.00
	JES2	0023	8655	983	17624	0.51	1248488	0.69	64	0.00
	CONSOLE	000A	2473	145	2880	0.08	57288	0.03	11672	0.70
	TSO	0055	379	77	920	0.02	2424	0.00	0	0.00
	TS5485	004E	2116	117	136	0.00	3160	0.00	96	0.00
	TCPIP	005A	13635	340	136	0.00	49920	0.02	0	0.00
	XDCSRVER	0073	3602	136	136	0.00	29240	0.01	0	0.00
	TN3270	0074	2701	119	136	0.00	34552	0.01	0	0.00
	PCAUTH	0002	111	61	0	0.00	0	0.00	64	0.00
	RASP	0003	327	312	0	0.00	0	0.00	0	0.00
	TRACE	0004	5850	593	0	0.00	0	0.00	0	0.00
	DUMPSRV	0005	415	129	0	0.00	4696	0.00	64	0.00
	XCFAS	0006	5058	1668	0	0.00	0	0.00	160	0.00
	GRS	0007	24637	340	0	0.00	2304	0.00	48	0.00
	SMSPDSE	0008	697	126	0	0.00	0	0.00	0	0.00
	SMSPDSE1	0009	1580	126	0	0.00	0	0.00	0	0.00
	WLM	000B	2097	164	0	0.00	104488	0.05	0	0.00
	ANTMAIN	000C	1654	208	0	0.00	801432	0.44	0	0.00
	ANTAS000	000D	1550	184	0	0.00	185984	0.10	0	0.00
	DEVMAN	000E	505	74	0	0.00	93648	0.05	0	0.00
	GTZ	000F	279	71	0	0.00	1584	0.00	0	0.00

Tip: sort CSA descending to show highest utilization

Address Space Storage (AS) Panel

Display Filter View Print Options Search Help

SDSF AS DISPLAY RS86 RS86 LINE 1-24 (71)
COMMAND INPUT ===> SCROLL ===> HALF
PREFIX=* DEST=(ALL) OWNER=* SORT=CSA/D SYSNAME=
ACTION=+-Extend,/-Show,/-Block,%-RunExec,=-Repeat,JC-JobModule,JD-JobDevices,
ACTION=JM-JobMemory,JT-JobTasks

NP	JOBNAME	MemObjNum	MemObjUsed	MemObjHWM	HVComNum	HVComUsed	HVComHWM	ShrMON
	MXIMAST	21	1212MB	1468MB	0	0	0	
	MASTER	3	5MB	6MB	5	38MB	38MB	
	RACF	3	6MB	6MB	1	1MB	1MB	
	VTAM	4	7MB	7MB	2	5MB	5MB	
	JES2	11	824MB	824MB	1	1MB	1MB	
	CONSOLE	1	3MB	3MB	1	1MB	1MB	
	TSO	6	9MB	9MB	0	0	0	
	TS5485	16	98MB	99MB	0	0	0	
	TCPIP	120	178MB	178MB	4	2711MB	2711MB	
	XDCSRVER	8	11MB	11MB	0	0	0	
	TN3270	14	1042MB	1042MB	2	3MB	3MB	
	PCAUTH	0	0	0	1	1MB	1MB	
	RASP	0	0	0	0	0	0	
	TRACE	13	25MB	25MB	0	0	0	
	DUMPSRV	4	2021MB	2021MB	3	3MB	3MB	
	XCFAS	6	9MB	9MB	1	1MB	1MB	
	GRS	11	241661MB	241661MB	1	1MB	1MB	
	SMSPDSE	27	45MB	45MB	0	0	0	
	SMSPDSE1	29	47MB	47MB	0	0	0	
	WLM	3	6MB	6MB	1	1MB	1MB	
	ANTMAIN	11	14MB	15MB	0	0	0	
	ANTAS000	11	14MB	14MB	0	0	0	
	DEVMAN	3	6MB	6MB	0	0	0	
	GTZ	4	205MB	205MB	0	0	0	

Tip: set display on to show current prefix and owner

Memory objects

Address Space Storage (AS) Panel

Display Filter View Print Options Search Help											
SDSF AS DISPLAY RS86			RS86		LINE 1-24 (71)						
COMMAND INPUT ==>			SCROLL ==> HALF								
PREFIX=* DEST=(ALL) OWNER=* SORT=CSA/D SYSNAME=											
ACTION=+-Extend,/-Show,/-Block,%-RunExec,=-Repeat,JC-JobModule,JD-JobDevices,											
ACTION=JM-JobMemory,JT-JobTasks											
NP	JOBNAME	StepName	ProcStep	JobID	Owner	Pos	SR	Type	ASID	SSName	SysN
	MXIMAST	MXIMAST	MXXMSTK4	STC08645	MXISTC	NS		STC	94	JES2	RS86
	MASTER			STC08593	+MASTER+	NS		STC	1	JES2	RS86
	RACF	RACF	RACF	STC08665	RACF	NS		STC	41	JES2	RS86
	VTAM	VTAM	VTAM	STC08594	VTAM	NS		STC	37	JES2	RS86
	JES2	JES2	IEFPROC			NS		STC	35	JES2	RS86
	CONSOLE	CONSOLE				NS		STC	10		RS86
	TSO	TSO	STEP1	STC08636	+++++++	OUT	LW	STC	85	JES2	RS86
	TS5485	ROCKPROC	S86TCP05	TSU08759	TS5485	IN		TSU	78	JES2	RS86
	TCPIP	TCPIP	TCPIP	STC08639	TCPIP	NS		STC	90	JES2	RS86
	XDCSRVER	XDCSRVER	XDCSRVER	STC08679	+++++++	NS		STC	115	JES2	RS86
	TN3270	TN3270	TN3270	STC08682	TN3270	NS		STC	116	JES2	RS86
	PCAUTH	PCAUTH				NS		STC	2		RS86
	RASP	RASP				NS		STC	3		RS86
	TRACE	TRACE				NS		STC	4		RS86
	DUMPSRV	DUMPSRV	DUMPSRV			NS		STC	5		RS86
	XCFAS	XCFAS	IEFPROC			NS		STC	6		RS86
	GRS	GRS				NS		STC	7		RS86
	SMSPDSE	SMSPDSE				NS		STC	8		RS86
	SMSPDSE1	SMSPDSE1				NS		STC	9		RS86
	WLM	WLM	IEFPROC			NS		STC	11		RS86
	ANTMAIN	ANTMAIN	IEFPROC			NS		STC	12		RS86
	ANTAS000	ANTAS000	IEFPROC			NS		STC	13		RS86
	DEVMAN	DEVMAN	IEFPROC			NS		STC	14		RS86
	GTZ	GTZ	GTZ			NS		STC	15		RS86

Job detail columns

APF Panel

```
Display Filter View Print Options Search Help
-----
SDSF APF DISPLAY RS86      RS86      EXT      69      LINE 1-24 (41)
COMMAND INPUT ===>          SCROLL ===> HALF
PREFIX=*  DEST=(ALL)  OWNER=*  SYSNAME=
ACTION=+-Extend,/-Show,//-Block,%-RunExec,=-Repeat,D-Display,DA-DisplayAll,
ACTION=SB-ISPFBrowse,SE-ISPFEEdit
NP  DSNNAME
SYS1.LINKLIB      1 RZ203A OK      32760      1 NO      0
SYS1.SVCLIB      2 RZ203A OK      32760      1 NO      0
CEE.SCEERUN      3 RZ203A OK      32760      1 NO      0
CEE.SCEERUN2     4 RZ203A OK      32760      1 NO      0
CSF.SCSFMODE0    5 RZ203A OK      32760      1 NO      0
DIT.HOGB310.SDITMOD1 6 RZ203A OK      32760      1 NO      0
EQAW.SEQAAUTH    7 RZ203A MISSING    0          0 NO      0
EQAW.SEQABMOD    8 RZ203A MISSING    0          0 NO      0
EQAW.SEQAMOD     9 RZ203A MISSING    0          0 NO      0
FFST.V120ESA.SEPWMOD1 10 RZ203A OK      32760      1 NO      0
FFST.V120ESA.SEPWMOD2 11 RZ203A OK      32760      1 NO      0
REXX.SEAGALT     12 RZ203A OK      32760      1 NO      0
REXX.SEAGLPA     13 RZ203A MISSING    0          0 NO      0
SYS1.CSSLIB      14 RZ203A OK      32760      1 NO      0
SYS1.MIGLIB      15 RZ203A OK      32760      1 NO      0
SYS1.NFSLIBE     16 RZ203A OK      32760      1 NO      0
SYS1.SBDTCMD     17 RZ203A OK      32760      1 NO      0
SYS1.SBDTLIB     18 RZ203A OK      32760      1 NO      0
SYS1.SERBLINK    19 RZ203A OK      32760      1 NO      0
SYS1.SHASLNKE    20 RZ203A OK      32760      1 NO      0
SYS1.SHASMIG     21 RZ203A OK      32760      1 NO      0
SYS1.SISTCLIB    22 RZ203A OK      32760      4 NO      0
SYS1.VTAMLIB     23 RZ203A OK      32760      1 NO      0
TCP/IP.SEZADSIL  24 RZ203A OK      32760      7 NO      0
```

Might need attention

Job Step Panel

```
Display Filter View Print Options Search Help
-----
SDSF STATUS DISPLAY ALL CLASSES LINE 510-515 (515)
COMMAND INPUT ===> SCROLL ===> HALF
PREFIX=** DEST=(ALL) OWNER=* SYSNAME=
NP  JOBNAME JobID Owner Prty Queue C Pos SAff ASys Status
    BPXAS STC07638 BPXAS 1 PRINT A 280
    OOPSLIST JOB07642 PDZTEAM 1 PRINT A 281
    BPXAS STC07643 BPXAS 1 PRINT A 282
    SENDALRT STC07647 STCUSER 1 PRINT A 283
    TESTSTEP JOB07648 TS5485 1 PRINT A 284
    JOBB JOB09406 TS5485 9 SETUP A 4
```

js_

js action to access Job
Step panel

```
Display Filter View Print Options Search Help
-----
SDSF JOB STEP DISPLAY - JOB TESTSTEP (JOB07648) SMF LINE 1-10 (10)
COMMAND INPUT ===> SCROLL ===> HALF
PREFIX=** DEST=(ALL) OWNER=* SYSNAME=
ACTION=+-Extend,/-Show,/--Block,%-RunExec,=-Repeat,S-Browse,Sn-BrowseLocDS,
ACTION=SB-ISPFBrowse,SE-ISPFEdit,SJ-JCLEdit,X-Print,XC-PrintClose,XD-PrintDS,
ACTION=XDC-PrintDSClose,XF-PrintFile,XFC-PrintFileClose,XS-PrintSysout,
ACTION=XSC-PrintSysoutClose
NP  STEPNAME ProcStep Pgm-Name Step-CC StepNum Elapsed EXCP-Cnt CPU-Tim
    STEP1 IEFBR14 CC 0000 1 0:00:00.01 8 0:00:0
    STEP2 IEBGENER CC 0012 2 0:00:00.01 9 0:00:0
    STEP3 IEFBR14 CC 0000 3 0:00:00.01 6 0:00:0
    STEP4 AMBLIST CC 0000 4 0:00:00.01 28 0:00:0
    STEP5 IEBCOPY CC 0008 5 0:00:00.03 62 0:00:0
    STEP6 IEFBR14 CC 0000 6 0:00:00.00 9 0:00:0
    STEP7 IEBDG CC 0012 7 0:00:00.01 24 0:00:0
    STEP8 IDCAMS CC 0016 8 0:00:00.01 8 0:00:0
    STEP9 IEFBR14 CC 0000 9 0:00:00.01 10 0:00:0
    STEP10 SDSF ABENDU0013 10 0:00:05.34 1427 0:00:0
```

Step details from
SMF

Link List (LNK) Panel

Display Filter View Print Options Search Help									
SDSF LNK DISPLAY RS86 RS86		EXT	68	LINE 1-24 (49)			SCROLL ==> HALF		
COMMAND INPUT ==> PREFIX=* DEST=(ALL) OWNER=* SYSNAME= ACTION=+-Extend,/-Show,//-Block,%-RunExec,=-Repeat,D-Display,DN-DisplayNames, ACTION=SB-ISPFBrowse,SE-ISPFEEdit NP DSNAME									
	Seq	VolSer	BlkSize	Extent	SMS	APF	LRecL		
SYS1.LINKLIB	1	RZ203A	32760	1	NO	YES	0		
SYS1.MIGLIB	2	RZ203A	32760	1	NO	YES	0		
SYS1.CSSLIB	3	RZ203A	32760	1	NO	YES	0		
SYS1.SIEALNKE	4	RZ203A	32760	1	NO	NO	0		
SYS1.SIEAMIGE	5	RZ203A	32760	1	NO	NO	0		
DEV RTE.HSF.SMPE.SDSF0203.SISFLOAD	6	R3P1D1	32760	2	YES	NO	0		
RS86.LINKLIB	7	MCPG00	32760	1	NO	NO	0		
RSPLEX0G.LINKLIB	8	MCPG00	32760	1	NO	NO	0		
RS RTE.LINKLIB	9	R3P100	32760	1	YES	NO	0		
ASM.SASMMOD1	10	RZ203A	32760	1	NO	NO	0		
CBC.SCCNCMP	11	RZ203A	32760	1	NO	NO	0		
CBC.SCLBDLL	12	RZ203A	32760	1	NO	NO	0		
CBC.SCLBDLL2	13	RZ203A	32760	1	NO	NO	0		
CEE.SCEERUN	14	RZ203A	32760	1	NO	YES	0		
CEE.SCEERUN2	15	RZ203A	32760	1	NO	YES	0		
CSF.SCSFMODE0	16	RZ203A	32760	1	NO	YES	0		
DIT.HOGB310.SDITMOD1	17	RZ203A	32760	1	NO	YES	0		
FFST.V120ESA.SEPWMOD2	18	RZ203A	32760	1	NO	YES	0		
FFST.V120ESA.SEPWMOD4	19	RZ203A	32760	1	NO	NO	0		
GDDM.SADMMOD	20	RZ203A	32760	1	NO	NO	0		
GIM.SGIMLMD0	21	RZ203A	32760	1	NO	NO	0		
ISP.SISPLOAD	22	RZ203A	32760	1	NO	NO	0		
REXX.SEAGALT	23	RZ203A	32760	1	NO	YES	0		
SYS1.CMDLIB	24	RZ203A	32760	1	NO	NO	0		

Total extents
being shown

Concatenation
sequence

Data set extents

LPA List (LPA) Panel

```

Display Filter View Print Options Search Help
-----
SDSF LPA DISPLAY RS86 RS86 EXT 48 LINE 1-16 (16)
COMMAND INPUT ===>
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=
ACTION=+-Extend,-/-Show,/-Block,-RunExec,--Repeat,SB-ISPFBrowse,SE-ISPFEit
NP DSNAM Seq VolSer BlkSize Extent SMS APF LRecl DSOrg
SYS1.LPALIB 1 RZ203A 32760 5 NO NO 0 PO
RSRTE.LPALIB 2 R3P104 32760 10 YES NO 0 PO
ROCKET.USER.RS86.LPALIB 3 S1PG00 27920 1 YES NO 0 PO
ROCKET.USER.LPALIB 4 S1PG00 27920 1 YES NO 0 PO
SYS1.SERBLPA 5 RZ203A 32760 6 NO NO 0 PO
SYS1.SBDTLPA 6 RZ203A 32760 1 NO NO 0 PO
CEE.SCEELPA 7 RZ203A 32760 9 NO NO 0 PO
ISP.SISPLPA 8 RZ203A 32760 3 NO NO 0 PO
TCPIP.SEZALPA 9 RZ203A 32760 1 NO NO 0 PO
RSRTE.VENDOR.XDC.XDCPLPA 10 R3P103 32760 5 YES NO 0 PO
SYS1.SORTLPA 11 RZ203A 32760 1 NO NO 0 PO
SYS1.SDWDLPA 12 RZ203A 32760 1 NO NO 0 PO
SYS1.SICELPA 13 RZ203A 32760 1 NO NO 0 PO
SYS1.SIATLPA 14 RZ203A 32760 1 NO NO 0 PO
DEV RTE.HSF.DEVB0203.SISFLPA 15 R3P100 6144 1 YES NO 0 PO
ISF.SISFLPA 16 RZ203A 32760 1 NO NO 0 PO
  
```

Concatenation
sequence

System you are
logged on to

System pattern being processed
(SYSNAME command)

*Tip: sysname (blank)
for local system*

Page Data Sets (PAG) Panel

```
Display Filter View Print Options Search Help
-----
SDSF PAG DISPLAY RS86 (ALL) LINE 1-6 (6)
COMMAND INPUT ==> set action on SCROLL ==> HALF
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*
ACTION=+-Extend,/-Show,/-Block,%-RunExec,=-Repeat,D-Display,DC-DisplayCommon,
ACTION=DD-DisplayPageDel,DL-DisplayLocal,DP-DisplayPLPA,DS-DisplaySCM
NP DSNAME Type Slots Used Use% VolSer Status VIO IOError
RS86.PAGE.PLPA PLPA 179 179 100 PGPG02 OK NO 0
RS86.PAGE.COMMON COMMON 53999 15918 29 PGPG02 OK NO 0
RS86.PAGE.LOCAL1 LOCAL 539999 0 0 PGPG02 OK YES 0
RS88.PAGE.PLPA PLPA 179 179 100 PGPG04 OK NO 0
RS88.PAGE.COMMON COMMON 53999 15918 29 PGPG04 OK NO 0
RS88.PAGE.LOCAL1 LOCAL 539999 0 0 PGPG04 OK YES 0
```

*Tip: set action on to show
action characters*

Parmlib Data Sets (PARM) Panel

```

Display Filter View Print Options Search Help
-----
SDSF PARMLIB DISPLAY RS86 (ALL) EXT 58 LINE 1-10 (10)
COMMAND INPUT ==>
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*
ACTION=+-Extend,/-Show,/--Block,%-RunExec,=-Repeat,D-Display,DE-DisplayErrors,
ACTION=SB-ISPFBrowse,SE-ISPFEEdit
NP DSNNAME Seq VolSer BlkSize Extent SMS CrDate SysName Sy
RSPLEXOG.PARMLIB.ZOS202 1 MCPG00 27920 1 NO 2015.266 RS86 z/
RSPLEXOG.PARMLIB 2 MCPG00 27920 10 NO 2015.142 RS86 z/
RSRTE.PARMLIB 3 R3P104 27920 1 YES 2007.031 RS86 z/
ROCKET.USER.PARMLIB 4 S1PG00 27920 16 YES 2016.196 RS86 z/
SYS1.PARMLIB 5 RZ203A 27920 1 NO 2015.273 RS86 z/
RSPLEXOG.PARMLIB.ZOS202 1 MCPG00 27920 1 NO 2015.266 RS88 z/
RSPLEXOG.PARMLIB 2 MCPG00 27920 10 NO 2015.142 RS88 z/
RSRTE.PARMLIB 3 R3P104 27920 1 YES 2007.031 RS88 z/
ROCKET.USER.PARMLIB 4 S1PG00 27920 16 YES 2016.196 RS88 z/
SYS1.PARMLIB 5 RZ203A 27920 1 NO 2015.273 RS88 z/
  
```

Concatenation
sequence

*Tip: use arrange command
to reorder columns as is
shown here*

Proclib Data Sets (PROC) Panel (JES2 only)

```

Display Filter View Print Options Search Help
-----
SDSF PROC DISPLAY RS86 EXT 10 LINE 1-9 (9)
COMMAND INPUT ==> SCROLL ==> HALF
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*
ACTION=+-Extend,/-Show,//-Block,%-RunExec,=-Repeat,D-Display,DD-DisplayDebug
NP DDNAME Seq DSName VolSer DefVol St
PROC00 1 RS86.PROCLIB.ZOS203 MCPG00 MCPG00 OK
PROC00 2 RS86.PROCLIB MCPG00 MCPG00 OK
PROC00 3 RSPLEX0G.PROCLIB.ZOS203 MCPG00 MCPG00 OK
PROC00 4 RSPLEX0G.PROCLIB MCPG00 MCPG00 OK
PROC00 5 RSRTE.TSOU.PROCLIB R3P101 R3P101 OK
PROC00 6 RSRTE.PROCLIB R3P108 R3P108 OK
PROC00 7 ROCKET.PROD.PROCLIB S1PG00 S1PG00 OK
PROC00 8 ROCKET.USER.PROCLIB S1PG00 S1PG00 OK
PROC00 9 SYS1.PROCLIB RZ203A RZ203A OK

```

Search For Member (SRCH) Panel

```

Display Filter View Print Options Search Help
-----
SDSF PARMLIB DISPLAY RS86 (ALL) EXT 58 LINE 1-10 (10)
COMMAND INPUT ==> srch isfprm* SCROLL ==> HALF
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*
NP DSNNAME Seq VolSer SysName SysLevel CrDate BlkSize
RSPLEXOG.PARMLIB.ZOS202 1 MCPG00 RS86 z/OS 02.03.00 2015.266 27920
RSPLEXOG.PARMLIB 2 MCPG00 RS86 z/OS 02.03.00 2015.142 27920
RSRTE.PARMLIB 3 R3P104 RS86 z/OS 02.03.00 2007.031 27920
ROCKET.USER.PARMLIB 4 S1PG00 RS86 z/OS 02.03.00 2016.196 27920
SYS1.PARMLIB 5 RZ203A RS86 z/OS 02.03.00 2015.273 27920
RSPLEXOG.PARMLIB.ZOS202 1 MCPG00 RS88 z/OS 02.03.00 2015.266 27920
RSPLEXOG.PARMLIB 2 MCPG00 RS88 z/OS 02.03.00 2015.142 27920
RSRTE.PARMLIB 3 R3P104 RS88 z/OS 02.03.00 2007.031 27920
ROCKET.USER.PARMLIB 4 S1PG00 RS88 z/OS 02.03.00 2016.196 27920
SYS1.PARMLIB 5 RZ203A RS88 z/OS 02.03.00 2015.273 27920
  
```

Member name
pattern

```

Display Filter View Print Options Search Help
-----
SDSF SRCH DISPLAY ISFPRM* LINE 1-10 (10)
COMMAND INPUT ==> SCROLL ==> HALF
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*
ACTION=+-Extend,/-Show,/--Block,=-Repeat,SB-ISPFBrowse,SE-ISPFEdition
NP DSNNAME Seq VolSer Status DSN Org BlkSize Extent S
RSPLEXOG.PARMLIB.ZOS202 1 MCPG00 NOT FOUND PO 27920 1 N
RSPLEXOG.PARMLIB 2 MCPG00 NOT FOUND PO 27920 10 N
RSRTE.PARMLIB 3 R3P104 FOUND PO 27920 1 Y
ROCKET.USER.PARMLIB 4 S1PG00 FOUND PO 27920 16 Y
SYS1.PARMLIB 5 RZ203A NOT FOUND PO 27920 1 N
RSPLEXOG.PARMLIB.ZOS202 1 MCPG00 NOT FOUND PO 27920 1 N
RSPLEXOG.PARMLIB 2 MCPG00 NOT FOUND PO 27920 10 N
RSRTE.PARMLIB 3 R3P104 FOUND PO 27920 1 Y
ROCKET.USER.PARMLIB 4 S1PG00 FOUND PO 27920 16 Y
SYS1.PARMLIB 5 RZ203A NOT FOUND PO 27920 1 N
  
```

Pattern found (row
highlighted)

Search for Member (SRCH) Panel

```

Menu  Functions  Utilities  Help
-----
EDIT  RSRTE.PARMLIB                      Row 0000001 of
Command ==>                               Scroll ==
Name      Prompt      Size    Created      Changed
. ISFPRMR@      352    2014/03/10    2014/03/10 08:20:45
s ISFPRMRS      341    2011/04/15    2014/03/10 08:29:32
. ISFPRMRX      350    2003/11/04    2009/11/19 05:19:35
. ISFPRM11      277    2007/02/01    2007/02/01 08:39:59
**End**

File  Edit  Edit_Settings  Menu  Utilities  Compilers  Test  Help
-----
EDIT  RSRTE.PARMLIB(ISFPRMRS) - 01.05      Columns 00001 00072
Command ==>                               Scroll ==> PAGE
000016 /*****
000017 /*
000018 /*
000019 /*      Sample Initialization Statements
000020 /*
000021 /*      This is a sample SDSF parameter definition.  It is equivalent
000022 /*      to the macros supplied in ISFPARMS.
000023 /*
000024 /*      The following are general syntax rules for coding the SDSF
000025 /*      initialization statements.  Refer to the SDSF Customization
000026 /*      and Security manual for more detail.
000027 /*
000028 /*      - Statements are free form, and can appear in any column 1-72.
000029 /*      An optional sequence number may be coded in columns 73-80,
000030 /*      but it is not used by SDSF.
000031 /*
000032 /*      - A statement can span any number of lines.  Use a trailing
000033 /*      comma to indicate that a statement is continued.

```

ISPF displays member list
when pattern matches multiple
members

Select member to edit.
You can also use SB on
SRCH panel to browse.

System (SYS) Panel

```
Display Filter View Print Options Search Help
-----
SDSF SYS DISPLAY RS86 (ALL) LINE 1-2 (2)
COMMAND INPUT ==> SCROLL ==> HALF
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*
ACTION=+-Extend,/-Show,/-Block,%-RunExec,=-Repeat,D-DisplayIPL,DAA-DisplayAll,
ACTION=DAL-DisplayList,DALO-DisplayAlloc,DC-DisplayConsoles,DCEE-DisplayLE,
ACTION=DD-DisplayDump,DEM-DisplayEMCS,DG-DisplayGRS,DI-DisplayIOS,
ACTION=DIQP-DisplayIQP,DLL-DisplayLLA,DLO-DisplayLogger,DLR-DisplayLogrec,
ACTION=DM-DisplayConfig,DMP-DisplayMPF,DO-DisplayOMVS,DP-DisplayProd,
ACTION=DPCD-DisplayPCIEDev,DPCI-DisplayPCIE,DSF-DisplaySMF,DSL-DisplaySlip,
ACTION=DSM-DisplaySMS,DSY-DisplaySymbols,DT-DisplayTime,DTO-DisplayTSOptions,
ACTION=DTR-DisplayTrace,DTS-DisplayTSUsers,DW-DisplayWLM,DX-DisplaySysplex
NP  SYSNAME SysLevel CPU% SIO Aux% CSA% SQA% ECSA% ESQA% UIC Spool%
RS86 z/OS 02.03 38 0 0 15 20 21 93 65535 9
RS88 z/OS 02.03 62 0 0 14 20 21 91 65535 9
```

```
Display Filter View Print Options Search Help
-----
SDSF SYS DISPLAY RS86 (ALL) LINE 1-2 (2)
COMMAND INPUT ==> 1 cads% SCROLL ==> HALF
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*
NP  SYSNAME CADS% PageRate Real RealAFC RealAFCB Fix% FixB% MaxASID Free
RS86 42 0 1276155 752380 3720 4 1 605
RS88 42 0 1276159 973581 3687 4 1 605
```

```
Display Filter View Print Options Search Help
-----
SDSF SYS DISPLAY RS86 (ALL) LINE 1-2 (2)
COMMAND INPUT ==> 1 free SCROLL ==> HALF
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*
NP  SYSNAME FreeASID BadASID STC TSU Job WTOR Sysplex LPAR VMUs
RS86 481 2 70 1 3 2 RSPLEXOG RSPLEXOG RS86
RS88 485 2 66 1 0 2 RSPLEXOG RSPLEXOG RS88
```

*Tip: use locate (l) command
to position to first column
that matches*

System (SYS) Panel

```
Display Filter View Print Options Search Help
-----
SDSF SYS DISPLAY RS86 (ALL) LINE 1-2 (2)
COMMAND INPUT ==> SCROLL ==> HALF
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*
NP SYSNAME VMUser JES JESNode SMF IPLVol IPLUnit IPLDate IP
  RS86 RS86 JES2 N1 RS86 RZ203A 6501 06/12/2017 08:38:40 CO
  RS88 RS88 JES2 N1 RS88 RZ203A 6501 06/12/2017 08:10:35 CO
```

```
Display Filter View Print Options Search Help
-----
SDSF SYS DISPLAY RS86 (ALL) LINE 1-2 (2)
COMMAND INPUT ==> SCROLL ==> HALF
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*
NP SYSNAME IPLUnit IPLDate IPLType IPLDays LoadParm CTVVERID
  RS86 6501 06/12/2017 08:38:40 COLD 8 6132SCM1 RPD7FXP7 09M
  RS88 6501 06/12/2017 08:10:35 COLD 8 6132SCM1 RPD7FXP7 09M
```

```
Display Filter View Print Options Search Help
-----
SDSF SYS DISPLAY RS86 (ALL) LINE 1-2 (2)
COMMAND INPUT ==> SCROLL ==> HALF
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*
NP SYSNAME LoadDSName LoadUnit IEASYS IEASYM GRS HW
  RS86 SYS1.IPLPARM 6132 RS RS STAR Z1
  RS88 SYS1.IPLPARM 6132 RS RS STAR Z1
```

```
Display Filter View Print Options Search Help
-----
SDSF SYS DISPLAY RS86 (ALL) LINE 1-2 (2)
COMMAND INPUT ==> SCROLL ==> HALF
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*
NP SYSNAME HWName CPC MSU SysMSU AvgMSU
  RS86 Z13 002964.N30.IBM.02.00000009F6C7 1496 332
  RS88 Z13 002964.N30.IBM.02.00000009F6C7 1496 332
```

System (SYS) Panel

```
Display Filter View Print Options Search Help
-----
SDSF SYS DISPLAY RS86 (ALL) LINE 1-2 (2)
COMMAND INPUT ==> SCROLL ==> HALF
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*
NP  SYSNAME #CPU #ZAAP #ZIIP OSConfig EDT NUCLST IEANUC IODFDSName IODFDate
    RS86      2    0    0 OS390VM VM 01 SYS1.IODF99 05/04/201
    RS88      2    0    0 OS390VM VM 01 SYS1.IODF99 05/04/201
```

```
Display Filter View Print Options Search Help
-----
SDSF SYS DISPLAY RS86 (ALL) LINE 1-2 (2)
COMMAND INPUT ==> SCROLL ==> HALF
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*
NP  SYSNAME CatDSName CatVol MLA CatType NetID SSCP
    RS86 CATALOG.RSPLEX0G.MASTER MCPG00 1 ICF ROCKNET1 ROCKNET1.RS86
    RS88 CATALOG.RSPLEX0G.MASTER MCPG00 1 ICF ROCKNET1 ROCKNET1.RS88
```

```
Display Filter View Print Options Search Help
-----
SDSF SYS DISPLAY RS86 (ALL) LINE 1-2 (2)
COMMAND INPUT ==> SCROLL ==> HALF
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*
NP  SYSNAME IPLCurr IODFUnit IODFCurr
    RS86 6501 6132 6132
    RS88 6501 6132 6132
```

*Tip: use arrange command to
change column width:
arr iodfds 10*

Added in
V2R3

Dynamic Exits (DYNX) Panel

Display Filter View Print Options Search Help								
SDSF DYNX DISPLAY RS86		RS86		LINE 12-33 (120)				
COMMAND INPUT ==>		SCROLL ==> HALF						
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=								
ACTION=+-Extend,/-Show,/-Block,%-RunExec,=-Repeat,A-Activate,D-Display,								
ACTION=DA-DisplayAll,DAI-DisplayAllImp,DD-DisplayDiag,DI-DisplayInstallation,								
ACTION=DNP-DisplayNotProgram,DP-DisplayProgram,H-Inactivate,P-Delete,								
ACTION=PF-DeleteForce,U-Undefined								
NP	EXITNAME	Seq	ModName	Active	FastPath	ModEPA	LoadPt	ModLen
	CSVDYLPA	1	IGGODLPA	YES	YES	84B9C000	00000000	00000000
	CSVDYLPA	2	CELSDLPA	YES	YES	8375A7E8	00000000	00000000
	CSVDYLPA	3	GXLINDLX	YES	YES	83447648	00000000	00000000
	CSVDYLPA	4	IKJXDLPA	YES	YES	83A1FB88	00000000	00000000
	CSVDYLPA	5	HASJES2L	YES	YES	80C1BEC0	00000000	00000000
	CSVDYNEX	1	ISGGCSXT	YES	NO	85511040	00000000	00000000
	CSVDYNEX	2	CSVLLDYX	YES	NO	91AF91D8	11AF91D8	00000100
	CSVDYNEX	3	CNZM1DYX	YES	NO	83800068	00000000	00000000
	CSVDYNEX	4	CSFDYNEX	YES	NO	914BD010	114BD010	00000078
	CSVFETCH			NO	YES	00000000	00000000	00000000
	CSVLLIX1	1	MXILIX1	YES	YES	8F96A000	00000000	00000000
	CSVLLIX2			NO	YES	00000000	00000000	00000000
	EZAFCCMD			NO	NO	00000000	00000000	00000000
	EZAFCREP			NO	NO	00000000	00000000	00000000
	HASP.\$EXITO			NO	YES	00000000	00000000	00000000
	HZSADDCHECK	1	IARHCADC	YES	NO	91598460	11598460	00000678
	HZSADDCHECK	2	IGVHCADC	YES	NO	91593178	11593178	000009E0
	HZSADDCHECK	3	ILRHCADC	YES	NO	91542840	11542840	000006C0
	HZSADDCHECK	4	IEATCADC	YES	NO	9165D7F8	1165D7F8	000001C0
	HZSADDCHECK	5	IEAVTSHI	YES	NO	91542088	11542088	000007B8
	HZSADDCHECK	6	ADYHCADC	YES	NO	9165D490	1165D490	00000368
	HZSADDCHECK	7	BLWHCADC	YES	NO	915981F0	115981F0	00000270

Exit name

Implementing
module name

Call sequence

Enqueues (ENQ) Panel

Display Filter View Print Options Search Help

SDSF ENQ DISPLAY RS86 RS86 MAJ SYSDSN LINE 61-85 (157)
COMMAND INPUT ==> enq syszdsn rs* SCROLL ==> HALF
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=
ACTION=+-Extend,/-Show,/-Block,/-RunExec,=-Repeat,D-Display

NP	MINOR	Major	Req	JobName
	RSPLEX0G.OMVS.CDS01	SYSDSN	SHR	XCFAS
	RSPLEX0G.TCPPARMS	SYSDSN	SHR	PORTMAP
	RSPLEX0G.TCPPARMS	SYSDSN	SHR	TN3270
	RSPLEX0G.TCPPARMS	SYSDSN	SHR	MXITCP
	RSPLEX0G.TCPPARMS	SYSDSN	SHR	SNMPQE
	RSPLEX0G.TCPPARMS	SYSDSN	SHR	TCPIP
	RSPLEX0G.VTAMLIB	SYSDSN	SHR	TCPIP
	RSPLEX0G.VTAMLIB	SYSDSN	SHR	VTAM
	RSPLEX0G.VTAMLIB	SYSDSN	SHR	TN3270
	RSPLEX0G.VTAMLST	SYSDSN	SHR	VTAM
	RSPLEX0G.WLM.CDS01	SYSDSN	SHR	XCFAS
	RSPLEX0G.WLM.CDS02	SYSDSN	SHR	XCFAS
	RSPLEX0G.XCF.CDS01	SYSDSN	SHR	XCFAS
	RSPLEX0G.XCF.CDS02	SYSDSN	SHR	XCFAS
	RSPROD.RS86.HZSPDATA	SYSDSN	EXC	HZSPROC
	RSQA.HSF.PRINT.SIMULATR.LOAD	SYSDSN	SHR	XCFAS
	RSRTE.TBMPORT.HES	SYSDSN	SHR	OMVS
	RSRTE.JVA6031	SYSDSN	SHR	ZFS
	RSRTE.JVA6064	SYSDSN	SHR	ZFS
	RSRTE.JVA6131	SYSDSN	SHR	ZFS
	RSRTE.JVA6164	SYSDSN	SHR	ZFS
	RSRTE.JVA7031	SYSDSN	SHR	ZFS
	RSRTE.JVA7064	SYSDSN	SHR	ZFS
	RSRTE.JVA7131	SYSDSN	SHR	ZFS
	RSRTE.JVA7164	SYSDSN	SHR	ZFS

Major name pattern
(default SYSDSN)

System name pattern
(default local)

Owned and exclusive highlighted

Enqueue Contention (ENQC) Panel

```

Display Filter View Print Options Search Help
-----
SDSF ENQ DISPLAY RS86 CONTENTION LINE 1-3 (3)
COMMAND INPUT ===> SCROLL ===> HALF
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*
ACTION=+-Extend,-/-Show,/-Block,%-RunExec,=-Repeat,D-Display
NP MINOR
TS5485.XX.DATA
TS5485.XX.DATA
TS5485.XX.DATA
Major Req JobName
SYSDSN EXC TS5485W
SYSDSN EXC TS5485W1
SYSDSN EXC TS5485W2
    
```

All major names for all systems shown

Owner is highlighted

Request type (EXC or SHR)

Contention found when at least one waiter for the resource

System Symbols (SYM) Panel

Display Filter View Print Options Search Help

DSF SYMBOL DISPLAY RS86 (ALL) LINE 1-25 (106)
OMMAND INPUT ==> SCROLL ==> HALF

REFIX=* DEST=(ALL) OWNER=* SYSNAME=*
CTION=+-Extend,/-Show,/--Block,%-RunExec,=-Repeat,D-Display,DL-DisplayLong

P	SYMBOL	Value	Type	SysName	SysLevel
	&DAY.	22	DYNAMIC	RS86	Z/OS 02.03.00 HBB77B0
	&HHMMSS.	183153	DYNAMIC	RS86	Z/OS 02.03.00 HBB77B0
	&HLQPLEX.	RSPLEX0G	STATIC	RS86	Z/OS 02.03.00 HBB77B0
	&HR.	18	DYNAMIC	RS86	Z/OS 02.03.00 HBB77B0
	&HSMHOST.	6	STATIC	RS86	Z/OS 02.03.00 HBB77B0
	&HSMPRI.	YES	STATIC	RS86	Z/OS 02.03.00 HBB77B0
	&JDAY.	173	DYNAMIC	RS86	Z/OS 02.03.00 HBB77B0
	&JOBNAME.	SDSFAUX	DYNAMIC	RS86	Z/OS 02.03.00 HBB77B0
	&LDAY.	22	DYNAMIC	RS86	Z/OS 02.03.00 HBB77B0
	&LHHMMSS.	143153	DYNAMIC	RS86	Z/OS 02.03.00 HBB77B0
	&LHR.	14	DYNAMIC	RS86	Z/OS 02.03.00 HBB77B0
	&LJDAY.	173	DYNAMIC	RS86	Z/OS 02.03.00 HBB77B0
	&LMIN.	31	DYNAMIC	RS86	Z/OS 02.03.00 HBB77B0
	&LMON.	06	DYNAMIC	RS86	Z/OS 02.03.00 HBB77B0
	&LSEC.	53	DYNAMIC	RS86	Z/OS 02.03.00 HBB77B0
	&LWDAY.	THU	DYNAMIC	RS86	Z/OS 02.03.00 HBB77B0
	&LYR2.	17	DYNAMIC	RS86	Z/OS 02.03.00 HBB77B0
	&LYR4.	2017	DYNAMIC	RS86	Z/OS 02.03.00 HBB77B0
	&LYYMDD.	170622	DYNAMIC	RS86	Z/OS 02.03.00 HBB77B0
	&MIN.	31	DYNAMIC	RS86	Z/OS 02.03.00 HBB77B0
	&MON.	06	DYNAMIC	RS86	Z/OS 02.03.00 HBB77B0
	&NUMSYS.	2	STATIC	RS86	Z/OS 02.03.00 HBB77B0
	&PLEXNAME.	RSPLEX0G	STATIC	RS86	Z/OS 02.03.00 HBB77B0
	&RTHLQ.	RSRTE	STATIC	RS86	Z/OS 02.03.00 HBB77B0
	&SEC.	53	DYNAMIC	RS86	Z/OS 02.03.00 HBB77B0

Current value for
dynamic symbols



SDSF V2R3 USABILITY ENHANCEMENTS

SDSF V2R3 Usability Enhancements

- Scrollable main panel
- Reorganized Options pull-down
- Fixed field point-and-shoot
- Show column values (/ action character)

Scrollable Main Panel

Display Filter View Print Options Search Help				
SDSF MENU V2R3M0 RSPLEX0G RS86		LINE 1-26 (49)		
COMMAND INPUT ==>		SCROLL ==> HALF		
PREFIX=*	DEST=(ALL)	OWNER=*	SYSNAME=*	
NP	NAME	Description	Group	Status
DA		Active users	Jobs	
I		Input Queue	Jobs	
O		Output Queue	Output	
H		Held output Queue	Output	
ST		Status of jobs	Jobs	
JG		Job groups	JES	
SYM		System symbols	System	
LOG		System log	Log	
SR		System requests	Log	
MAS		Members in the MAS	JES	
JC		Job classes	JES	
SE		Scheduling environments	WLM	
RES		WLM resources	WLM	
ENC		Enclaves	WLM	
PS		Processes	OMVS	
SYS		System information	System	
ENQ		Enqueues	System	
DYNX		Dynamic exits	System	
AS		Address space memory	Jobs	
INIT		Initiators	JES	
PR		Printers	JES	
PUN		Punches	JES	
RDR		Readers	JES	
LINE		Lines	Network	
NODE		Nodes	Network	
SO		Spool offload	JES	

SDSF release, sysplex
name, system name

Point-and-shoot to select
(by default turquoise)

Classification (group name)

Scrollable Main Panel

Display Filter View Print Options Search Help

SDSF MENU V2R3M0 RSPLEX0G RS86 LINE 1-26 (49)
COMMAND INPUT ==> sort name SCROLL ==> HALF
PREFIX=* DEST=(ALL) OWNER=* SORT=NAME/A SYSNAME=*
NP NAME Description Group Status

APF	APF data sets	System	
AS	Address space memory	Jobs	
CFC	CF Connections	Sysplex	
CFS	CF Structures	Sysplex	
CK	Health checker	System	
CSR	Common storage remaining	Memory	
DA	Active users	Jobs	
DEV	Device activity	Devices	
DYNX	Dynamic exits	System	
ENC	Enclaves	WLM	
ENQ	Enqueues	System	
FS	File systems	OMVS	
GT	Generic tracker	System	
H	Held output Queue	Output	
I	Input Queue	Jobs	
INIT	Initiators	JES	
JC	Job classes	JES	
JG	Job groups	JES	
LINE	Lines	Network	
LNK	Link list data sets	System	
LOG	System log	Log	
LPA	Link pack data sets	System	
MAS	Members in the MAS	JES	
NA	Network activity	Network	
NC	Network connections	Network	
NODE	Nodes	Network	

Sort by name

Select using action character

Scrollable Main Panel

```

Display Filter View Print Options Search Help
-----
SDSF MENU V2R3M0 RSPLEX0G RS86 LINE 1-4 (4)
COMMAND INPUT ==> s l* SCROLL ==> HALF
PREFIX=* DEST=(ALL) OWNER=* SORT=NAME/A SYSNAME=*
NP NAME Description Group Status
LINE Lines Network
LNK Link list data sets System
LOG System log Log
LPA Link pack data sets System
  
```

Fast path select: list all panels that start with "l"

Tip: Fast path select (s command) can be used on any tabular panel and matches fixed field

Scrollable Main Panel

```
Display Filter View Print Options Search Help
-----
SDSF MENU V2R3M0 RSPLEX0G RS86 LINE 1-11 (11)
COMMAND INPUT ==> s * jes SCROLL ==> HALF
PREFIX=* DEST=(ALL) OWNER=* SORT=NAME/A SYSNAME=*
NP NAME Description Group Status
INIT Initiators JES
JC Job classes JES
JG Job groups JES
MAS Members in the MAS JES
PR Printers JES
PROC Proclib data sets JES
PUN Punches JES
RDR Readers JES
RM Resource monitor JES
SO Spool offload JES
SP Spool volumes JES
```

Matches all panels in
"JES" group

Tip: use s (blank) to reset fast path select

Scrollable Main Panel

```
Display Filter View Print Options Search Help
-----
SDSF MENU V2R3M0      RSPLEX0G RS86      LINE 1-26 (50)
COMMAND INPUT ==> set menu all          SCROLL ==> HALF
PREFIX=* DEST=(ALL) OWNER=* SORT=NAME/A SYSNAME=*
NP  NAME      Description      Group      Status
APF  APF data sets      System
AS   Address space memory  Jobs
CFC  CF Connections     Sysplex
CFS  CF Structures      Sysplex
CK   Health checker      System
CSR  Common storage remaining Memory
DA   Active users        Jobs
DEV  Device activity     Devices
DYNX Dynamic exits        System
ENC  Enclaves            WLM
ENQ  Enqueues            System
FS   File systems        OMVS
GT   Generic tracker     System
H    Held output Queue  Output
I    Input Queue         Jobs
INIT Initiators          JES
JC   Job classes         JES
JG   Job groups          JES
JO   Job zero            JES
LINE Lines               Network
LNK  Link list data sets System
LOG  System log          Log
LPA  Link pack data sets System
MAS  Members in the MAS  JES
NA   Network activity    Network
NC   Network connections Network
```

Use set menu command to show/hide available options

JES3 environment only

Scrollable Main Panel

```
Display Filter View Print Options Search Help
-----
SDSF MENU V2R3M0      RSPLEX0G RS86      LINE 1-26 (49)
COMMAND INPUT ==> set menu hide          SCROLL ==> HALF
PREFIX=* DEST=(ALL) OWNER=* SORT=NAME/A SYSNAME=*
NP  NAME      Description      Group      Status
APF  APF data sets      System
AS   Address space memory  Jobs
CFC  CF Connections     Sysplex
CFS  CF Structures      Sysplex
CK   Health checker      System
CSR  Common storage remaining Memory
DA   Active users        Jobs
DEV  Device activity     Devices
DYNX Dynamic exits        System
ENC  Enclaves            WLM
ENQ  Enqueues            System
FS   File systems        OMVS
GT   Generic tracker     System
H    Held output Queue  Output
I    Input Queue         Jobs
INIT Initiators          JES
JC   Job classes         JES
JG   Job groups          JES
LINE Lines              Network
LNK  Link list data sets System
LOG  System log          Log
LPA  Link pack data sets System
MAS  Members in the MAS  JES
NA   Network activity    Network
NC   Network connections Network
NODE Nodes              Network
```

J0 option not shown
since not applicable

*Tip: set command settings
saved in ISPF profile*

Reorganized Options Pull-Down

Display Filter View Print Options Search Help

SDSF MENU V2R3M0 RSPLEX0G
COMMAND INPUT ==>
PREFIX=* DEST=(ALL) OWNER=*
NP NAME Description

APF	APF data sets	
AS	Address space memory	Jobs
CK	Health checker	System
CSR	Common storage remaining	Memory
DA	Active users	Jobs
DEV	Device activity	Devices
DYNX	Dynamic exits	System
ENC	Enclaves	WLM
ENQ	Enqueues	System
FS	File systems	OMVS
GT	Generic tracker	System
H	Held output Queue	Output

(50)
ROLL ==> HALF

1. General...
2. Browse and Print...
3. Screen...
4. Console and Response...

Options are grouped

Reorganized Options Pull-Down

Display Filter View Print Options Search Help

SDSF MENU V2R3M0 RSPLEXOG (49)
 COMMAND INPUT ==> ROLL ==> HALF
 PREFIX=* DEST=(ALL) OWNER=*

NP	NAME	Description
APF	APF	APF data sets
AS	AS	Address space memory
CFC	CFC	CF Connections
CFS	CFS	CF Structures
CK	CK	Health checker
CSR	CSR	Common storage remaining
DA	DA	Active users
DEV	DEV	Device activity
DYNX	DYNX	Dynamic exits
ENC	ENC	Enclaves
ENQ	ENQ	Enqueues
FS	FS	File systems
GT	GT	Generic tracker
H	H	Held output Queue

3 1. General...
 2. Browse and Print...
 3. Screen...
 4. Console and Response...

Select a group

Reorganized Options Pull-Down

```
Display Filter View Print Options Search Help
SDSF MENU V2R3M0 RSPLE
COMMAND INPUT ==>
PREFIX=* DEST=(ALL) OWN
NP NAME Description
APF APF data se
AS Address spa
CFC CF Connecti
CFS CF Structur
CK Health chec
CSR Common stor
DA Active user
DEV Device acti
DYNX Dynamic exi
ENC Enclaves
ENQ Enqueues
FS File system
GT Generic tra
H Held output
I Input Queue
```

Screen Options

Option ==> _____

- 1 Set action character display...
- 2 Set cursor option...
- 3 Change cursor sort to OFF
- 4 Set date format...
- 5 Set display values...
- 6 Change row numbering to ON
- 7 Set screen characteristics...
- 8 Change show menu items to ALL
- 9 Change fixed field point-and-shoot to OFF

F1=Help F12=Cancel

Jobs

Toggles show the value to be set

Tip: use the pull-down in case you can't remember the command!

Fixed Field Point-and-Shoot

- Fixed field on several panels enabled for point-and-shoot (ISPF only)
- Convenient way to navigate to secondary panel
- Control with SET FFPS ON | OFF command

Panel	Target
DA,I,ST,O,H,J0	JDS
JG	Job Dependencies
JC	ST
SE	RES
AS	Job Memory
CK	CKH
SMSG	SMSV
JDS	Output data set
SRCH	ISPF browse

Fixed Field Point-and-Shoot

Display Filter View Print Options Search Help

SDSF STATUS DISPLAY ALL CLASSES LINE 1-26 (301)
COMMAND INPUT ==> SCROLL ==> HALF

PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*

NP	JOBNAME	JobID	Owner	Prty	Queue	C	Pos	SAff	ASys	Status
	JOB8	JOB03289	TS5485	9	EXECUTION	A		RS86		HOLD
	TS5485W	JOB08801	TS5485	9	EXECUTION	A		RS86		
	TS5485W1	JOB08802	TS5485	9	EXECUTION	A		RS86		
	TS5485W2	JOB08803	TS5485	9	EXECUTION	A		RS86		
	PDSCOT	TSU09005	PDSCOT	15	EXECUTION			RS88	RS88	
	TS5485	TSU09006	TS5485	15	EXECUTION			RS86	RS86	
	BPXAS	STC08485	BPXAS	15	EXECUTION			RS88	RS88	
	VTAM	STC08486	VTAM	15	EXECUTION			RS88	RS88	
	HZSPROC	STC08489	HZSPROC	15	EXECUTION			RS88	RS88	
	SYSLOG	STC08491	+MASTER+	15	EXECUTION			RS88	RS88	
	INIT	STC08492	INIT	15	EXECUTION			RS88	RS88	
	INIT	STC08493	INIT	15	EXECUTION			RS88	RS88	
	INIT	STC08494	INIT	15	EXECUTION			RS88	RS88	
	INIT	STC08495	INIT	15	EXECUTION			RS88	RS88	
	INIT	STC08496	INIT	15	EXECUTION			RS88	RS88	
	INIT	STC08497	INIT	15	EXECUTION			RS88	RS88	
	INIT	STC08498	INIT	15	EXECUTION			RS88	RS88	

Point-and-Shoot
enabled (turquoise)

Put cursor within field
and press enter

*Tip: change point-and-shoot attributes
using CUAATTR command*

Fixed Field Point-and-Shoot

```

Display Filter View Print Options Search Help
-----
SDSF JOB DATA SET DISPLAY - JOB TS5485W (JOB08801) LINE 1-3 (3)
COMMAND INPUT ==>
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*
NP DDNAME StepName ProcStep DSID Owner C Dest Rec-Cnt Page
   JESMSG LG JES2 2 TS5485 K 4
   JESJCL JES2 3 TS5485 K 17
   JESYSMSG JES2 4 TS5485 K 2
  
```

Put cursor here and
press enter

```

Display Filter View Print Options Search Help
-----
SDSF OUTPUT DISPLAY TS5485W JOB08801 DSID 2 LINE 0 COLUMNS 02- 81
COMMAND INPUT ==>
***** TOP OF DATA *****
      JES2 JOB LOG -- SYSTEM RS86 -- N

09.22.11 JOB08801 ---- WEDNESDAY, 14 JUN 2017 ----
09.22.11 JOB08801 IRR010I USERID TS5485 IS ASSIGNED TO THIS JOB.
09.22.12 JOB08801 ICH70001I TS5485 LAST ACCESS AT 09:19:48 ON WEDNESDAY, JUNE
09.22.12 JOB08801 $HASP373 TS5485W STARTED - INIT 1 - CLASS A - SYS
09.22.12 JOB08801 @0010 Reply any character to end.
***** BOTTOM OF DATA *****
  
```

Browse
data set

Show Columns Pop-Up

- New Show Columns pop-up
- Access with / (slash) action character (ISPF only)
- Displays all columns and their values in a scrollable pop-up
 - Long values split across multiple lines
 - Multiple column values shown on consecutive rows
- Especially useful on panel with many columns

```

Display Filter View Print Options Search Help
-----
SDSF LPA DISPLAY RS86 (ALL) EXT 96 LINE 1-25 (32)
COMMAND INPUT ==> SCROLL ==> HALF
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*
ACTION=+-Extend,/-Show,/-Block,%-RunExec,=-Repeat,SB-ISPFBrowse,SE-ISPFE
NP DSNAM Seq VolSer BlkSize Extent SMS APF LRecl DSOrg
   SYS1.LPALIB 1 RZ203A 32760 5 NO NO 0 PO
   RSRTE.LPALIB 2 R3P104 32760 10 YES NO 0 PO
  
```

Show Columns Pop-Up

```
Display Filter View Print Options Search Help
-----
SDSF HEALTH CHECKER DISPLAY (ALL)
COMMAND INPUT ==>
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*
NP NAME CheckOwner State Statu
   DMO_REFUCB IBMDMO ACTIVE(ENABLED) SUCCE
   DMO_TAPE_LIBRARY_INIT_ERRORS IBMDMO ACTIVE(ENABLED) SUCCE
   GRS_AUTHQLVL_SETTING IBMGRS ACTIVE(ENABLED) EXCEP
   GRS_CONVERT_RESERVES IBMGRS INACTIVE(ENABLED) INACT
   GRS_EXIT_PERFORMANCE IBMGRS ACTIVE(ENABLED) SUCCE
   GRS_GRSQ_SETTING IBMGRS ACTIVE(ENABLED) SUCCE
   GRS_MODE IBMGRS ACTIVE(ENABLED) SUCCE
   GRS_RNL_IGNORED_CONV IBMGRS ACTIVE(DISABLED) GLOBA
   GRS_SYNCHRES IBMGRS ACTIVE(DISABLED) GLOBA
   ICSF_COPROCESSOR_STATE_NEGCHANGE IBMICSF ACTIVE(ENABLED) SUCCE
   ICSF_DEPRECATED_SERV_WARNINGS IBMICSF ACTIVE(ENABLED) SUCCE
   ICSF_KEY_EXPIRATION IBMICSF ACTIVE(ENABLED) SUCCE
   ICSF_MASTER_KEY_CONSISTENCY IBMICSF ACTIVE(ENABLED) SUCCE
```

Enter / action
character

Show Columns Pop-Up

```
Command ==> Show Columns Row 15 to 36 of 39
Sort column with F5. Use Locate to position to column.
- All values - Column width
Column      ##  Value
WTOType     01  INFO
WTONum      01  0
NumCat      01  0
ExitName    01  ISGHCADC
ModName     01  ISGHCGRS
MsgName     01  ISGHCMSG
UserData    01  20050315
DefDate     01  20050315
Debug       01  OFF
Start-Date-Time 01  ***** N/A *****
Interval    01  ONETIME
NextSch-Date-Time 01  ***** N/A *****
Log-Date-Time 01  ***** N/A *****
Deleted-Date-Time 01  ***** N/A *****
ProcName    01  HZSPROC
TaskId      01  HZSPROC
Reason      01  If an entry in the RESERVE Conversion RNL is super
                sed by an entry in the SYSTEMS Exclusion RNL, it
                will be ignored.
ParmLen     01  0
SysLevel    01  z/OS 02.03.00 HBB77B0
SysName     01  RS86
```

Only non-null values are shown (option not selected)

Long values wrap

Show Columns Pop-Up

```
Command ==> 1 reason
Sort column with PS. Use Locate to position to column.
- All values      - Column width
Column           ##  Value
NumCat           01  5
Category         01  A
Category         02  B
Category         03  C
Category         04  D
Category         05  E
Category2        01  B
Category3        01  C
Category4        01  D
ExitName         01  ISGHCADC
ModName          01  ISGHCGRS
MsgName          01  ISGHCMSG
UserDate         01  20050315
DefDate          01  20050315
Debug            01  OFF
Start-Date-Time  01  ***** N/A *****
Interval         01  ONETIME
NextSch-Date-Time 01  ***** N/A *****
Log-Date-Time    01  ***** N/A *****
Deleted-Date-Time 01  ***** N/A *****
ProcName         01  HZSPROC
TaskId           01  HZSPROC
```

Use Locate command to position to a column

Column has multiple values

Value number

Show Columns Pop-Up

```

Command ==> _____ Show Columns Row 40 to 48 of 48

Sort column with F5. Use Locate to position to column.

_ All values      _ Column width

Column          ## Value
Reason          01 If an entry in the RESERVE Conversion RNL is super
                  sed by an entry in the SYSTEMS Exclusion RNL, it
                  will be ignored.
ParmLen         01 0
SysLevel        01 z/OS 02.03.00 HBB77B0
SysName         01 RS86
EInterval       01 SYSTEM
Verbose         01 NO
LogStream       01 HZS.HEALTH.CKR.LOG.RS86
***** Bottom of data *****

```

Panel positioned to column

Show Columns Pop-Up

Command ==> Show Columns Row 7 to 27 of 48

Sort column with F5. Use Locate to position to column.

— All values — Column width

<u>Column</u>	##	Value
Category3	01	C
Category4	01	D
CheckOwner	01	IBMGRS
Debug	01	OFF
DefDate	01	20050315
Deleted-Date-Time	01	***** N/A *****
Diag1	01	00000000
Diag2	01	00000000
ExcCount	01	0
ExitName	01	ISGHCADC
EInterval	01	SYSTEM
Fail	01	0
Global	01	YES
GlobalSys	01	RS88
Interval	01	ONETIME
Log-Date-Time	01	***** N/A *****
LogStream	01	HZS.HEALTH_CKR.LOG.RS86
ModifiedBy	01	MODIFY COMMAND
ModName	01	ISGHCGRS
MsgName	01	ISGHCMSG
NextSch-Date-Time	01	***** N/A *****

F1=Help F5=SortCol F7=Backward F8=Forward F12=Cancel

Press F5 to toggle sort by column
(heading underlined when sorted)



SDSF V2R3 NEW TABULAR PANELS

New Tabular Panels and Commands

- CF Connections (CFC)
- CF Structures (CFS)
- Device Activity (DEV)
- File Systems (FS)
- Generic Tracker (GT)
- Network Activity (NA)
- SMS Groups (SMSG)
- SMS Volumes (SMSV)
- Subsystems (SSI)
- Common Storage Remaining (CSR)
- Virtual Storage Map (VMAP)
- Job modules (CDEs – JC action)
- Job Tasks (TCBs – JT action)

Device Activity Panel (DEV)

- DEV Command
 - Default shows all online DASD devices
 - Use DEV ACT to show only active devices
 - Sysplex wide using SYSNAME pattern
- Actions
 - Display device
 - Vary only
 - Vary offline

Device Activity Panel (DEV)

Display Filter View Print Options Search Help

SDSF DEVICE ACTIVITY RS86 (ALL) LINE 1-21 (186)
COMMAND INPUT ==> SCROLL ==> HALF

PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*
ACTION=+-Extend,/-Show,/-Block,%-RunExec,=-Repeat,D-Display,DA-DisplayAlloc,
ACTION=DI-DisplayIPL,DSP-DevServPath,DSQD-DevServQDasd,DSQP-DevServQPath,
ACTION=DSS-DevServSMS,V-VaryOn,VF-VaryOff

NP	VOLSER	Unit	StorGrp	IOIntens	QIntens	SSCH	Response	IOSQ	Connect
	DMPG00	649C	DMPG1	0.000	0.000	0.000	0.000	0.000	0.000
	D1XF00	D190		0.306	0.025	0.399	0.768	0.000	0.704
	D1XF01	D191		0.000	0.000	0.000	0.000	0.000	0.000
	D1XF02	D419		0.306	0.025	0.399	0.768	0.000	0.704
	D1XF03	D5B6		0.331	0.051	0.399	0.832	0.000	0.704
	HCP100	6132		0.000	0.000	0.000	0.000	0.000	0.000
	HFBG00	647E	HFBG1	0.050	0.025	0.199	0.256	0.000	0.128
	JSPG00	6372		0.536	0.076	0.798	0.672	0.000	0.576
	JSPG50	6227		0.000	0.000	0.000	0.000	0.000	0.000
	JSPG51	6380		0.000	0.000	0.000	0.000	0.000	0.000
	JSPG60	6327		0.000	0.000	0.000	0.000	0.000	0.000
	JSPG70	632A		0.000	0.000	0.000	0.000	0.000	0.000
	JSPG71	6429		0.306	0.051	0.399	0.768	0.000	0.640
	JSPG80	632B		0.000	0.000	0.000	0.000	0.000	0.000
	J3PG00	64C2		0.000	0.000	0.000	0.000	0.000	0.000
	J3PG50	60B9		0.000	0.000	0.000	0.000	0.000	0.000
	J3PG51	6381		0.000	0.000	0.000	0.000	0.000	0.000

Active devices are highlighted

Device Activity Panel (DEV)

Command ==> Show Columns Row 1 to 16 of 16

Sort column with F5. Use Locate to position to column.

/ All values _ Column width

Column	##	Value
VOLSER	01	D1XF00
Unit	01	D190
StorGrp	01	
IOIntens	01	0.306
QIntens	01	0.025
SSCH	01	0.399
Response	01	0.768
IOSQ	01	0.000
Connect	01	0.704
Disc	01	0.000
Pending	01	0.064
Util%	01	0.02
Resv%	01	0.00
PAVNum	01	1
SysName	01	RS86
SysLevel	01	z/OS 02.03.00 HBB77B0

***** Bottom of data *****

Network Activity Panel (NA)

- NA Command
 - Shows all network (TCP/IP) activity in system (all stacks)
 - Sysplex wide using SYSNAME pattern
- Actions
 - Display connection information

Network Activity Panel (NA)

Display Filter View Print Options Search Help

SDSF NETWORK ACTIVITY **RS86** **(ALL)** LINE 1-20 (42)
COMMAND INPUT ==> SCROLL ==> HALF

PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*
ACTION=+-Extend,/-Show,/-Block,%-RunExec,=-Repeat,DA-DisplayAll,
ACTION=DAL-DisplayAllFmtL,DB-DisplayByteInfo,DBL-DisplayByteInfoFmtL,
ACTION=DN-DisplayConn,DNL-DisplayConnFmtL,DR-DisplayRoute,
ACTION=DRD-DisplayRouteDetail,DRDL-DisplayRouteDetailFmtL,DRL-DisplayRouteFmtL

NP	JOBNAME	Status	IPAddr	Port	InBufSz	OutBufSz	EXCP-Cnt
	BPXOINIT	LISTEN	0.0.0.0	10007	0	0	0
	CFZCIM	LISTEN	:::0	5988	0	0	0
	FTPD1	LISTEN	:::0	21	0	0	0
	INETD1	LISTEN	10.253.253.242	512	0	0	0
	INETD1	LISTEN	0.0.0.0	513	0	0	0
	INETD1	LISTEN	0.0.0.0	1023	0	0	0
	IZUSVR1	LISTEN	:::0	11443	0	0	0
	MXITCP	LISTEN	:::0	8361	0	0	0
	OSNMPD	LISTEN	:::0	1026	0	0	0
	OSNMPD	UDP	::FFFF:172.16.37.132	50017	0	0	349776
	PORTMAP	UDP	0.0.0.0	0	0	0	0
	PORTMAP	LISTEN	0.0.0.0	111	0	0	0
	SNMPQE	UDP	0.0.0.0	0	0	0	0
	SNMPQE	UDP	0.0.0.0	0	0	0	0
	SNMPQE	LISTEN	0.0.0.0	1024	0	0	0
	SSHD3	LISTEN	0.0.0.0	22	0	0	0
	SSHD3	LISTEN	:::0	22	0	0	0
	SYSLOGD	UDP	0.0.0.0	0	0	0	0
	TN3270	LISTEN	:::0	23	0	0	0
	TN3270	ESTABLSH	::FFFF:10.5.30.68	51035	65536	65536	15

Rows not in listen status highlighted

Tip: header shows system you are logged on to and systems being shown (sysname pattern)

File Systems Panel (FS)

- FS Command
 - Shows all OMVS file systems used by the system
 - Sysplex wide using SYSNAME pattern
- Actions
 - Display file system information

File Systems Panel (FS)

```
Display Filter View Print Options Search Help
-----
SDSF FILE SYSTEM DISPLAY RS86 (ALL) LINE 1-24 (80)
COMMAND INPUT ==> SCROLL ==> HALF
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*
ACTION=+-Extend,/-Show,/-Block,%-RunExec,=-Repeat,D-Display,DA-DisplayAll,
ACTION=DE-DisplayException
NP DEVICE Path Type Mode Owner Name
1 / HFS RDWR RS86 RSPLEXO
8 /proj AUTOMNT RDWR RS88 *AMD/pr
16 /rsetc/ssh ZFS READ RS88 RSRTE.S
9 /rsopt AUTOMNT RDWR RS88 *AMD/rs
10 /rsusr AUTOMNT RDWR RS88 *AMD/rs
41 /rsusr/ibmport HFS READ RS86 RSRTE.I
17 /rsusr/java ZFS READ RS88 RSRTE.M
18 /rsusr/java/IBM/J6.0 ZFS READ RS88 RSRTE.J
19 /rsusr/java/IBM/J6.0_64 ZFS READ RS88 RSRTE.J
20 /rsusr/java/IBM/J6.01 ZFS READ RS88 RSRTE.J
21 /rsusr/java/IBM/J6.01_64 ZFS READ RS88 RSRTE.J
22 /rsusr/java/IBM/J7.0 ZFS READ RS88 RSRTE.J
23 /rsusr/java/IBM/J7.0_64 ZFS READ RS88 RSRTE.J
24 /rsusr/java/IBM/J7.1 ZFS READ RS88 RSRTE.J
25 /rsusr/java/IBM/J7.1_64 ZFS READ RS88 RSRTE.J
26 /rsusr/java/IBM/J8.0 ZFS READ RS88 RSRTE.J
39 /rsusr/java/IBM/J8.0_64 ZFS READ RS86 RSRTE.J
11 /u AUTOMNT RDWR RS88 *AMD/u
35 /u/cfzsrv HFS RDWR RS86 RSHFSDE
```

RDWR file systems
are highlighted

Subsystem Panel (SSI)

- SSI Command
 - Shows all subsystems defined to system
 - Sysplex wide using SYSNAME pattern
- Actions
 - Display subsystem
 - Display opdata
 - Activate subsystem
 - Deactivate subsystem
 - Delete subsystem

Subsystem Panel (SSI)

Display Filter View Print Options Search Help										
SDSF SUBSYSTEM DISPLAY RS86 (ALL)				LINE 1-24 (30)						
COMMAND INPUT ==>				SCROLL ==> HALF						
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*										
ACTION=+-Extend,-/-Show,/-/-Block,%-RunExec,=-Repeat,A-Activate,D-Display,										
ACTION=DA-DisplayAll,DO-DisplayOpdata,H-Deactivate,PF-DeleteForce										
NP	NAME	NameX	Type	Status	Primary	Dynamic	SetSSI	EventRtn	SSCT	S
	AXR	C1E7D940		ACTIVE	NO	YES	NO	NO	00C32CA8	0
	DFRM	C4C6D9D4		INACTIVE	NO	YES	NO	NO	00C32B88	0
	HASP	C8C1E2D7	JES2	ACTIVE	NO	YES	NO	NO	00C32D08	0
	JESD	D1C5E2C4		INACTIVE	NO	YES	NO	NO	00C329A8	0
	JESS	D1C5E2E2		INACTIVE	NO	YES	NO	NO	00C32948	0
	JES2	D1C5E2F2	JES2	ACTIVE	YES	YES	NO	NO	00C328E8	0
	LOGR	D3D6C7D9		ACTIVE	NO	YES	NO	NO	00C32BE8	0
	MPFX	D4D7C6E7		INACTIVE	NO	YES	NO	NO	00C32C48	0
	MSTR	D4E2E3D9		ACTIVE	NO	NO	NO	NO	00C32828	0
	RACF	D9C1C3C6		ACTIVE	NO	YES	NO	NO	00C32A08	0
	RRS	D9D9E240		INACTIVE	NO	YES	NO	NO	00C32B28	0
	SMS	E2D4E240		ACTIVE	NO	YES	NO	NO	00C32888	0
	TNF	E3D5C640		INACTIVE	NO	YES	NO	NO	00C32A68	0
	VMCF	E5D4C3C6		INACTIVE	NO	YES	NO	NO	00C32AC8	0
	XDC.	E7C4C34B		ACTIVE	NO	NO	NO	NO	00C27F00	0

Active subsystems
are highlighted

Subsystem names may
contain hex characters

Subsystem Panel (SSI)

Command ==> Show Columns Row 1 to 24 of 24

Sort column with F5. Use Locate to position to column.

/ All values Column width

Column	##	Value
NAME	01	XDC.
NameX	01	E7C4C34B
Type	01	
Status	01	ACTIVE
Primary	01	NO
Dynamic	01	NO
SetSSI	01	NO
EventRtn	01	NO
SSCT	01	00C27F00
SSCTSUSE	01	00FAB5E8
SSCTSUS2	01	00000000
SSVT	01	00C27278
FC04	01	NO
FC08	01	YES
FC09	01	NO
FC10	01	NO
FC14	01	NO
FC50	01	YES
FC54	01	NO
FC58	01	NO
FC78	01	NO
Seq	01	15
SysName	01	RS86
SysLevel	01	z/OS 02.03.00 HBB77B0

***** Bottom of data *****

SMS Storage Groups Panel (SMSG)

- SMSG Command
 - Shows all SMS storage groups defined to system
 - Sysplex wide using SYSNAME pattern
- Actions
 - Display storage group
 - Enable, Disable, and Quiesce storage group
 - List all volumes in storage group
 - Accesses SMSV panel

SMS Storage Groups Panel (SMSG)

Display Filter View Print Options Search Help

SDSF STORAGE GROUP DISPLAY RS86 (ALL) LINE 1-18 (18)
COMMAND INPUT ==> SCROLL ==> HALF

PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*
ACTION=+-Extend,-/-Show,/-/-Block,-/-RunExec,-/-Repeat,D-Display,DL-DisplayList,
ACTION=L-ListVol,VD-VaryDisable,VQN-VaryDisableNew,VE-VaryEnable,
ACTION=VQ-VaryQuiesce,VQN-VaryQuiesceNew,VS-VarySpace

NP	NAME	Type	Status	TotalMB	Used%	FreeMB	LargestFre
	DB2G1	POOL	DISABLED	0	0.00	0	
	DMPG1	POOL	ENABLED	2707	84.44	421	
	EMCCXSG	POOL	ENABLED	0	0.00	0	
	HFSG1	POOL	ENABLED	2707	74.54	689	
	RCKG1	POOL	ENABLED	2707	26.63	1986	1
	SYSG1	POOL	ENABLED	2707	26.30	1995	1
	SYSG2	POOL	ENABLED	2707	88.80	303	
	TSOG1	POOL	ENABLED	2707	97.56	66	
	WRKG1	POOL	ENABLED	2707	0.77	2686	2
	DB2G1	POOL	ENABLED	0	0.00	0	
	DMPG1	POOL	ENABLED	2707	84.44	421	
	EMCCXSG	POOL	ENABLED	0	0.00	0	
	HFSG1	POOL	ENABLED	2707	74.54	689	
	RCKG1	POOL	ENABLED	2707	26.63	1986	1
	SYSG1	POOL	ENABLED	2707	26.30	1995	1
	SYSG2	POOL	ENABLED	2707	88.80	303	
	TSOG1	POOL	ENABLED	2707	97.56	66	
	WRKG1	POOL	ENABLED	2707	0.77	2686	2

Groups with non-zero total storage are highlighted

Tip: use RGEN X to generate sample REXX exec

SMS Storage Volumes Panel (SMSV)

- SMSV Command
 - Shows all volumes defined to SMS
 - Online and offline to MVS
 - Sysplex wide using SYSNAME pattern
- Actions
 - Display volume
 - Enable, Disable, and Quiesce volume
 - List all volumes in storage group

SMS Storage Volumes Panel (SMSV)

Display Filter View Print Options Search Help						
SDSF SMS VOLUME DISPLAY RS86			(ALL)		LINE 1-23 (34)	
COMMAND INPUT ==>			SCROLL ==> HALF			
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*						
ACTION=+-Extend,-/-Show,/-/-Block,%-RunExec,=-Repeat,D-Display,DC-DisplayCFVol,						
ACTION=DS-DisplaySG,DSL-DisplaySGList,VD-VaryDisable,VDN-VaryDisableNew,						
ACTION=VE-VaryEnable,VQ-VaryQuiesce,VQN-VaryQuiesceNew,VS-VarySpace						
NP	VOLSER	Status	TotalMB	Used%	FreeMB	LargestFreeMB Device-Status
	DBPG00	DISABLED	0	0.00	0	0 OFFLINE
	DBXX00	ENABLED	0	0.00	0	0 OFFLINE
	DMPG00	ENABLED	2707	84.44	421	420 ONLINE
	DMXX00	ENABLED	0	0.00	0	0 OFFLINE
	ECXX00	ENABLED	0	0.00	0	0 OFFLINE
	HFPG00	ENABLED	2707	74.54	689	689 ONLINE
	HFXX00	ENABLED	0	0.00	0	0 OFFLINE
	R1PG00	ENABLED	2707	26.63	1986	1136 ONLINE
	R1XX00	ENABLED	0	0.00	0	0 OFFLINE
	S1PG00	ENABLED	2707	26.30	1995	1618 ONLINE
	S1XX00	ENABLED	0	0.00	0	0 OFFLINE
	S2PG00	ENABLED	2707	88.80	303	16 ONLINE
	S2XX00	ENABLED	0	0.00	0	0 OFFLINE
	TSPG00	ENABLED	2707	97.56	66	38 ONLINE
	TSXX00	ENABLED	0	0.00	0	0 OFFLINE
	WKPG00	ENABLED	2707	0.77	2686	2685 ONLINE
	WKXX00	ENABLED	0	0.00	0	0 OFFLINE
	DBPG00	ENABLED	0	0.00	0	0 OFFLINE
	DBXX00	ENABLED	0	0.00	0	0 OFFLINE

Volumes with non-zero total storage are highlighted

SMS Storage Volumes Panel (SMSV)

Command ==> Show Columns Row 1 to 12 of 12

Sort column with F5. Use Locate to position to column.

/ All values _ Column width

Column	##	Value
VOLSER	01	DMPG00
Status	01	ENABLED
TotalMB	01	2707
Used%	01	84.44
FreeMB	01	421
LargestFreeMB	01	420
Device-Status	01	ONLINE
Unit	01	649C
StorGrp	01	DMPG1
LastUser	01	PDILYA
SysName	01	RS86
SysLevel	01	z/OS 02.03.00 HBB77B0

***** Bottom of data *****

SMS Groups to Volumes

```
Display Filter View Print Options Search Help
-----
SDSF STORAGE GROUP DISPLAY RS86 (ALL) LINE 1-18 (18)
COMMAND INPUT ===> SCROLL ===> HALF
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*
ACTION=+-Extend,/-Show,/-Block,%-RunExec,=-Repeat,D-Display,DL-DisplayList,
ACTION=L-ListVol,VD-VaryDisable,VDN-VaryDisableNew,VE-VaryEnable,
ACTION=VQ-VaryQuiesce,VQN-VaryQuiesceNew,VS-VarySpace
NP NAME Type Status TotalMB Used% FreeMB LargestFree
1 DB2G1 POOL DISABLED 0 0.00 0
DMPG1 POOL ENABLED 2707 89.39 287
EMCCXSG POOL ENABLED 0 0.00 0
HESG1 POOL ENABLED 2707 74.58 688
RCKG1 POOL ENABLED 2707 26.63 1986 1
```

Volumes in selected group

```
Display Filter View Print Options Search Help
-----
SDSF SMS VOLUME DISPLAY RS86 (ALL) LINE 1-2 (2)
COMMAND INPUT ===> SCROLL ===> HALF
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*
ACTION=+-Extend,/-Show,/-Block,%-RunExec,=-Repeat,D-Display,DC-DisplayCFVol,
ACTION=DS-DisplaySG,DSL-DisplaySGList,VD-VaryDisable,VDN-VaryDisableNew,
ACTION=VE-VaryEnable,VQ-VaryQuiesce,VQN-VaryQuiesceNew,VS-VarySpace
NP VOLSER Status TotalMB Used% FreeMB LargestFreeMB Device-Status
DMPG00 ENABLED 2707 89.39 287 287 ONLINE
DMXX00 ENABLED 0 0.00 0 0 OFFLINE
```

CF Connections Panel (CFC)

- CFC Command
 - Shows information about coupling facility structure connections in the sysplex
- Actions
 - Display connection
 - Display structure

CF Connections Panel (CFC)

```
Display Filter View Print Options Search Help
-----
SDSF CF CONNECTION DISPLAY RS86                LINE 1-8 (8)
COMMAND INPUT ==>                               SCROLL ==> HALF
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*
ACTION=+-Extend,/-Show,//-Block,%-RunExec,=-Repeat,D-Display,DA-DisplayAll,
ACTION=DS-DisplayStructure
NP  CONNAME      ConState      StrName      StrType      Status
    ISGLOCK#RS86  ACTIVE      ISGLOCK      LOCK         ALLOCATED
    IXGLOGR_RS86  ACTIVE      OPERLOG      LIST         ALLOCATED
    SIGPATH_010000FA ACTIVE      IXCLIST1     LIST         ALLOCATED
    SIGPATH_010000FA ACTIVE      IXCLIST2     LIST         ALLOCATED
    ISGLOCK#RS88  ACTIVE      ISGLOCK      LOCK         ALLOCATED
    IXGLOGR_RS88  ACTIVE      OPERLOG      LIST         ALLOCATED
    SIGPATH_020000FB ACTIVE      IXCLIST1     LIST         ALLOCATED
    SIGPATH_020000FB ACTIVE      IXCLIST2     LIST         ALLOCATED
```

Rows with active connections are highlighted

CF Connections Panel (CFC)

Command ==> Show Columns Row 1 to 22 of 24

Sort column with F5. Use Locate to position to column.

/ All values _ Column width

Column	##	Value
CONNAME	01	ISGLOCK#RS86
ConState	01	ACTIVE
StrName	01	ISGLOCK
StrType	01	LOCK
Status	01	ALLOCATED
JobName	01	GRS
ASID	01	7
ASIDX	01	0007
ConDisp	01	DELETE
ID	01	01
Version	01	00010089
CFLevel	01	0
ConData	01	0000000000000000
DiscData	01	0000000000000000
Policy	01	CFRMPOL
CFName	01	CF85
NumCF	01	1
ConTokenX	01	C9E7C3D3D6F0F0F27EF9F20000010089
ConLevel	01	0000000000000000
SToken	01	0000001C00000001
ConFlags	01	82008005
SysNum	01	1

Command ==> Show Columns Row 23 to 24 of 24

Sort column with F5. Use Locate to position to column.

/ All values _ Column width

Column	##	Value
SysSeq	01	250
SysName	01	RS86

***** Bottom of data *****

CF Structures Panel (CFS)

- CFS Command
 - Shows information about coupling facility structures
- Actions
 - Display structure

CF Structures Panel (CFS)

```
Display Filter View Print Options Search Help
-----
SDSF CF STRUCTURE DISPLAY RS86                               LINE 13-24 (24)
COMMAND INPUT ===>                                         SCROLL ===> HALF
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*
ACTION=+-Extend,-/-Show,///-Block,%-RunExec,=-Repeat,D-Display,DA-DisplayAll
NP  STRNAME                                     Type      Status      Disp      Size      Size%      Conn
   RRS_ARCHIVE                                NOTALLOCATED                                0      0.00      0
   RRS_DELAYED_UR                             NOTALLOCATED                                0      0.00      0
   RRS_MAIN_UR                                NOTALLOCATED                                0      0.00      0
   RRS_RESTART                                NOTALLOCATED                                0      0.00      0
   RRS_RM_DATA                                NOTALLOCATED                                0      0.00      0
   SCLM_CACHE                                 NOTALLOCATED                                0      0.00      0
   SYSIGGCAS_ECS                             NOTALLOCATED                                0      0.00      0
   VSAM1_CACHE                                NOTALLOCATED                                0      0.00      0
   ISGLOCK                                    LOCK      ALLOCATED    DELETE      9216    100.00     2
   IXCLIST1                                   LIST      ALLOCATED    DELETE      10240   100.00     2
   IXCLIST2                                   LIST      ALLOCATED    DELETE      10240   100.00     2
   OPERLOG                                    LIST      ALLOCATED    DELETE      24576   100.00     2
```

Structures with non-zero
users are highlighted

Virtual Storage Map Panel (VMAP)

- VMAP Command
 - Shows map of virtual storage for system by area name
 - Displays size and allocation of each area

Virtual Storage Map Panel (VMAP)

Display Filter View Print Options Search Help

SDSF VMAP DISPLAY R586 (ALL) LINE 1-25 (48)
COMMAND INPUT ===> snap se SCROLL ===> HALF
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*
ACTION=+-Extend,-/-Show,/-Block,-RunExec,-Repeat

NP	NAME	Start-Address	End-Address	Size	Alloc	Alloc%	H
	HV-SHARED	00000200_00000000	0001FFFF_FFFFFFFF	510T	403M	0.00	
	HV-COMMON	000001EF_80000000	000001FF_FFFFFFFF	66G	7008M	10.36	
	HV-PRIVATE	00000048_00000000	000001EF_7FFFFFFF	1694G	0	0.00	
	LOCALSYSAREA	00000008_00000000	00000047_FFFFFFFF	256G	0	0.00	
	RESERVED	00000000_80000000	00000007_FFFFFFFF	30G	0	0.00	
	EXTENDED-PRIVATE	00000000_11B00000	00000000_7FFFFFFF	1765M	0	0.00	
	EXTENDED-CSA	00000000_07019000	00000000_11AFFFFFFF	171M	37M	21.41	3
	EXTENDED-MLPA	00000000_00000000	00000000_00000000	0	0	0.00	
	EXTENDED-FLPA	00000000_07016000	00000000_07018FFF	12288	0	0.00	
	EXTENDED-PLPA	00000000_03385000	00000000_07015FFF	62020K	0	0.00	
	EXTENDED-SQA	00000000_01D09000	00000000_03384FFF	23024K	21M	93.37	2
	EXTENDED-R/W-NUC	00000000_01CBC000	00000000_01D08FFF	315392	0	0.00	
	EXTENDED-R/O-NUC	00000000_01000000	00000000_01CBBCEF	13039K	0	0.00	
	R/O-NUC	00000000_00FDF000	00000000_00FFFFFF	135168	0	0.00	
	R/W-NUC	00000000_00FD3000	00000000_00FDE3BF	46016	0	0.00	
	SQA	00000000_00E40000	00000000_00FD2FFF	1612K	328K	20.34	9
	PLPA	00000000_00C45000	00000000_00E3FFFF	2028K	0	0.00	
	FLPA	00000000_00000000	00000000_00000000	0	0	0.00	
	MLPA	00000000_00000000	00000000_00000000	0	0	0.00	
	CSA	00000000_00900000	00000000_00C44FFF	3348K	511K	15.25	5
	PRIVATE	00000000_00006000	00000000_008FFFFF	9192K	0	0.00	
	V=R	00000000_00000000	00000000_00000000	0	0	0.00	
	SYSTEM	00000000_00002000	00000000_00005FFF	16384	0	0.00	
	PSA	00000000_00000000	00000000_00001FFF	8192	0	0.00	

Tip: use snap command to capture table

Virtual Storage Map Panel (VMAP)

```
SDSF EDIT      *SNAP
Command ==> create

Columns 00001 00072
Scroll ==> HALF

***** Top of Data *****
c99999 NAME      Start-Address  End-Address  Size  Alloc  A
000002 HV-SHARED  00000200_00000000 0001FFFF_FFFFFFFF 510T  412672K
000003 HV-COMMON  000001EF_80000000 000001FF_FFFFFFFF 66G   7008M
000004 HV-PRIVATE 00000048_00000000 000001EF_7FFFFFFF 1694G  0
000005 LOCALSYSAREA 00000008_00000000 00000047_FFFFFFFF 256G  0
000006 RESERVED    00000000_80000000 00000007_FFFFFFFF 30G   0
000007 EXTENDED-PRIVATE 00000000_11800000 00000000_7FFFFFFF 1807360K 0
000008 EXTENDED-CSA 00000000_07019000 00000000_11AFFFFF 175004K 38372144
000009 EXTENDED-MLPA 00000000_00000000 00000000_00000000 0 0
000010 EXTENDED-FLPA 00000000_07016000 00000000_07018FFF 12288 0
000011 EXTENDED-PLPA 00000000_03385000 00000000_07015FFF 63508480 0
000012 EXTENDED-SQA 00000000_01D09000 00000000_03384FFF 23576576 21968672
000013 EXTENDED-R/W-NUC 00000000_01CBC000 00000000_01D08FFF 315392 0
000014 EXTENDED-R/O-NUC 00000000_01000000 00000000_01CBBCEF 13352176 0
000015 R/O-NUC      00000000_00FDF000 00000000_00FFFFFF 135168 0
000016 R/W-NUC     00000000_00FD3000 00000000_00FDE3BF 46016 0
000017 SQA         00000000_00E40000 00000000_00FD2FFF 1650688 335768
000018 PLPA        00000000_00C45000 00000000_00E3FFFF 2076672 0
000019 FLPA        00000000_00000000 00000000_00000000 0 0
000020 MLPA         00000000_00000000 00000000_00000000 0 0
000021 CSA         00000000_00900000 00000000_00C44FFF 3428352 522992
000022 PRIVATE      00000000_00006000 00000000_008FFFFF 9412608 0
000023 V=R         00000000_00000000 00000000_00000000 0 0
000024 SYSTEM      00000000_00002000 00000000_00005FFF 16384 0
000025 PSA         00000000_00000000 00000000_00001FFF 8192 0
000026 HV-SHARED    00000200_00000000 00020000_00000000 510T  0
000027 HV-COMMON    000001EF_80000000 000001FF_FFFFFFFF 66G   7007M
000028 HV-PRIVATE   00000048_00000000 000001EF_7FFFFFFF 1694G  0
000029 LOCALSYSAREA 00000008_00000000 00000047_FFFFFFFF 256G  0
```

Tip: use edit to copy the table to a data set

Virtual Storage Map Panel (VMAP)

```
Command ==>                     Show Columns                     Row 1 to 11 of 11
Sort column with F5. Use Locate to position to column.
/ All values      _ Column width
Column            ## Value
NAME             01 HV-SHARED
Start-Address    01 00000200_00000000
End-Address      01 0001FFFF_FFFFFFFF
Size             01 510T
Alloc            01 422576128
Alloc%           01 0.00
HWM              01 422576128
HWM%             01 0.00
Seq              01 1
SysName          01 RS86
SysLevel         01 z/OS 02.03.00 HBB77B0
***** Bottom of data *****
```

Common Storage Remaining Panel (CSR)

- CSR Command
 - Shows common storage remaining (orphan) after address space ends
 - Requires CSA and SQA tracking enabled in DIAGxx

Common Storage Remaining Panel (CSR)

Display Filter View Print Options Search Help											
SDSF CSR DISPLAY RS86				(ALL)				LINE 1-16 (16)			
COMMAND INPUT ==>											
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*											
ACTION=+-Extend,/-Show,/-Block,%-RunExec,=-Repeat											
NP	JOBNAME	JobID	ASID	ASIDX	CSA	CSA%	SQA	SQA%	ECSA	ECSA%	ES
	CATALOG		20	0014	0	0.0000	128	0.0077	0	0.0000	2
	EZAZSSI	STC09063	39	0027	288	0.0084	0	0.0000	0	0.0000	
	HWIBCPII		29	001D	0	0.0000	0	0.0000	3672	0.0020	
	IFGEDI		33	0021	0	0.0000	0	0.0000	4864	0.0027	
	IPLTIME	JOB09153	48	0030	0	0.0000	0	0.0000	0	0.0000	10
	MOUNTFS	JOB09155	48	0030	0	0.0000	0	0.0000	64	0.0000	
	SMFDUMP	STC09065	44	002C	0	0.0000	0	0.0000	0	0.0000	4
	TS5485	TSU09276	120	0078	136	0.0039	0	0.0000	5512	0.0030	
	CATALOG		20	0014	0	0.0000	128	0.0077	0	0.0000	2
	EZAZSSI	STC09168	39	0027	288	0.0084	0	0.0000	0	0.0000	
	HWIBCPII		29	001D	0	0.0000	0	0.0000	3672	0.0020	
	IFGEDI		33	0021	0	0.0000	0	0.0000	4864	0.0027	
	IPLTIME	JOB09259	32	0020	0	0.0000	0	0.0000	0	0.0000	10
	MOUNTFS	JOB09261	32	0020	0	0.0000	0	0.0000	64	0.0000	
	SMFDUMP	STC09169	44	002C	0	0.0000	0	0.0000	0	0.0000	4
	SMFSWTCH	STC09303	114	0072	0	0.0000	0	0.0000	2416	0.0013	

Common Storage Remaining Panel (CSR)

Command ==> _____

Sort column with F5. Use Locate to position to column.

/ All values _ Column width

Column	##	Value
JOBNAME	01	CATALOG
JobID	01	
ASID	01	20
ASIDX	01	0014
CSA	01	0
CSA%	01	0.0000
SQA	01	128
SQA%	01	0.0077
ECSA	01	0
ECSA%	01	0.0000
ESQA	01	2576
ESQA%	01	0.0109
Date	01	06/20/2017 15:56:49
SCSA%	01	15
SECSA%	01	21
SSQA%	01	20
SESQA%	01	93
Aux%	01	0
RealAFC	01	761589
SysName	01	RS86
SysLevel	01	z/OS 02.03.00 HBB77B0
***** Bottom of data *****		

Generic Tracker Panel (GT)

- GT Command
 - Shows generic tracker events
 - Event tracking must be active: `setgtz tracking=on`
- Actions
 - Display events
- SDSF generates some events
 - NOPARM fallback: SDSF server not available or ISFPRMxx not active
 - Main menu as table disabled

Generic Tracker Panel (GT)

```
Display Filter View Print Options Search Help
-----
SDSF GENERIC TRACKER  RS86      (ALL)                LINE 1-8 (8)
COMMAND INPUT ==>>                                SCROLL ==>> HALF
PREFIX=*  DEST=(ALL)  OWNER=*  SYSNAME=*
ACTION=+-Extend,/-Show,/-Block,%-RunExec,=-Repeat,D-Display,DA-DisplayAll,
ACTION=DD-DisplayDebug,DE-DisplayExclude,DH-DisplayHomeJob,DS-DisplayStatus
NP  OWNER   Source   Program  ProgramOffset  EventDesc
IBMJES2  HASCINJR *UNKNOWN 0000000000000000 00000000 0|00000000 0| INTRDR
IBMJES2  HASCINJR *UNKNOWN 0000000000000000 00000000 0|00000000 0| INTRDR
IBMJES2  HASCINJR *UNKNOWN 0000000000000000 00000000 0|00000000 0| STCINR
IBMJES2  HASCINJR *UNKNOWN 0000000000000000 00000000 0|00000000 0| STCINR
IBMJES2  HASCINJR *UNKNOWN 0000000000000000 00000000 0|00000000 0| STCINR
IBMSDSF  ISFINITC ISFVTBL 000000000020C15E SDSF MENU TABLE DISABLED: ISFM
IBMSDSF  ISFINITC ISFVTBL 000000000020C15E SDSF NOPARM FALLBACK: ISFPRMXX
IBMJES2  HASCINJR *UNKNOWN 0000000000000000 00000000 0|00000000 0| STCINR
```

SDSF generated events

Generic Tracker Panel (GT)

```

Command ==>
Sort column with F5. Use Locate to position to column.

/ All values      _ Column width

Column    ##  Value
OWNER      01  IBMSDSF
Source     01  ISFINITC
Program    01  ISFVTBL
ProgramOffset 01  0000000000020C15E
EventDesc  01  SDSF MENU TABLE DISABLED: ISFMIGMN ALLOCATED
EventData  01  00000000000000000000000000000000
EJobName   01  TS5485
HJobName   01  TS5485
EASIDX     01  0078
HASIDX     01  0078
Auth       01  YES
Count      01  3
First-Date-Time 01  06/21/2017 13:07:11
SPathLen   01  0
SourcePath 01
PPathLen   01  0
ProgramPath 01
SysName     01  RS86
SysLevel    01  z/OS 02.03.00 HBB77B0
***** Bottom of data *****

```

Main menu as table disabled.
Application may need updates

Generic Tracker Panel (GT)

Show Columns			Row 1 to 19 of 19
Command ==> _____			
Sort column with F5. Use Locate to position to column.			
/ All values _ Column width			
Column	##	Value	
OWNER	01	IBMSDSF	
Source	01	ISFINITC	
Program	01	ISFVTBL	
ProgramOffset	01	000000000020C15E	
EventDesc	01	SDSF NOPARM FALLBACK: ISFPRMXX NOT ACTIVE	
EventData	01	00000000000000000000000000000000	
EJobName	01	TS5485	
HJobName	01	TS5485	
EASIDX	01	0078	
HASIDX	01	0078	
Auth	01	YES	
Count	01	1	
First-Date-Time	01	06/21/2017 13:07:36	
SPathLen	01	0	
SourcePath	01		
PPathLen	01	0	
ProgramPath	01		
SysName	01	RS86	
SysLevel	01	z/OS 02.03.00 HBB77B0	
***** Bottom of data *****			

Fallback to ISFPARMS due to SDSF server or ISFPRMxx not active



NEW SECONDARY PANELS

New Secondary Panels

- Secondary panels accessed using an action character
 - Job Module
 - JC action on DA or AS
 - Job Tasks
 - JT action on DA or AS

Job Module Panel (JC action)

- JC action from DA or AS
 - Shows CDEs for the selected address space

```

Display Filter View Print Options Search Help
-----
SDSF AS DISPLAY RS86 (ALL) LINE 1-4 (4)
COMMAND INPUT ===> SCROLL ===> HALF
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*
ACTION=+-Extend,/-Show,/-Block,%-RunExec,=-Repeat,JC-JobModule,JD-JobDevices,
ACTION=JM-JobMemory,JT-JobTasks
NP  JOBNAME  ASIDX Real Fixed CSA      CSA%  ECSA      ECSA%  SQA      SQA%
jc  SDSF     0082  1696  120      0  0.00  697408  0.38      0  0.00
    SDSFAUX  0084  1353  154      0  0.00   7136  0.00      0  0.00
    
```

```

Display Filter View Print Options Search Help
-----
SDSF JOB MODULE RS86 ASID 0082 SDSF STC09799 LINE 13-36 (36)
COMMAND INPUT ===> SCROLL ===> HALF
PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*
ACTION=+-Extend,/-Show,/-Block,%-RunExec,=-Repeat
NP  MODULE Major EPA ModLen SP TCB Program JPAQ LP
    HSFMSG 00000000_11C72000 00006EC0 252 008F8588 ISFHCTL YES NO
    HSFPCSCH 00000000_0FBCB5F8 00000A08 241 008F8588 ISFHCTL YES NO
    HSFPCSCL 00000000_0FBCA5D0 00000A30 241 008F8588 ISFHCTL YES NO
    HSFPCSCR 00000000_0FBC9610 000009F0 241 008F8588 ISFHCTL YES NO
    HSFPCSCT 00000000_0FAC7248 00000A08 241 008F8588 ISFHCTL YES NO
    HSFPCSDI 00000000_11EAB000 00000F70 252 008F8588 ISFHCTL YES NO
    HSFPCSML 00000000_11C71340 000009C8 252 008F8588 ISFHCTL YES NO
    HSFPCSRQ 00000000_11EAC000 00016640 252 008F8588 ISFHCTL YES NO
    
```

JC action

Job Module Panel (JC action)

Command ==> Show Columns Row 1 to 22 of 26

Sort column with F5. Use Locate to position to column.

/ All values _ Column width

Column	##	Value
MODULE	01	HSFESTAE
Major	01	
EPA	01	00000000_11B68000
ModLen	01	00002B38
SP	01	252
TCB	01	008F8588
Program	01	ISFHCTL
JPAQ	01	YES
LPDE	01	NO
Use	01	1
SysUse	01	0
CDE	01	008F8798
AC	01	0
AM	01	31
RM	01	31
APF	01	YES
Rent	01	YES
Reus	01	YES
Attr	01	31
Attr2	01	22
AttrB	01	10
JobName	01	SDSFKJ

Command ==> Show Columns Row 23 to 26 of 26

Sort column with F5. Use Locate to position to column.

/ All values _ Column width

Column	##	Value
ASID	01	127
ASIDX	01	007F
SysName	01	R586
SysLevel	01	z/OS 02.03.00 HBB77B0
***** Bottom of data *****		

Job Tasks Panel (JT action)

- JT action from DA or AS
 - Shows all tasks (TCBs) for selected address space

Display Filter View Print Options Search Help

SDSF AS DISPLAY RS86 (ALL) LINE 71-94 (139)

COMMAND INPUT ==> SCROLL ==> HALF

PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*

ACTION=+-Extend,/-Show,/--Block,%-RunExec,=-Repeat,JC-JobModule,JD-JobDevices, ACTION=JM-JobMemory,JT-JobTasks

NP	JOBNAME	ASIDX	Real	Fixed	CSA	CSA%	ECSA	ECSA%	SQA	SQA%
jt	SDSFKJ	007F	1672	113	0	0.00	697408	0.38	0	0.00
	SDSFAUX	0080	1355	155	0	0.00	7136	0.00	0	0.00

Display Filter View Print Options Search Help

SDSF JOB TASKS RS86 ASID 007F SDSFKJ STC09323 LINE 1-15 (15)

COMMAND INPUT ==> SCROLL ==> HALF

PREFIX=* DEST=(ALL) OWNER=* SYSNAME=*

ACTION=+-Extend,/-Show,/--Block,%-RunExec,=-Repeat

NP	TCB	RB	Type	Program	Storage	FreeStor	CPU-Time
	008FD520		TCB		835584	120576	0.00
	008FD520	008FFF98	PRB	IEAVAR00			0.00
	008FEE88		TCB		647168	60352	0.00
	008FEE88	008FF0A0	PRB	IEFSD060			0.00
	008FEE88	008FED78	PRB	IEESB605			0.00
	008F8588		TCB		5005312	155688	0.06
	008F8588	008F8500	PRB	ISFHCTL			0.00
	008D6738		TCB		45056	6992	0.01
	008D6738	008D6658	PRB	HSFSYSMN			0.00
	008D69B0		TCB		114688	28232	0.01
	008D69B0	008D68D0	PRB	HSFSRVPL			0.00
	008FC830		TCB		102400	29560	0.07
	008FC830	008D6EA0	PRB	HSFSRVML			0.00
	008FF128		TCB		323584	8064	0.00
	008FF128	008FEE00	PRB	IEAVTSDT			0.00

JT action

Job Tasks Panel (JT action)

```

Command ==> _____ Show Columns Row 1 to 20 of 20

Sort column with F5. Use Locate to position to column.

/ All values      _ Column width

Column      ##  Value
TCB          01  008FD520
RB           01  00000000
Type         01  TCB
Program      01
Storage      01  835584
FreeStor     01  120576
CPU-Time     01  0.000
TCBCMP       01  00000000
TCBFlags     01  0000800400000000
IntC         01  0000
STCB         01  7FFFA450
XSB          01
OPSW         01  00000000_00000000
ASID         01  127
ASIDX        01  007F
TCBPtr       01  008FD520
Level        01  1
JobName      01  SDSFKJ
SysName      01  RS86
SysLevel     01  z/OS 02.03.00 HBB77B0
***** Bottom of data *****

```



MISCELLANEOUS CHANGES

New Columns and Overtypes

- SCSA%, SECSA%, SSQA%, SESQA%, Aux%, RealAFC, Priv, PrivUsed, Priv%, Epriv, EPrivUsed, Epriv% on the AS panel
- Type on the DYNX panel
- BERGNum on the H and O panels
- Email, BERTNum, JOENum, JOEBERTs, Dubious, BeforeJob, BeforeJID, AfterJob, AfterJID, SchDelay, OrigNHold, CurrNHold, Normal, Abnormal, NrCmp, AbCmp, OpHold on I and ST panels
- GDGBias on the JC panel (overtypable)
- ConDisp, ConState on the Job Device panel
- CopyGroups on the JDS panel

New Columns and Overtypes

- VfyPath on the NO panel
- Nsecure on the NS panel
- UseCount on the PROC panel
- Description, Statement, Keyword on the RM panel
- IPLCurr, IODFUnit, IODFCurr on the SYS panel
- SMFB limit on the RM panel (overtypable)

Other Enhancements and Changes

- New DL action on the JC panel (JES2 only)
- New A, H, P, PF, and U actions on the DYNX panel
- Actions on initiator panel can optionally use initiator number rather than initiator name
- Job ID added to WHO command response
- SDSF SERVER keyword and ISFSERVER REXX special variable obsolete
- SET LANGUAGE command obsolete
 - Japanese feature no longer shipped (JQX77xJ)
 - Use new SDSF User's Guide
- MQ support removed




Z/OSMF SDSF PLUG-IN

z/OSMF SDSF/UI Plug-In

- SDSF V2R3 new panels
 - Device Activity
 - Network Activity
 - SMS Storage Groups
 - CF Structures
- Overview page folders reorganized

Folder	Panel
Device	DEV, SMSG
Jobs	AS, DA, I, H, O, PS, ST
Network	NA
Sysplex	CFS, CK, SP, SYS
System	APF, LNK, LPA, PAG, PARM

z/OSMF SDSF Plug-In – Overview



z/OSMF SDSF Plug-In – Device Activity Panel

The screenshot displays the IBM z/OS Management Facility (z/OSMF) SDSF Plug-In interface. The browser address bar shows the URL <https://rs92.rocketsoftware.com:11443/zosmf/>. The main content area is titled "SDSF (RSPLEX0H)" and includes a "Common Filters" button. The "Overview" tab is selected, showing a "Work with disk device activity." section. Below this, the "Device Activity" section displays two bar charts: "Top SSCH Counts" and "Top Responses".

Top SSCH Counts

Device	Count
MCPH00	3.188
ZFPH00	0.199

Top Responses

Device	Count
MCPH00	0.304
ZFPH00	0.256

The "DEV" tab is also visible, showing a table of device activity data. The table has columns for "VOLSER", "Unit", "StorGrp", and "IOIntens". The "VOLSER" column is filtered to show "D1XF01", "D1XF02", and "D1XF03". The "Unit" column is filtered to show "D191", "D419", and "D5B6". The "IOIntens" column shows values of 0 for all three devices.

VOLSER	Unit	StorGrp	IOIntens
D1XF01	D191		0
D1XF02	D419		0
D1XF03	D5B6		0

The "Properties of D1XF01" section is also visible, showing a table of properties for the selected device. The table has columns for "General", "Connect", "Disc", "IOIntens", "IOSQ", and "PAVNum". The "General" column shows values of 0 for "Connect", "Disc", "IOIntens", and "IOSQ", and 1 for "PAVNum".

General	Connect	Disc	IOIntens	IOSQ	PAVNum
	0	0	0	0	1

z/OSMF SDSF Plug-In – Network Activity Panel

The screenshot displays the IBM z/OS Management Facility (z/OSMF) interface, specifically the SDSF (RSPLEX0H) Network Activity Panel. The interface is divided into several sections:

- Left Sidebar:** Contains navigation links such as Welcome, Notifications, Sysplex Management, Workflow Editor, Workflows, Cloud Provisioning, Configuration, Jobs and Resources, SDSF (highlighted), Links, Performance, Problem Determination, Software, z/OS Classic Interfaces, z/OSMF Administration, z/OSMF Settings, and Consoles. A Refresh button is located at the bottom of the sidebar.
- Top Bar:** Displays the IBM z/OS Management Facility logo, a search bar, and a welcome message for user ts5485.
- Main Content Area:**
 - SDSF (RSPLEX0H) Overview:** Shows a bar chart representing network activity for various MXITCP connections. The chart includes data points for 22670111, 22667847, 22666941, 22666488, 22661281, 41276744, 21628728, 21626568, 21625704, and 21625272.
 - Listeners:** 15, **Established:** 14, **Time Wait:** 1, **Connect:** 0, **Closing:** 0.
 - NA (Network Activity) Table:** A table with columns for JOBNAME, Status, and IPAddr. The table lists several connections, including CFZC1M, which is selected. The table shows a total of 35 selected items.
 - Properties of CFZC1M:** A detailed view of the selected connection, showing properties such as Appl, ApplData, ASID, ASIDX, BytesIn, BytesOut, Client, EXCP-Cnt, InBufSz, and IPAddr.

z/OSMF SDSF Plug-In – SMS Storage Groups

IBM z/OS Management Facility

Welcome ts5485

SDSF (RSPLEX0H)

Overview SMSG

Work with system managed storage groups.

System: RS92 (Local)

SMSG Top Used

Storage Group	Usage
ZFSG1	86.59
TSOG1	62.17
SYSG2	47.46
SYSG1	35.64
RCKG1	1.03
WRKG1	0.18

Online: 6 Offline: 11 Enabled: 9 Quiesced: 0 Disabled: 0

SMSG

NAME	Type	Status	Total
DB2G1	POOL	ENABLED	
DMPG1	POOL	ENABLED	

Properties of DB2G1

NAME: DB2G1
SysName: RS92
Type: POOL

Recent Service

- A problem may occur where the SDSF plug-in overview panel is not rendered properly
 - Overview panel may appear as blank or one line message box
- Fixed by Java APAR PH01244
 - Work around described in Java APAR PI93233
- Open PMR if you encounter this problem so you can be notified when fix is available.



INSTALLATION AND TOLERATION

SDSF Address Spaces

- SDSF address space
 - Manages client connections
 - Processes ISFPRMxx
 - Operator commands
 - Starts/stops SDSFAUX
- SDSFAUX address space
 - Processes data gathering requests
 - Manages XCF connections for remote data gathering requests
 - Internally started by SDSF address space
 - Do not start manually with START command

SDSF Address Spaces

- Copy sample JCL to PROCLIB
 - ISF.SISFJCL(SDSF)
 - ISF.SISFJCL(SDSFAUX)
- Copy sample parmlib to PARMLIB
 - ISF.SISFJCL(ISFPRM00)
 - Sample ISF.SISFJCL(ISFPRM01) is an example of ISFPRMxx with most statements and keywords with defaults specified
- Add ISF.SISFLOAD to Inklst
- Add ISF.SISFLPA to LPA list
- Update COMMNDxx to start SDSF
 - S SDSF

SDSF Address Spaces

- SDSF V2R3 requires SDSF and SDSFAUX address spaces to be active for full function
 - SDSF will tolerate the address spaces not being active provided:
 - User is permitted to SDSF.NOPARM resource in SDSF class
 - Allows fall back to ISFPARMS
 - Panels that require SDSFAUX will not be available
 - APF, AS, CFC, CFS, CSR, DEV, DYNX, ENQ, FS, GT, NA, PAG, PARM, PROC, SMSG, SMSV, SRCH, SSI, SYM, SYS, VMAP
- ***We strongly recommend that SDSF and SDSFAUX be started !!***

SDSF Address Spaces

- In V2R3, clients connect to SDSF address space at initialization
 - Previously connect was deferred until address space service was needed
- Connect requires READ access to ISF.CONNECT.*system* in SDSF class
 - Avoid connect failures and permit your users to this resource

SDSF Address Spaces

- Multiple SDSF servers no longer supported
 - Was used to support multiple JES levels running on the same system
 - Configuration no longer applicable
 - Only a single SDSF server (and SDSFAUX) can be started at a time
 - Can be any jobname (default SDSF and SDSFAUX)
 - Specify jobname and procname on CONNECT statement of ISFPRMxx
- Now obsolete:
 - **SERVER** keyword of SDSF command
 - SDSF/REXX special variable **isfserver**
 - SDSF/Java method **addISFServer()** of ISFRequestSettings

Group Statement Changes

- New keywords for panel field lists
 - *We recommend field lists are not coded* – Use ARRANGE command instead

GROUP	ISFGRP	Description
CDEFLDS(<i>FLD-name</i>)		Primary field list for job module panel
CFCFLDS(<i>FLD-name</i>)		Primary field list for CFC panel
CFSFLDS(<i>FLD-name</i>)		Primary field list for CFS panel
CSRFLDS(<i>FLD-name</i>)		Primary field list for CSR panel
DEVFLDS(<i>FLD-name</i>)		Primary field list for DEV panel
FSFLDS(<i>FLD-name</i>)		Primary field list for FS panel
GTFLDS(<i>FLD-name</i>)		Primary field list for GT panel
NAFLDS(<i>FLD-name</i>)		Primary field list for NA panel
SMSGFLDS(<i>FLD-name</i>)		Primary field list for SMSG panel
SMSVFLDS(<i>FLD-name</i>)		Primary field list for SMSV panel
SSIFLDS(<i>FLD-name</i>)		Primary field list for SSI panel
TCBFLDS(<i>FLD-name</i>)		Primary field list for job tasks panel
VMAPFLDS(<i>FLD-name</i>)		Primary field list for VMAP panel

New Custom Properties

- New custom properties in ISFPRMxx

Property	Description	Comments
Panel.CSR.JES PlexScope	Controls scope of CSR panel	TRUE if JES Plex wide
Panel.DEV.JES PlexScope	Controls scope of DEV panel	TRUE if JES Plex wide
Panel.FS.JES PlexScope	Controls scope of FS panel	TRUE if JES Plex wide
Panel.GT.JES PlexScope	Controls scope of GT panel	TRUE if JES Plex wide
Panel.NA.JES PlexScope	Controls scope of NA panel	TRUE if JES Plex wide
Panel.SMSG.JES PlexScope	Controls scope of SMSG panel	TRUE if JES Plex wide
Panel.SMSV.JES PlexScope	Controls scope of SMSV panel	TRUE if JES Plex wide
Panel.SSI.JES PlexScope	Controls scope of SSI panel	TRUE if JES Plex wide
Panel.VMAP.JES PlexScope	Controls scope of VMAP panel	TRUE if JES Plex wide
Panel.Main.DisableTable	Controls display of main panel	TRUE if old style non-scrollable panel to be used. Can also ALLOC Fi(ISFMIGMN) DUMMY to session
Panel.INIT.UseInitNum	Controls generated commands on INIT panel	TRUE if initiator number to be used rather than name

Obsolete Statements and Keywords

- Obsolete statements and keywords due to removal of obsolete function
- Statements are accepted but not syntax checked

Statement	Macro	Keyword	Description
SERVERGROUP			No longer used due to removal of MQ support
SERVER			No longer used due to removal of MQ support
COMM			No longer used due to removal of MQ support
OPTIONS	ISFPMAC	ATHOPEN	Removed as of APAR PI59691
CONNECT		DEFAULT	No longer used due to multiple servers no longer allowed
CONNECT		AUXNAME(NONE)	Value NONE no longer used since SDSFAUX is required
CONNECT		AUXPROC(NONE)	Value NONE no longer used since SDSFAUX is required
GROUP	ISFGRP	LANG	No longer used due to removal of Japanese feature
PROPERTY		NAME(Panel.JDD.NoUseAux)	No longer used since SDSFAUX is required
PROPERTY		NAME(Panel.JM.NoUseAux)	No longer used since SDSFAUX is required

Toleration PTFs

- Allows SDSF V2R3 level ISFPRMxx to be shared with SDSF V2R1 and V2R2
 - PTF UI90063 (HGX7790)
 - PTF UI90064 (HGX77A0)
- Install PTFs at any time but prior to installation of SDSF V2R3

Main Menu Toleration

- New scrollable main menu may cause incompatibilities
 - SDSF batch scripts
 - Scripts that post-process SDSF output
- Revert to non-scrollable menu
 - ISFPRMxx custom property Panel.Main.DisableTable
 - Affects entire GROUP
 - Dummy allocation **ISFMIGMN** ddname
 - Affects only that job or user
- Non-scrollable menu will only show the options that fit
 - Options that are not visible are still available



SECURITY

- User must be authorized to connect to SDSF address space
 - Requires READ access to ISF.CONNECT.*system* in SDSF class
- SDSF class must be active and raclisted
 - SDSF V2R3 tolerates SDSF class not active or not raclisted
 - Specify CONNECT AUXSAF(NOFAILRC4) in ISFPRMxx
 - Permit user to SERVER.NOPARM in SDSF class to allow fallback to ISFPARMS
- SDSF/SDSFAUX SAF verify calls that result in RC=04 (indeterminate) will be failed
 - Use CONNECT AUXSAF(NOFAILRC4) in ISFPRMxx to override
- *We strongly recommend you implement SAF security for SDSF !!*

New SAF Resources

- New SAF resources for access to panels

Command	Resource Name	Class	Required Access
CFC	ISFCMD.ODSP.COUPLE. <i>system</i>	SDSF	READ
CFS	ISFCMD.ODSP.CFSTRUCT. <i>system</i>	SDSF	READ
CSR	ISFCMD.ODSP.CSR. <i>system</i>	SDSF	READ
DEV	ISFCMD.ODSP.DEVACT. <i>system</i>	SDSF	READ
FS	ISFCMD.ODSP.FILESYS. <i>system</i>	SDSF	READ
GT	ISFCMD.ODSP.TRACKER. <i>system</i>	SDSF	READ
NA	ISFCMD.ODSP.NETACT. <i>system</i>	SDSF	READ
SMSG	ISFCMD.ODSP.STORGRP. <i>system</i>	SDSF	READ
SMSV	ISFCMD.ODSP.SMSVOL. <i>system</i>	SDSF	READ
SSI	ISFCMD.ODSP.SUBSYS. <i>system</i>	SDSF	READ
VMAP	ISFCMD.ODSP.VIRTSTOR. <i>system</i>	SDSF	READ

New SAF Resources

- New SAF resources for panel objects (refer to Operation and Customization)

Command	Resource Name	Class	Required Access
CFC	ISFCFC. <i>connectionname</i>	SDSF	READ
CFS	ISFCFS. <i>structurename</i>	SDSF	READ
DEV	ISFDEV. <i>volser</i>	SDSF	READ/CONTROL
DYNX	ISFDYNX. <i>exitname</i>	SDSF	UPDATE/ALTER
FS	ISFFS. <i>filesystemname</i>	SDSF	READ
GT	ISFGT. <i>eventowner</i>	SDSF	READ
NA	ISFNETACT. <i>jobname</i>	SDSF	READ
SMSG	ISFSTORGRP. <i>storagegroupname</i>	SDSF	READ/UPDATE
SMSV	ISFSMSVOL. <i>volume</i>	SDSF	READ/UPDATE
SSI	ISFSUBSYS. <i>subsysname</i>	SDSF	READ
JC action	ISFJOB.MODULE. <i>owner.jobname.system</i>	SDSF	READ
JT action	ISFJOB.TASK. <i>owner.jobname.system</i>	SDSF	READ



DOCUMENTATION

Documentation

- SDSF Operation and Customization (SA23-2274-30)
 - ISFPARMS
 - Operator commands
 - Security definitions
 - Messages
- SDSF User's Guide (SC27-9028-30) – **New !!**
 - SDSF panels and commands
 - SDSF/REXX
 - SDSF/Java
- Download from IBM Publications Center
- View through Knowledge Center

Documentation

- SDSF REXXHELP command
 - Shows SDSF/REXX usage, syntax, and examples
- SDSF RGEN command
 - Generates starter SDSF/REXX execs and examples
- SDSF Javadoc
 - Contains SDSF/Java documentation
 - Download from `/usr/lpp/sdsf/java/classes/isfjcallDoc.jar`
- SDSF SEARCH command
 - Searches SDSF help system for word or phrase
 - Don't confuse with SRCH command

Documentation – SEARCH Command

```

Display Filter View Print Options Search Help
-----
SDSF MENU V2R3M0 RSPLEXOG RS86 LINE 1-25 (50)
COMMAND INPUT ==> search isfact SCROLL ==> HALF
PREFIX=* DEST=(ALL) OWNER=* SORT=NAME/A SYSNAME=*
ACTION=S-Select
NP NAME Description Group Status
  APF APF data sets System
  AS Address space memory Jobs
  CFC CF Connections Sysplex
  
```

Word or phase
to search for

```

Display Filter View Print Options Search Help
-----
Command ==> Search Help Row 38 to 53 of 71
Search for: ISFACT Show titles
Select a search result to display the help panel.
token on ISFACT
column values, using the ISFACT host environment
Address SDSF "ISFACT sdsf-cmd TOKEN((stem-name) | token-list) PARM(par
set by ISFEXEC or ISFACT in the returned TOKEN.stem variable and must
  
```

List of all help
panels found

Select panel
to display

Documentation – SEARCH Command

Display Filter View Print Options Search Help

Search Help

Row 41 to 56 of 71

SDSF REXX: Take Actions and Modify Columns

You invoke SDSF action characters and overtype, or modify, column values, using the ISFACT host environment command, as follows: More: +

Address SDSF "ISFACT sdsf-cmd TOKEN((stem-name) | token-list)
PARM(parms) (options)"

where:

sdsf-cmd
is the command for the panel. It must be the same SDSF command, including any parameters, that was previously entered with the ISFEXEC command.

stem-name
is the name of a stem variable containing one or more row tokens which identify the rows to be acted upon. Enclose stem-name in parentheses to indicate that it is a stem variable. The 0 variable in the stem must contain a count of the number of variables in the

Help panel containing
text is shown

Documentation – RGEN Command

```
Display Filter View Print Options Search Help
SDSF MENU V2R3M0 RSPLX06 RS86 LINE 1-25 (50)
COMMAND INPUT ==> rgen x SCROLL ==> HALF
PREFIX=* DEST=(ALL) OWNER=* SORT=NAME/A SYSNAME=*
ACTION=S-Select
NP NAME Description Group Status
APF APF data sets System
AS Address space memory Jobs
CFC CF Connections Sysplex
CFS CF Structures Sysplex
CK Health checker System
CSR Common storage remaining Memory
DA Active users Jobs
DEV Device activity Devices
DYNX Dynamic exits System
ENC Enclaves WLM
ENQ Enqueues System
FS File systems OMVS
```

```
Display Filter View Print Options Search Help
REXX Examples Row 1 to 15 of 22
Command ==>
Sort by type (F5) or description (F6).
Type Description
- Action Cancel a job
- Action Cancel a set of jobs
- Action Invoke an EXEC with the % action character
- Action List action characters
- Action List job data sets
- Action Modify a value for a set of jobs
- Action Modify values for selected jobs (overtyp)
- Browse Browse a single data set with EXECIO
- Browse Browse a single data set with ISFBROWSE
- Browse Browse check output
- Browse Browse check output from check history
- Browse Browse check output with ISFBROWSE
- Browse Browse job output with EXECIO
- Browse Browse job output with ISFBROWSE
- Browse Browse job output with ISFBROWSE - groups of lines
```

Documentation – RGEN Command

```
SDSF EDIT      RGEN TS5485.RS86.SPFTEMP1.CNTL      Columns 00001 00072
Command ==>                                         Scroll ==> HALF
***** Top of Data *****
000001 /* REXX */
000002 Arg debug
000003
==MSG>      Important: Copy this generated exec from temporary dataset
==MSG>      TS5485.RS86.SPFTEMP1.CNTL
==MSG>      and edit that copy to prevent your changes from being lost.
==MSG>
000004 /*****
000005 *
000006 *   SDSF RGEN Generated Example:
000007 *   Browse check output
000008 *
000009 *   This exec was generated by the SDSF RGEN command on
000010 *   Wednesday 2017/07/19 at 15:01:55.67.
000011 *
000012 *   5650-ZOS
000013 *   SDSF level = z/OS 02.03.00 (HQX77B0)
000014 *
000015 *   This sample uses function available since z/OS V1R9.
000016 *
=====
=====   For more information and examples, use the SDSF REXXHELP
=====   command. To search SDSF's help, use SEARCH search-string.
000017 *****/
000018
=NOTE= Tip: All SDSF/REXX execs must include the following statement:
000019 rc=isfcalls('ON')
```

RGEN generates a fully functional exec that you can modify

Documentation

- See “What’s New” in SDSF help panels for complete list of changes
 - From main menu, press F1

Display Filter View Print Options Search Help

COMMAND INPUT ===> HELP: SDSF -- Table of Contents

Select a topic by number, or press Enter to view topics in sequence.

- | | |
|--------------------------------|----------------------------------|
| 1 - What's new | 13 - Help commands |
| 2 - Job and workload panels | 14 - Action bar |
| 3 - Device and resource panels | 15 - PF keys and keylists |
| 4 - System information panels | 16 - Action characters |
| 5 - Search and scroll commands | 17 - Overtimeable fields |
| 6 - Filter commands | 18 - JES and MVS commands |
| 7 - View commands | 19 - Point-and-shoot |
| 8 - Printing data | 20 - Online library |
| 9 - Options commands | |
| 10 - Other commands | 99 - SDSF messages |
| 11 - Server commands | |
| 12 - SDSF command | REXXHelp - SDSF REXX (ISPF only) |

SEARCH - Search the help (ISPF only)

F1 = Help F10 = Previous Enter = Forward
F3 = Exit F7 = Up TOC = Menu

Display Filter View Print Options Search Help

COMMAND INPUT ===> HELP: What's New in SDSF

Select a topic or press Enter to view them in sequence.

- 1 - Main menu
- 2 - Network and device activity panels
- 3 - CF connection and structures panels
- 4 - File system panel
- 5 - Subsystem panel
- 6 - Generic tracker panel
- 7 - Common storage remaining and virtual map panels
- 8 - TCB and CDE panels
- 9 - Show column values
- 10 - New columns and overtypes
- 11 - Other enhancements and changes
- 99 - Enhancements in previous releases

F1 = Help F10 = Previous Enter = Forward
F3 = Exit F7 = Up TOC = Menu

Trademarks

The following terms are trademarks of Rocket Software, Inc. in the United States and/or other countries:

Rocket®

The following terms are trademarks of the International Business Machines Corporation in the United States and/or other countries:

IBM®, z/OS®

Other company, product, and service names may be trademarks or service marks of others.

Copyright ©1981, 2017 IBM Corp.

Copyright ©2015, 2017 Rocket Software, Inc. All Rights Reserved.

SDSF V2R3 Product Update

Questions ?

SDSF V2R3 Product Update

Thank You !

The Race to
15,000!

Don't miss
Thursday's Farewell
Reception!

PERSON

PROGRAM

PROJECT

Be a part of the...

HOOPLA!



Complete your session
evaluations at
www.share.org/evaluation
and see your progress on the
leaderboard!