



CADMANAGERTOOLS.COM

BatchInDatabase

*Automated Batch process tool for AutoCAD and
Verticals*

Compatible with AutoCAD 2012 to 2015





BatchInDatabase - Batch process for AutoCAD


Introduction:

The BatchInDatabase is a powerful and easy to use batch process tool for AutoCAD. It comes from years of experience in AutoCAD and it is one of the AutoCAD productivity tools developed by CADManagerTools.com.

It lets you effortlessly run multiple in-built commands on multiple drawings and it is compatible with 32-bit and 64-bit AutoCAD.

In this batch process drawings are being edited in the database level, so the time taken to accomplish the same task is much lesser than doing in BatchInEditor. Since drawings are processed in memory rather than opening in editor, there is limitation in accessing editor based commands which are available in “BatchInEditor” and the user defined lisp and script commands are not available here.

Each drawing can be executed with same or different set of multiple commands, the file list and command list can be exported for later use.



Installation:

The installer that ran when you downloaded this plug-in from Autodesk Exchange Apps has already installed the plug-in. You may need to restart AutoCAD to activate the plug-in. The command for command line is “CMT_BID”.






There is a limitation in unregistered version (Free version); the maximum number of files per session is limited to three (3) files only. But the limitation of three files per session could be continued by removing the processed files first. We strongly recommend registering the tool to have full access to it; registering your product to have full access in FREE and we need your information for our records only and the registration process is detailed at the end of this help file.

The registered users will benefit the full version, informed of new/updated commands, new version releases and new tools available to download from Autodesk Exchange Apps.

User Interface:

Add Drawings:

There are four methods available to add drawings to batch process and drawings currently opened in AutoCAD will be skipped.




Right Click Menus [Drawing List]:

1. **Add File(s) -> Files:** opens standard file selection dialog box.
2. **Add File(s) -> Folder:** opens standard folder browser dialog box. All drawing files from selected folder will be added to drawing list.






3. **Add File(s) -> Folder & Subfolders:** opens standard folder browser dialog box. All drawing files from selected folder and its subfolders will be added to drawing list.
4. Drag & Drop drawings from windows explorer.
 - **Remove File(s):** Removes selected files from list alternatively press “DEL” key
 - **Select All files:** Select all files in the list alternatively press “Ctrl” + “A” combination keys
 - **Import file list:** Import drawing list from exported drawing list. Drawing validity will be checked while importing. If any drawing in the list does not exist in the specified location or renamed then warning message will pops-up with missing drawing name.
 - **Export file list:** Export drawing list to user specified location for future batch use
 - **Clear file list:** Clears file list
 - **Select Layouts:** Individual layout can be selected for batch process, by default all layouts (“All”) option is set and if user wants to run commands on selected layouts then the selected layouts from the dialog box will be added.



Layout option chosen in individual commands will override this level. That means, if Model only option is chosen in commands, the layout selection is ignored and changes will be made only on model space.

Changes will be done only on selected layouts, if selected layout option is chosen in individual commands.

- **Fit view:** Realign the width of drawing list view headers
- **Reset status:** The batch process will process only files which are in default status (“...”), the default status of the file being processed will be changed during batch process, the succeeded files will be marked as “Done” and Failed will be marked as “Failed”. To rerun the processed file, the reset status command will reset the status of selected files to default status.
- **Open Drawing:** Opens a selected drawing
- **Export File list with commands:** Exports file list along with its associated commands
- **Import File list with commands:** Imports file list along with its associated commands
-  Double click on a single file will show “select layouts” dialog box





File sorting and moving:

Drawing List:	
A>> File Name	Path
A-01	P:\12
A-02	P:\12
A-03	P:\12
A-04	P:\12
A-05	P:\12
AS-01	P:\12
PB-BASE	P:\12
PB-EX41	P:\12
PB-EX61	P:\12
PB-TITLE	P:\12
S-01	P:\12
S-02	P:\12
S-03	P:\12
S-04	P:\12
T-01	P:\12

Drawing List:	
Z<< File Name	Path
T-01	P:\12
S-04	P:\12
S-03	P:\12
S-02	P:\12
S-01	P:\12
PB-TITLE	P:\12
PB-EX61	P:\12
PB-EX41	P:\12
PB-BASE	P:\12
AS-01	P:\12
A-05	P:\12
A-04	P:\12
A-03	P:\12
A-02	P:\12
A-01	P:\12

- Sort order - click on the drawing list view headers to sort - Ascending /Descending.
- Move file Up/Down - select files and Drag and Drop to the desired location.
- Status –Shows last saved drawing version.




Drawing version numbers could be quickly checked by adding files to drawing list.



Select Commands for Batch Process:

There are three methods available to select commands for batch

1. Double click on the command to select for batch process
2. Select a command and right click and select “Select Command”
3. Select a command and click “Select Cmd” button



The command buttons “Edit File” and “Reload File” are disabled and are kept for the purpose of having identical interface between the batch process tools “BatchInEditor” and “BatchInDatabase”.



Add Commands to file:


Each command will be assigned a command numbers in the command list view and the command numbers is linked to drawings. Multiple command numbers can be added or removed to a single or group of selected drawings and user can configure the way he/she wants to add commands to drawings in the settings dialog box.

The commands are executed in the order “Top to Bottom” from the commands selected for batch list and do not follow the command number sequence.

Drag and Drop the files within the list to change its order.



Right Click Menus [commands]:



- **Add Commands To File:** Add selected command numbers to selected files, First select the files to which you want to add the command then select single or group of commands and then select “Add Commands to File” from right click menu or click on “Cmd Add” button.
- **Remove commands From File:** Removes selected command numbers from selected files, First select the files to which you want to remove the command then select single or group of commands and then select “Remove Commands from File” from right click menu or click on “Cmd Remove” button.
- **Import Commands:** Imports commands from previously saved file, Though it saves time by cutting the command selection and setting it's values every time, there may be changes in

command functions in the new version and Updates, So It is recommended to pay attention in using saved command list with new/updated versions.

- **Export Commands:** Exports commands to user specified location
- **Remove Commands:** Delete selected commands from commands selected for batch list and this operation will remove the selected commands from file, if already added to files.
- **Clear All Commands:** Clears all commands from command list and clears commands from files.



- Double click on a single command to add that command to all selected files.



Settings:

There are five settings that need to be set it up before proceeding with current batch process and the settings can be saved or reverted to default settings.

Settings:

Timeout in seconds (>15) per drawing: 600

Maximum files (>5) per session: 100

Drawing Units: Millimeters

Drawing Version: ACAD 2010

Save Status: Save drawing

Drawing save path:

Test Run Run Batch Exit

The batch process is monitored with an external application “BatchInDatabaseMonitor.exe” for time out and the status of AutoCAD; if AutoCAD crashes or Batch process takes more time to process a drawing than the set timeout per drawing then the batch process will close AutoCAD and restart AutoCAD and Batch process without user intervention. The batch process monitor can be closed, if a user chooses to monitor the batch process.

1. **Timeout in seconds per drawing:** Set timeout in seconds that should be greater than 15 seconds, the default is set to 600 seconds which would be sufficient enough for most of the files but it is recommended to increase the timeout based on the speed of the system, drawing size and drawings with more layouts to print. Setting timeout to higher value will not affect the speed of batch process.
2. **Maximum files per session:** Restarts batch operation after maximum no. of files processed per session is reached. The default is set to 100 files but should be greater than 5 files. Set to higher values, if your files are not heavy and the AutoCAD performance is not dropping after processing the specified no. of files.
3. **Drawing version:** Set drawing save version

There are five options available

- a. As Original – No conversion on drawing version will be made
- b. ACAD 2013
- c. ACAD 2010
- d. ACAD 2007
- e. ACAD 2004
- f. ACAD 2000




4. **Drawing Units:** Set drawing units

There are seven options available

- a. As Original– No conversion on drawing units will be made
- b. Unitless
- c. Inches
- d. Feet
- e. Millimeters
- f. Centimeters
- g. Meters

5. **Drawing Save Status:** Set save options


There are four options available



- a. Save drawing: Saves drawing with selected drawing version and selected drawing units
- b. Save in different folder: Saves drawing to the specified location with selected drawing version and selected drawing units
- c. Save with prefix: Saves drawing with prefix (“BID-FILENAME”) in the same location from where it is currently opened with selected drawing version and selected drawing units
- d. Do not save



Run Batch:



Test Run: It is recommended to check the batch process with “Test Run” before running on hundreds of files and this will process only the first file in the drawing list.

Run Batch: Start batch process

Warning message will be shown, if no command is added to file.



Drawing version only can be changed with no command added to command list with “Drawing version” set to another version and save status set to any save option.

Exit: Exit batch dialog box



During the batch process, If timeout or maximum number of files per session reached then AutoCAD will be closed and reopened, So it is recommend to save and close all open files and at least one drawing (New/Existing) should be active during the batch process.



In situation where the batch operation did not restart automatically after AutoCAD crash or for some other reason, users will have no information of the current batch status .to restart the batch process manually from where it was terminated, run the command “CMT_RBID” to resume the batch process.



It is strongly recommended to disable all company specific AutoCAD startup settings , Events like document created, activated, closed and saving during the batch process or any other lisp running during file opening; At the start of each batch process a temporary file named “BatchInProgress.tmp” will be created under Documents folder and the same will be deleted at the end of batch process. If there are custom events setup in your environment to do some kind task during file opening process , disabling them by checking the presence of temporary file will avoid unexpected result





General Settings:

There are two types of settings available, Default and User

BiD Settings

Drawing Version: As Original Drawing Units: As Original

Batch timeout per drawing (>=15 sec) 600

Restart batch after no. of files processed per session (>=5) 100

Drawing Save Status
Save drawing

File name prefix for save in same folder with Prefix BIE-

Add command to files on command selection: None

Close Palettes during batch: Yes

Set size limit for Low disk space Warning: ☐ 1024 MB ☐ Stop batch Operation on low disp space

Start batch with settings: User

Save Close

1. **Default :** Default settings are disabled for modifications
2. **User:** User settings enable to modify the default settings and launch batch process with user settings
 - a. **Drawing version:** Set drawing save version
 - b. **Drawing units:** Set drawing units
 - c. **Batch timeout per drawing:** Set batch timeout per drawing and should be greater than 15 seconds
 - d. **Restart batch after no. of files processed:** Set maximum no. of files per session
 - e. **Drawing Save Status:** Set save type
 - f. **File name prefix:** Set file name prefix for the save option " Save with prefix"
 - g. **Add command to files on command selection:** There are three settings available.





- **None:** no action will be performed, means commands selected for batch process will not be added to file straight away. This is a default option.
- **Selected:** commands selected for batch process will be added to selected files.

First select the files from file list and then add command to batch

- **All:** commands selected for batch process will be added to all files in the file list

h. **Close Palettes during batch:** Closes the palettes to speed up batch process. It closes the following Palettes

1. Layer properties dialog box
2. Tool Palettes
3. External reference
4. Material browser
5. Quick calculator
6. Sun properties
7. Visual Styles
8. Markup dialog

i. **Set size limit for Low disk space warning:** Enable this to displays Low disk space warning message of file save location, set the size limit in Megabytes (MB) and enabling the option “Stop batch process on low disk space” will halt the batch process.

j. **Start batch with settings:** Set the startup setting option “Default” or “User”

k. **Save:** Click save to save the changes made to settings

l. **Close:** Close the dialog box



**Built-in commands:****Annotation Scales Remove:**

Removes all unused annotation scales

Annotation All Visible-ON/OFF:

Show/hide annotative objects for all scales in all layouts

Attribute - Create Drawing List:

Creates drawing list from selected attribute tags from all or selected layouts and Attribute block information from model space also can be exported to external text/CSV file

Video: <http://www.youtube.com/watch?v= 9o7pox2vOw>

Block Name: TTLB-TEXT

☒ Add custom File name prefix

	DRAWING NAME	DRAWING TITLE	SCALE	REVISION
▶	(FILENAMEPREFIX[8])	<LINE1>	<SCALE>	<REV>
	(LAYOUTNAME)	(SPACE)		
		<LINE2>		
		(SPACE)		
		<LINE3>		
		(SPACE)		
		<LINE4>		
*				


Export From: All layouts Save file to: P:\OUTGOING\ABC-DRAWING LIST FRO DD.csv Apply

- **Block Name:** Select block from drawing
- **Add custom:** Enable this option and choose custom value to add user specific values, file name prefix with specified number of characters from left of the file name and system variables
- **Add field:** Click to add field
- **Remove field:** Click to remove selected field

Double click on the header field to rename and combine the values in each column, drag and drop the columns to new position.


- **Export From:** specify option (All layouts, Selected layouts, Model)
- **Save file to:** specify location to save the drawing list in csv format.





Attribute - Export:


Export attribute values to external text file from entire drawing/ selected layouts/ All layouts and Model space.





Attribute Lock/Unlock Position:

Lock/Unlock single or multiple attribute values in model and layouts.



- **Lock Attribute:** Sets lock Attribute as current option
- **Unlock Attribute:** Sets Unlock Attribute as current option
- **Block Name:** Enter block name or pick from screen
- **Tag Name:** Block contains Attributes Tags will be added to Tag name or enter Tag name.
- **Entire drawing:** Updated in all layouts and Model.
- **All layouts:** Updated in all layouts.
- **Selected layouts:** Updated in selected layouts only.
- **Model:** Updated in Model only.
- **Apply to all Attributes:** Selected Lock/Unlock action will be carried out on all attribute definitions in a block.



Attribute Update:

Update single or multiple attribute values in model and layouts.

Video: Update Attribute - single <http://www.youtube.com/watch?v=e7qxFOq0waI>

Video: Update Attribute - searching empty value <http://www.youtube.com/watch?v=-kPmHlwwyFo>

Attributes - Update

Block Name:

Tag Name:

Find Text: ☒ CONCEPT

☐ Match whole word ☐ Match case ☐ Use wildcards ☐ Use Regex

Replace Text:

Copy from Tag: ☐ Update in:

Search Options

Find Text[AB] with no check box enabled will update Attribute value contain letters [AB]
Find Text[AB] with "Match whole name" enabled will update Attribute value equals [AB]
Find Text[AB*] with "Use wildcards" enabled will update Attribute value starts with [AB]
Find Text[*AB] with "Use wildcards" enabled will update Attribute value ends with [AB]
Find Text[~AB] with "Use wildcards" enabled will update Attribute value that donot contains [AB]
Find Text enabled and left with no search value(empty) searches Attribute value which is empty
Find Text enabled with value <> searches Attribute value which is not empty
Warning: Using Tilde symbol[~] will repalce whole Attribute value. Test run is highly recommended to check the result before apply this find and replce pattern.


- **Block Name:** Specify block name or pick from screen
- **Tag Name:** Specify Attribute Tag name to find matching Tag name from specified block.
- **Find Text:** This enables to update the attribute value which matches the find value.
- **Match whole word:** updates attribute which matches the whole find value.
- **Match case:** updates attribute which matches the find text case.
- **Use wildcards:** updates attribute which matches the wildcards search pattern.
- **New Value/Replace Text:** New value to replace existing value, if left empty that will clear the value.
- **Entire drawing:** All matching block will be updated in all layouts and Model.
- **All layouts:** All matching block will be updated in all layouts.
- **Selected layouts:** All matching block will be updated in selected layouts only.
- **Model:** All matching block will be updated in Model only.
- **Copy from Tag:** Copy value from another Attribute Tag.





Attribute Synchronize:

Synchronize attributes in entire drawing/model and layouts.



- **Block Name:** Enter block name or pick from screen
- **Entire drawing:** Attributes will be synchronized in all layouts and Model.
- **All layouts:** Attributes will be synchronized in all layouts.
- **Selected layouts:** Attributes will be synchronized in selected layouts only.
- **Model:** Attributes will be synchronized in Model only.



Attribute Tag Rename:

Renames single or multiple attribute definitions in model and layouts.

- **Block Name:** Specify block name or pick from screen
- **Find string:** Specify Attribute Tag name to find matching Tag name from specified block.
- **Rename string:** Specify rename value.
- **Entire drawing:** All matching block will be updated in all layouts and Model.
- **All layouts:** All matching block will be updated in all layouts.
- **Selected layouts:** All matching block will be updated in selected layouts only.
- **Model:** All matching block will be updated in Model only.
- **Number style:** Select number style.
- **Starting number:** Specify starting number.
- **Add increment number to Tag:** Specify increment number to all attribute Tag names.



Attribute - Update - Selected:

Update single or multiple attribute values in All/Selected layouts/Model. User can choose selected Attribute to be changed from the list.

Video: Update Attributes- group by selection <http://www.youtube.com/watch?v=hah4EqWc3Yg>

Select	TAG Name	Attribute Value
<input checked="" type="checkbox"/>	TITLE_1	XYZ PROJECT
<input checked="" type="checkbox"/>	TITLE_2	STORM WATER NETWORK
<input checked="" type="checkbox"/>	TITLE_3	LAYOT PLAN
<input checked="" type="checkbox"/>	TITLE_4	SHEET 01 OF 25
<input checked="" type="checkbox"/>	SCALE	1:1000
<input checked="" type="checkbox"/>	REV_NO	A
<input type="checkbox"/>		

- **Block Name:** Specify block name or pick from screen
- **Tag Name:** Select Attribute Tag name to be updated
- **Select All:** Selects all Attributes.
- **Update in:** Select an option from the list.



**Attribute - Update – By Custom Data:**

Create Attribute value by combining values from available custom data options to Update attribute in All/Selected layouts/Model space.

Video: Update Attribute - by custom values http://www.youtube.com/watch?v=Y4gVc_zkfpE

Video: Update Attribute - by custom values in ModelSpace <http://www.youtube.com/watch?v=8LDA3XHF89I>

Block Name: TITLE TEXT-A1

Tag Name: TITLE 4 **Update in:** All layouts

Find Text:

☐ Match case ☐ Use wildcards ☐ Match whole word

Parameter	Attribute Value	Information
Custom_Value	SHEET	Any string value
CounterStart_Increment_Digits	1,1,3	Starting number,Increment,No of digits (1,1,1)
Custom_Value	OF	Any string value
Layout_Count	3	No of digits (1=1, 2=01, 3=001)
▶*		

Find Text[AB] with no check box enabled will update Attribute value contain letters [AB]
 Find Text[AB] with "Match whole name" enabled will update Attribute value equals [AB]
 Find Text[AB*] with "Use wildcards" enabled will update Attribute value starts with [AB]
 Find Text[*AB] with "Use wildcards" enabled will update Attribute value ends with [AB]
 Find Text[~AB] with "Use wildcards" enabled will update Attribute value that donot contains [AB]
 Find Text enabled and left with no search value(empty) searches Attribute value which is empty
 Find Text enabled with value <> searches Attribute value which is not empty
 Warning: Using Tilde symbol[~] will repalce whole Attribute value, Test run is highly recommended to check the result before apply this find and replce pattern.

- **Block Name:** Specify block name or pick from screen
- **Tag Name:** Select Attribute Tag name to be updated
- **Update in:** Select an option to update in All/Selected/Model space from the list.
- **Find Text:** Enable this option to search and replace matched values
- **Delete Row:** Deletes the selected row



**Attribute - Update - Title Block:**

Update single or multiple attribute values in All/Selected layouts. User can check value in one block and update another block if condition meets or check the value of one item and update the other in the same block

Video: *Update Attribute - based on another Attribute value* <http://www.youtube.com/watch?v=vtbRwEZiFP8>

Find Text[AB] with no check box enabled will update Attribute value contain letters [AB]
 Find Text[AB] with "Match whole name" enabled will update Attribute value equals [AB]
 Find Text[AB*] with "Use wildcards" enabled will update Attribute value starts with [AB]
 Find Text[*AB] with "Use wildcards" enabled will update Attribute value ends with [AB]
 Find Text[~AB] with "Use wildcards" enabled will update Attribute value that donot contains [AB]
 Find Text enabled and left with no search value(empty) searches Attribute value which is empty
 Find Text enabled with value <> searches Attribute value which is not empty
 Warning: Using Tilde symbol[~] will repalce whole Attribute value, Test run is highly recommended
 to check the result before apply this find and replce pattern.


- **Block Name to update:** Specify block name to be updated or pick from screen
- **Tag Name to update:** Specify Attribute Tag name to update its value.
- **Find Text:** This enables to update the attribute value of block name to update which matches the find value in block name to search.
- **Match whole word:** updates attribute which matches the whole find value.
- **Match case:** updates attribute which matches the find text case.
- **Use wildcards:** updates attribute which matches the wildcards search pattern.
- **Replace Text:** New value to replace existing value, if left empty that will clear the value.
- **All layouts:** All matching block will be updated in all layouts.
- **Selected layouts:** All matching block will be updated in selected layouts only.
- **Block Name to search:** Specify block name to be searched or pick from screen
- **Tag Name to search:** Specify Attribute Tag name to search for value.
- **Copy from Tag:** Copy value from another Attribute Tag, by default tag names from block name to update will be listed, to list tag names from search block enable the option.





Block – Convert Dynamic to Static:

Convert dynamic block to static block, Dynamic blocks converted to static block will have random number added as prefix to block name.




- **Block Name** : Specify block name or pick from screen
- **All layouts**: All matching block will be converted to static block from all layouts.
- **Selected layouts**: All matching block will be converted to static block from selected layouts.
- **Model**: All matching block will be converted to static block from Model only.
- **Entire drawing**: All matching block will be converted to static block from all layouts and Model.
- **Match whole name**: Whole Block name matching to given value will be converted to static block
- **Use wildcards**: supports wildcards search, refer to search options.
- **Apply to all**: All dynamic blocks will be converted to static block.
- **Include Nested Blocks**: Enabling this option will include nested blocks.





Block - Delete:

Delete blocks from model and layouts.



- **Block Name** : Specify block name or pick from screen
- **All layouts**: All matching block will be deleted from all layouts.
- **Selected layouts**: All matching block will be deleted from selected layouts.
- **Model**: All matching block will be deleted from Model only.
- **Entire drawing**: All matching block will be deleted from all layouts and Model.
- **Match whole name**: Whole Block name matching to given value will be deleted.
- **Use wildcards**: supports wildcards search, refer to search options.
- **Include Nested Blocks**: Enabling this option will include nested blocks.



This command can be used to delete xref files (Title block from multiple layouts) which cannot be detached, if it is inserted more than one layouts.



Block - Insert:

Insert an existing block within the file or insert a whole external file as a block or a block from an external file. If a block already exists in the file then the existing block definition will be used.

Block Name: REV TEXT-A1

Block Path: P:\XREF\REV TEXT-A1.dwg

Insert block from external file

☐ No ☒ Insert whole external file as a block ☐ Insert a block from an external file

Insertion Point

X: 0.0000

Y: 0.0000

Z: 0.0000

Scale / Rotation

Scale: 1.0000

Rotation: 0

Explode: No

Insert in: All layouts

Apply

- **Block Name:** Specify block name or pick from screen

Insert block from external file


- **No:** Choose this option, if block already exists in a file.
- **Insert whole external file as a block:** Choose this option to insert a whole external file as a block, browse to file location and the file name will be used as block name. If different block name is given that is not same as file name then the block name will be used.
- **Insert a block from an external file:** Choose this option to insert a particular block from an external file
- **Insertion Point:** Specify X, Y, Z coordinate values.
- **Scale/Rotation:** Specify Scale and Rotation angle.
- **Explode:** Yes – will explode the inserted block.
- **Insert in:** - All Layouts – block will be inserted to all layouts; selected layouts - block will be inserted to selected layouts only; Model – block will inserted to Model space only.





Block – Move/ Rotate/ Scale:

Move, Rotate and Scale existing blocks in Model and Layouts.



- **Block Name** : Specify block name or pick from screen
- **All layouts**: All matching block will be edited from all layouts.
- **Selected layouts**: All matching block will be edited from selected layouts.
- **Model**: All matching block will be edited from Model only.
- **Entire drawing**: All matching block will be edited from all layouts and Model
- **X Displacement**: Specify X offset value
- **Y Displacement**: Specify Y offset value
- **Rotation**: Specify rotation value
- **Scale**: Specify scale value




Block - Replace:

Replace block with another block both exist in the same drawing or replace block with new block from external file.

To redefine a block with another block exist in an external file make sure you have same block name in the external file.

Video: http://www.youtube.com/watch?v=mmC_vPc6MHM



Blocks can be replaced in entire drawing, Model only and in all layouts or selected layouts

- **Find block name:** Specify block name to search.
- **Replace block name:** Specify replace block name.

Replace block from external file

- **Find and Replace blocks are exist in the drawing:** Replaces find block with replace block, both (Find&Replace) blocks must exist in the drawing.
- **Insert whole external file as a block:** Replaces find block with another external file.
- **Insert Replace block from external file:** Replaces find block with another block from external file.
- **Layout Only:** will be searched and replaced in all layouts, if layout selection was made then block will be replaced from selected layouts only.
- **Model Only:** will be searched and replaced in Model only.





- **Entire drawing:** will be searched and replaced in all layouts and Model
- **Ignore find block Attributes:** find block attributes will be discarded and replace block attributes will be added, If replace block has attributes.
- **Retain all Attributes properties for matching Tags:** The matching find block attribute Tag name with replace block attribute Tag name properties (Text Style, height, color, position, rotation) are retained otherwise the find block attributes will be deleted and new Tags from replace block are added.



Use this option to add new entries to existing attribute definition or remove

To add new attribute to an existing attribute, the replace block should have all the attribute tag names matching to find block attributes with new Tag name to add.


To remove attribute from an existing attribute, the replace block should not include that particular attribute Tag.

- **Retain Attribute values only for matching Tags:** The matching find block attribute Tag name with replace block attribute Tag name values are retained and replace block attribute properties (Text Style, height, color, position, rotation) will be applied.



Block – Set Layer:

Change the layer of inserted block to a specific layer or to its parent layer




- **Block name:** Specify block name or pick from screen
- **Layer name:** select a layer from the list or enter layer name, It will create the layer, if specified layer does not exist.
- **All layouts:** All matching blocks will be changed to specified layer from all layouts.
- **Selected layouts:** All matching blocks will be changed to specified layer from selected layouts only.
- **Set block to parent layer:** blocks will be changed to its parent layer.



Block – Toggle Annotative:

Converts Annotative block to non-Annotative and vice-versa.




- **Toggle Annotative** : OFF will set annotative block to non-Annotative; ON will set non-Annotative block to Annotative block
- **Block Name** : Specify block name or pick from screen
- **Match whole name**: Whole Block name matching to given value will be modified
- **Use wildcards**: supports wildcards search, refer to search options.
- **Apply to all**: All blocks in model and layouts will be modified.
- **Search in nested blocks**: Enabling this option will include nested blocks.






Change to ByLayer:

Change all entities properties to Bylayer



DrawOrder - ByBlock:

Change the draw order of block to bottom or top




- **Block name:** Specify block name or pick from screen
- **Draw Order:** Select Move To Bottom or Move To Top option.
- **All layouts:** All matching blocks draw order will be changed from all layouts.
- **Selected layouts:** All matching blocks draw order will be changed from selected layouts only.
- **Model:** All matching blocks draw order will be changed from Model space only.



DrawOrder – By Layer:

Change the draw order of all entities in a specific layer to bottom or top




- **Layer name:** Select a layer name from the list or enter layer name.
- **Draw Order:** Select Move To Bottom or Move To Top option.
- **All layouts:** All matching blocks draw order will be changed from all layouts.
- **Selected layouts:** All matching blocks draw order will be changed from selected layouts only.
- **Model:** All matching blocks draw order will be changed from Model space only.

Education Stamp - Status:

Reports the presence of education water mark stamp

Entity - Erase:

Erase entities of similar type, size, location and layer



- **Entities to Erase:** Select reference entities to erase from drawing. First set the Model or layout as current from where you want to erase entities then set Model/Layout for the Erase from option and then select pick from the screen button to select the entities from current space
- **All layouts:** All matching entities will be erased from all layouts.
- **Selected layouts:** All matching entities will be erased from selected layouts only.
- **Model:** All matching entities will be erased from Model space only.
- **Entire Drawing:** All matching entities will be erased from Model space and all layouts.

Include Entity Type: This option can be used alone and combination of other options



If it is used alone, this will erase selected entity type

For example, if the selection contain circle, line and text then all the circles, lines and text entities will be erased.

Include Entity Size and Location: This option cannot be used alone and should be used combination of other options

If it is used with “Include Entity Type”, this will erase entities which matches the selected entity type, size and location

Include Layer: This option can be used alone and combination of other options

If it is used alone, this will erase entities which layer is one of the layers of the reference entities selected for erase



Use this option to delete layer, like layer kill command, enabling the option “Search layer inside block” will search the entities in particular layer and erases them.



Warning: Blocks containing entities in that layer will be erased and block redefined


If it is used with “Include Entity Type”, this will erase entities which matches the selected entity type and layer combination

If it is used with “Include Entity Type” and “Include Entity Size and Location”, this will erase entities which matches the selected entity type, size, location and layer combination



Export - DXF:

Creates DXF files with specified format



Export location: Set the path for DXF file, file name will be same as drawing name.

Export DXF file to drawing location: DXF file will be saved to drawing location.


DXF Format: Select DXF file format.





Image – Detach/Reload/Unload:

Detach/Reload/Unload a single or multiple images by its reference name or by its path.




- **Image name:** Specify image reference name (see search options). All images in the current drawing will be listed for selection or user can input the image name in the name field.
Match whole name: Finds only whole words that match the image name.
- **Use wildcards:** Allows the use of wild-cards in searches.
- **Image path:** Alternatively image can be searched by its path; there may be cases where a single image is attached with different image reference names. In such cases the command will be executed on all image names those use the same file; enable the check box to browse and select a drawing file.
- **Detach:** Detaches image
- **Reload:** Reloads image
- **Unload:** Unloads image
- **Apply to all Images:** The selected action (Detach/Reload/Unload) will be applied to all images.





Image - Extract:

Extract attached images from drawing. This command is useful to send the images with bound drawings. Images from the attached xref files could not be extracted but use this command after bind command to copy the images from bound xrefs.



Path to save image: Set the path for extracted images.

Save image file to drawing location: images will be saved to drawing location.





Image - Insert:

Attaches image to drawing.

Image Name:
I:\CADManagerTools\12-3333\Images\Stair Details.JPG Browse

Insertion Point
X: 0.0000
Y: 0.0000
Z: 0.0000

Scale / Rotation
Scale: 1.0000
Rotation: 0

Path Type: Full Path
Insert in: All layouts

Apply

- **Image Name:** Image file name to attach
- **Insertion Point:** Specify X, Y, Z coordinate values.
- **Scale/Rotation:** Specify Scale and Rotation angle.
- **Path Type:** Specify path type Full Path/Relative Path/No Path
- **Insert in:** - All Layouts – Image will be inserted to all layouts; selected layouts - Image will be inserted to selected layouts; Model – image will be inserted to model space.






Image – Is Referenced:

This command searches through drawings to find out the presence of specified image and add the path to the list


Search can be done either by name or by its full path (path and filename)





Layer - Create:

Create new layer and set it to current layer or set the existing layer to current.



- **Layer Name:** Specify full layer name.
- **Set as current layer:** Enable this option to set the specified layer as current.
- **Apply Line Type:** Enable this option and select line type from the list.
- **LineType file:** Specify linetype file name to load the specified linetype.
- **Apply Line Width:** Enable this option and select line width from the list.
- **Apply Transparency:** Enable this option and set transparency value.
- **Apply Color:** Enable this option and choose either index or true color from the color dialog box.




To make an existing layer as a current layer enter the existing layer name and enable “Set as current layer” option and if needed, the existing layer properties could be changed by enabling and assigning values.



Change Layer Properties:

Change properties and status of xref/non-xref layers.



- **Apply to non-Xref layers:** layer properties and status changes will be applied to non-Xref layers only
- **Apply to Xref layers:** layer properties and status changes will be applied to Xref layers only
- **Layer Name:** Specify valid layer name (refer Layer search options)
- **Apply Line Type:** Enable and select line type from the list.



- **Apply Line Width:** Enable and select line width from the list.
- **Apply Transparency:** Enable and set transparency value.
- **Apply Color:** Enable and choose either index or true color from the color dialog box.
- **On/Off:** Enable to change On/Off status of layers.
- **Thaw/Freeze:** Enable to change Thaw/Freeze status of layers.
- **Lock/Unlock:** Enable to change Lock/Unlock status of layers.
- **Plot/nonPlot:** Enable to change Plot/nonPlot status of layers.

Xref search options:

This gives additional option to change layer properties of an individual external reference.

External reference name: Specify Xref reference name to make changes only to a particular Xref layers.

External reference file: Select Xref reference file to make changes to Xref layers which references match the reference path.

All Xrefs: Apply changes to all Xrefs.





Layout Name Find and Replace:

Find and replace layout names.

Video: <http://www.youtube.com/watch?v=3GY2hPIMTqY>

BiD Layout Name Find and Replace

Find What: SW

Replace with: SD

Add Prefix: Add Suffix:

Replace in: All layouts

Number style: 001, 002, 003... Starting number:

☐ Drawing name as layout name Apply

Layout search options

- Find[*] & Replace[-RD] = Adds "-RD" as suffix to layout name
- Find[*] & Replace[RD-] = Adds "RD-" as prefix to layout name
- Find[*] & Replace[RD-] & Starting number[1] = Replaces layout name with RD-1, RD-2, RD-3....
- Find[*] & Replace[*] & Starting number[1] = Adds counter number to layout name
- Find[*] & Replace[] & Starting number[1] = Clears layout name and add counter number
- Find[RD] and Replace[SW] = Replaces "RD" with "SW"
- Find[RD] and Replace[] = Clears "RD" from layout name
- Find[*] & Replace[*] & Prefix/Suffix= Adds Prefix/Suffix to layout name

- **Find What:** Specify search strings.
- **Replace with:** Specify replace s Find What: Specify search strings.
- **Add Prefix:** Specify prefix value to add to layout name.
- **Add Suffix:** Specify suffix value to add to layout name
- **Replace in:** Choose All layouts or selected layout only.
- **Choose number style and starting number to add increment number to layouts**
- **Drawing name as layout name:** Enable this option to rename layout name as drawing name

If drawing contains more than one layout, counter number will be added.

e.g – Drawing name: A-BLDG-PLAN

First Layout name: A-BLDG-PLAN-1

Second Layout name: A-BLDG-PLAN-2 and so on.





Layout - Delete:

Delete layout which matches search criteria.

Layout Selection: Search in All layouts Layout name: *NP

Layout Tab Order: Match whole name Use wildcards

Search Options Apply

Layout name[AB] with no check box enabled will delete a layout contain letters [AB]
Layout name[AB] with "Match whole name" enabled will delete a layout name equals [AB]
Layout name[AB*] with "Use wildcards" enabled will delete a layout name starts with [AB]
Layout name[*AB] with "Use wildcards" enabled will delete a layout name ends with [AB]
Layout name[***AB*] with "Use wildcards" enabled will delete a layout name that donot contain [AB]
for more wildcards usage , see AutoCAD help "Find and Replace Text"

- **Layout Name:** Specify search strings for layout name.
- **Match whole name:** Delete layout which whole name matches to search layout name.
- **Use wildcards:** Delete layout which matches to search layout name pattern.

Layout Selection: Delete Layout By Tab Order Search in All layouts Search in Selected layouts Delete Selected layouts Delete All layouts Delete First layout Delete Last layout Delete Layout By Tab Order

Layout name: Match whole name Use wildcards

Search Options Apply

Layout name[AB] with no check box enabled will delete a layout contain letters [AB]
Layout name[AB] with "Match whole name" enabled will delete a layout name equals [AB]
Layout name[AB*] with "Use wildcards" enabled will delete a layout name starts with [AB]
Layout name[*AB] with "Use wildcards" enabled will delete a layout name ends with [AB]
Layout name[***AB*] with "Use wildcards" enabled will delete a layout name that donot contain [AB]
for more wildcards usage , see AutoCAD help "Find and Replace Text"

- **Search in All layouts:** Search will be done in all layouts.
- **Search in Selected layouts:** Search will be done only in layouts which are selected in the file list.
- **Delete selected layouts:** All layouts which are selected in the file list will be deleted.
- **Delete All layouts:** All existing layouts will be deleted and a new layout will be created
- **Delete First/Last layout:** First/Last layout will be deleted
- **Delete layout by Tab order:** Layout will be deleted based on the given tab order value





Layout – Set Current:

Sets the layout current which matches search criteria.

- **Layout Name:** Specify search strings for layout name.
- **Match whole name:** Sets layout current which whole name matches to search layout name.
- **Use wildcards:** Sets layout current which matches to search layout name pattern.

- **Search in All layouts:** Search will be done in all layouts.
- **Search in Selected layouts:** Search will be done only in layouts which are selected in the file list.
- **First Selected layout:** First layout of the selected layouts will be set as current
- **First/Last layout:** First/Last layout will be set as current
- **Last accessed layout:** The layout which was as current previously will be set as current(you open a drawing which was saved in Model space and you have multiple layouts , want to set to layout which was last accessed)
- **Delete layout by Tab order:** Layout will be set as current based on the given tab order value






Model - Set Current:

Sets the current space to Model space.

Page Setup - Import:


Imports page setup to all/selected layouts and set us current.





Page Setup – None:

This command sets the page setup to none to All/selected layouts or Model. Plot style name can be assigned so as to let the user know the last used pen style name (ctb) for printing




Paper Space - Set Active:

Sets the current space to last used layout or first layout.

PDF - Extract:


Extracts the overlaid PDF file to user specified location





Plotstyle - Report:

Reports the assigned page setup name, pen style for individual layouts and extracts the assigned plot style from drawing





Proxies - Erase:


Erases all proxy graphics from drawing.

PSLTSCALE Set to 0/1:

Sets PSLTSCALE in all layouts or selected layouts.

Purge - All:

Purge all unused items from drawing.




- **Include Locked Layers:** Locked layers will be unlocked and reset them back to locked state at the end of the purge operation.
- **Preserve Layer Properties:** Layer overwrite properties applied on xref layers will be preserved and it adds additional workload to purge command which leads to delay in completing the command.





Purge - DGN LineTypes:


Purge all DGN linetypes which comes from Microstation DGN files. All Xref files will be included in the purge process, if “Include Xrefs” option is selected or only the current file will be cleared of DGN linetypes.





Purge Shape File:

Purge not found shape files from the drawing.




- **Shape Font Path:** Set the font file path to load all available shx fonts to choose to substitute for missing file
- **Alternate Font Name:** Select the shx font to substitute the missing one
- **Purge Shapes from all Xrefs:** Includes all xref in removing missing shx fonts operation
- **Font Name to Replace:** The command will check the text styles for existence of all shx fonts name in the Shape File Path, if any font name is not exist then that file will be substituted by Alternate font name, In some cases font name will be same as the one exist in your font library but with different shapes defined in it, in such cases enter the font name to force to replace with font in your library.



Warning: All entities linetypes including in blocks will be changed to bylayer.

Rename Objects:

Cleans bound drawings by removing “XREFNAME\$0\$” prefix or rename objects (Layers, LineTypes, Blocks, Text Styles and Dimension Styles).




- **Remove \$0\$ from bind drawing:** Enabling this option will remove Xref name and \$0\$ prefix from the selected named objects. Counter number will be added as suffix, if name already exist.
- Disabling the above will allow to find and replace names from the selected named objects.



Save Drawing:

Add different save version, units and save status options to individual drawing.

Add this command as a last in the command list and set the drawing save status to “Do not Save” on the main Dialog to avoid saving them again with default settings.



Drawing version: Set drawing save version

There are five options available

- As Original – No conversion on drawing version will be made
- ACAD 2013
- ACAD 2010
- ACAD 2007
- ACAD 2004
- ACAD 2000

Drawing save status: Set save options

There are three options available

- Save drawing: Saves drawing with selected drawing version and selected drawing units
- Save in different folder: Saves drawing to the specified location with selected drawing version and selected drawing units
- Save with prefix: Saves drawing with prefix (“BIE-FILENAME”) in the same location from where it is currently opened with selected drawing version and selected drawing units





Drawing units: Set drawing units

There are seven options available


- a. As Original– No conversion on drawing units will be made
- b. Unitless
- c. Inches
- d. Feet
- e. Millimeters
- f. Centimeters
- g. Meters





Text – Find&Replace:

Finds and replaces text, Mtext, Leader and Attributes.



- **Find What:** Specify text string you want to find.
- **Replace with:** Specify the text string you want to use to replace the found text.
- **Text Types:** Specify the type of text objects you want to include in the search

Text/Dtext: Includes text objects such as single-line in search results.

Multi-line Text/Leader text: Includes text objects such as Multi-line text and Leader object in search results.

Block attributes value: Includes block attribute text values in search results.

Find Whole word only: Finds only whole words that match the text in Find What. For example, if you select Find Whole Words Only and search for "TEST," FIND does not locate the text string "TESTED".

Search In: Specify whether to search the entire drawing, Layout only or Model only





- Search in blocks: search text types in all blocks.
- **Trim text at left side:** Update value with new value which matches find value and Trim all text at left side of the text.
- **Trim text at right side:** Update value with new value which matches find value and Trim all text at right side of the text.

VBA Macro Remove:


Remove all attached VBA macros from drawing.





Viewport – Apply Layer State:

Apply layer state to all layouts.



First activate a viewport in a layout and prepare a viewport with required layer override properties then select the viewport to copy the properties to viewports which are meet the viewport selection option.

Viewport Selection:


- **Apply to similar location and size:** Apply layer state to viewports which matches the reference viewport location and size in all layouts.
- **Apply to similar sizes:** Apply layer state to viewports which size matches to reference viewport size in all layouts.
- **Apply to all Viewports:** Apply layer state to all viewports in all layouts.
- **Apply to Viewport Area >=:** Apply to viewports which area is greater than or equal to reference viewport in all layouts, useful for clipped viewports which are in different sizes
- **Apply to Viewport Area <=:** Apply to viewports which area is less than or equal to reference viewport in all layouts





Viewports – Change Layer:

Changes viewport name is all/selected layouts6t5.



Viewports Lock-All:

Lock all viewports in all layouts.

Viewports Objects Turn-ON:

Turns the viewport objects visibility ON.

Viewports UnLock-All:

Unlock all viewports in all layouts.

Viewports – Visibility OFF/ON:

Sets the viewport visibility hide/show.




Warning: There is no legacy AutoCAD command to turn the viewport visibility ON, So make sure if the file with viewport visibility turned OFF is sent to someone outside of your place have access to this tool or similar to turn them back if needed.





Xref - Bind:

Bind all external references with selected bind method.



External references with unloaded child Xrefs would fail during bind operation, So the bind command repath all unloaded child xrefs to an empty drawing called “\$blank.dwg”

Bind method: Set the bind method “Bind” or “Insert”




To confirm the success of bind operation, user can add the command “Xref-Status” after the bind command which will confirm with message “No Xref found” if the bind operation was successful else it will list all the xrefs and its status





Xref – Change Path type:


Change the path type to Relative Path/Full Path/No Path/Custom Path for single or multiple references



- **Path Type:** There are four options available Make Relative Path/Make Full Path/Make No Path/Make custom path. The path type of all selected references will be changed to selected path type
- **Custom Value:** Selecting “Make custom Path” enables this box to add custom value
- **Single item:** The path type of single reference will be changed to selected path type, browse to reference file (only one reference type can be changed)and select the file path

Xref - Copy:

Copy xrefs (parent/child) to user specified location or drawing location.




To send out the main file and its references use this command for drawings, add command Image-Extract for images and PDF-Extract for PDF files



Xref – Create Drawing List

Create drawing list file of xref drawings which can be loaded into batch file list for further process



Xref – Detach Overlay:


This command detaches all overlay parent xrefs





Xref – Detach/Reload/Unload:

Detach/Reload/Unload a single or multiple external references (drawing only) by its reference name or by its path.



- **Xref name:** Specify Xref reference name (see search options). All Xrefs in the current drawing will be listed for selection or user can input the reference name in the name field.
Match whole name: Finds only whole words that match the value in Xref name.
- **Use wildcards:** Allows the use of wild-cards in searches.
- **Xref path:** Alternatively Xref can be searched by its path; there may be cases where a single drawing is attached/overlayed with different Xref names. In such cases the command will be executed on all Xref names those use the same file; enable the check box to browse and select a drawing file.
- **Detach:** Detaches Xref
- **Reload:** Reloads Xref
- **Unload:** Unloads Xref
- **Apply to all Xrefs:** The selected action (Detach/Reload/Unload) will be applied to all Xrefs.


Xref – Detach_Unloaded:

This command detaches all unloaded parent xrefs



Xref - Insert:

Attach or Overlay a drawing to selected layout (Model/Paper space)



The image shows a Windows-style dialog box titled "Xref - Insert". It contains several input fields and dropdown menus. At the top, there is a "Xref Name:" field with the text "TITLE BLOCK-A1" and a "Xref Path:" field with the text "P:\XREF\TITLE-BLOCK-A1.dwg". Below these are three sections: "Insertion Point" with X, Y, and Z coordinate fields (all set to 0.0000), "Scale / Rotation" with Scale (1.0000) and Rotation (0) fields, and "Reference Type" (Overlay), "Path Type" (Full Path), and "Insert In" (All layouts) dropdown menus. An "Apply" button is at the bottom right.


- **Xref name:** Specify Xref reference name.
- **Xref path:** Specify Xref path.
- **Insertion Point:** Specify X, Y, Z coordinate values.
- **Scale/Rotation:** Specify Scale and Rotation angle.
- **Reference Type:** Specify whether the external reference is an attachment or an overlay
- **Path Type:** Specify path type Full/Relative/No pathy
- **Insert in:** -All layouts – Xref will be inserted to all layouts; if layout selection was made then Xref will be inserted to selected layouts only.



Xref – Is Referenced:

This command searches through drawings for the presence of a specified drawing reference and add the resulting file path is added to the list.

Search can be done either by name or by its full path (path and filename)



- **Include child Xref in Search:** Includes the child xref in the search of references.
- **Refresh Xref Status:** The status of the found references will be reported




Xref - Redirect:

Redirect references, xref, Image, PDF underlay and DWF underlay will be redirected to new location. Use this command to redirect all references to new location:

Enter * in old path which means all selected reference type will be redirected to new location

Alternatively use this command to find and replace a part of path with new path values

Each reference file which is going to be changed will be checked for the existence in the new location; if the reference file does not exist in the destination location then the path of that file will not be updated



- **Search in sub-folders:** Enabling this option will search for the new references in the current folder value given in the new path and its sub-folder.

If there are two or more same file names exist in current and sub-folders, the first one from the current folder will be taken

- **Search Path type:** There are two options Found At Path/Saved Path, if mixed path are used then Found At Path will handle these multiple path types and the Saved path will work only with Full path xrefs






Usage:

Example-1

You have an image "Test.jpg" which has been referenced in multiple files

You create another image with same name but different image type, let us say "Test.png"

Since we are changing only the extension, the path will remain same, so both images should be in the same folder, the command checks the file first for its location, if found then replace the name, thus the reference is changed to new image type.




Example-2

You have an image "P:\ABC-123\DD\Images\Test.jpg" which has been referenced in multiple files

You have another image which is located in different directory "P:\ABC-123\WD\Images\Test.jpg"

Here we have a part of image path is different, the command parameter will be as below






Example-3

You have an image "P:\ABC-123\DD\Images\Test.jpg" which has been referenced in multiple files

You have another image which is located in different directory "P:\ABC-123\WD\Images\NEW.png"


Here we have a different path, file name and image type, the command parameter will be as below





Xref - Rename:

Rename a single or all external reference names to its parent file name (drawing only)



- **Search Option:** There are three options available All Parent Xrefs/By Reference Name/By Reference Path.
- **Find Value:** provide xref name for option By reference Name or xref full path for option By reference path
- **Match whole name:** For reference name option, if enabled, the search will be done on the whole reference name otherwise all parent xref reference name which contains the find value will be renamed
- **Replace Value:** provide value to rename the xref name
- **Rename to source name:** Existing xref name is renamed to its file name
- **Preserve Xref layer properties:** Enable this option to keep all the xref layer properties and its status,




To revert all xref layer properties to its original file layer properties, add this command twice as detailed below

1. Set search option to “By reference Name”
2. Enter * in the find value and Enter any value following the * (example *-Temp)
3. This will add –Temp as suffix to all parent xref names
4. Add the command and repeat the same command with below steps
5. Set search option to “By reference Name”
6. Enter –Temp in the find value
7. Either enable “Rename to source name or leave the Replace value empty to remove the value added by first “Xref-Rename” command and Add the command



Xref - Replace Path:

Replace external references (drawing only) path to new path and xref name can be renamed to new parent file name.



- **Find Xref by name:** Select xref name from the list or enter xref name to find.
- **Find Xref by path:** Xref can be searched by its path, if more than one reference name having same path then all reference names will be repathed to new path
- **Repath Xref Name:** Specify new Xref path.
- **Rename to new Xref name:** Enable this option to rename Xref name to its parent file name.




Child reference names will be discarded.



Xref – Set as Attach / Overlay:

Swap external references status from Attach to Overlay or vice-versa.



- **Xref name:** Select xref name from the list or enter xref name to find.
- **Xref Path:** Xref can be searched by its path, if more than one reference name having same path then all reference names will be swapped to set status.
- **Apply to all xrefs:** Change all xrefs status to selected status

Xref - Status:

Shows the presence and status of Xrefs in drawing. The purpose of this command is to check presence of Xref and confirm the success/Failure of bind command. If there is no xref found in a drawing “No Xref found” will be logged to Batch status otherwise the Batch status log will show the name, path and status of Xref.






Xref – Swap with prefix matching

This command was added when there was a situation where users created xref name without a standard naming convention for xref prefix

Previous xref names were, “KEY PLAN”, “WATER NETWORK” and “ELECTRICAL MAINS” and the new xref name with standard prefix added were “X2-P702-110-KEY PLAN”, “X2-P702-110-WATER NETWORK” and “X2-P702-110-ELECTRICAL MAINS”




1. Enter Xref prefix to search in the the text box
2. Browse to new path where the new xrefs with added prefix are exist or enable “Search in current Xref location” to search in the old xref location
3. Enable “Include Child Xrefs” to open all xrefs and swap xref with added prefix.



Xref – Toggle Network Path:

This command toggles the xref path from “UNC Path to Mapped drive” or Mapped drive to UNC Path”



Zoom Extents:



Zoom extents the current space (Model/Layout)






Product Registration Process

1. Click About button



2. Click on Register Product button that will generate request code and Product serial number.




3. Copy and paste the Request code in your E-mail and send to register@cadmanagertools.com with below details
 - a. Your name/Company name
 - b. Product name (Batch-In-Editor or Batch-In-Database)





- c. Product Version (v1.0)
- d. Product serial number
- e. Request Code
- f. Build version(1.0.1.2)
- g. Country/State name

E-mail will be sent back with license key within 24 hours after verification of details submitted.



- 4. Repeat the steps 1 & 2 which will enable the first license key box
- 5. Copy and paste the License key which you have received from CADManagerTools.com into the first License key box.
- 6. Click the Validate Lic. Key button and Close the tool (Not AutoCAD) and restart it.
- 7. Now the About dialog box will show [Full version] and the registration process feature will be disabled.

