

AsTeRICS v2.8 Plugin Development StringFormatter Example


Martin Deinhofer, Department of Embedded Systems



Agenda


- Plugin characteristics
- Exercise definition
- Setup development environment
- ARE concept overview
- Plugin creation
- Build plugin
- Plugin activation and testing

- Is a functional block (component) with defined
 - **input ports:** receives data to be processed (e.g. face tracked coordinates)
 - **output ports:** send processed data (e.g. formatted string)
 - **event listener:** receive event and execute assigned action (e.g. left mouse click)
 - **event trigger:** send event to other functional blocks (e.g. time elapsed)
 - **properties:** Configure behaviour through property values



Exercise definition

- Create AsTeRICS plugin:
MyStringFormatter
- User can define string formats similar to printf function in C ([See Java-Class: Formatter](#))
- Input port values to be formatted
- Output port sends resulting formatted String
- Event Listener **sendFormattedStr**
 - formats and sends formatted string to port **formattedStr**
 - Triggers event **formattedStrSent**



Properties	
formatString	%1\$4.2f

Exercise Example

- String format

„%1\$4.2f“

- Code example

```
String formatted=String.format("%1$4.2f",3.32643423);
```

- Resulting output string


3.33

Setup Development Environment git Installation

1. Install GIT for Windows*

With the recommended settings in the screenshot (disable shell integration)


2. TortoiseGIT with predefined options



Setup Development Environment

Clone AsTeRICS

- Choose target folder for clone
- Rightclick in explorer folder and select
 - Git Clone



Setup Development Environment JDK & Eclipse installation

1. Download and Install the [Java Development Kit](#) (JDK8, **32 bit-version**)
2. Download and install/extract [Eclipse Luna](#) (32 bit-version)



In case of trouble, try to

1. Set “**JAVA_HOME**” to the JDK installation folder and add the JDK/bin path to the Environment Variable “**Path**”
2. and/or check the [Developer Manual](#)

Setup Development Environment


Create Eclipse Project

- Start eclipse.exe
- Choose File -> New -> Java Project in the Eclipse main menu, disable the option “*Use default location*” and browse to the *ARE* subfolder
- You should get a project as shown in the right picture



Right click on **bulid.xml** in the root folder of the ARE project
Run As -> Ant Build

Note: ARE must not run during build



Setup Development Environment


Run ARE

1. Go to bin/ARE folder
2. Start ARE with debug* output
start_debug.bat

- Important folders of source code repository
 - **ACS:** AsTeRICS Configuration Suite source code.
 - **ARE:** middleware and service layers and ARE components/plugins.
 - **ARE/components:** Source-code location of plugins, one folder per plugin. (**LICENSE** subfolder for involved licenses)
 - **APE:** tool and project template for creating standalone AsTeRICS-based SW packages
 - **bin:** subfolders where ARE, ACS and APE executable files are placed during the build flow.
 - **Documentation:** contains the User- and the Developer Manual, an OSKA manual and the license information for AsTeRICS source code and third party libraries.


ARE concept

- ARE middleware provides **Runtime Environment** for components/plugins
- Components based on **OSGi**
- Components can be
 - **Sensors:** Sense and create/send data (e.g. face tracker)
 - **Processors:** Process data (e.g. calculate moving average of data)
 - **Actuators:** Control environment (e.g. mouse cursor)




1. Plugin Creation Wizard → Generate plugin folder structure
 1. src folder
 2. ant build script
 3. Manifest file
 4. Bundle descriptor
 5. ...
2. Add plugin to Eclipse project
3. Implement plugin functionality
4. Build project
5. Activate Plugin in ACS
6. Create test model with plugin

Plugin Creation Wizard



- Define characteristics of plugin
- Generate folder structure, source code stubs and build script



The screenshot shows the 'AsTeRICS Plugin Creation Wizard' window. It has a title bar with 'Exit' and standard window controls. The main area is divided into several sections:

- Setup:** Contains fields for 'PluginName' (MyPlugin), 'Type' (processor), 'Subcategory' (Others), and 'Path to existing target folder' (C:\asterics\are\components\).
- Input Ports:** A list box containing 'myInPort (double)'. Below it are fields for 'Name' (myInPort), 'Data-Type' (double), and 'Description' (input port description), along with 'add Input Port' and 'delete' buttons.
- Output Ports:** A list box containing 'myOutPort (double)' and 'myOutPort2 (double)'. Below it are fields for 'Name' (myOutPort2), 'Data-Type' (double), and 'Description' (output port description), along with 'add Output Port' and 'delete' buttons.
- Event Listener Ports:** A list box containing 'myElpPort'. Below it are fields for 'Name' (myElpPort), 'Description' (elp description), and 'add Event Listener Port' and 'delete' buttons.
- Event Trigger Ports:** A list box containing 'myEtpPort', 'myEtpPort2', and 'myEtpPort3'. Below it are fields for 'Name' (myEtpPort3), 'Description' (etp description), and 'add Event Trigger Port' and 'delete' buttons.
- Properties:** A list box containing 'myProperty (integer)' and 'myProperty2 (integer)'. Below it are fields for 'Name' (myProperty2), 'Data-Type' (integer), 'Default Value' (1), 'Combo-Box Entries' (test1/test2/test3), and 'Description' (property description), along with 'add Property' and 'delete' buttons.
- Plugin-Description:** A text field containing 'My Plugin description'.
- Options:** Four checkboxes: 'Plugin is a Singleton', 'Plugin has a GUI', 'Plugin uses CIM Port Manager', and 'Plugin uses Java Native Interface (JNI)'. The first two are unchecked, and the last two are checked.
- Buttons:** A large 'CREATE PLUGIN!' button at the bottom right.

Plugin Creation Wizard

Common Parameter

- PluginName: „MyStringFormatter“
(CamelCase notation)
- Type: „processor“ (others: sensor, actuator)
- Subcategory: „Event and String Processing“
(See existing ACS components)
- Path to existing target folder:
<AsTeRICS ROOT>/ARE/components

Setup

PluginName:	<input type="text" value="StringFormatter"/>	Type:	<input type="text" value="processor"/>	Subcategory:	<input type="text" value="Event and String"/>	Path to existing target folder:	<input type="text" value="C:\asterics\are\components\"/>
-------------	--	-------	--	--------------	---	---------------------------------	--

Plugin Creation Wizard

Input Ports

Input Ports

in1Double (double)
in2Integer (integer)
in3String (string)

Name:

Data-Type:

Description:

Plugin Creation Wizard

Output Ports

Output Ports

formattedStr (string)

Name: formattedStr

Data-Type: string

Description: ng formatted string

add Output Port delete

Plugin Creation Wizard

Event Listener

Event Listener Ports

sendFormattedStr

Name:

Description:

Plugin Creation Wizard Event Trigger

Event Trigger Ports

formattedStrSent

Name: formattedStrSent

Description: atted string is sent.

add Event Trigger Port delete

Plugin Creation Wizard Properties

Properties

formatString (string)

Name:

Data-Type:

Default Value:

Combo-Box Entries:

Description:

Plugin Creation Wizard

Generate Plugin

Plugin-Description:

☐ Plugin is a Singleton

☐ Plugin has a GUI

X-size: Y-size: (% of screen size)


☐ Plugin uses CIM Port Manager

☐ Plugin uses Java Native Interface (JNI)

 **Click to generate**


Plugin Creation Wizard

Created folder structure




Source folder to Build Path

Add Java source folder
to Build Path



Right click on **bulid.xml** and
Run As -> Ant Build

Note: ARE must not run during build



Activate Plugin

ARE

1. Go to bin/ARE folder
2. Start ARE with debug output
start_debug.bat

ACS

1. Go to bin/ACS folder
2. Start ACS.exe
3. System/
Download Component
Collection

Member variables

```
final IRuntimeOutputPort opFormattedStr = new  
DefaultRuntimeOutputPort();  
// Usage of an output port e.g.:  
opMyOutPort.sendData(ConversionUtils.intToBytes(10));
```

```
final IRuntimeEventTriggererPort etpFormattedStrSent = new  
DefaultRuntimeEventTriggererPort();  
// Usage of an event trigger port e.g.:  
etpMyEtPort.raiseEvent();
```

```
String propFormatString = "%1$4.2f";
```

```
// declare member variables here  
//Hold values of incoming input port data  
private Double in1Double;  
private Long in2Integer;  
private String in3String;
```

Property setting & getting

```
/**
 * returns the value of the given property.
 * @param propertyName the name of the property
 * @return the property value or null if not found
 */
public Object getRuntimePropertyValue(String propertyName)
{
    if ("formatString".equalsIgnoreCase(propertyName))
    {
        return propFormatString;
    }
    return null;
}

/**
 * sets a new value for the given property.
 * @param propertyName the name of the property
 * @param newValue the desired property value or null if not found
 */
public Object setRuntimePropertyValue(String propertyName, Object newValue)
{
    if ("formatString".equalsIgnoreCase(propertyName))
    {
        final Object oldValue = propFormatString;
        propFormatString = (String)newValue;
        return oldValue;
    }

    return null;
}
```

Converting incoming port data

```
/**
 * Input Ports for receiving values.
 */
private final IRuntimeInputPort ipIn1Double = new DefaultRuntimeInputPort()
{
    public void receiveData(byte[] data)
    {
        //Convert incoming data to a double value.
        in1Double = ConversionUtils.doubleFromBytes(data);
    }
};
private final IRuntimeInputPort ipIn2Integer = new DefaultRuntimeInputPort()
{
    public void receiveData(byte[] data)
    {
        //Convert incoming data to a Long (not int) value, because Formatter class expects Long value
        instead of int.
        in2Integer=new Long(ConversionUtils.intFromBytes(data));
    }
};
private final IRuntimeInputPort ipIn3String = new DefaultRuntimeInputPort()
{
    public void receiveData(byte[] data)
    {
        //Convert incoming data to a String value.
        in3String=ConversionUtils.stringFromBytes(data);
    }
};
```

Formatting & Sending Data


```
/**
 * Formats and sends the resulting formatted string to the output port.
 */
private void formatAndSendString() {
    //get current format string
    String curFormatString=(String)getRuntimePropertyValue("formatString");
    //Execute actual formatting of string
    String formattedString=String.format(curFormatString, in1Double, in2Integer, in3String);
    //Convert formatted string to byte[] and send it to the output port
    opFormattedStr.sendData(ConversionUtils.stringToBytes(formattedString));
    //Inform others, trigger event
    etpFormattedStrSent.raiseEvent();
}
```

Implement Event Listener

```
/**
 * Event Listener Ports.
 */
final IRuntimeEventListenerPort elpSendFormattedStr =
new IRuntimeEventListenerPort()
{
    public void receiveEvent(final String data)
    {
        formatAndSendString();
    }
};
```



Test model

Properties	
number	20
delay	0
slot1	3.32643423
slot2	0
slot3	0
slot4	0
slot5	0
slot6	0
slot7	0
slot8	0
slot9	0
slot10	0
slot11	0
slot12	0
slot13	0
slot14	0
slot15	0
slot16	0
slot17	0
slot18	0
slot19	0
slot20	0
autosendSlot	1



Properties	
caption	Keyboard
horizontalOrientation	<input type="checkbox"/>
textColor	default
backgroundColor	default
borderColor	default
borderThickness	2
selectionFrameColor	default
selectionFrameThickness	4
displayGUI	<input checked="" type="checkbox"/>
buttonCaption1	Send formatted string

Test model – GUI Designer



Click on button „Send formatted string“

