

Cross-Project Piping

By Scott J. Pearson/Travis Wilson

Configure Cross Project Piping

This module must be enabled on the DESTINATION project. Once enabled the configuration is done with in the external module tab on the project.

Currently Enabled Modules

Cross-Project Piping - v1.1 Discoverable

Cross-Project Piping pipes from one field in one project into another field in another project. The projects have to be MATCHED on a third field in both projects. Enable this module in the DESTINATION project and select appropriate fields in the configure panel. As of 02/28/2018 the use of action tags for piping is deprecated and will be removed in a future release.

[View Documentation](#)

Configure

Disable

Project configurations that must be set up prior to field configurations.

1. Go to your DESTINATION project.
2. In the Destination project, click on External Modules on the left-hand navigation bar. Then click on the Configure button.
3. **Source Project:**

This field is a drop down list of all the projects the **configuring user** has access to.

Project Settings	Value
1. Source Project:	1. Pipe Project: <input data-bbox="1166 905 1195 930" type="button" value="+"/>
	<input type="text" value="Cross Project Piping/Enroll"/>

4. **Unique Match Field:**

Select the unique field on the destination project that represents the record (first field of project). REDCap uses record_id as the default value but can be different on every project.

1. Unique Match Field: Unique field used to match records across projects (usually the record_id):	<input type="text" value="record_id - Record ID"/>
--	--

5. **Alternate Source Match Field:**

This is used if the unique match field on the destination project is different from the source project. For example if Project A records are subject_id but Project B records are record_id.

1. Unique Match Field: Unique field used to match records across projects (usually the record_id):	<input type="text" value="record_id - Record ID"/>
--	--

1. Alternate Source Match Field: This is only used if the Unique Match Field in the destination project has a different variable name from the Unique Match Field in the source project:	<input type="text" value="subject_id"/>
--	---

Note all configurations can repeat, in the instance you need to pipe values from multiple projects into one. Simply select the + icon in the gray space at the top.

Setting up your piped field.

1. Select the destination field from the drop down list.

1.1. Destination Field:	1.1. Pipe Field: <input data-bbox="1138 1675 1167 1701" type="button" value="+"/>
	<input type="text"/>

2. You will only need to enter a value in the Source field if the variable name on the destination field is different from the source field.

1.1.

Source Field: This field is only needed if the Destination Field has a different variable name from the Source Field on the source project:

Note to add more piped fields select the + icon in the gray space to the right of Pipe Field:

Forms to allow piping

Here you will select the instrument piping will occur on. To add more than one instrument select the + icon to the right.

1. Active Form(s): Limit piping to only these forms:



Once all configurations have been set make sure to select save at the bottom.

Piping Mode

There are two different ways to use piping:

1. Auto pipe on incomplete- This method will always load the piping screen and bring data into the destination instrument every time the page is loaded unless the form is marked as complete.
2. Piping Button at top- This method will place an "Initiate Data Piping" button at the top of the designated instrument and only activate piping when selected.

Note: Auto piping will only run on 'Incomplete' status, and the piping button will only appear on instruments with an 'Incomplete' status. Once a record has moved from incomplete to any other status piping will not be available. The status can always be reverted to incomplete to utilize this function.

Piping Mode:

* must provide value

Auto pipe on Incomplete Form(s) ▼

Piping Mode:

* must provide value

Piping Button at top of Form(s) ▼

Please note that if cross project piping is used there is a risk of overwriting data in an instrument. Any record saved with data on it whether piped or not will save on that record.