

More Details www.AnoopCNair.com

Group Name	Located	Members	Use	Permission
ConfigMgr_CollectedFilesAccess	Primary Site	Full Admin Account - Membership includes administrative users that are granted the View Collected Files permission to the Collection securable object from an assigned security role.	This group is used by Configuration Manager to grant access to view files collected by software inventory.	Read permission to the following folder on the site server: %path%\Microsoft Configuration Manager\smv.box\FileCol.
ConfigMgr_DViewAccess	Primary Site	CAS Server	This group is a local security group created on the site database server or database replica server by CM12	
ConfigMgr Remote Control Users	Client	Permitted Viewers - When you add users to the Permitted Viewers list, they are automatically added to this group.	This group is used by Configuration Manager remote tools to store the accounts and groups that you configure in the permitted viewers list that are assigned to each client.	By default, this group does not have permissions to any locations on the computer, and is used only to hold the list of Permitted Viewers.
SMS Admin	SMS Provider	Each administrative user in a hierarchy and the site server computer account are members of the SMS Admins group on each SMS Provider computer in a site.	This group is used by Configuration Manager to grant access to the SMS Provider, through WMI. Access to the SMS Provider is required to view and modify objects in the Configuration Manager console.	SMS Admins rights and permissions are set in the WMI Control MMC snap-in. By default, the SMS Admins group is granted Enable Account and Remote Enable on the Root\SMS namespace. Authenticated Users has Execute Methods, Provider Write, and Enable Account
SMS_SiteSystemToSiteServerConnection_MP_XXX	SMS Provider	Computer Accounts of remote computers that have a MP for the site	This group is used by Configuration Manager management points that are remote from the site server to connect to the site database. This group provides a management point access to the inbox folders on the site server and the site database.	By default, this group has Read, Read & execute, and List folder contents permission to the %path%\Microsoft Configuration Manager\inbox folder on the site server. Additionally, this group has the additional permission of Write to various subfolders below the inboxes to which the management point writes client data.
SMS_SiteSystemToSiteServerConnection_SMSProv_XXX	Site Server	Membership includes the computer account or the domain user account that is used to connect to the site server from each remote computer that has installed a SMS Provider for the site.	This group is used by Configuration Manager SMS Provider computers that are remote from the site server to connect to the site server.	This group has Read, Read & execute, and List folder contents permission to the %path%\Microsoft Configuration Manager\inbox folder on the site server. Additionally, this group has the additional permission of Write or the permissions of Write and Modify to various subfolders below the inboxes to which the SMS Provider requires access. This group also has Read, Read & execute, List folder contents, Write, and Modify permissions to the folders below %path%\Microsoft Configuration Manager\OSD\boot and Read permission to the folders below %path%\Microsoft Configuration Manager\OSD\Bin on the site server.
SMS_SiteSystemToSiteServerConnection_Stat_XXX	Site Server	Membership includes the computer account or the domain user account that is used to connect to the site server from each remote site system computer that runs the File Dispatch Manager.	This group is used by the File Dispatch Manager on Configuration Manager remote site system computers to connect to the site server.	This group has Read, Read & execute, and List folder contents permission to the %path%\Microsoft Configuration Manager\inbox folder and various subfolders below that location on the site server. Additionally, this group has the additional permissions of Write and Modify to the %path%\Microsoft Configuration Manager\inbox\statmgr.box folder on the site server.
SMS_SiteToSiteConnection_XXX	Site Server	Configuration Manager automatically adds the computer account of the new site to the group on the parent site server, and the parent sites computer account to the group on the new site server. If you specify another account for file-based transfers, add that account to this group on the destination site server.	Configuration Manager to enable file-based replication between sites in a hierarchy. For each remote site that directly transfers files to this site, this group contains the following accounts:Accounts configured as a Site Address Account, from Configuration Manager sites with no service pack and Accounts configured as a File Replication Account, from Configuration Manager SP1 sites. In SP1, the File Replication Account replaces the Site Address Account.	This group has full control to the %path%\Microsoft Configuration Manager\inbox\despoolr.box\receive folder.

Configuration Manager automatically creates and in many cases, automatically maintains the following Windows groups: