

Module Interface Specification for Projectile

Samuel J. Crawford

July 3, 2019

Contents

1	Symbols, Abbreviations and Acronyms	1
2	Introduction	1
3	Notation	1
4	Module Decomposition	1
5	MIS of Control Module	3
5.1	Module	3
5.2	Uses	3
5.3	Syntax	3
5.3.1	Exported Access Programs	3
5.4	Semantics	3
5.4.1	State Variables	3
5.4.2	Access Routine Semantics	3
6	MIS of Input Parameters Module	5
6.1	Module	5
6.2	Uses	5
6.3	Syntax	5
6.4	Semantics	5
6.4.1	Environment Variables	5
6.4.2	State Variables	5
6.4.3	Assumptions	6
6.4.4	Access Routine Semantics	6
6.5	Considerations	7
7	MIS of Temperature ODEs Module	8
7.1	Module	8
7.2	Uses	8
7.3	Syntax	8
7.3.1	Exported Access Programs	8
7.4	Semantics	8
7.4.1	State Variables	8
7.4.2	Assumptions	8
7.4.3	Access Routine Semantics	8
8	MIS of ODE Solver Module	10
8.1	Module	10
8.2	Uses	10
8.3	Syntax	10

8.3.1	Exported Access Programs	10
8.4	Semantics	10
8.4.1	State Variables	10
8.4.2	Access Routine Semantics	10
9	MIS of Energy Module	12
9.1	Module	12
9.2	Uses	12
9.3	Syntax	12
9.3.1	External Access Programs	12
9.4	Semantics	12
9.4.1	State Variables	12
9.4.2	Assumptions	12
9.4.3	Access Routine Semantics	12
10	MIS of Output Verification Module	14
10.1	Module	14
10.2	Uses	14
10.3	Syntax	14
10.3.1	Exported Constant	14
10.3.2	Exported Access Programs	14
10.4	Semantics	14
10.4.1	State Variables	14
10.4.2	Assumptions	14
10.4.3	Access Routine Semantics	14
10.4.4	Local Functions	15
11	MIS of Plotting Module	16
11.1	Module	16
11.2	Uses	16
11.3	Syntax	16
11.3.1	Exported Access Programs	16
11.4	Semantics	16
11.4.1	State Variables	16
11.4.2	Environment Variables	16
11.4.3	Assumptions	16
11.4.4	Access Routine Semantics	16
12	MIS of Output Module	17
12.1	Module	17
12.2	Uses	17
12.3	Syntax	17
12.3.1	Exported Constants	17

12.3.2	Exported Access Program	17
12.4	Semantics	17
12.4.1	State Variables	17
12.4.2	Environment Variables	17
12.4.3	Access Routine Semantics	17
13	MIS of Specification Parameters	18
13.1	Module	18
13.2	Uses	18
13.3	Syntax	18
13.3.1	Exported Constants	18
13.4	Semantics	19
14	Appendix	21

1 Symbols, Abbreviations and Acronyms

See SRS Documentation at https://jacquescarette.github.io/Drasil/examples/Projectile/srs/Projectile_SRS.pdf

2 Introduction

The following document details the Module Interface Specifications for the implemented modules in a program simulating projectile motion. It is intended to ease navigation through the program for design and maintenance purposes.

Complementary documents include the System Requirement Specifications and Module Guide. The full documentation and implementation can be found at [No manual version of Projectile? Should this link be removed or should there be a link? —SC].

3 Notation

The structure of the MIS for modules comes from Hoffman and Strooper (1995), with the addition that template modules have been adapted from Ghezzi et al. (2003). The mathematical notation comes from Chapter 3 of Hoffman and Strooper (1995). For instance, the symbol $:=$ is used for a multiple assignment statement and conditional rules follow the form $(c_1 \Rightarrow r_1 | c_2 \Rightarrow r_2 | \dots | c_n \Rightarrow r_n)$.

The following table summarizes the primitive data types used by Projectile.

Data Type	Notation	Description
character	char	a single symbol or digit
real	\mathbb{R}	any number in $(-\infty, \infty)$

The specification of Projectile uses strings, a derived data type. Strings are lists of characters. In addition, Projectile uses functions, which are defined by the data types of their inputs and outputs. Local functions are described by giving their type signature followed by their specification.

4 Module Decomposition

The following table is taken directly from the Module Guide document for this project.

Level 1	Level 2
Hardware-Hiding	
Behaviour-Hiding	Input Parameters Output Format Output Verification Temperature ODEs Energy Equations Control Module Specification Parameters Module
Software Decision	Sequence Data Structure ODE Solver Plotting

Table 1: Module Hierarchy

5 MIS of Control Module

5.1 Module

main

5.2 Uses

Param (Section 6), Temperature (Section 7), Solver (Section 8), Energy (Section 9), verify_output (Section 10), plot (Section 11), output (Section 12)

5.3 Syntax

5.3.1 Exported Access Programs

Name	In	Out	Exceptions
main	-	-	-

5.4 Semantics

5.4.1 State Variables

None

5.4.2 Access Routine Semantics

main():

- transition: Modify the state of Param module and the environment variables for the Plot and Output modules by following these steps

Get (filenameIn: string) and (filenameOut: string) from user

load_params(filenameIn)

#Find temperature function ($T_W^{\text{Solid}}, T_W^{\text{Melting}}, T_W^{\text{Liquid}}, T_P^{\text{Solid}}, T_P^{\text{Melting}}, T_P^{\text{Liquid}}$), and energy (Q_P) and times of transition between solid, melting and liquid phases ($t_{\text{melt}}^{\text{init}}, t_{\text{melt}}^{\text{final}}$)

$t_{\text{melt}}^{\text{init}}, [T_W^{\text{Solid}}, T_P^{\text{Solid}}]^T := \text{solve}(\text{ODE_SolidPCM}, 0.0, [T_{\text{init}}, T_{\text{init}}]^T, \text{event_StartMelt}, t_{\text{final}})$

$t_{\text{melt}}^{\text{final}}, [T_W^{\text{Melting}}, T_P^{\text{Melting}}, Q_p]^T := \text{solve}(\text{ODE_MeltingPCM}, t_{\text{melt}}^{\text{init}}, [T_W^{\text{Solid}}(t_{\text{melt}}^{\text{init}}), T_P^{\text{Solid}}(t_{\text{melt}}^{\text{init}}), 0.0]^T, \text{event_EndMelt}, t_{\text{final}})$

$[T_W^{\text{Liquid}}, T_P^{\text{Liquid}}]^T := \text{solveNoE}(\text{ODE_LiquidPCM}, t_{\text{melt}}^{\text{final}}, [T_W^{\text{Melting}}(t_{\text{melt}}^{\text{final}}), T_P^{\text{Melting}}(t_{\text{melt}}^{\text{final}})]^T, t_{\text{final}})$

#Combine temperatures for $0 \leq t \leq t_{\text{final}}$

$$T_W(t) = (0 \leq t < t_{\text{melt}}^{\text{init}} \Rightarrow T_W^{\text{Solid}}|t_{\text{melt}}^{\text{init}} \leq t < t_{\text{melt}}^{\text{final}} \Rightarrow T_W^{\text{Melting}}|t_{\text{melt}}^{\text{final}} \leq t \leq t_{\text{final}} \Rightarrow T_W^{\text{Liquid}})$$

$$T_P(t) = (0 \leq t < t_{\text{melt}}^{\text{init}} \Rightarrow T_P^{\text{Solid}}|t_{\text{melt}}^{\text{init}} \leq t < t_{\text{melt}}^{\text{final}} \Rightarrow T_P^{\text{Melting}}|t_{\text{melt}}^{\text{final}} \leq t \leq t_{\text{final}} \Rightarrow T_P^{\text{Liquid}})$$

#Energy values ($E_W(t), E_P(t)$) for $0 \leq t \leq t_{\text{final}}$

$$E_W(t) = (0 \leq t < t_{\text{melt}}^{\text{init}} \Rightarrow \text{energyWater}(T_W^{\text{Solid}})|t_{\text{melt}}^{\text{init}} \leq t < t_{\text{melt}}^{\text{final}} \Rightarrow \text{energyWater}(T_W^{\text{Melting}})|t_{\text{melt}}^{\text{final}} \leq t \leq t_{\text{final}} \Rightarrow \text{energyWater}(T_W^{\text{Liquid}}))$$

$$E_P(t) = (0 \leq t < t_{\text{melt}}^{\text{init}} \Rightarrow \text{energySolidPCM}(T_P^{\text{Solid}})|t_{\text{melt}}^{\text{init}} \leq t < t_{\text{melt}}^{\text{final}} \Rightarrow \text{energyMeltingPCM}(Q_P)|t_{\text{melt}}^{\text{final}} \leq t \leq t_{\text{final}} \Rightarrow \text{energyLiquidPCM}(T_P^{\text{Liquid}}))$$

#Output calculated values to a file and to a plot. Verify calculated values obey conservation of energy.

`verify_output($T_w, T_p, E_w, E_p, t_{\text{final}}$)`

`plot($T_w, T_p, E_w, E_p, t_{\text{final}}$)`

`output(filenameOut, $T_w, T_p, E_w, E_p, t_{\text{final}}$)`

6 MIS of Input Parameters Module

The secrets of this module are the data structure for input parameters, how the values are input and how the values are verified. The load and verify secrets are isolated to their own access programs.

6.1 Module

Param

6.2 Uses

SpecParam (Section 13)

6.3 Syntax

Name	In	Out	Exceptions
load_params	string	-	FileError
verify_params	-	-	InputError
v	-	\mathbb{R}	
θ	-	\mathbb{R}	
p_{target}	-	\mathbb{R}	
p_{land}	-	\mathbb{R}	
offset	-	\mathbb{R}	
message	-	string	

6.4 Semantics

6.4.1 Environment Variables

inputFile: sequence of string $\#f[i]$ is the i th string in the text file f

6.4.2 State Variables

To Support IM1 and IM2

v : \mathbb{R}

θ : \mathbb{R}

To Support IM3 and IM4

p_{target} : \mathbb{R}

From FR4

p_{land} : \mathbb{R}

offset: \mathbb{R}
message: string

6.4.3 Assumptions

- load_params will be called before the values of any state variables will be accessed.
- The file contains the string equivalents of the numeric values for each input parameter in order, each on a new line. Any comments in the input file should be denoted with a '#' symbol.

6.4.4 Access Routine Semantics

Param.v:

- output: $out := v$
- exception: none

Param. θ :

- output: $out := \theta$
- exception: none

Param. p_{target} :

- output: $out := p_{\text{target}}$
- exception: none

Param. p_{land} :

- output: $out := p_{\text{land}}$
- exception: none

Param.offset:

- output: $out := \text{offset}$
- exception: none

Param.message:

- output: $out := \text{message}$
- exception: none

load_params(s):

- transition: The filename s is first associated with the file f . `inputFile` is used to modify the state variables using the following procedural specification:

1. Read data sequentially from `inputFile` to populate the state variables from FR1 (v , θ , and p_{target}).
2. Calculate the derived quantities (p_{land} , `offset`, and `message`) as follows:
 - $p_{\text{land}} := \frac{2v^2 \sin(\theta) \cos(\theta)}{9.8}$
 - `offset` := $p_{\text{land}} - p_{\text{target}}$
 - `message` :=

$|\frac{\text{offset}}{p_{\text{target}}}| < 0.02 \Rightarrow$ “The target was hit.”

`offset` < 0 \Rightarrow “The projectile fell short.”

`True` \Rightarrow “The projectile went long.”

3. `verify_params()`

- exception: `exc` := a file name s cannot be found OR the format of `inputFile` is incorrect \Rightarrow `FileError`

`verify_params()`:

- out: `out` := none
- exception: `exc` :=

$\neg(0 < v) \Rightarrow$ `InputError`

$\neg(0 < \text{offset}) \Rightarrow$ `InputError`

$\neg(0 < p_{\text{target}}) \Rightarrow$ `InputError`

etc. See Appendix (Section 14) for the complete list of exceptions and associated error messages. [I think the error messages should be more descriptive, and be defined in the Appendix. —SC]

6.5 Considerations

The value of each state variable can be accessed through its name (getter). An access program is available for each state variable. There are no setters for the state variables, since the values will be set and checked by `load params` and not changed for the life of the program.

7 MIS of Temperature ODEs Module

7.1 Module

Temperature

7.2 Uses

Param (Section 6)

7.3 Syntax

7.3.1 Exported Access Programs

Name	In	Out	Exceptions
ODE_SolidPCM	–	$(\mathbb{R}^3 \rightarrow \mathbb{R})^2$	-
ODE_MeltingPCM	–	$(\mathbb{R}^4 \rightarrow \mathbb{R})^3$	-
ODE_LiquidPCM	–	$(\mathbb{R}^3 \rightarrow \mathbb{R})^2$	-
event_StartMelt	–	$\mathbb{R}^2 \rightarrow \mathbb{R}$	-
event_EndMelt	–	$\mathbb{R}^3 \rightarrow \mathbb{R}$	-

7.4 Semantics

7.4.1 State Variables

none

7.4.2 Assumptions

none

7.4.3 Access Routine Semantics

ODE_SolidPCM():

- output: $out := \frac{d}{dt} \begin{bmatrix} T_W \\ T_P \end{bmatrix} = \begin{bmatrix} \frac{1}{\tau_W}[(T_C - T_W(t)) + \eta(T_P(t) - T_W(t))] \\ \frac{1}{\tau_P}(T_W(t) - T_P(t)) \end{bmatrix}$

- exception: none

ODE_MeltingPCM():

- output: $out := \frac{d}{dt} \begin{bmatrix} T_W \\ T_P \\ Q_P \end{bmatrix} = \begin{bmatrix} \frac{1}{\tau_W}[(T_C - T_W(t)) + \eta(T_P(t) - T_W(t))] \\ 0 \\ h_P A_P(T_W(t) - T_{\text{melt}}^P) \end{bmatrix}$

- exception: none

ODE_LiquidPCM():

- output: $out := \frac{d}{dt} \begin{bmatrix} T_W \\ T_P \end{bmatrix} = \begin{bmatrix} \frac{1}{\tau_W}[(T_C - T_W(t)) + \eta(T_P(t) - T_W(t))] \\ \frac{1}{\tau_P}(T_W(t) - T_P(t)) \end{bmatrix}$

- exception: none

event_StartMelt():

- output: $out := g([T_W, T_P]^T) = T_{\text{melt}}^P - T_P$

- exception: none

event_EndMelt():

- output: $out := g([T_W, T_P, Q_P]^T) = 1 - \phi$, where $\phi = \frac{Q_P}{E_{P_{\text{melt}}}^{\text{all}}}$

- exception: none

8 MIS of ODE Solver Module

#Bold font is used to indicate variables that are a sequence type

8.1 Module

Solver($n : \mathbb{N}$) *#n is the length of the sequences*

8.2 Uses

None

8.3 Syntax

8.3.1 Exported Access Programs

Name	In	Out	Except.
solve	$\mathbf{f} : (\mathbb{R}^{n+1} \rightarrow \mathbb{R})^n, t_0 : \mathbb{R}, \mathbf{y}_0 : \mathbb{R}^n, g : \mathbb{R}^n \rightarrow \mathbb{R}, t_{\text{fin}} : \mathbb{R}$	$t_1 : \mathbb{R}, \mathbf{y} : (\mathbb{R} \rightarrow \mathbb{R})^n$	ODE_ERR, NO_EVENT
solveNoE	$\mathbf{f} : (\mathbb{R}^{n+1} \rightarrow \mathbb{R})^n, t_0 : \mathbb{R}, \mathbf{y}_0 : \mathbb{R}^n, t_{\text{fin}} : \mathbb{R}$	$\mathbf{y} : (\mathbb{R} \rightarrow \mathbb{R})^n$	ODE_ERR

8.4 Semantics

8.4.1 State Variables

None

8.4.2 Access Routine Semantics

#Solving $\frac{d}{dt}\mathbf{y} = \mathbf{f}(t, \mathbf{y}(t))$

solve($\mathbf{f}, t_0, \mathbf{y}_0, g, t_{\text{fin}}$):

- output: $out := t_1, \mathbf{y}(t)$ where

$$\mathbf{y}(t) = \mathbf{y}_0 + \int_{t_0}^t \mathbf{f}(s, \mathbf{y}(s)) ds$$

with t_1 determined by the first time where $g(\mathbf{y}(t_1)) = 0$. $\mathbf{y}(t)$ is calculated from $t = t_0$ to $t = t_1$.

- exception: $exc := (\neg(\exists t : \mathbb{R} | t_0 \leq t \leq t_{\text{fin}} : g(\mathbf{y}(t)) = 0) \Rightarrow \text{NO_EVENT} \mid \text{ODE Solver Fails} \Rightarrow \text{ODE_ERR})$

solveNoE($\mathbf{f}, t_0, \mathbf{y}_0, t_{\text{fin}}$):

- output: $out := \mathbf{y}(t)$ where

$$\mathbf{y}(t) = \mathbf{y}_0 + \int_{t_0}^{t_{\text{fin}}} \mathbf{f}(s, \mathbf{y}(s)) ds$$

$y(t)$ is calculated from $t = t_0$ to $t = t_{\text{fin}}$.

- exception: $exc := (\text{ODE Solver Fails} \Rightarrow \text{ODE_ERR})$

9 MIS of Energy Module

9.1 Module

Energy

9.2 Uses

Param (Section 6)

9.3 Syntax

9.3.1 External Access Programs

Name	In	Out	Exceptions
energyWater	$\mathbb{R} \rightarrow \mathbb{R}$	$\mathbb{R} \rightarrow \mathbb{R}$	-
energySolidPCM	$\mathbb{R} \rightarrow \mathbb{R}$	$\mathbb{R} \rightarrow \mathbb{R}$	-
energyMeltingPCM	$\mathbb{R} \rightarrow \mathbb{R}$	$\mathbb{R} \rightarrow \mathbb{R}$	-
energyLiquidPCM	$\mathbb{R} \rightarrow \mathbb{R}$	$\mathbb{R} \rightarrow \mathbb{R}$	-

9.4 Semantics

9.4.1 State Variables

None

9.4.2 Assumptions

None

9.4.3 Access Routine Semantics

energyWater(T_W):

- output: $out := C_W m_W (T_W - T_{init})$
- exception: none

energySolidPCM(T_P):

- output: $out := C_P^S m_P (T_P - T_{init})$
- exception: none

energyMeltingPCM(Q_P):

- output: $out := E_{P_{\text{melt}}}^{\text{init}} + Q_P$
- exception: none

energyLiquidPCM(T_P):

- output: $out := E_{P_{\text{melt}}}^{\text{init}} + H_f m_p + C_P^L m_P (T_P(t) - T_{\text{melt}}^P)$
- exception: none

10 MIS of Output Verification Module

10.1 Module

verify_output

10.2 Uses

Param (Section 6)

10.3 Syntax

10.3.1 Exported Constant

ADMIS_ER = 1×10^{-6}

10.3.2 Exported Access Programs

Name	In	Out	Exceptions
verify_output	$T_W(t) : \mathbb{R} \rightarrow \mathbb{R}, T_P(t) : \mathbb{R} \rightarrow \mathbb{R}, E_W(t) : \mathbb{R} \rightarrow \mathbb{R}, E_P(t) : \mathbb{R} \rightarrow \mathbb{R}, t_{\text{final}} : \mathbb{R}$	-	EWAT_NOT_CONSERVE, EPCM_NOT_CONSERVE

10.4 Semantics

10.4.1 State Variables

None

10.4.2 Assumptions

All of the fields of the input parameters structure have been assigned a value.

10.4.3 Access Routine Semantics

verify_output($T_W, T_P, E_W, E_P, t_{\text{final}}$):

- exception: exc := (

$(\forall t | 0 \leq t \leq t_{\text{final}} : \text{relErr}(E_W, \int_0^t h_C A_C (T_C - T_W(t)) dt - \int_0^t h_P A_P (T_W(t) - T_P(t)) dt) < \text{ADMIS_ER}) \Rightarrow \text{EWAT_NOT_CONSERVE}$

|
 $(\forall t | 0 \leq t \leq t_{\text{final}} : \text{relErr}(E_P, \int_0^t h_P A_P (T_W(t) - T_P(t)) dt) < \text{ADMIS_ER}) \Rightarrow \text{EPCM_NOT_CONSERVE}$
)

10.4.4 Local Functions

relErr: $\mathbb{R} \times \mathbb{R} \rightarrow \mathbb{R}$

$$\text{relErr}(t, e) \equiv \frac{|t-e|}{|t|}$$

11 MIS of Plotting Module

11.1 Module

plot

11.2 Uses

N/A

11.3 Syntax

11.3.1 Exported Access Programs

Name	In	Out	Exceptions
plot	$T_W(t) : \mathbb{R} \rightarrow \mathbb{R}, T_P(t) : \mathbb{R} \rightarrow \mathbb{R}, E_W(t) : \mathbb{R} \rightarrow \mathbb{R}, E_P(t) : \mathbb{R} \rightarrow \mathbb{R}, t_{\text{final}} : \mathbb{R}$	-	-

11.4 Semantics

11.4.1 State Variables

None

11.4.2 Environment Variables

win: 2D sequence of pixels displayed on the screen

11.4.3 Assumptions

None

11.4.4 Access Routine Semantics

plot($T_w, T_p, E_w, E_p, t_{\text{final}}$):

- transition: Modify win to display a plot where the vertical axis is time and one horizontal axis is temperature and the other horizontal axis is energy. The time should run from 0 to t_{final}
- exception: none

12 MIS of Output Module

12.1 Module

output

12.2 Uses

Param (Section 6)

12.3 Syntax

12.3.1 Exported Constants

max_width: integer

12.3.2 Exported Access Program

Name	In	Out	Exceptions
output	$\text{fname: string, } T_W(t) : \mathbb{R} \rightarrow \mathbb{R}, T_P(t) : \mathbb{R} \rightarrow \mathbb{R}, E_W(t) : \mathbb{R} \rightarrow \mathbb{R}, E_P(t) : \mathbb{R} \rightarrow \mathbb{R}, t_{\text{final}} : \mathbb{R}$	-	-

12.4 Semantics

12.4.1 State Variables

None

12.4.2 Environment Variables

file: A text file

12.4.3 Access Routine Semantics

output(fname, T_w , T_p , E_w , E_p , t_{final}):

- transition: Write to environment variable named fname the following: the input parameters from Param, and the calculated values T_w , T_p , E_w , E_p from times 0 to t_{final} . The functions will be output as sequences in this file. The spacing between points in the sequence should be selected so that the heating behaviour is captured in the data.
- exception: none

13 MIS of Specification Parameters

The secrets of this module is the value of the specification parameters.

13.1 Module

SpecParam

13.2 Uses

N/A

13.3 Syntax

13.3.1 Exported Constants

From Table 2 in SRS

$L_{\min} := 0.1$

$L_{\max} := 50$

$\frac{D}{L}_{\min} := 0.002$

$\frac{D}{L}_{\max} := 200$

$\text{minfrac} := 10^{-6}$

$h_{\min} := 0.001$

$\rho_P^{\min} := 500$

$\rho_P^{\max} := 20000$

$C_{P_{\min}}^S := 100$

$C_{P_{\max}}^S := 4000$

$C_{P_{\min}}^L := 100$

$C_{P_{\max}}^L := 5000$

$A_C^{\max} := \pi(\frac{D}{2})^2$

$\rho_W^{\min} := 950$

$\rho_W^{\max} := 1000$

$C_W^{\min} := 4170$

$C_W^{\max} := 4210$

$h_C^{\min} := 10$

$h_C^{\max} := 10000$

$h_P^{\min} := 10$

$h_P^{\max} := 10000$

$t_{\text{final}}^{\max} := 86400$

$[A_C^{\max}$ shouldn't be in this table of constants —SS]

13.4 Semantics

N/A

References

- Carlo Ghezzi, Mehdi Jazayeri, and Dino Mandrioli. *Fundamentals of Software Engineering*. Prentice Hall, Upper Saddle River, NJ, USA, 2nd edition, 2003.
- Daniel M. Hoffman and Paul A. Strooper. *Software Design, Automated Testing, and Maintenance: A Practical Approach*. International Thomson Computer Press, New York, NY, USA, 1995.

14 Appendix

Table 2: Possible Exceptions

Message ID	Error Message
badLength	Error: Tank length must be > 0
badDiam	Error: Tank diameter must be > 0
badPCMVolume	Error: PCM volume must be > 0
badPCMAndTankVol	Error: PCM volume must be $<$ tank volume
badPCMArea	Error: PCM area must be > 0
badPCMDensity	Error: ρ_p must be > 0
badMeltTemp	Error: T_{melt} must be > 0 and $< T_c$
badCoilAndInitTemp	Error: T_c must be $> T_{init}$
badCoilTemp	Error: T_c must be > 0 and < 100
badPCMHeatCapSolid	Error: C_{ps} must be > 0
badPCMHeatCapLiquid	Error: C_{pl} must be > 0
badHeatFusion	Error: H_f must be > 0
badCoilArea	Error: A_c must be > 0
badWaterDensity	Error: ρ_w must be > 0
badWaterHeatCap	Error: C_w must be > 0
badCoilCoeff	Error: h_c must be > 0
badPCMCoeff	Error: h_p must be > 0
badInitTemp	Error: T_{init} must be > 0 and < 100
badFinalTime	Error: t_{final} must be > 0
badInitAndMeltTemp	Error: T_{init} must be $< T_{melt}$
ODE_ACCURACY	$reltol$ and $abstol$ were not satisfied by the ODE solver for a given solution step.
ODE_BAD_INPUT	Invalid input to ODE solver
ODE_MAXSTEP	ODE solver took <i>MaxStep</i> steps and did not find solution
warnLength	Warning: It is recommended that $0.1 \leq L \leq 50$
warnDiam	Warning: It is recommended that $0.002 \leq D/L \leq 200$
warnPCMVol	Warning: It is recommended that V_p be $\geq 0.0001\%$ of V_t
warnVolArea	Warning: It is recommended that $V_p \leq A_p \leq (2/0.001) * V_p$
warnPCMDensity	Warning: It is recommended that $500 < \rho_p < 20000$
warnPCMHeatCapSolid	Warning: It is recommended that $100 < C_{ps} < 4000$

warnPCMHeatCapLiquid	Warning: It is recommended that $100 < C_{pl} < 5000$
warnCoilArea	Warning: It is recommended that $Ac \leq \pi * (D/2)^2$
warnWaterDensity	Warning: It is recommended that $950 < \rho_w \leq 1000$
warnWaterHeatCap	Warning: It is recommended that $4170 < C_w < 4210$
warnCoilCoeff	Warning: It is recommended that $10 < hc < 10000$
warnPCMCoeff	Warning: It is recommended that $10 < hp < 10000$
warnFinalTime	Warning: It is recommended that $0 < t_{final} < 86400$
warnWaterError	Warning: There is greater than $x\%$ relative error between the energy in the water output and the expected output based on the law of conservation of energy. (Where x is the value of <i>ConsTol</i>)
warnPCMError	Warning: There is greater than $x\%$ relative error between the energy in the PCM output and the expected output based on the law of conservation of energy. (Where x is the value of <i>ConsTol</i>)
