

# Aircrack-ng Newbie Guide for Linux

---

Idea and initial work: ASPj

Additions by: a number of good souls

Last updated: May 09, 2008

This tutorial will give you the basics to get started using the aircrack-ng suite. It is impossible to provide every piece of information you need and cover every scenario. So be prepared to do some homework and research on your own. The Forum [<http://forum.aircrack-ng.org/>] and the Wiki [<http://aircrack-ng.org/doku.php>] have lots of supplementary tutorials and information.

Although it does not cover all the steps from start to finish like this tutorial, the [Simple WEP Crack](#) tutorial covers the actual aircrack-ng steps in much more detail.

## Setting up Hardware, Installing Aircrack-ng

---

The first step in getting aircrack-ng working properly on your Linux system is patching and installing the proper driver for your wireless card. Many cards work with multiple drivers, some of which provide the necessary features for using aircrack-ng, and some of which do not.

Needless to say, you need a wireless card which is compatible with the aircrack-ng suite. This is hardware which is fully compatible and can inject packets. A compatible wireless card can be used to crack a wireless access point in under an hour.

To determine to which category your card belongs to, see [hardware compatibility page](#). Read [Tutorial: Is My Wireless Card Compatible?](#) if you don't know where to look in this table. It still does not hurt to read this tutorial to build your knowledge and confirm your card attributes.

First, you need to know which chipset is used in your wireless card and which driver you need for it. You will have determined this using the information in the previous paragraph. The [drivers section](#) will tell you which drivers you need for your specific chipset. Download them and then get the corresponding patch from <http://patches.aircrack-ng.org> [<http://patches.aircrack-ng.org>]. (These patches enables the support for injection.)

As I own a Ralink USB device, I am providing the steps to get it working with Aircrack-ng. Before you are able to compile and install drivers, you need the kernel-sources for your distribution installed.

If you own another type of card, check the [installing drivers page](#) for instructions about other drivers. As well, do a search in the net if you're unsure how to install them.

## RaLink USB rt2570 Setup guide

---

If you own a rt2570 USB device (like D-Link DWL-G122 rev. B1 or Linksys WUSB54G v4) you should use the drivers from [http://homepages.tu-darmstadt.de/~p\\_larbig/wlan/](http://homepages.tu-darmstadt.de/~p_larbig/wlan/) [[http://homepages.tu-darmstadt.de/~p\\_larbig/wlan/](http://homepages.tu-darmstadt.de/~p_larbig/wlan/)] These are special modified drivers, which support injection and are reported to work best with Aircrack-ng. They don't need to be patched. Of course these drivers do also work for normal operation. (Starting with kernel 2.6.25 and Aircrack-ng v1.0-rc1, the in-kernel driver, rt2500usb, can also be used.)

Lets unpack, compile and install the drivers:

```
tar xvj rt2570-k2wrlz-1.3.0.tar.bz2
cd rt2570-k2wrlz-1.3.0/Module
make
make install
```

The last step has to be performed as root. Use su to change to root. Now we can load the module into the kernel:

```
modprobe rt2570
```

Plug in your card, it should be recognized as rausb0 now. Run iwconfig to list your wireless devices and check if everything is working.

## Aircrack-ng installation

---

### Source

Get the latest copy of aircrack-ng from the homepage: <http://www.aircrack-ng.org> [<http://www.aircrack-ng.org>] The following commands would have to be changed if you use a newer version of the software.

Unpacking, compiling, installing:

```
tar xvf aircrack-ng-1.0-rc1.tar.gz
cd aircrack-ng-1.0-rc1
make
make install
```

As usual, the last step needs to be performed as root, use **su** or **sudo -s** to login as root (use **sudo make install** for Ubuntu).

### YUM

**WARNING!!!** Currently, neither of the repositories hosts the latest version of Aircrack-ng. It's recommended that you use the first method instead.

If you are using a system like Redhat Linux or Fedora Core you can install aircrack-ng with yum. First you have to add the repository of Dag Wieers [<http://dag.wieers.com/home-made/apt/>] or Dries [<http://dries.studentenweb.org/rpm/>].

```
su
yum -y install aircrack-ng
```

### RPM

**WARNING!!!** Currently, neither of the repositories hosts the latest version of Aircrack-ng. It's recommended that you use the first method instead.

If you are using a system which is rpm-based then you can take the easy way to install aircrack-ng. (Example for Redhat Linux 4)

```
su  
rpm -ihv http://dag.wieers.com/rpm/packages/aircrack-ng/aircrack-ng-0.7-1.el4.rf.i386.rpm
```

IMPORTANT: Check <http://dag.wieers.com/rpm/packages/aircrack-ng/> [http://dag.wieers.com/rpm/packages/aircrack-ng/] for the latest version of the aircrack-ng suite and change the command above to reference the latest version.

## IEEE 802.11 basics

---

Ok, now everything is ready, time to make a pit stop before the action finally starts and learn something about how wireless networks work.

The following chapter is very important, if something doesn't work as expected. Knowing what all is about helps you find the problem or helps you at least to describe it so someone else who can help you. This is a little bit scientific and maybe you feel like skipping it. However, a little knowledge is necessary to crack wireless networks and because it is a little more than just typing one command and letting aircrack do the rest.

## How a wireless network is found

---

This is a short introduction into managed networks, these ones working with Access Points (AP). Every AP sends out about 10 so called beacon frames a second. These packets contain the following information:

- Name of the network (ESSID)
- If encryption is used (and what encryption is used; pay attention, that may not be always true just because the AP advertises it)
- What MBit data rates are supported
- Which channel the network is on

This information is then shown in your tool that connects to this network. It is shown when you let your card scan for networks with **iwlist <interface> scan** and when you run [airodump-ng](#).

Every AP has a unique MAC address (48 bit, 6 pair of hexadecimal numbers). It looks like 00:01:23:4A:BC:DE. Every network hardware device has such an address and network devices communicate with each other by using this MAC address. So its basically like a unique name. MAC addresses are unique, no two network devices in the world have the same MAC address.

## Connecting with a network

---

If you want to connect to a wireless network, there are some possibilities. In most cases, Open System Authentication is used. (Optional: If you want to learn more about authentication, check this [http://documentation.netgear.com/reference/fra/wireless/WirelessNetworkingBasics-3-06.html] out.)

Open System Authentication:

1. Ask the AP for authentication.
2. The AP answers: OK, you are authenticated.
3. Ask the AP for association

4. The AP answers: OK, you are now connected.

This is the simplest case, BUT there could be some problems if you are not legitimate to connect:

- WPA/WPA2 is in use, you need EAPOL authentication. The AP will deny you at step 2.
- Access Point has a list of allowed clients (MAC addresses), and it lets no one else connect. This is called MAC filtering.
- Access Point uses Shared Key Authentication, you need to supply the correct WEP key to be able to connect. (See the [How to do shared key fake authentication? tutorial](#) for advanced techniques.)

## Simple sniffing and cracking

---

### Discovering Networks

---

The first thing to do is looking out for a potential target. The aircrack-ng suite contains [airodump-ng](#) for this - but other programs like Kismet [<http://www.kismetwireless.net/>] can be used too.

Prior to looking for networks, you must put your wireless card into what is called "monitor mode". Monitor mode is a special mode that allows your PC to listen to every wireless packet. This monitor mode also allows you to optionally inject packets into a network. Injection will be covered later in this tutorial.

To put your wireless card into monitor mode:

[airmon-ng](#) start rausb0

To confirm it is in monitor mode, run "iwconfig" and confirm the mode. The [airmon-ng page](#) on the Wiki has generic information and how to start it for other drivers.

Then, start airodump-ng to look out for networks:

```
airodump-ng rausb0
```

"rausb0" is the network interface (nic) name. If you are using a different WLAN device than a rt2570 you'll have to use a different nic name. Take a look in the documentation of the nic driver. For most newer drivers, the primary interface name is "wlan0", but for monitoring, a secondary interface ("mon0", created when you run airmon-ng) is used.

If airodump-ng could connect to the WLAN device, you'll see a screen like this:

```

CH 13 [ Elapsed: 3 mins ] [ 2006-07-29 16:46
Current channel
BSSID                PWR  Beacons   # Data  CH  MB  ENC   ESSID
00:01:02:03:04:05    51    155      81    1  11  WEP
00:09:5B:01:02:03    40     45       5   11  54. WPA
00:0F:CB:01:02:03    32     39       0    6  54. WEP? 3Com
00:03:C9:01:02:03    33     26       0   11  48  WEP?
00:12:17:01:02:03    30     15       0   11  48  OPN  WLAN
00:15:0C:01:02:03    26     14       0    6  54. WEP?

BSSID                STATION            PWR  Packets  Probes
00:01:02:03:04:05    00:04:05:06:07:08  48      45

Access points
Clients

```

airodump-ng hops from channel to channel and shows all access points it can receive beacons from. Channels 1 to 14 are used for 802.11b and g (in US, they only are allowed to use 1 to 11; 1 to 13 in Europe with some special cases; 1-14 in Japan). Channels between 36 and 149 are used for 802.11a. The current channel is shown in the top left corner.

After a short time some APs and (hopefully) some associated clients will show up.

The upper data block shows the access points found:

<b>BSSID</b>	The MAC address of the AP
<b>PWR</b>	Signal strength. Some drivers don't report it
<b>Beacons</b>	Number of beacon frames received. If you don't have a signal strength you can estimate it by the number of beacons: the more beacons, the better the signal quality
<b>Data</b>	Number of data frames received
<b>CH</b>	Channel the AP is operating on
<b>MB</b>	Speed or AP Mode. 11 is pure 802.11b, 54 pure 802.11g. Values between are a mixture
<b>ENC</b>	Encryption: OPN: no encryption, WEP: WEP encryption, WPA: WPA or WPA2 encryption, WEP?: WEP or WPA (don't know yet)
<b>ESSID</b>	The network name. Sometimes hidden

The lower data block shows the clients found:

<b>BSSID</b>	The MAC of the AP this client is associated to
<b>STATION</b>	The MAC of the client itself
<b>PWR</b>	Signal strength. Some drivers don't report it
<b>Packets</b>	Number of data frames received
<b>Probes</b>	Network names (ESSIDs) this client has probed

Now you should look out for a target network. It should have a client connected because cracking networks without a client is an advanced topic (See [How to crack wep with no clients](#)). It should use WEP encryption and have a high signal strength. Maybe you can re-position your antenna to get a better signal. Often a few centimeters make a big difference in signal strength.

In the example above the net 00:01:02:03:04:05 would be the only possible target because it's the only one with an associated client. But it also has a high signal strength so it's really a good target

to practice.

## Sniffing IVs

---

Because of the channel hopping you won't capture all packets from your target net. So we want to listen just on one channel and additionally write all data to disk to be able to use it for cracking:

```
airodump-ng -c 11 --bssid 00:01:02:03:04:05 -w dump rausb0
```

With the `-c` parameter you tune to a channel and the parameter after `-w` is the prefix to the network dumps written to disk. The `--bssid` combined with the AP MAC address limits the capture to the one AP. The `--bssid` option is only available on new versions of airodump-ng.

Before being able to crack WEP you'll usually need between 40 000 and 85 000 different Initialization Vectors (IVs). Every data packet contains an IV. IVs can be re-used, so the number of different IVs is usually a bit lower than the number of data packets captured.

So you'll have to wait and capture 40K to 85K of data packets (IVs). If the network is not busy it will take a very long time. Often you can speed it up a lot by using an active attack (=packet replay). See the next chapter.

## Cracking

---

If you've got enough IVs captured in one or more file, you can try to crack the WEP key:

```
aircrack-ng -b 00:01:02:03:04:05 dump-01.cap
```

The MAC after the `-b` option is the BSSID of the target and `dump-01.cap` the file containing the captured packets. You can use multiple files, just add all their names or you can use a wildcard such as `dump*.cap`.

For more information about [aircrack-ng](#) parameters, description of the output and usage see the [manual](#).

The number of IVs you need to crack a key is not fixed. This is because some IVs are weaker and leak more information about the key than others. Usually these weak IVs are randomly mixed in between the stronger ones. So if you are lucky, you can crack a key with only 20 000 IVs. But often this is not enough and aircrack-ng will run a long time (up to a week or even longer with a high fudge factor) and then tell you the key could not be cracked. If you have more IVs cracking can be done a lot faster and is usually done in a few minutes, or even seconds. Experience shows that 40 000 to 85 000 IVs is usually enough for cracking.

There are some more advanced APs out there that use an algorithm to filter out weak IVs. The result is either that you can't get more than "n" different IVs from the AP or that you'll need millions (like 5 to 7 million) to crack the key. Search in the Forum [<http://forum.aircrack-ng.org/>], there are some threads about cases like this and what to do.

## Active attacks

---

## Injection support

---

Most devices don't support injection - at least not without patched drivers. Some only support certain attacks. Take a look at the [compatibility page](#), column aireplay. Sometimes this table is not up-to-date, so if you see a "NO" for your driver there don't give up yet, but look at the driver homepage, the driver mailing list or our Forum [<http://forum.aircrack-ng.org/>]. If you were able to successfully replay using a driver which is not listed as supported, don't hesitate to update the [compatibility page](#) table and add a link to a short howto. (To do this, request a wiki account on IRC.)

The first step is to make sure packet injection really works with your card and driver. The easiest way to test it is the [injection test](#) attack. Make sure to perform this test prior to proceeding. Your card must be able to successfully inject in order to perform the following steps.

You'll need the BSSID (AP MAC) and ESSID (network name) of an AP that does not do MAC filtering (e.g. your own) and must be in range of the AP.

Try to connect to your AP using [aireplay-ng](#):

```
aireplay-ng --fakeauth 0 -e "your network ESSID" -a 00:01:02:03:04:05 rausb0
```

The value after -a is the BSSID of your AP.

If injection works you should see something like this:

```
12:14:06 Sending Authentication Request
12:14:06 Authentication successful
12:14:06 Sending Association Request
12:14:07 Association successful :-)
```

If not

1. double-check ESSID and BSSID
2. make sure your AP has MAC filtering disabled
3. test it against another AP
4. make sure your driver is properly patched and supported
5. Instead of "0", try "6000 -o 1 -q 10"

## ARP replay

---

Now that we know that packet injection works, we can do something to massively speed up capturing IVs: [ARP-request reinjection](#)

### The idea

ARP [[http://en.wikipedia.org/wiki/Address\\_Resolution\\_Protocol](http://en.wikipedia.org/wiki/Address_Resolution_Protocol)] works (simplified) by broadcasting a query for an IP and the device that has this IP sends back an answer. Because WEP does not protect against replay, you can sniff a packet, send it out again and again and it is still valid. So you just have to capture and replay an ARP-request targeted at the AP to create lots of traffic (and sniff IVs).

### The lazy way

First open a window with an [airodump-ng](#) sniffing for traffic (see above). [aireplay-ng](#) and [airodump-ng](#) can run together. Wait for a client to show up on the target network. Then start the attack:

```
aireplay-ng --arpreplay -b 00:01:02:03:04:05 -h 00:04:05:06:07:08 rausb0
```

-b specifies the target BSSID, -h the MAC of the connected client.

Now you have to wait for an ARP packet to arrive. Usually you'll have to wait for a few minutes (or look at the next chapter).

If you were successful, you'll see something like this:

```
Saving ARP requests in replay_arp-0627-121526.cap
You must also start airodump to capture replies.
Read 2493 packets (got 1 ARP requests), sent 1305 packets...
```

If you have to stop replaying, you don't have to wait for the next ARP packet to show up, but you can re-use the previously captured packet(s) with the -r <filename> option.

When using the arp injection technique, you can use the PTW method to crack the WEP key. This dramatically reduces the number of data packets you need and also the time needed. You must capture the full packet in airodump-ng, meaning do not use the "--ivs" option when starting it. For [aircrack-ng](#), use "aircrack -z <file name>". (PTW is the default attack in 1.0-rc1.)

If the number of data packets received by airodump-ng sometimes stops increasing you maybe have to reduce the replay-rate. You do this with the -x <packets per second> option. I usually start out with 50 and reduce until packets are received continuously again. Better positioning of your antenna usually also helps.

## The aggressive way

Most operating systems clear the ARP cache on disconnection. If they want to send the next packet after reconnection (or just use DHCP), they have to send out ARP requests. So the idea is to disconnect a client and force it to reconnect to capture an ARP-request. A side-effect is that you can sniff the ESSID and possibly a keystream during reconnection too. This comes in handy if the ESSID of your target is hidden, or if it uses shared-key authentication.

Keep your airodump-ng and aireplay-ng running. Open another window and run a [deauthentication](#) attack:

```
aireplay-ng --deauth 5 -a 00:01:02:03:04:05 -c 00:04:05:06:07:08 rausb0
```

-a is the BSSID of the AP, -c the MAC of the targeted client.

Wait a few seconds and your arp replay should start running.

Most clients try to reconnect automatically. But the risk that someone recognizes this attack or at least attention is drawn to the stuff happening on the WLAN is higher than with other attacks.

## Further tools and information

Tutorial in french for aircrack-ng [<http://www.tuto-fr.com/tutoriaux/crack-wep/aircrack-ng.php>] or in english [<http://www.tuto-fr.com/en/tutorial/tutorial-crack-wep-aircrack.php>]



newbie\_guide.txt · Last modified: 2010/11/21 00:05 by sleek

Except where otherwise noted, content on this wiki is licensed under the following license:CC  
Attribution-Noncommercial-Share Alike 3.0 Unported [<http://creativecommons.org/licenses/by-nc-sa/3.0/>]