

# Prime Factorization for the HP-12C model

Prof. Bernd Ulmann

March 7, 2013

## Contents

<b>1</b>	<b>Prime Factorization HP-12C code</b>	<b>2</b>
<b>2</b>	<b>How to use the Prime Factorization program</b>	<b>4</b>

# 1 Prime Factorization HP-12C code

key strokes	step	display code(s)	remark
ON			Switch the calculator ON
$\boxed{f}$ P/R			Enter program mode
$\boxed{f}$ CLEAR PRGM			Clear all program memory
STO 0	01	44 0	Save input
2	02	2	
STO 1	03	44 1	Save first prime
STO 2	04	44 2	Save first prime
RCL 0	05	45 0	Read working number
RCL 1	06	45 1	Read prime
$\div$	07	10	
ENTER	08	36	
$\boxed{g}$ FRAC	09	43 24	
$\boxed{g}$ X=0	10	43 35	X=0?
$\boxed{g}$ GTO 29	11	43,33 29	
1	12	1	
STO + 1	13	44 40 1	
RCL 2	14	45 2	
$x \leq y$	15	34	
$\boxed{g}$ X $\leq$ Y	16	43 34	
$\boxed{g}$ GTO 21	17	43,33 21	

key strokes	step	display code(s)	remark
1	18	1	
STO 2	19	44 2	
STO + 1	20	44 40 1	
RCL 0	21	45 0	Read working number
RCL 1	22	45 1	Read prime
ENTER	23	36	
×	24	20	$x^2$
$\boxed{g}$ X $\leq$ Y	25	43 34	
$\boxed{g}$ GTO 05	26	43,33 05	and loop
RCL 0	27	45 0	Read last and biggest prime
$\boxed{g}$ GTO 00	28	43,33 00	End program
RCL 1	29	45 1	Display prime factor
$\boxed{g}$ PSE	30	43 31	and pause one second
R↓	31	33	
R↓	32	33	Get register Z
STO 0	33	44 0	
$\boxed{g}$ GTO 05	34	43,33 05	and loop
$\boxed{g}$ P/R			Leave program mode

## 2 How to use the Prime Factorization program

Enter number N and run with R/S. The program will show all the prime factors of N from a low prime (2) and then up.

Example:

10

R/S

Output:

*running*

2.00      *(pause one second)*

*running*

5.00