

Open BIL, BIP or BSQ files in QGIS

QGIS Tutorials and Tips



Author

Ujaval Gandhi

<http://google.com/+UjavalGandhi>

Translations by

Marina Pavlova Ilya Trofimov Fayçal Fatihi

Response	Percentage
Very bad	45%
Bad	55%

like **BIL**, **BIP** or **BSQ**. [The GDAL library](#) - which is used by QGIS to read raster files - has support for these formats, but it cannot open these files by itself. We will go through the process of creating

common methods of organizing image data for multiband images. ([Read more about these formats](#))

measure the root name of the .bil, .bsq or .bip file and the .hdf files match and they are in the same directory. For example, if the file is called `image.bil`, the associated file should be named `image.hdr` and present in the same directory as the `image.bil` file. Then when you go to *Layer*

many a times, the file do not come with an associated `file` folder in each cases, you must create this file by hand as shown in this tutorial.

We will use the **AVHRR Global Land Cover Classification** data from **Global Land Cover Facility** as an example.

The Global Coverage datasets are distributed as **BSQ** files. Download the [1 Degree pixel resolution](#) dataset.

■■■■■■■■■■ ■■■■■■■■: [GLCF]

Response	Percentage
Yes	85%

- extract .gz file. You will see that you only have a .bsq file named gl-latlong-1deg-landcover.bsq. There is no hdr file.



2. Note that if you try to open the `gl-latlong-1deg-landcover.bsq` file in QGIS as it is, you will get an error message.



3. To overcome this error, we will create a header file with `.hdr` extension. The header file contains information about the dataset and how it is organized. Usually, this information is supplied as part of Metadata for the dataset. If you do not have the metadata, look at the website or documentation for clues. Some of the information can be guessed if you do not know it. In case of this dataset, the data download page links to the [metadata](#). Download the metadata and open it.



4. The .hdr file needs to be a plain text file in the following format. Some of these parameters are given to us and some needs to be worked out. [Learn more about the format.](#)

```
ncols <number of columns or width of the raster>
nrows <number of rows or height of the raster>
cellsize <pixel size or resolution>
xllcorner <X coordinate of lower-left corner of the raster>
yllcorner <Y coordinate of the lower-left corner of the raster>
nodata_value <pixel value to be ignored>
nbits <number of bits per pixel>
pixeltype <type of values stored in a pixel, typically float or integer>
byteorder <byte order in which image pixel values are stored, msb or lsb>
```

5. Open a text editor and create a file in the format specified in the previous step. Save the file as `gl-latlong-1deg-landcover.hdr`. Make sure the file doesn't have `.txt` at the end. Some of the values in the text files are easy to understand. The **ncols** and **nrows** come from the metadata as the Number of Lines and Number of Pixels per Line. The **cellsize** is 1 as the Pixel resolution from the metadata. The X,Y coordinate of lower-left corner needs to be worked out by us. Since the file covers the entire world and units are lat/long, **xllcorner** and **yllcorner** are -180 and -90 respectively. We do not have any information about the `nodata_value`, so -9999 is a safe bet. From metadata again, Pixel Format is Byte, so **nbits** will equal to 8 and pixeltype will be **byte_unsigned**. We do not have information about the byteorder, so leave it as `msbfirst`.



6. Now that you have the header file, put it in the same directory as `gl-latlong-1deg-landcover.bsq`. Then in QGIS, go to *Layer* ■ *Add Raster Layer*. Select `gl-latlong-1deg-landcover.bsq` as your input and click *Open*.



7. In the next screen, you may be prompted to choose a CRS. Since the data is in Lat/Long, choose **WGS84 EPSG:4326** as your CRS. Now you will see the dataset loaded in QGIS.

