

**Question:** What is the difference between the ip default-gateway, ip default-network, and ip route 0.0.0.0/0 commands?

**A.** The ip default-gateway command is used **when IP routing is disabled on the router**. This command serves non-routing network device that need to reach any network outside its own subnet or outside of its local network. The command is to function when the network device is not in routing mode. When the *ip routing* is disabled, the router becomes merely a host, similar to regular PC. To reach any network outside its own subnet or outside of its local network, the device needs to have a default-gateway.

However, ip default-network and ip route 0.0.0.0/0 are effective **when IP routing is enabled on the router** and they are used to route any packets which do not have an exact route match in the routing table.

## Configuration Commands

### Default Gateway

*#ip default-gateway x.x.x.x*

### Default Network

*#ip default-network a.b.c.d*

### Gateway of Last Resort

*#ip route 0.0.0.0 0.0.0.0 (next-hop-ip/exit-interface)*