

**NAME**

sane-umax1220u – SANE backend for the UMAX Astra 1220U and similar scanners

**DESCRIPTION**

The **sane-umax1220** library implements a SANE (Scanner Access Now Easy) backend for the the UMAX Astra 1220U and similar scanners.

For more information on this backend, please visit <http://umax1220u-sane.sourceforge.net/>.

**UMAX ASTRA 1600U/2000U/2100U SUPPORT**

This backend is also able to drive the UMAX Astra 1600U/2000U/2100U. The 2100U is confirmed to work. For the other scanners no reports have been received yet. Please contact us and tell us if your scanner works ([sane-devel@lists.alioth.debian.org](mailto:sane-devel@lists.alioth.debian.org)).

**CONFIGURATION**

Usually, no manual configuration is necessary. The configuration file for this backend resides in *@CONFIGDIR@/umax1220u.conf*.

Its contents is a list of device names that correspond to UMAX Astra scanners. Empty lines and lines starting with a hash mark (#) are ignored. A sample configuration file is shown below:

```
#usb vendor product
usb 0x1606 0x0010
# Device list for non-linux systems
/dev/scanner
/dev/usb/scanner0
```

See *sane-usb(5)* for information on how to set the access permissions on the usb device files.

**FILES**

The backend configuration file:

*@CONFIGDIR@/umax1220u.conf*

The static library implementing this backend:

*@LIBDIR@/libsane-umax1220u.a*

The shared library implementing this backend:

*@LIBDIR@/libsane-umax1220u.so* (present on systems that support dynamic loading)

**ENVIRONMENT****SANE\_DEBUG\_UMAX1220U**

If the library was compiled with debug support enabled, this environment variable controls the debug level for this backend. E.g., a value of 128 requests all debug output to be printed. Smaller levels reduce verbosity:

SANE\_DEBUG\_UMAX1220U values

Number	Remark
1	print failures
2	print information
3	print high-level function calls
4	print high-level function checkpoints
9	print mid-level function calls

```
10      print mid-level function checkpoints
80      print protocol-level function entry
90      print protocol-level function exit
```

Example:

```
export SANE_DEBUG_UMAX1220U=10
```

## KNOWN BUGS

600 dpi scanning may fail for large image sizes.

If you keep getting I/O errors, try cycling the power on your scanner to reset it.

There is no way to cancel a scan, since the driver ignores `sane_cancel()`.

If you try scanning an image which is too small, you will get I/O errors. Be sure to adjust the scan area before doing a scan, since by default, the scan area is zero.

## SEE ALSO

`sane(7)`, `sane-usb(5)`

(Old) homepage:

<http://umax1220u-sane.sourceforge.net/>

## AUTHOR

Marcio Luis Teixeira <marciot@users.sourceforge.net>

## EMAIL-CONTACT

`sane-devel@lists.alioth.debian.org`

## REPORTING BUGS

This backend isn't actively maintained. Nevertheless, bug reports and comments should be sent to the `sane-devel` mailing list. When reporting bugs, please run the backend with `SANE_DEBUG_UMAX1220U` set to 10 and attach a copy of the log messages.