



The **OpenVX™** Specification

Version 1.2

Document Revision: dba1aa3

Generated on Wed Oct 11 2017 20:00:10

Khronos Vision Working Group

Editor: Stephen Ramm

Copyright ©2016-2017 The Khronos Group Inc.



Copyright ©2016-2017 The Khronos Group Inc. All Rights Reserved.

This specification is protected by copyright laws and contains material proprietary to the Khronos Group, Inc. It or any components may not be reproduced, republished, distributed, transmitted, displayed, broadcast or otherwise exploited in any manner without the express prior written permission of Khronos Group. You may use this specification for implementing the functionality therein, without altering or removing any trademark, copyright or other notice from the specification, but the receipt or possession of this specification does not convey any rights to reproduce, disclose, or distribute its contents, or to manufacture, use, or sell anything that it may describe, in whole or in part.

Khronos Group grants express permission to any current Promoter, Contributor or Adopter member of Khronos to copy and redistribute UNMODIFIED versions of this specification in any fashion, provided that NO CHARGE is made for the specification and the latest available update of the specification for any version of the API is used whenever possible. Such distributed specification may be re-formatted AS LONG AS the contents of the specification are not changed in any way. The specification may be incorporated into a product that is sold as long as such product includes significant independent work developed by the seller. A link to the current version of this specification on the Khronos Group web-site should be included whenever possible with specification distributions.

Khronos Group makes no, and expressly disclaims any, representations or warranties, express or implied, regarding this specification, including, without limitation, any implied warranties of merchantability or fitness for a particular purpose or non-infringement of any intellectual property. Khronos Group makes no, and expressly disclaims any, warranties, express or implied, regarding the correctness, accuracy, completeness, timeliness, and reliability of the specification. Under no circumstances will the Khronos Group, or any of its Promoters, Contributors or Members or their respective partners, officers, directors, employees, agents or representatives be liable for any damages, whether direct, indirect, special or consequential damages for lost revenues, lost profits, or otherwise, arising from or in connection with these materials.

Khronos, DevU, StreamInput, glTF, WebGL, WebCL, COLLADA, OpenKODE, OpenVG, OpenVX, OpenSL ES and OpenMAX are trademarks of the Khronos Group Inc. ASTC is a trademark of ARM Holdings PLC, OpenCL is a trademark of Apple Inc. and OpenGL is a registered trademark and the OpenGL ES and OpenGL SC logos are trademarks of Silicon Graphics International used under license by Khronos. All other product names, trademarks, and/or company names are used solely for identification and belong to their respective owners.

Contents

1	Introduction	2
1.1	Abstract	2
1.2	Purpose	2
1.3	Scope of Specification	2
1.4	Normative References	2
1.5	Version/Change History	3
1.6	Deprecation	3
1.7	Requirements Language	3
1.8	Typographical Conventions	3
1.8.1	Naming Conventions	3
1.8.2	Vendor Naming Conventions	4
1.9	Glossary and Acronyms	4
1.10	Acknowledgements	5
2	Design Overview	7
2.1	Software Landscape	7
2.2	Design Objectives	7
2.2.1	Hardware Optimizations	8
2.2.2	Hardware Limitations	8
2.3	Assumptions	8
2.3.1	Portability	8
2.3.2	Opacity	8
2.4	Object-Oriented Behaviors	8
2.5	OpenVX Framework Objects	8
2.6	OpenVX Data Objects	9
2.7	Error Objects	10
2.8	Graphs Concepts	10
2.8.1	Linking Nodes	10
2.8.2	Virtual Data Objects	10
2.8.3	Node Parameters	11
2.8.4	Graph Parameters	11
2.8.5	Execution Model	12
	Asynchronous Mode	12
2.8.6	Graph Formalisms	12
	Contained & Overlapping Data Objects	13
2.8.7	Node Execution Independence	14
2.8.8	Verification	16
2.9	Callbacks	16
2.10	User Kernels	16
2.10.1	Parameter Validation	17
	The Meta Format Object	17
2.10.2	User Kernels Naming Conventions	17
2.11	Immediate Mode Functions	18
2.12	Targets	18
2.13	Base Vision Functions	18
2.13.1	Inputs	18
2.13.2	Outputs	21

2.13.3	Parameter ordering convention	23
2.14	Lifecycles	23
2.14.1	OpenVX Context Lifecycle	23
2.14.2	Graph Lifecycle	23
2.14.3	Data Object Lifecycle	24
	OpenVX Image Lifecycle	24
2.15	Host Memory Data Object Access Patterns	25
2.15.1	Matrix Access Example	25
2.15.2	Image Access Example	26
2.15.3	Array Access Example	27
2.16	Concurrent Data Object Access	27
2.17	Valid Image Region	27
2.18	Extending OpenVX	29
2.18.1	Extending Attributes	29
2.18.2	Vendor Custom Kernels	29
2.18.3	Vendor Custom Extensions	29
2.18.4	Hinting	30
2.18.5	Directives	30
3	Module Documentation	31
3.1	Vision Functions	31
3.1.1	Detailed Description	31
3.2	Absolute Difference	35
3.2.1	Detailed Description	35
3.2.2	Function Documentation	35
	vxAbsDiffNode(vx_graph graph, vx_image in1, vx_image in2, vx_image out)	35
	vxuAbsDiff(vx_context context, vx_image in1, vx_image in2, vx_image out)	35
3.3	Accumulate	37
3.3.1	Detailed Description	37
3.3.2	Function Documentation	37
	vxAccumulateImageNode(vx_graph graph, vx_image input, vx_image accum)	37
	vxuAccumulateImage(vx_context context, vx_image input, vx_image accum)	37
3.4	Accumulate Squared	39
3.4.1	Detailed Description	39
3.4.2	Function Documentation	39
	vxAccumulateSquareImageNode(vx_graph graph, vx_image input, vx_scalar shift, vx_image accum)	39
	vxuAccumulateSquareImage(vx_context context, vx_image input, vx_scalar shift, vx_image accum)	39
3.5	Data Object Copy	41
3.5.1	Detailed Description	41
3.5.2	Function Documentation	41
	vxCopyNode(vx_graph graph, vx_reference input, vx_reference output)	41
	vxuCopy(vx_context context, vx_reference input, vx_reference output)	41
3.6	Accumulate Weighted	43
3.6.1	Detailed Description	43
3.6.2	Function Documentation	43
	vxAccumulateWeightedImageNode(vx_graph graph, vx_image input, vx_scalar alpha, vx_image accum)	43
	vxuAccumulateWeightedImage(vx_context context, vx_image input, vx_scalar alpha, vx_image accum)	43
3.7	Control Flow	45
3.7.1	Detailed Description	45
3.7.2	Function Documentation	46
	vxScalarOperationNode(vx_graph graph, vx_enum scalar_operation, vx_scalar a, vx_scalar b, vx_scalar output)	46
	vxSelectNode(vx_graph graph, vx_scalar condition, vx_reference true_value, vx_reference false_value, vx_reference output)	46

3.8	Arithmetic Addition	48
3.8.1	Detailed Description	48
3.8.2	Function Documentation	48
	vxAddNode(vx_graph graph, vx_image in1, vx_image in2, vx_enum policy, vx_image out)	48
	vxuAdd(vx_context context, vx_image in1, vx_image in2, vx_enum policy, vx_image out)	48
3.9	Arithmetic Subtraction	50
3.9.1	Detailed Description	50
3.9.2	Function Documentation	50
	vxSubtractNode(vx_graph graph, vx_image in1, vx_image in2, vx_enum policy, vx_image out)	50
	vxuSubtract(vx_context context, vx_image in1, vx_image in2, vx_enum policy, vx_image out)	50
3.10	Bitwise AND	52
3.10.1	Detailed Description	52
3.10.2	Function Documentation	52
	vxAndNode(vx_graph graph, vx_image in1, vx_image in2, vx_image out)	52
	vxuAnd(vx_context context, vx_image in1, vx_image in2, vx_image out)	52
3.11	Bitwise EXCLUSIVE OR	54
3.11.1	Detailed Description	54
3.11.2	Function Documentation	54
	vxXorNode(vx_graph graph, vx_image in1, vx_image in2, vx_image out)	54
	vxuXor(vx_context context, vx_image in1, vx_image in2, vx_image out)	54
3.12	Bitwise INCLUSIVE OR	56
3.12.1	Detailed Description	56
3.12.2	Function Documentation	56
	vxOrNode(vx_graph graph, vx_image in1, vx_image in2, vx_image out)	56
	vxuOr(vx_context context, vx_image in1, vx_image in2, vx_image out)	56
3.13	Bitwise NOT	58
3.13.1	Detailed Description	58
3.13.2	Function Documentation	58
	vxNotNode(vx_graph graph, vx_image input, vx_image output)	58
	vxuNot(vx_context context, vx_image input, vx_image output)	58
3.14	Box Filter	60
3.14.1	Detailed Description	60
3.14.2	Function Documentation	60
	vxBox3x3Node(vx_graph graph, vx_image input, vx_image output)	60
	vxuBox3x3(vx_context context, vx_image input, vx_image output)	60
3.15	Non-Maxima Suppression	62
3.15.1	Detailed Description	62
3.15.2	Function Documentation	62
	vxNonMaxSuppressionNode(vx_graph graph, vx_image input, vx_image mask, vx_int32 win_size, vx_image output)	62
	vxuNonMaxSuppression(vx_context context, vx_image input, vx_image mask, vx_int32 win_size, vx_image output)	63
3.16	Canny Edge Detector	64
3.16.1	Detailed Description	64
3.16.2	Enumeration Type Documentation	65
	vx_norm_type_e	65
3.16.3	Function Documentation	65
	vxCannyEdgeDetectorNode(vx_graph graph, vx_image input, vx_threshold hyst, vx_int32 gradient_size, vx_enum norm_type, vx_image output)	65
	vxuCannyEdgeDetector(vx_context context, vx_image input, vx_threshold hyst, vx_int32 gradient_size, vx_enum norm_type, vx_image output)	66
3.17	Channel Combine	67
3.17.1	Detailed Description	67
3.17.2	Function Documentation	67
	vxChannelCombineNode(vx_graph graph, vx_image plane0, vx_image plane1, vx_image plane2, vx_image plane3, vx_image output)	67
	vxuChannelCombine(vx_context context, vx_image plane0, vx_image plane1, vx_image plane2, vx_image plane3, vx_image output)	67

3.18	Channel Extract	69
3.18.1	Detailed Description	69
3.18.2	Function Documentation	69
	vxChannelExtractNode(vx_graph graph, vx_image input, vx_enum channel, vx_image output)	69
	vxuChannelExtract(vx_context context, vx_image input, vx_enum channel, vx_image output)	69
3.19	Color Convert	71
3.19.1	Detailed Description	71
3.19.2	Function Documentation	73
	vxColorConvertNode(vx_graph graph, vx_image input, vx_image output)	73
	vxuColorConvert(vx_context context, vx_image input, vx_image output)	74
3.20	Convert Bit depth	75
3.20.1	Detailed Description	75
3.20.2	Function Documentation	75
	vxConvertDepthNode(vx_graph graph, vx_image input, vx_image output, vx_enum policy, vx_scalar shift)	75
	vxuConvertDepth(vx_context context, vx_image input, vx_image output, vx_enum policy, vx_int32 shift)	76
3.21	Custom Convolution	77
3.21.1	Detailed Description	77
3.21.2	Function Documentation	77
	vxConvolveNode(vx_graph graph, vx_image input, vx_convolution conv, vx_image output)	77
	vxuConvolve(vx_context context, vx_image input, vx_convolution conv, vx_image output)	78
3.22	Dilate Image	79
3.22.1	Detailed Description	79
3.22.2	Function Documentation	79
	vxDilate3x3Node(vx_graph graph, vx_image input, vx_image output)	79
	vxuDilate3x3(vx_context context, vx_image input, vx_image output)	79
3.23	Equalize Histogram	81
3.23.1	Detailed Description	81
3.23.2	Function Documentation	81
	vxEqualizeHistNode(vx_graph graph, vx_image input, vx_image output)	81
	vxuEqualizeHist(vx_context context, vx_image input, vx_image output)	81
3.24	Erode Image	82
3.24.1	Detailed Description	82
3.24.2	Function Documentation	82
	vxErode3x3Node(vx_graph graph, vx_image input, vx_image output)	82
	vxuErode3x3(vx_context context, vx_image input, vx_image output)	82
3.25	Fast Corners	84
3.25.1	Detailed Description	84
3.25.2	Segment Test Detector	84
3.25.3	Function Documentation	85
	vxFastCornersNode(vx_graph graph, vx_image input, vx_scalar strength_thresh, vx_bool nonmax_suppression, vx_array corners, vx_scalar num_corners)	85
	vxuFastCorners(vx_context context, vx_image input, vx_scalar strength_thresh, vx_bool nonmax_suppression, vx_array corners, vx_scalar num_corners)	85
3.26	Gaussian Filter	87
3.26.1	Detailed Description	87
3.26.2	Function Documentation	87
	vxGaussian3x3Node(vx_graph graph, vx_image input, vx_image output)	87
	vxuGaussian3x3(vx_context context, vx_image input, vx_image output)	87
3.27	Non Linear Filter	89
3.27.1	Detailed Description	89
3.27.2	Function Documentation	89
	vxNonLinearFilterNode(vx_graph graph, vx_enum function, vx_image input, vx_matrix mask, vx_image output)	89
	vxuNonLinearFilter(vx_context context, vx_enum function, vx_image input, vx_matrix mask, vx_image output)	89
3.28	Harris Corners	91

3.28.1 Detailed Description	91
3.28.2 Function Documentation	92
vxHarrisCornersNode(vx_graph graph, vx_image input, vx_scalar strength_thresh, vx_scalar min_distance, vx_scalar sensitivity, vx_int32 gradient_size, vx_int32 block_size, vx_array corners, vx_scalar num_corners)	92
vxuHarrisCorners(vx_context context, vx_image input, vx_scalar strength_thresh, vx_scalar min_distance, vx_scalar sensitivity, vx_int32 gradient_size, vx_int32 block_size, vx_array corners, vx_scalar num_corners)	93
3.29 Histogram	94
3.29.1 Detailed Description	94
3.29.2 Function Documentation	94
vxHistogramNode(vx_graph graph, vx_image input, vx_distribution distribution)	94
vxuHistogram(vx_context context, vx_image input, vx_distribution distribution)	94
3.30 Gaussian Image Pyramid	96
3.30.1 Detailed Description	96
3.30.2 Function Documentation	96
vxGaussianPyramidNode(vx_graph graph, vx_image input, vx_pyramid gaussian)	96
vxuGaussianPyramid(vx_context context, vx_image input, vx_pyramid gaussian)	96
3.31 Laplacian Image Pyramid	98
3.31.1 Detailed Description	98
3.31.2 Function Documentation	98
vxLaplacianPyramidNode(vx_graph graph, vx_image input, vx_pyramid laplacian, vx_image output)	98
vxuLaplacianPyramid(vx_context context, vx_image input, vx_pyramid laplacian, vx_image output)	99
3.32 Reconstruction from a Laplacian Image Pyramid	100
3.32.1 Detailed Description	100
3.32.2 Function Documentation	100
vxLaplacianReconstructNode(vx_graph graph, vx_pyramid laplacian, vx_image input, vx_image output)	100
vxuLaplacianReconstruct(vx_context context, vx_pyramid laplacian, vx_image input, vx_image output)	101
3.33 Integral Image	102
3.33.1 Detailed Description	102
3.33.2 Function Documentation	102
vxIntegralImageNode(vx_graph graph, vx_image input, vx_image output)	102
vxuIntegralImage(vx_context context, vx_image input, vx_image output)	102
3.34 Magnitude	104
3.34.1 Detailed Description	104
3.34.2 Function Documentation	104
vxMagnitudeNode(vx_graph graph, vx_image grad_x, vx_image grad_y, vx_image mag)	104
vxuMagnitude(vx_context context, vx_image grad_x, vx_image grad_y, vx_image mag)	105
3.35 Mean and Standard Deviation	106
3.35.1 Detailed Description	106
3.35.2 Function Documentation	106
vxMeanStdDevNode(vx_graph graph, vx_image input, vx_scalar mean, vx_scalar stddev)	106
vxuMeanStdDev(vx_context context, vx_image input, vx_float32 *mean, vx_float32 *stddev)	106
3.36 Median Filter	108
3.36.1 Detailed Description	108
3.36.2 Function Documentation	108
vxMedian3x3Node(vx_graph graph, vx_image input, vx_image output)	108
vxuMedian3x3(vx_context context, vx_image input, vx_image output)	108
3.37 Min, Max Location	110
3.37.1 Detailed Description	110
3.37.2 Function Documentation	110
vxMinMaxLocNode(vx_graph graph, vx_image input, vx_scalar minVal, vx_scalar maxVal, vx_array minLoc, vx_array maxLoc, vx_scalar minCount, vx_scalar maxCount)	110

	<code>vxuMinMaxLoc(vx_context context, vx_image input, vx_scalar minVal, vx_scalar maxVal, vx_array minLoc, vx_array maxLoc, vx_scalar minCount, vx_scalar maxCount)</code>	111
3.38	Min	112
3.38.1	Detailed Description	112
3.38.2	Function Documentation	112
	<code>vxMinNode(vx_graph graph, vx_image in1, vx_image in2, vx_image out)</code>	112
	<code>vxuMin(vx_context context, vx_image in1, vx_image in2, vx_image out)</code>	112
3.39	Max	114
3.39.1	Detailed Description	114
3.39.2	Function Documentation	114
	<code>vxMaxNode(vx_graph graph, vx_image in1, vx_image in2, vx_image out)</code>	114
	<code>vxuMax(vx_context context, vx_image in1, vx_image in2, vx_image out)</code>	114
3.40	Optical Flow Pyramid (LK)	116
3.40.1	Detailed Description	116
3.40.2	Function Documentation	117
	<code>vxOpticalFlowPyrLKNode(vx_graph graph, vx_pyramid old_images, vx_pyramid new_images, vx_array old_points, vx_array new_points_estimates, vx_array new_points, vx_enum termination, vx_scalar epsilon, vx_scalar num_iterations, vx_scalar use_initial_estimate, vx_size window_dimension)</code>	117
	<code>vxuOpticalFlowPyrLK(vx_context context, vx_pyramid old_images, vx_pyramid new_images, vx_array old_points, vx_array new_points_estimates, vx_array new_points, vx_enum termination, vx_scalar epsilon, vx_scalar num_iterations, vx_scalar use_initial_estimate, vx_size window_dimension)</code>	117
3.41	Phase	119
3.41.1	Detailed Description	119
3.41.2	Function Documentation	119
	<code>vxPhaseNode(vx_graph graph, vx_image grad_x, vx_image grad_y, vx_image orientation)</code>	119
	<code>vxuPhase(vx_context context, vx_image grad_x, vx_image grad_y, vx_image orientation)</code>	119
3.42	Pixel-wise Multiplication	121
3.42.1	Detailed Description	121
3.42.2	Function Documentation	121
	<code>vxMultiplyNode(vx_graph graph, vx_image in1, vx_image in2, vx_scalar scale, vx_enum overflow_policy, vx_enum rounding_policy, vx_image out)</code>	121
	<code>vxuMultiply(vx_context context, vx_image in1, vx_image in2, vx_float32 scale, vx_enum overflow_policy, vx_enum rounding_policy, vx_image out)</code>	122
3.43	Remap	123
3.43.1	Detailed Description	123
3.43.2	Function Documentation	123
	<code>vxRemapNode(vx_graph graph, vx_image input, vx_remap table, vx_enum policy, vx_image output)</code>	123
	<code>vxuRemap(vx_context context, vx_image input, vx_remap table, vx_enum policy, vx_image output)</code>	123
3.44	Scale Image	125
3.44.1	Detailed Description	125
3.44.2	Function Documentation	127
	<code>vxScaleImageNode(vx_graph graph, vx_image src, vx_image dst, vx_enum type)</code>	127
	<code>vxHalfScaleGaussianNode(vx_graph graph, vx_image input, vx_image output, vx_int32 kernel_size)</code>	127
	<code>vxuScaleImage(vx_context context, vx_image src, vx_image dst, vx_enum type)</code>	128
	<code>vxuHalfScaleGaussian(vx_context context, vx_image input, vx_image output, vx_int32 kernel_size)</code>	128
3.45	Sobel 3x3	129
3.45.1	Detailed Description	129
3.45.2	Function Documentation	129
	<code>vxSobel3x3Node(vx_graph graph, vx_image input, vx_image output_x, vx_image output_y)</code>	129
	<code>vxuSobel3x3(vx_context context, vx_image input, vx_image output_x, vx_image output_y)</code>	129
3.46	TableLookup	131
3.46.1	Detailed Description	131

3.46.2	Function Documentation	131
	vxTableLookupNode(vx_graph graph, vx_image input, vx_lut lut, vx_image output)	131
	vxuTableLookup(vx_context context, vx_image input, vx_lut lut, vx_image output)	131
3.47	Thresholding	133
3.47.1	Detailed Description	133
3.47.2	Function Documentation	133
	vxThresholdNode(vx_graph graph, vx_image input, vx_threshold thresh, vx_image output)	133
	vxuThreshold(vx_context context, vx_image input, vx_threshold thresh, vx_image output)	134
3.48	Warp Affine	135
3.48.1	Detailed Description	135
3.48.2	Function Documentation	135
	vxWarpAffineNode(vx_graph graph, vx_image input, vx_matrix matrix, vx_enum type, vx_image output)	135
	vxuWarpAffine(vx_context context, vx_image input, vx_matrix matrix, vx_enum type, vx_image output)	136
3.49	Warp Perspective	137
3.49.1	Detailed Description	137
3.49.2	Function Documentation	137
	vxWarpPerspectiveNode(vx_graph graph, vx_image input, vx_matrix matrix, vx_enum type, vx_image output)	137
	vxuWarpPerspective(vx_context context, vx_image input, vx_matrix matrix, vx_enum type, vx_image output)	138
3.50	Bilateral Filter	139
3.50.1	Detailed Description	139
3.50.2	Function Documentation	139
	vxBilateralFilterNode(vx_graph graph, vx_tensor src, vx_int32 diameter, vx_float32 sigmaSpace, vx_float32 sigmaValues, vx_tensor dst)	139
	vxuBilateralFilter(vx_context context, vx_tensor src, vx_int32 diameter, vx_float32 sigmaSpace, vx_float32 sigmaValues, vx_tensor dst)	140
3.51	MatchTemplate	141
3.51.1	Detailed Description	141
3.51.2	Enumeration Type Documentation	141
	vx_comp_metric_e	141
3.51.3	Function Documentation	142
	vxMatchTemplateNode(vx_graph graph, vx_image src, vx_image templateImage, vx_enum matchingMethod, vx_image output)	142
	vxuMatchTemplate(vx_context context, vx_image src, vx_image templateImage, vx_enum matchingMethod, vx_image output)	142
3.52	LBP	143
3.52.1	Detailed Description	143
3.52.2	Enumeration Type Documentation	144
	vx_lbp_format_e	144
3.52.3	Function Documentation	145
	vxLBPNode(vx_graph graph, vx_image in, vx_enum format, vx_int8 kernel_size, vx_image out)	145
	vxuLBP(vx_context context, vx_image in, vx_enum format, vx_int8 kernel_size, vx_image out)	145
3.53	HOG	146
3.53.1	Detailed Description	146
3.53.2	Data Structure Documentation	146
	struct vx_hog_t	146
3.53.3	Function Documentation	147
	vxHOGCellsNode(vx_graph graph, vx_image input, vx_int32 cell_width, vx_int32 cell_height, vx_int32 num_bins, vx_tensor magnitudes, vx_tensor bins)	147
	vxHOGFeaturesNode(vx_graph graph, vx_image input, vx_tensor magnitudes, vx_tensor bins, const vx_hog_t *params, vx_size hog_param_size, vx_tensor features)	148
	vxuHOGCells(vx_context context, vx_image input, vx_int32 cell_width, vx_int32 cell_height, vx_int32 num_bins, vx_tensor magnitudes, vx_tensor bins)	149

vxuHOGFeatures(vx_context context, vx_image input, vx_tensor magnitudes, vx_tensor bins, const vx_hog_t *params, vx_size hog_param_size, vx_tensor features) . . .	150
3.54 HoughLinesP	152
3.54.1 Detailed Description	152
3.54.2 Data Structure Documentation	152
struct vx_hough_lines_p_t	152
3.54.3 Function Documentation	153
vxHoughLinesPNode(vx_graph graph, vx_image input, const vx_hough_lines_p_t *params, vx_array lines_array, vx_scalar num_lines)	153
vxuHoughLinesP(vx_context context, vx_image input, const vx_hough_lines_p_t *params, vx_array lines_array, vx_scalar num_lines)	153
3.55 Tensor Multiply	155
3.55.1 Detailed Description	155
3.55.2 Function Documentation	155
vxTensorMultiplyNode(vx_graph graph, vx_tensor input1, vx_tensor input2, vx_scalar scale, vx_enum overflow_policy, vx_enum rounding_policy, vx_tensor output)	155
vxuTensorMultiply(vx_context context, vx_tensor input1, vx_tensor input2, vx_scalar scale, vx_enum overflow_policy, vx_enum rounding_policy, vx_tensor output)	155
3.56 Tensor Add	157
3.56.1 Detailed Description	157
3.56.2 Function Documentation	157
vxTensorAddNode(vx_graph graph, vx_tensor input1, vx_tensor input2, vx_enum policy, vx_tensor output)	157
vxuTensorAdd(vx_context context, vx_tensor input1, vx_tensor input2, vx_enum policy, vx_tensor output)	157
3.57 Tensor Subtract	159
3.57.1 Detailed Description	159
3.57.2 Function Documentation	159
vxTensorSubtractNode(vx_graph graph, vx_tensor input1, vx_tensor input2, vx_enum policy, vx_tensor output)	159
vxuTensorSubtract(vx_context context, vx_tensor input1, vx_tensor input2, vx_enum policy, vx_tensor output)	159
3.58 Tensor TableLookup	161
3.58.1 Detailed Description	161
3.58.2 Function Documentation	161
vxTensorTableLookupNode(vx_graph graph, vx_tensor input1, vx_lut lut, vx_tensor output)	161
vxuTensorTableLookup(vx_context context, vx_tensor input1, vx_lut lut, vx_tensor output)	161
3.59 Tensor Transpose	163
3.59.1 Detailed Description	163
3.59.2 Function Documentation	163
vxTensorTransposeNode(vx_graph graph, vx_tensor input, vx_tensor output, vx_size dimension1, vx_size dimension2)	163
vxuTensorTranspose(vx_context context, vx_tensor input, vx_tensor output, vx_size dimension1, vx_size dimension2)	163
3.60 Tensor Convert Bit-Depth	165
3.60.1 Detailed Description	165
3.60.2 Function Documentation	165
vxTensorConvertDepthNode(vx_graph graph, vx_tensor input, vx_enum policy, vx_scalar norm, vx_scalar offset, vx_tensor output)	165
vxuTensorConvertDepth(vx_context context, vx_tensor input, vx_enum policy, vx_scalar norm, vx_scalar offset, vx_tensor output)	166
3.61 Tensor Matrix Multiply	167
3.61.1 Detailed Description	167
3.61.2 Data Structure Documentation	167
struct vx_tensor_matrix_multiply_params_t	167
3.61.3 Function Documentation	168

vxTensorMatrixMultiplyNode(vx_graph graph, vx_tensor input1, vx_tensor input2, vx_tensor input3, const vx_tensor_matrix_multiply_params_t *matrix_multiply_params, vx_tensor output)	168
vxuTensorMatrixMultiply(vx_context context, vx_tensor input1, vx_tensor input2, vx_tensor input3, const vx_tensor_matrix_multiply_params_t *matrix_multiply_params, vx_tensor output)	168
3.62 Basic Features	169
3.62.1 Detailed Description	169
3.62.2 Data Structure Documentation	175
struct vx_coordinates2d_t	175
struct vx_coordinates2df_t	175
struct vx_coordinates3d_t	176
struct vx_keypoint_t	176
struct vx_line2d_t	176
struct vx_rectangle_t	176
3.62.3 Macro Definition Documentation	177
VX_TYPE_MASK	177
VX_DF_IMAGE	177
VX_ENUM_BASE	177
3.62.4 Typedef Documentation	177
vx_enum	177
vx_bool	177
vx_status	178
3.62.5 Enumeration Type Documentation	178
vx_bool_e	178
vx_type_e	178
vx_status_e	180
vx_enum_e	181
vx_convert_policy_e	182
vx_df_image_e	182
vx_target_e	182
vx_channel_e	183
vx_interpolation_type_e	183
vx_non_linear_filter_e	184
vx_pattern_e	184
vx_vendor_id_e	184
3.62.6 Function Documentation	185
vxGetStatus(vx_reference reference)	185
3.63 Objects	186
3.63.1 Detailed Description	186
3.64 Object: Reference	187
3.64.1 Detailed Description	187
3.64.2 Macro Definition Documentation	187
VX_MAX_REFERENCE_NAME	187
3.64.3 Typedef Documentation	188
vx_reference	188
3.64.4 Enumeration Type Documentation	188
vx_reference_attribute_e	188
3.64.5 Function Documentation	188
vxQueryReference(vx_reference ref, vx_enum attribute, void *ptr, vx_size size)	188
vxReleaseReference(vx_reference *ref_ptr)	188
vxRetainReference(vx_reference ref)	189
vxSetReferenceName(vx_reference ref, const vx_char *name)	189
3.65 Object: Context	191
3.65.1 Detailed Description	191
3.65.2 Typedef Documentation	192
vx_context	192
3.65.3 Enumeration Type Documentation	192

vx_context_attribute_e	192
vx_memory_type_e	194
vx_termination_criteria_e	194
vx_accessor_e	194
vx_round_policy_e	194
3.65.4 Function Documentation	195
vxCreateContext(void)	195
vxReleaseContext(vx_context *context)	195
vxGetContext(vx_reference reference)	195
vxQueryContext(vx_context context, vx_enum attribute, void *ptr, vx_size size)	196
vxSetContextAttribute(vx_context context, vx_enum attribute, const void *ptr, vx_size size)	196
vxSetImmediateModeTarget(vx_context context, vx_enum target_enum, const char *target_string)	197
3.66 Object: Graph	198
3.66.1 Detailed Description	198
3.66.2 Typedef Documentation	199
vx_graph	199
3.66.3 Enumeration Type Documentation	199
vx_graph_state_e	199
vx_graph_attribute_e	200
3.66.4 Function Documentation	200
vxCreateGraph(vx_context context)	200
vxReleaseGraph(vx_graph *graph)	200
vxVerifyGraph(vx_graph graph)	201
vxProcessGraph(vx_graph graph)	201
vxScheduleGraph(vx_graph graph)	202
vxWaitGraph(vx_graph graph)	202
vxQueryGraph(vx_graph graph, vx_enum attribute, void *ptr, vx_size size)	203
vxSetGraphAttribute(vx_graph graph, vx_enum attribute, const void *ptr, vx_size size)	203
vxIsGraphVerified(vx_graph graph)	204
vxRegisterAutoAging(vx_graph graph, vx_delay delay)	204
3.67 Object: Node	205
3.67.1 Detailed Description	205
3.67.2 Typedef Documentation	206
vx_node	206
3.67.3 Enumeration Type Documentation	206
vx_node_attribute_e	206
3.67.4 Function Documentation	206
vxQueryNode(vx_node node, vx_enum attribute, void *ptr, vx_size size)	206
vxSetNodeAttribute(vx_node node, vx_enum attribute, const void *ptr, vx_size size)	207
vxReleaseNode(vx_node *node)	207
vxRemoveNode(vx_node *node)	208
vxSetNodeTarget(vx_node node, vx_enum target_enum, const char *target_string)	208
vxReplicateNode(vx_graph graph, vx_node first_node, vx_bool replicate[], vx_uint32 number_of_parameters)	209
3.68 Object: Array	210
3.68.1 Detailed Description	210
3.68.2 Macro Definition Documentation	211
vxFormatArrayPointer	211
vxArrayItem	211
3.68.3 Enumeration Type Documentation	211
vx_array_attribute_e	211
3.68.4 Function Documentation	211
vxCreateArray(vx_context context, vx_enum item_type, vx_size capacity)	211
vxCreateVirtualArray(vx_graph graph, vx_enum item_type, vx_size capacity)	212
vxReleaseArray(vx_array *arr)	212
vxQueryArray(vx_array arr, vx_enum attribute, void *ptr, vx_size size)	213
vxAddArrayItems(vx_array arr, vx_size count, const void *ptr, vx_size stride)	213

vxTruncateArray(vx_array arr, vx_size new_num_items)	214
vxCopyArrayRange(vx_array array, vx_size range_start, vx_size range_end, vx_size user← _stride, void *user_ptr, vx_enum usage, vx_enum user_mem_type)	214
vxMapArrayRange(vx_array array, vx_size range_start, vx_size range_end, vx_map← id *map_id, vx_size *stride, void **ptr, vx_enum usage, vx_enum mem_type, vx_uint32 flags)	215
vxUnmapArrayRange(vx_array array, vx_map_id map_id)	216
3.69 Object: Convolution	218
3.69.1 Detailed Description	218
3.69.2 Enumeration Type Documentation	218
vx_convolution_attribute_e	218
3.69.3 Function Documentation	219
vxCreateConvolution(vx_context context, vx_size columns, vx_size rows)	219
vxCreateVirtualConvolution(vx_graph graph, vx_size columns, vx_size rows)	219
vxReleaseConvolution(vx_convolution *conv)	219
vxQueryConvolution(vx_convolution conv, vx_enum attribute, void *ptr, vx_size size)	220
vxSetConvolutionAttribute(vx_convolution conv, vx_enum attribute, const void *ptr, vx_size size)	220
vxCopyConvolutionCoefficients(vx_convolution conv, void *user_ptr, vx_enum usage, vx← enum user_mem_type)	221
3.70 Object: Distribution	222
3.70.1 Detailed Description	222
3.70.2 Enumeration Type Documentation	222
vx_distribution_attribute_e	222
3.70.3 Function Documentation	223
vxCreateDistribution(vx_context context, vx_size numBins, vx_int32 offset, vx_uint32 range)	223
vxCreateVirtualDistribution(vx_graph graph, vx_size numBins, vx_int32 offset, vx_uint32 range)	223
vxReleaseDistribution(vx_distribution *distribution)	224
vxQueryDistribution(vx_distribution distribution, vx_enum attribute, void *ptr, vx_size size)	224
vxCopyDistribution(vx_distribution distribution, void *user_ptr, vx_enum usage, vx_enum user_mem_type)	224
vxMapDistribution(vx_distribution distribution, vx_map_id *map_id, void **ptr, vx_enum us- age, vx_enum mem_type, vx_bitfield flags)	225
vxUnmapDistribution(vx_distribution distribution, vx_map_id map_id)	226
3.71 Object: Image	228
3.71.1 Detailed Description	228
3.71.2 Data Structure Documentation	230
struct vx_imagepatch_addressing_t	230
union vx_pixel_value_t	230
3.71.3 Typedef Documentation	231
vx_image	231
3.71.4 Enumeration Type Documentation	231
vx_image_attribute_e	231
vx_color_space_e	231
vx_channel_range_e	232
vx_map_flag_e	232
3.71.5 Function Documentation	232
vxCreateImage(vx_context context, vx_uint32 width, vx_uint32 height, vx_df_image color)	232
vxCreateImageFromROI(vx_image img, const vx_rectangle_t *rect)	233
vxCreateUniformImage(vx_context context, vx_uint32 width, vx_uint32 height, vx_df_image color, const vx_pixel_value_t *value)	233
vxCreateVirtualImage(vx_graph graph, vx_uint32 width, vx_uint32 height, vx_df_image color)	233
vxCreateImageFromHandle(vx_context context, vx_df_image color, const vx_imagepatch← _addressing_t addrs[], void *const ptrs[], vx_enum memory_type)	234
vxSwapImageHandle(vx_image image, void *const new_ptrs[], void *prev_ptrs[], vx_size num_planes)	235
vxQueryImage(vx_image image, vx_enum attribute, void *ptr, vx_size size)	236

vxSetImageAttribute(vx_image image, vx_enum attribute, const void *ptr, vx_size size) . . .	236
vxSetImagePixelValues(vx_image image, const vx_pixel_value_t *pixel_value)	237
vxReleaseImage(vx_image *image)	237
vxFormatImagePatchAddress1d(void *ptr, vx_uint32 index, const vx_imagepatch_↵ addressing_t *addr)	238
vxFormatImagePatchAddress2d(void *ptr, vx_uint32 x, vx_uint32 y, const vx_imagepatch_↵ addressing_t *addr)	238
vxGetValidRegionImage(vx_image image, vx_rectangle_t *rect)	238
vxCopyImagePatch(vx_image image, const vx_rectangle_t *image_rect, vx_uint32 image_↵ plane_index, const vx_imagepatch_addressing_t *user_addr, void *user_ptr, vx_enum usage, vx_enum user_mem_type)	239
vxMapImagePatch(vx_image image, const vx_rectangle_t *rect, vx_uint32 plane_index, vx_map_id *map_id, vx_imagepatch_addressing_t *addr, void **ptr, vx_enum usage, vx_enum mem_type, vx_uint32 flags)	240
vxUnmapImagePatch(vx_image image, vx_map_id map_id)	241
vxCreateImageFromChannel(vx_image img, vx_enum channel)	242
vxSetImageValidRectangle(vx_image image, const vx_rectangle_t *rect)	242
3.72 Object: LUT	244
3.72.1 Detailed Description	244
3.72.2 Enumeration Type Documentation	244
vx_lut_attribute_e	244
3.72.3 Function Documentation	245
vxCreateLUT(vx_context context, vx_enum data_type, vx_size count)	245
vxCreateVirtualLUT(vx_graph graph, vx_enum data_type, vx_size count)	245
vxReleaseLUT(vx_lut *lut)	245
vxQueryLUT(vx_lut lut, vx_enum attribute, void *ptr, vx_size size)	246
vxCopyLUT(vx_lut lut, void *user_ptr, vx_enum usage, vx_enum user_mem_type)	246
vxMapLUT(vx_lut lut, vx_map_id *map_id, void **ptr, vx_enum usage, vx_enum mem_↵ type, vx_bitfield flags)	247
vxUnmapLUT(vx_lut lut, vx_map_id map_id)	248
3.73 Object: Matrix	250
3.73.1 Detailed Description	250
3.73.2 Enumeration Type Documentation	250
vx_matrix_attribute_e	250
3.73.3 Function Documentation	251
vxCreateMatrix(vx_context c, vx_enum data_type, vx_size columns, vx_size rows)	251
vxCreateVirtualMatrix(vx_graph graph, vx_enum data_type, vx_size columns, vx_size rows)	251
vxReleaseMatrix(vx_matrix *mat)	251
vxQueryMatrix(vx_matrix mat, vx_enum attribute, void *ptr, vx_size size)	252
vxCopyMatrix(vx_matrix matrix, void *user_ptr, vx_enum usage, vx_enum user_mem_type)	252
vxCreateMatrixFromPattern(vx_context context, vx_enum pattern, vx_size columns, vx_size rows)	253
vxCreateMatrixFromPatternAndOrigin(vx_context context, vx_enum pattern, vx_size columns, vx_size rows, vx_size origin_col, vx_size origin_row)	253
3.74 Object: Pyramid	255
3.74.1 Detailed Description	255
3.74.2 Enumeration Type Documentation	256
vx_pyramid_attribute_e	256
3.74.3 Function Documentation	256
vxCreatePyramid(vx_context context, vx_size levels, vx_float32 scale, vx_uint32 width, vx_↵ uint32 height, vx_df_image format)	256
vxCreateVirtualPyramid(vx_graph graph, vx_size levels, vx_float32 scale, vx_uint32 width, vx_uint32 height, vx_df_image format)	256
vxReleasePyramid(vx_pyramid *pyr)	257
vxQueryPyramid(vx_pyramid pyr, vx_enum attribute, void *ptr, vx_size size)	257
vxGetPyramidLevel(vx_pyramid pyr, vx_uint32 index)	258
3.75 Object: Remap	259
3.75.1 Detailed Description	259

3.75.2	Enumeration Type Documentation	259
	vx_remap_attribute_e	259
3.75.3	Function Documentation	260
	vxCreateRemap(vx_context context, vx_uint32 src_width, vx_uint32 src_height, vx_uint32 dst_width, vx_uint32 dst_height)	260
	vxCreateVirtualRemap(vx_graph graph, vx_uint32 src_width, vx_uint32 src_height, vx_uint32 dst_width, vx_uint32 dst_height)	260
	vxReleaseRemap(vx_remap *table)	260
	vxMapRemapPatch(vx_remap remap, const vx_rectangle_t *rect, vx_map_id *map_id, vx_size *stride_y, void **ptr, vx_enum coordinate_type, vx_enum usage, vx_enum mem_type)	261
	vxUnmapRemapPatch(vx_remap remap, vx_map_id map_id)	262
	vxCopyRemapPatch(vx_remap remap, const vx_rectangle_t *rect, vx_size user_stride_y, void *user_ptr, vx_enum user_coordinate_type, vx_enum usage, vx_enum user_mem_type)	263
	vxQueryRemap(vx_remap table, vx_enum attribute, void *ptr, vx_size size)	264
3.76	Object: Scalar	265
3.76.1	Detailed Description	265
3.76.2	Typedef Documentation	266
	vx_scalar	266
3.76.3	Enumeration Type Documentation	266
	vx_scalar_attribute_e	266
	vx_scalar_operation_e	266
3.76.4	Function Documentation	267
	vxCreateScalar(vx_context context, vx_enum data_type, const void *ptr)	267
	vxCreateScalarWithSize(vx_context context, vx_enum data_type, const void *ptr, vx_size size)	267
	vxCreateVirtualScalar(vx_graph graph, vx_enum data_type)	267
	vxReleaseScalar(vx_scalar *scalar)	268
	vxQueryScalar(vx_scalar scalar, vx_enum attribute, void *ptr, vx_size size)	268
	vxCopyScalar(vx_scalar scalar, void *user_ptr, vx_enum usage, vx_enum user_mem_type)	269
	vxCopyScalarWithSize(vx_scalar scalar, vx_size size, void *user_ptr, vx_enum usage, vx_enum user_mem_type)	269
3.77	Object: Threshold	271
3.77.1	Detailed Description	271
3.77.2	Enumeration Type Documentation	272
	vx_threshold_type_e	272
	vx_threshold_attribute_e	272
3.77.3	Function Documentation	272
	vxCreateThresholdForImage(vx_context context, vx_enum thresh_type, vx_df_image input_format, vx_df_image output_format)	272
	vxCreateVirtualThresholdForImage(vx_graph graph, vx_enum thresh_type, vx_df_image input_format, vx_df_image output_format)	273
	vxCopyThresholdValue(vx_threshold thresh, vx_pixel_value_t *value_ptr, vx_enum usage, vx_enum user_mem_type)	273
	vxCopyThresholdRange(vx_threshold thresh, vx_pixel_value_t *lower_value_ptr, vx_pixel_value_t *upper_value_ptr, vx_enum usage, vx_enum user_mem_type)	274
	vxCopyThresholdOutput(vx_threshold thresh, vx_pixel_value_t *true_value_ptr, vx_pixel_value_t *false_value_ptr, vx_enum usage, vx_enum user_mem_type)	275
	vxReleaseThreshold(vx_threshold *thresh)	276
	vxSetThresholdAttribute(vx_threshold thresh, vx_enum attribute, const void *ptr, vx_size size)	276
	vxQueryThreshold(vx_threshold thresh, vx_enum attribute, void *ptr, vx_size size)	277
3.78	Object: ObjectArray	278
3.78.1	Detailed Description	278
3.78.2	Enumeration Type Documentation	278
	vx_object_array_attribute_e	278
3.78.3	Function Documentation	279
	vxCreateObjectArray(vx_context context, vx_reference exemplar, vx_size count)	279

vxCreateVirtualObjectArray(vx_graph graph, vx_reference exemplar, vx_size count)	279
vxGetObjectArrayItem(vx_object_array arr, vx_uint32 index)	279
vxReleaseObjectArray(vx_object_array *arr)	280
vxQueryObjectArray(vx_object_array arr, vx_enum attribute, void *ptr, vx_size size)	280
3.79 Object: Tensor	281
3.79.1 Detailed Description	281
3.79.2 Typedef Documentation	282
vx_tensor	282
3.79.3 Enumeration Type Documentation	282
vx_tensor_attribute_e	282
3.79.4 Function Documentation	282
vxCreateTensor(vx_context context, vx_size number_of_dims, const vx_size *dims, vx_↔ enum data_type, vx_int8 fixed_point_position)	282
vxCreateImageObjectArrayFromTensor(vx_tensor tensor, const vx_rectangle_t *rect, vx_↔ size array_size, vx_size jump, vx_df_image image_format)	283
vxCreateTensorFromView(vx_tensor tensor, vx_size number_of_dims, const vx_size *view_start, const vx_size *view_end)	283
vxCreateVirtualTensor(vx_graph graph, vx_size number_of_dims, const vx_size *dims, vx_↔ enum data_type, vx_int8 fixed_point_position)	283
vxCopyTensorPatch(vx_tensor tensor, vx_size number_of_dims, const vx_size *view_start, const vx_size *view_end, const vx_size *user_stride, void *user_ptr, vx_enum usage, vx_enum user_memory_type)	284
vxQueryTensor(vx_tensor tensor, vx_enum attribute, void *ptr, vx_size size)	285
vxReleaseTensor(vx_tensor *tensor)	285
3.80 Administrative Features	286
3.80.1 Detailed Description	286
3.81 Advanced Objects	287
3.81.1 Detailed Description	287
3.82 Object: Array (Advanced)	288
3.82.1 Detailed Description	288
3.82.2 Function Documentation	288
vxRegisterUserStruct(vx_context context, vx_size size)	288
3.83 Object: Node (Advanced)	289
3.83.1 Detailed Description	289
3.83.2 Function Documentation	289
vxCreateGenericNode(vx_graph graph, vx_kernel kernel)	289
3.84 Node: Border Modes	290
3.84.1 Detailed Description	290
3.84.2 Data Structure Documentation	290
struct vx_border_t	290
3.84.3 Enumeration Type Documentation	290
vx_border_e	290
vx_border_policy_e	291
3.85 Object: Delay	292
3.85.1 Detailed Description	292
3.85.2 Typedef Documentation	292
vx_delay	292
3.85.3 Enumeration Type Documentation	293
vx_delay_attribute_e	293
3.85.4 Function Documentation	293
vxQueryDelay(vx_delay delay, vx_enum attribute, void *ptr, vx_size size)	293
vxReleaseDelay(vx_delay *delay)	293
vxCreateDelay(vx_context context, vx_reference exemplar, vx_size num_slots)	294
vxGetReferenceFromDelay(vx_delay delay, vx_int32 index)	294
vxAgeDelay(vx_delay delay)	295
3.86 Object: Kernel	296
3.86.1 Detailed Description	296
3.86.2 Data Structure Documentation	298

struct vx_kernel_info_t	298
3.86.3 Typedef Documentation	300
vx_kernel	300
3.86.4 Enumeration Type Documentation	300
vx_library_e	300
vx_kernel_e	300
vx_kernel_attribute_e	305
3.86.5 Function Documentation	306
vxGetKernelByName(vx_context context, const vx_char *name)	306
vxGetKernelByEnum(vx_context context, vx_enum kernel)	307
vxQueryKernel(vx_kernel kernel, vx_enum attribute, void *ptr, vx_size size)	307
vxReleaseKernel(vx_kernel *kernel)	308
3.87 Object: Parameter	309
3.87.1 Detailed Description	309
3.87.2 Typedef Documentation	310
vx_parameter	310
3.87.3 Enumeration Type Documentation	310
vx_direction_e	310
vx_parameter_attribute_e	310
vx_parameter_state_e	310
3.87.4 Function Documentation	310
vxGetKernelParameterByIndex(vx_kernel kernel, vx_uint32 index)	310
vxGetParameterByIndex(vx_node node, vx_uint32 index)	311
vxReleaseParameter(vx_parameter *param)	311
vxSetParameterByIndex(vx_node node, vx_uint32 index, vx_reference value)	311
vxSetParameterByReference(vx_parameter parameter, vx_reference value)	312
vxQueryParameter(vx_parameter parameter, vx_enum attribute, void *ptr, vx_size size)	312
3.88 Advanced Framework API	314
3.88.1 Detailed Description	314
3.89 Framework: Node Callbacks	315
3.89.1 Detailed Description	315
3.89.2 Typedef Documentation	317
vx_action	317
vx_nodecomplete_f	317
3.89.3 Enumeration Type Documentation	317
vx_action_e	317
3.89.4 Function Documentation	317
vxAssignNodeCallback(vx_node node, vx_nodecomplete_f callback)	317
vxRetrieveNodeCallback(vx_node node)	318
3.90 Framework: Performance Measurement	319
3.90.1 Detailed Description	319
3.90.2 Data Structure Documentation	319
struct vx_perf_t	319
3.91 Framework: Log	320
3.91.1 Detailed Description	320
3.91.2 Function Documentation	320
vxAddLogEntry(vx_reference ref, vx_status status, const char *message,...)	320
vxRegisterLogCallback(vx_context context, vx_log_callback_f callback, vx_bool reentrant)	321
3.92 Framework: Hints	322
3.92.1 Detailed Description	322
3.92.2 Enumeration Type Documentation	322
vx_hint_e	322
3.92.3 Function Documentation	322
vxHint(vx_reference reference, vx_enum hint, const void *data, vx_size data_size)	322
3.93 Framework: Directives	324
3.93.1 Detailed Description	324
3.93.2 Enumeration Type Documentation	324
vx_directive_e	324

3.93.3	Function Documentation	324
	vxDirective(vx_reference reference, vx_enum directive)	324
3.94	Framework: User Kernels	326
3.94.1	Detailed Description	326
3.94.2	Typedef Documentation	330
	vx_meta_format	330
	vx_publish_kernels_f	330
	vx_unpublish_kernels_f	330
	vx_kernel_f	330
	vx_kernel_initialize_f	331
	vx_kernel_deinitialize_f	331
	vx_kernel_validate_f	331
	vx_kernel_image_valid_rectangle_f	332
3.94.3	Enumeration Type Documentation	332
	vx_meta_valid_rect_attribute_e	332
3.94.4	Function Documentation	332
	vxAllocateUserKernelId(vx_context context, vx_enum *pKernelEnumId)	332
	vxAllocateUserKernelLibraryId(vx_context context, vx_enum *pLibraryId)	333
	vxLoadKernels(vx_context context, const vx_char *module)	333
	vxUnloadKernels(vx_context context, const vx_char *module)	334
	vxAddUserKernel(vx_context context, const vx_char name[VX_MAX_KERNEL_NAME], vx_enum enumeration, vx_kernel_f func_ptr, vx_uint32 numParams, vx_kernel↵ _validate_f validate, vx_kernel_initialize_f init, vx_kernel_deinitialize_f deinit)	335
	vxFinalizeKernel(vx_kernel kernel)	335
	vxAddParameterToKernel(vx_kernel kernel, vx_uint32 index, vx_enum dir, vx_enum data↵ _type, vx_enum state)	335
	vxRemoveKernel(vx_kernel kernel)	336
	vxSetKernelAttribute(vx_kernel kernel, vx_enum attribute, const void *ptr, vx_size size)	337
	vxSetMetaFormatAttribute(vx_meta_format meta, vx_enum attribute, const void *ptr, vx↵ size size)	337
	vxSetMetaFormatFromReference(vx_meta_format meta, vx_reference exemplar)	338
3.95	Framework: Graph Parameters	339
3.95.1	Detailed Description	339
3.95.2	Function Documentation	340
	vxAddParameterToGraph(vx_graph graph, vx_parameter parameter)	340
	vxSetGraphParameterByIndex(vx_graph graph, vx_uint32 index, vx_reference value)	341
	vxGetGraphParameterByIndex(vx_graph graph, vx_uint32 index)	341

Chapter 1

Introduction

1.1 Abstract

OpenVX is a low-level programming framework domain to enable software developers to efficiently access computer vision hardware acceleration with both functional and performance portability. OpenVX has been designed to support modern hardware architectures, such as mobile and embedded SoCs as well as desktop systems. Many of these systems are parallel and heterogeneous: containing multiple processor types including multi-core CPUs, DSP subsystems, GPUs, dedicated vision computing fabrics as well as hardwired functionality. Additionally, vision system memory hierarchies can often be complex, distributed, and not fully coherent. OpenVX is designed to maximize functional and performance portability across these diverse hardware platforms, providing a computer vision framework that efficiently addresses current and future hardware architectures with minimal impact on applications.

OpenVX contains:

- a library of predefined and customizable vision functions,
- a graph-based execution model to combine function enabling both task and data-independent execution, and;
- a set of memory objects that abstract the physical memory.

OpenVX defines a C Application Programming Interface (API) for building, verifying, and coordinating graph execution, as well as for accessing memory objects. The graph abstraction enables OpenVX implementers to optimize the execution of the graph for the underlying acceleration architecture.

OpenVX also defines the `vxu` utility library, which exposes each OpenVX predefined function as a directly callable C function, without the need for first creating a graph. Applications built using the `vxu` library do not benefit from the optimizations enabled by graphs; however, the `vxu` library can be useful as the simplest way to use OpenVX and as first step in porting existing vision applications.

As the computer vision domain is still rapidly evolving, OpenVX provides an extensibility mechanism to enable developer-defined functions to be added to the application graph.

1.2 Purpose

The purpose of this document is to detail the Application Programming Interface (API) for OpenVX.

1.3 Scope of Specification

The document contains the definition of the OpenVX API. The conformance tests that are used to determine whether an implementation is consistent to this specification are defined separately.

1.4 Normative References

The section “Module Documentation” forms the normative part of the specification. Each API definition provided in that chapter has certain preconditions and post conditions specified that are normative. If these normative conditions are not met, the behavior of the function is undefined.

1.5 Version/Change History

- OpenVX 1.0 Provisional - November, 2013
- OpenVX 1.0 Provisional V2 - June, 2014
- OpenVX 1.0 - September 2014
- OpenVX 1.0.1 - April 2015
- OpenVX 1.1 - May 2016
- OpenVX 1.2 - May 2017

1.6 Deprecation

Certain items that are deprecated through the evolution of this specification document are removed from it. However, to provide a backward compatibility for such items for a certain time period these items are made available via a compatibility header file available with the release of this specification document (`vx_compatibility.h`). The items listed in this compatibility header file are temporary only and are removed permanently when the backward compatibility is no longer supported for those items.

1.7 Requirements Language

In this specification, the words *shall* or *must* express a requirement that is binding, *should* expresses design goals or recommended actions, and *may* expresses an allowed behavior.

1.8 Typographical Conventions

The following typographical conventions are used in this specification.

- **Bold** words indicate warnings or strongly communicated concepts that are intended to draw attention to the text.
 - `Monospace` words signify an API element (i.e., class, function, structure) or a filename.
 - *Italics* denote an emphasis on a particular concept, an abstraction of a concept, or signify an argument, parameter, or member.
 - Throughout this specification, code examples given to highlight a particular issue use the format as shown below:
- ```
/* Example Code Section */
int main(int argc, char *argv[])
{
 return 0;
}
```
- Some “mscgen” message diagrams are included in this specification. The graphical conventions for this tool can be found on its website.

See also

<http://www.mcternan.me.uk/mscgen/>

### 1.8.1 Naming Conventions

The following naming conventions are used in this specification.

- Opaque objects and atomics are named as `vx_object`, e.g., `vx_image` or `vx_uint8`, with an underscore separating the object name from the “vx” prefix.
- Defined Structures are named as `vx_struct_t`, e.g., `vx_imagepatch_addressing_t`, with underscores separating the structure from the “vx” prefix and a “t” to denote that it is a structure.

- Defined Enumerations are named as `vx_enum_e`, e.g., `vx_type_e`, with underscores separating the enumeration from the “vx” prefix and an “e” to denote that it is an enumerated value.
- Application Programming Interfaces are named `vxSomeFunction()` using camel case, starting with lower-case, and no underscores, e.g., `vxCreateContext()`.
- Vision functions also have a naming convention that follows a lower-case, inverse dotted hierarchy similar to Java Packages, e.g.,

```
"org.khronos.openvx.color_convert".
```

This minimizes the possibility of name collisions and promotes sorting and readability when querying the namespace of available vision functions. Each vision function should have a unique dotted name of the style: *tld.vendor.library.function*. The hierarchy of such vision function namespaces is undefined outside the subdomain “org.khronos”, but they do follow existing international standards. For OpenVX-specified vision functions, the “function” section of the unique name does not use camel case and uses underscores to separate words.

## 1.8.2 Vendor Naming Conventions

The following naming conventions are to be used for vendor specific extensions.

- Opaque objects and atomics are named as `vx_object_vendor`, e.g., `vx_ref_array_acme`, with an underscore separating the vendor name from the object name.
- Defined Structures are named as `vx_struct_vendor_t`, e.g., `vx_mdview_acme_t`, with an underscore separating the vendor from the structure name and a “t” to denote that it is a structure.
- Defined Enumerations are named as `vx_enum_vendor_e`, e.g., `vx_convolution_name_acme_e`, with an underscores separating the vendor from the enumeration name and an “e” to denote that it is an enumerated value.
- Defined Enumeration values are named as `VX_ENUMVALUE_VENDOR`, e.g., `VX_PARAM_STRUCT_ATTRIBUTES_SIZE_ACME` using only capital letters starting with the “VX” prefix, and underscores separating the words.
- Application Programming Interfaces are named `vxSomeFunctionVendor()` using camel case, starting with lowercase, and no underscores, e.g., `vxCreateRefArrayAcme()`.

## 1.9 Glossary and Acronyms

- Atomic: The specification mentions *atomics*, which means a C primitive data type. Usages that have additional wording, such as *atomic operations* do not carry this meaning.
- API: Application Programming Interface that specifies how a software component interacts with another.
- Framework: A generic software abstraction in which users can override behaviors to produce application-specific functionality.
- Engine: A purpose-specific software abstraction that is tunable by users.
- Run-time: The execution phase of a program.
- Kernel: OpenVX uses the term *kernel* to mean an abstract *computer vision function*, not an Operating System kernel. Kernel may also refer to a set of convolution coefficients in some computer vision literature (e.g., the Sobel “kernel”). OpenVX does not use this meaning. OpenCL uses kernel (specifically `cl_kernel`) to qualify a function written in “CL” which the OpenCL may invoke directly. This is close to the meaning OpenVX uses; however, OpenVX does not define a language.

## 1.10 Acknowledgements

This specification would not be possible without the contributions from this partial list of the following individuals from the Khronos Working Group and the companies that they represented at the time:

- Erik Rainey - Amazon
- Radhakrishna Giduthuri - AMD
- Mikael Bourges-Sevenier - Aptina Imaging Corporation
- Dave Schreiner - ARM Limited
- Renato Grottesi - ARM Limited
- Hans-Peter Nilsson - Axis Communications
- Amit Shoham - BDTi
- Frank Brill - Cadence Design Systems
- Thierry Lepley - Cadence Design Systems
- Shorin Kyo - Huawei
- Paul Buxton - Imagination Technologies
- Steve Ramm - Imagination Technologies
- Ben Ashbaugh - Intel
- Mostafa Hagog - Intel
- Andrey Kamaev - Intel
- Yaniv klein - Intel
- Andy Kuzma - Intel
- Tomer Schwartz - Intel
- Alexander Alekhin - Itseez
- Roman Donchenko - Itseez
- Victor Erukhimov - Itseez
- Vadim Pisarevsky - Itseez
- Vlad Vinogradov - Itseez
- Cormac Brick - Movidius Ltd
- Anshu Arya - MulticoreWare
- Shervin Emami - NVIDIA
- Kari Pulli - NVIDIA
- Neil Trevett - NVIDIA
- Daniel Laroche - NXP Semiconductors
- Susheel Gautam - QUALCOMM
- Doug Knisely - QUALCOMM
- Tao Zhang - QUALCOMM
- Yuki Kobayashi - Renesas Electronics

- Andrew Garrard - Samsung Electronics
- Erez Natan - Samsung Electronics
- Tomer Yanir - Samsung Electronics
- Chang-Hyo Yu - Samsung Electronics
- Olivier Pothier - STMicroelectronics International NV
- Chris Tseng - Texas Instruments, Inc.
- Jesse Villareal - Texas Instruments, Inc.
- Jiechao Nie - Verisilicon.Inc.
- Shehrzad Qureshi - Verisilicon.Inc.
- Xin Wang - Verisilicon.Inc.
- Stephen Neuendorffer - Xilinx, Inc.

## Chapter 2

# Design Overview

### 2.1 Software Landscape

OpenVX is intended to be used either directly by applications or as the acceleration layer for higher-level vision frameworks, engines or platform APIs.




Figure 2.1: OpenVX Usage Overview

### 2.2 Design Objectives

OpenVX is designed as a framework of standardized computer vision functions able to run on a wide variety of platforms and potentially to be accelerated by a vendor's implementation on that platform. OpenVX can improve the



performance and efficiency of vision applications by providing an abstraction for commonly-used vision functions and an abstraction for aggregations of functions (a “graph”), thereby providing the implementer the opportunity to minimize the run-time overhead.

The functions in OpenVX are intended to cover common functionality required by many vision applications.

### 2.2.1 Hardware Optimizations

This specification makes no statements as to which acceleration methodology or techniques may be used in its implementation. Vendors may choose any number of implementation methods such as parallelism and/or specialized hardware offload techniques.

This specification also makes no statement or requirements on a “level of performance” as this may vary significantly across platforms and use cases.

### 2.2.2 Hardware Limitations

The OpenVX focuses on vision functions that can be significantly accelerated by diverse hardware. Future versions of this specification may adopt additional vision functions into the core standard when hardware acceleration for those functions becomes practical.

## 2.3 Assumptions

### 2.3.1 Portability

OpenVX has been designed to maximize functional and performance portability wherever possible, while recognizing that the API is intended to be used on a wide diversity of devices with specific constraints and properties. Tradeoffs are made for portability where possible: for example, portable Graphs constructed using this API should work on any OpenVX implementation and return similar results within the precision bounds defined by the OpenVX conformance tests.

### 2.3.2 Opaqueness

OpenVX is intended to address a very broad range of devices and platforms, from deeply embedded systems to desktop machines and distributed computing architectures. The OpenVX API addresses this range of possible implementations without forcing hardware-specific requirements onto any particular implementation via the use of *opaque* objects for most program data.

All data, except client-facing structures, are opaque and hidden behind a reference that may be as thin or thick as an implementation needs. Each implementation provides the standardized interfaces for accessing data that takes care of specialized hardware, platform, or allocation requirements. Memory that is *imported* or *shared* from other APIs is not subsumed by OpenVX and is still maintained and accessible by the originator.

OpenVX does not dictate any requirements on memory allocation methods or the layout of opaque memory objects and it does not dictate byte packing or alignment for structures on architectures.

## 2.4 Object-Oriented Behaviors

OpenVX objects are both strongly typed at compile-time for safety critical applications and are strongly typed at run-time for dynamic applications. Each object has its typedef'd type and its associated enumerated value in the `vx_type_e` list. Any object may be down-cast to a `vx_reference` safely to be used in functions that require this, specifically `vxQueryReference`, which can be used to get the `vx_type_e` value using an `vx_enum`.

## 2.5 OpenVX Framework Objects

This specification defines the following OpenVX framework objects.

- **Object: Context** - The OpenVX context is the object domain for all OpenVX objects. All data objects *live* in the context as well as all framework objects. The OpenVX context keeps reference counts on all objects and must do garbage collection during its deconstruction to free lost references. While multiple clients may connect to

the OpenVX context, all data are private in that the references that refer to data objects are given only to the creating party. The results of calling an OpenVX function on data objects created in different contexts are undefined.

- **Object: Kernel** - A Kernel in OpenVX is the abstract representation of a computer vision function, such as a “Sobel Gradient” or “Lucas Kanade Feature Tracking”. A vision function may implement many similar or identical features from other functions, but it is still considered a single, unique kernel as long as it is named by the same string and enumeration and conforms to the results specified by OpenVX. Kernels are similar to function signatures in this regard.
- **Object: Parameter** - An abstract input, output, or bidirectional data object passed to a computer vision function. This object contains the signature of that parameter's usage from the kernel description. This information includes:
  - *Signature Index* - The numbered index of the parameter in the signature.
  - *Object Type* - e.g. `VX_TYPE_IMAGE`, or `VX_TYPE_ARRAY`, or some other object type from `vx_type_e`.
  - *Usage Model* - e.g. `VX_INPUT`, `VX_OUTPUT`, or `VX_BIDIRECTIONAL`.
  - *Presence State* - e.g. `VX_PARAMETER_STATE_REQUIRED`, or `VX_PARAMETER_STATE_OPTIONAL`.
- **Object: Node** - A node is an instance of a kernel that will be paired with a specific set of references (the parameters). Nodes are created from and associated with a single graph only. When a `vx_parameter` is extracted from a Node, an additional attribute can be accessed:
  - *Reference* - The `vx_reference` assigned to this parameter index from the Node creation function (e.g., `vxSobel3x3Node`).
- **Object: Graph** - A set of nodes connected in a directed (only goes one-way) acyclic (does not loop back) fashion. A Graph may have sets of Nodes that are unconnected to other sets of Nodes within the same Graph. See [Graph Formalisms](#).

## 2.6 OpenVX Data Objects

Data objects are object that are processed by graphs in nodes.

- **Object: Array** An opaque array object that could be an array of primitive data types or an array of structures.
- **Object: Convolution** An opaque object that contains  $M \times N$  matrix of `vx_int16` values. Also contains a scaling factor for normalization. Used specifically with `vxuConvolve` and `vxConvolveNode`.
- **Object: Delay** An opaque object that contains a manually controlled, temporally-delayed list of objects.
- **Object: Distribution** An opaque object that contains a frequency distribution (e.g., a histogram).
- **Object: Image** An opaque image object that may be some format in `vx_df_image_e`.
- **Object: LUT** An opaque lookup table object used with `vxTableLookupNode` and `vxuTableLookup`.
- **Object: Matrix** An opaque object that contains  $M \times N$  matrix of some scalar values.
- **Object: Pyramid** An opaque object that contains multiple levels of scaled `vx_image` objects.
- **Object: Remap** An opaque object that contains the map of source points to destination points used to transform images.
- **Object: Scalar** An opaque object that contains a single primitive data type.
- **Object: Threshold** An opaque object that contains the thresholding configuration.
- **Object: ObjectArray** An opaque array object that could be an array of any data-object (not data-type) of OpenVX except Delay and ObjectArray objects.
- **Object: Tensor** An opaque multidimensional data object. Used in functions like `vxHOGFeaturesNode`, `vxHOGCellsNode` and the Neural Networks extension.

## 2.7 Error Objects

Error objects are specialized objects that may be returned from other object creator functions when serious platform issue occur (i.e., out of memory or out of handles). These can be checked at the time of creation of these objects, but checking also may be put-off until usage in other APIs or verification time, in which case, the implementation must return appropriate errors to indicate that an invalid object type was used.

```
vx_object obj = vxCreateObject(context, ...);
vx_status status = vxGetStatus((vx_reference) obj);
if (status == VX_SUCCESS) {
 // object is good
}
```

## 2.8 Graphs Concepts

The *graph* is the central computation concept of OpenVX. The purpose of using graphs to express the Computer Vision problem is to allow for the possibility of any implementation to maximize its optimization potential because all the operations of the graph and its dependencies are known ahead of time, before the graph is processed.

Graphs are composed of one or more *nodes* that are added to the graph through node creation functions. Graphs in OpenVX must be created ahead of processing time and verified by the implementation, after which they can be processed as many times as needed.

### 2.8.1 Linking Nodes

Graph Nodes are linked together via data dependencies with *no explicitly-stated ordering*. The same reference may be linked to other nodes. Linking has a limitation, however, in that only one node in a graph may output to any specific data object reference. That is, only a single writer of an object may exist in a given graph. This prevents indeterminate ordering from data dependencies. All writers in a graph shall produce output data before any reader of that data accesses it.

### 2.8.2 Virtual Data Objects

Graphs in OpenVX depend on data objects to link together nodes. When clients of OpenVX know that they do not need access to these *intermediate* data objects, they may be created as *virtual*. Virtual data objects can be used in the same manner as non-virtual data objects to link nodes of a graph together; however, virtual data objects are different in the following respects.

- **Inaccessible** - No calls to an Map/Unmap or Copy APIs shall succeed given a reference to an object created through a virtual create function from a Graph external perspective. Calls to Map/Unmap or Copy APIs from within client-defined node that belongs to the same graph as the virtual object will succeed as they are Graph internal.
- **Scoped** - Virtual data objects are scoped within the Graph in which they are created; they cannot be shared outside their scope. The live range of the data content of a virtual data object is limited to a single graph execution. In other word, data content of a virtual object is undefined before graph execution and no data of a virtual object should be expected to be preserved across successive graph executions by the application.
- **Intermediates** - Virtual data objects should be used only for intermediate operations within Graphs, because they are fundamentally inaccessible to clients of the API.
- **Dimensionless or Formatless** - Virtual data objects may have dimensions and formats partially or fully undefined at creation time. For instance, a virtual image can be created with undefined or partially defined dimensions (0x0, Nx0 or 0xN where N is not null) and/or without defined format (VX\_DF\_IMAGE\_VIRT). The undefined property of the virtual object at creation time is undefined with regard to the graph and mutable at graph verification time; it will be automatically adjusted at each graph verification, deduced from the node that outputs the virtual object. Dimensions and format properties that are well defined at virtual object creation time are immutable and can't be adjusted automatically at graph verification time.
- **Attributes** - Even if a given Virtual data object does not have its dimensionality or format completely defined, these attributes may still be queried. If queried before the object participates in a graph verification, the attribute value returned is what the user provided (e.g., "0" for the dimension). If queried after graph verification (or re-verification), the attribute value returned will be the value determined by the graph verification rules.

- The Dimensionless or Formatless aspect of virtual data is a commodity that allows creating graphs generic with regard to dimensions or format, but there are restrictions:
  1. Nodes may require the dimensions and/or the format to be defined for a virtual output object when it can't be deduced from its other parameters. For example, a Scale node requires well defined dimensions for the output image, while ColorConvert and ChannelCombine nodes require a well defined format for the output image.
  2. An image created from ROI must always be well defined (`vx_rectangle_t` parameter) and can't be created from a dimensionless virtual image.
  3. A ROI of a formatless virtual image shouldn't be a node output.
  4. A tensor created from View must always be well defined and can't be created from a dimensionless virtual tensor.
  5. A view of a formatless virtual tensor shouldn't be a node output.
  6. Levels of a dimensionless or formatless virtual pyramid shouldn't be a node output.
- Inheritance - A sub-object inherits from the virtual property of its parent. A sub-object also inherits from the Dimensionless or Formatless property of its parent with restrictions:
  1. it is adjusted automatically at graph verification when the parent properties are adjusted (the parent is the output of a node)
  2. it can't be adjusted at graph verification when the sub-object is itself the output of a node.
- Optimizations - Virtual data objects do not have to be created during Graph validation and execution and therefore may be of zero *size*.

These restrictions enable vendors the ability to optimize some aspects of the data object or its usage. Some vendors may not allocate such objects, some may create intermediate sub-objects of the object, and some may allocate the object on remote, inaccessible memories. OpenVX does not proscribe *which* optimization the vendor does, merely that it *may* happen.

### 2.8.3 Node Parameters

Parameters to node creation functions are defined as either atomic types, such as `vx_int32`, `vx_enum`, or as objects, such as `vx_scalar`, `vx_image`. The atomic variables of the Node creation functions shall be converted by the framework into `vx_scalar` references for use by the Nodes. A node parameter of type `vx_scalar` can be changed during the graph execution; whereas, a node parameter of an atomic type (`vx_int32` etc.) require at least a graph revalidation if changed. All node parameter objects may be modified by retrieving the reference to the `vx_parameter` via `vxGetParameterByIndex`, and then passing that to `vxQueryParameter` to retrieve the reference to the object.

```
vx_parameter param = vxGetParameterByIndex(node, p);
vx_reference ref;
vxQueryParameter(param, VX_PARAMETER_REF, &ref, sizeof(ref));
```

If the type of the parameter is unknown, it may be retrieved with the same function.

```
vx_enum type;
vxQueryParameter(param, VX_PARAMETER_TYPE, &type, sizeof(type)
);
/* cast the ref to the correct vx_<type>. Atomics are now vx_scalar */
```

### 2.8.4 Graph Parameters

Parameters may exist on Graphs, as well. These parameters are defined by the author of the Graph and each Graph parameter is defined as a specific parameter from a Node within the Graph using `vxAddParameterToGraph`. Graph parameters communicate to the implementation that there are specific Node parameters that may be modified by the client between Graph executions. Additionally, they are parameters that the client may set without the reference to the Node but with the reference to the Graph using `vxSetGraphParameterByIndex`. This allows for the Graph authors to construct *Graph Factories*. How these factories work falls outside the scope of this document.

See also

[Framework: Graph Parameters](#)

### 2.8.5 Execution Model

Graphs must execute in both:

- *Synchronous blocking mode* (in that `vxProcessGraph` will block until the graph has completed), and in
- *Asynchronous single-issue-per-reference mode* (via `vxScheduleGraph` and `vxWaitGraph`).

#### Asynchronous Mode

In asynchronous mode, Graphs must be single-issue-per-reference. This means that given a constructed graph reference  $G$ , it may be scheduled multiple times but only executes sequentially with respect to itself. Multiple graphs references given to the asynchronous graph interface do not have a defined behavior and may execute in parallel or in series based on the behavior or the vendor's implementation.

### 2.8.6 Graph Formalisms

To use graphs several rules must be put in place to allow deterministic execution of Graphs. The behavior of a `processGraph( G )` call is determined by the structure of the Processing Graph  $G$ . The Processing Graph is a bipartite graph consisting of a set of Nodes  $N_1 \dots N_n$  and a set of data objects  $d_1 \dots d_i$ . Each edge  $( N_x, D_y )$  in the graph represents a data object  $D_y$  that is written by Node  $N_x$  and each edge  $( D_x, N_y )$  represents a data object  $D_x$  that is read by Node  $N_y$ . Each edge  $e$  has a name  $\text{Name}( e )$ , which gives the parameter name of the node that references the corresponding data object. Each Node Parameter also has a type  $\text{Type}( \text{node}, \text{name} )$  in  $\{ \text{IN} \leftarrow \text{PUT}, \text{OUTPUT}, \text{INOUT} \}$ . Some data objects are *Virtual*, and some data objects are *Delay*. Delay data objects are just collections of data objects with indexing (like an image list) and known linking points in a graph. A node may be classified as a *head node*, which has no backward dependency. Alternatively, a node may be a *dependent node*, which has a backward dependency to the head node. In addition, the Processing Graph has several restrictions:

1. *Output typing* - Every output edge  $( N_x, D_y )$  requires  $\text{Type}( N_x, \text{Name}( N_x, D_y ) )$  in  $\{ \text{OUTPUT}, \text{INOUT} \}$
2. *Input typing* - Every input edge  $( D_x, N_y )$  requires  $\text{Type}( N_y, \text{Name}( D_x, N_y ) )$  in  $\{ \text{INPUT} \}$  or  $\{ \text{INOUT} \}$
3. *Single Writer* - Every data object is the target of at most one output edge.
4. *Broken Cycles* - Every cycle in  $G$  must contain at least input edge  $( D_x, N_y )$  where  $D_x$  is Delay.
5. *Virtual images must have a source* - If  $D_y$  is Virtual, then there is at least one output edge that writes  $D_y$   $( N_x, D_y )$
6. *Bidirectional data objects shall not be virtual* - If  $\text{Type}( N_x, \text{Name}( N_x, D_y ) )$  is INOUT implies  $D_y$  is non-Virtual.
7. *Delay data objects shall not be virtual* - If  $D_x$  is Delay then it shall not be Virtual.
8. *A uniform image cannot be output or bidirectional.*

The execution of each node in a graph consists of an atomic operation (sometimes referred to as *firing*) that consumes data representing each input data object, processes it, and produces data representing each output data object. A node may execute when all of its input edges are marked *present*. Before the graph executes, the following initial marking is used:

- All input edges  $( D_x, N_y )$  from non-Virtual objects  $D_x$  are marked (parameters must be set).
- All input edges  $( D_x, N_y )$  with an output edge  $( N_z, D_x )$  are unmarked.
- All input edges  $( D_x, N_y )$  where  $D_x$  is a Delay data object are marked.

Processing a node results in unmarking all the corresponding input edges and marking all its output edges; marking an output edge  $( N_x, D_y )$  where  $D_y$  is not a Delay results in marking all of the input edges  $( D_y, N_z )$ . Following these rules, it is possible to statically schedule the nodes in a graph as follows: Construct a precedence graph  $P$ , including all the nodes  $N_1 \dots N_n$ , and an edge  $( N_x, N_z )$  for every pair of edges  $( N_x, D_y )$  and  $( D_y, N_z )$  where  $D_y$  is not a Delay. Then unconditionally fire each node according to any topological sort of  $P$ .

The following assertions should be verified:

- $P$  is a Directed Acyclic Graph (DAG), implied by 4 and the way it is constructed.

- Every data object has a value when it is executed, implied by 5, 6, 7, and the marking.
- Execution is deterministic if the nodes are deterministic, implied by 3, 4, and the marking.
- Every node completes its execution exactly once.

The execution model described here just acts as a formalism. For example, independent processing is allowed across multiple depended and depending nodes and edges, provided that the result is invariant with the execution model described here.

### Contained & Overlapping Data Objects

There are cases in which two different data objects referenced by an output parameter of node  $N_1$  and input parameter of node  $N_2$  in a graph induce a dependency between these two nodes: For example, a pyramid and its level images, image and the sub-images created from it by `vxCreateImageFromROI` or `vxCreateImageFromChannel`, or overlapping sub-images of the same image. Following figure show examples of this dependency. To simplify subsequent definitions and requirements a limitation is imposed that if a sub-image  $I'$  has been created from image  $I$  and sub-image  $I''$  has been created from  $I'$ , then  $I''$  is still considered a sub-image of  $I$  and not of  $I'$ . In these cases it is expected that although the two nodes reference two different data objects, any change to one data object might be reflected in the other one. Therefore it implies that  $N_1$  comes before  $N_2$  in the graph's topological order. To ensure that, following definitions are introduced.




Figure 2.2: Pyramid Example




Figure 2.3: Image Example

1. *Containment Set* -  $C(d)$ , the set of recursively contained data objects of  $d$ , named *Containment Set*, is defined as follows:

- $C_0(d) = \{d\}$
- $C_1(d)$  is the set of all data objects that are *directly contained* by  $d$ :

- (a) If  $d$  is an image, all images created from an ROI or channel of  $d$  are directly contained by  $d$ .
- (b) If  $d$  is a pyramid, all pyramid levels of  $d$  are directly contained by  $d$ .
- (c) If  $d$  is an object array, all elements of  $d$  are directly contained by  $d$ .
- (d) If  $d$  is a delay object, all slots of  $d$  are directly contained by  $d$ .
- For  $i > 1$ ,  $C_i(d)$  is the set of all data objects that are contained by  $d$  at the  $i^{\text{th}}$  order

$$C_i(d) = \bigcup_{d' \in C_{i-1}(d)} C_1(d') \quad (2.1)$$

- $C(d)$  is the set that contains  $d$  itself, the data objects *contained* by  $d$ , the data objects that are contained by the data objects contained by  $d$  and so on. Formally:

$$C(d) = \bigcup_{i=0}^{\infty} C_i(d) \quad (2.2)$$

2.  $I(d)$  is a predicate that equals true if and only if  $d$  is an image.
3. *Overlapping Relationship* - The overlapping relation  $R_{ov}$  is a relation defined for images, such that if  $i_1$  and  $i_2$  in  $C(i)$ ,  $i$  being an image, then  $i_1 R_{ov} i_2$  is true if and only if  $i_1$  and  $i_2$  overlap, i.e there exists a point (x,y) of  $i$  that is contained in both  $i_1$  and  $i_2$ . Note that this relation is reflexive and symmetric, but not transitive:  $i_1$  overlaps  $i_2$  and  $i_2$  overlaps  $i_3$  does not necessarily imply that  $i_1$  overlaps  $i_3$ , as illustrated in the following figure:




Figure 2.4: Overlap Example

4. *Dependency Relationship* - The dependency relationship  $N_1 \rightarrow N_2$ , is a relation defined for nodes.  $N_1 \rightarrow N_2$  means that  $N_2$  depends on  $N_1$  and then implies that  $N_2$  must be executed after the completion of  $N_1$ .
5.  $N_1 \rightarrow N_2$  if  $N_1$  writes to a data object  $d_1$  and  $N_2$  reads from a data object  $d_2$  and:

$$d_1 \in C(d_2) \text{ or } d_2 \in C(d_1) \text{ or } (I(d_1) \text{ and } I(d_2) \text{ and } d_1 R_{ov} d_2) \quad (2.3)$$

If data object  $D_y$  of an output edge  $(N_x, D_y)$  overlaps with a data object  $D_z$  then the result is implementation defined.

### 2.8.7 Node Execution Independence

In the following example a client computes the gradient magnitude and gradient phase from a blurred input image. The `vxMagnitudeNode` and `vxPhaseNode` are *independently* computed, in that each does not depend on the output of the other. OpenVX does not mandate that they are run simultaneously or in parallel, but it could be implemented this way by the OpenVX vendor.




Figure 2.5: A simple graph with some independent nodes.

The code to construct such a graph can be seen below.

```

vx_context context = vxCreateContext();
vx_image images[] = {
 vxCreateImage(context, 640, 480, VX_DF_IMAGE_UYVY),
 vxCreateImage(context, 640, 480, VX_DF_IMAGE_S16),
 vxCreateImage(context, 640, 480, VX_DF_IMAGE_U8),
};

vx_graph graph = vxCreateGraph(context);
vx_image virts[] = {
 vxCreateVirtualImage(graph, 0, 0,
 VX_DF_IMAGE_VIRT),
 vxCreateVirtualImage(graph, 0, 0,
 VX_DF_IMAGE_VIRT),
 vxCreateVirtualImage(graph, 0, 0,
 VX_DF_IMAGE_VIRT),
 vxCreateVirtualImage(graph, 0, 0,
 VX_DF_IMAGE_VIRT),
};

vxChannelExtractNode(graph, images[0], VX_CHANNEL_Y, virts[0]),
vxGaussian3x3Node(graph, virts[0], virts[1]),
vxSobel3x3Node(graph, virts[1], virts[2], virts[3]),
vxMagnitudeNode(graph, virts[2], virts[3], images[1]),
vxPhaseNode(graph, virts[2], virts[3], images[2]),

status = vxVerifyGraph(graph);
if (status == VX_SUCCESS)
{
 status = vxProcessGraph(graph);
}
vxReleaseContext(&context); /* this will release everything */

```



### 2.8.8 Verification

Graphs within OpenVX must go through a rigorous validation process before execution to satisfy the design concept of eliminating run-time overhead (parameter checking) that guarantees safe execution of the graph. OpenVX must check for (but is not limited to) these conditions:

Parameters To Nodes:

- Each required parameter is given to the node ([vx\\_parameter\\_state\\_e](#)). Optional parameters may not be present and therefore are not checked when absent. If present, they are checked.
- Each parameter given to a node must be of the right *direction* (a value from [vx\\_direction\\_e](#)).
- Each parameter given to a node must be of the right *object type* (from the object range of [vx\\_type\\_e](#)).
- Each parameter attribute or value must be verified. In the case of a scalar value, it may need to be range checked (e.g.,  $0.5 \leq k \leq 1.0$ ). The implementation is not required to do run-time range checking of scalar values. If the value of the scalar changes at run time to go outside the range, the results are undefined. The rationale is that the potential performance hit for run-time range checking is too large to be enforced. It will still be checked at graph verification time as a time-zero sanity check. If the scalar is an output parameter of another node, it must be initialized to a legal value. In the case of [vxScaleImageNode](#), the relation of the input image dimensions to the output image dimensions determines the scaling factor. These values or attributes of data objects must be checked for compatibility on each platform.
- Graph Connectivity - the [vx\\_graph](#) must be a Directed Acyclic Graph (DAG). No cycles or feedback is allowed. The [vx\\_delay](#) object has been designed to explicitly address feedback between Graph executions.
- Resolution of Virtual Data Objects - Any changes to *Virtual* data objects from unspecified to specific format or dimensions, as well as the related creation of objects of specific type that are observable at processing time, takes place at Verification time.

The implementation must check that all node parameters are the correct type at node creation time, unless the parameter value is set to NULL. Additional checks may also be made on non-NULL parameters. The user must be allowed to set parameters to NULL at node creation time, even if they are required parameters, in order to create "exemplar" nodes that are not used in graph execution, or to create nodes incrementally. Therefore the implementation must not generate an error at node creation time for parameters that are explicitly set to NULL. However, the implementation must check that all required parameters are non-NULL and the correct type during [vxVerifyGraph](#). Other more complex checks may also be done during [vxVerifyGraph](#). The implementation should provide specific error reporting of NULL parameters during [vxVerifyGraph](#), e.g., "Parameter<parameter> of Node<node> is NULL."

## 2.9 Callbacks

Callbacks are a method to control graph flow and to make decisions based on completed work. The [vxAssignNodeCallback](#) call takes as a parameter a callback function. This function will be called after the execution of the particular node, but prior to the completion of the graph. If nodes are arranged into independent sets, the order of the callbacks is unspecified. Nodes that are arranged in a serial fashion due to data dependencies perform callbacks in order. The callback function may use the node reference first to extract parameters from the node, and then extract the data references. Data outputs of Nodes with callbacks shall be available (via Map/Unmap/Copy methods) when the callback is called.

## 2.10 User Kernels

OpenVX supports the concept of *client-defined functions* that shall be executed as *Nodes* from inside the Graph or are Graph *internal*. The purpose of this paradigm is to:

- Further exploit independent operation of nodes within the OpenVX platform.
- Allow componentized functions to be reused elsewhere in OpenVX.
- Formalize strict verification requirements (i.e., Contract Programming).




Figure 2.6: A graph with User Kernel nodes which are independent of the “base” nodes.

In this example, to execute client-supplied functions, the graph does not have to be halted and then resumed. These nodes shall be executed in an independent fashion with respect to independent base nodes within OpenVX. This allows implementations to further minimize execution time if hardware to exploit this property exists.

### 2.10.1 Parameter Validation

User Kernels must aid in the Graph Verification effort by providing an explicit validation function for each vision function they implement. Each parameter passed to the instantiated Node of a User Kernel is validated using the client-supplied validation function. The client must check these attributes and/or values of each parameter:

- Each attribute or value of the parameter must be checked. For example, the size of array, or the value of a scalar to be within a range, or a dimensionality constraint of an image such as width divisibility. (Some implementations may have restrictions, such as an image width be evenly divisible by some fixed number).
- If the output parameters depend on attributes or values from input parameters, those relationships must be checked.

#### The Meta Format Object

The Meta Format Object is an opaque object used to collect requirements about the output parameter, which then the OpenVX implementation will check. The Client must manually set relevant object attributes to be checked against output parameters, such as dimensionality, format, scaling, etc.

### 2.10.2 User Kernels Naming Conventions

User Kernels must be exported with a unique name (see [Naming Conventions](#) for information on OpenVX conventions) and a unique enumeration. Clients of OpenVX may use either the name or enumeration to retrieve a kernel,

so collisions due to non-unique names will cause problems. The kernel enumerations may be extended by following this example:

```
#define VX_KERNEL_NAME_KHR_XYZ "org.khronos.example.xyz"

#define VX_LIBRARY_XYZ (0x3) // assigned from Khronos, vendors control their own

enum vx_kernel_xyz_ext_e {
 VX_KERNEL_KHR_XYZ = VX_KERNEL_BASE(VX_ID_DEFAULT, VX_LIBRARY_XYZ) + 0x0,
 // up to 0xFFF kernel enums can be created.
};
```

Each vendor of a vision function or an implementation must apply to Khronos to get a unique identifier (up to a limit of  $2^{12} - 1$  vendors). Until they obtain a unique ID vendors must use `VX_ID_DEFAULT`.

To construct a kernel enumeration, a vendor must have both their ID and a *library* ID. The library ID's are completely *vendor* defined (however when using the `VX_ID_DEFAULT` ID, many libraries may collide in namespace).

Once both are defined, a kernel enumeration may be constructed using the `VX_KERNEL_BASE` macro and an offset. (The offset is optional, but very helpful for long enumerations.)

## 2.11 Immediate Mode Functions

OpenVX also contains an interface defined within `<VX/vxu.h>` that allows for immediate execution of vision functions. These interfaces are prefixed with `vxu` to distinguish them from the Node interfaces, which are of the form `vx<Name>Node`. Each of these interfaces replicates a Node interface with some exceptions. Immediate mode functions are defined to *behave* as *Single Node Graphs*, which have no leaking side-effects (e.g., no Log entries) within the Graph Framework after the function returns. The following tables refer to both the Immediate Mode and Graph Mode vision functions. The Module documentation for each vision function draws a distinction on each API by noting that it is either an immediate mode function with the tag `[Immediate]` or it is a Graph mode function by the tag `[Graph]`.

## 2.12 Targets

A 'Target' specifies a physical or logical devices where a node or an immediate mode function is executed. This allows the use of different implementations of vision functions on different targets. The existence of allowed Targets is exposed to the applications by the use of defined APIs. The choice of a Target allows for different levels of control on where the nodes can be executed. An OpenVX implementation must support at least one target. Additional supported targets are specified using the appropriate enumerations. See `vxSetNodeTarget`, `vxSetImmediateModeTarget`, and `vx_target_e`. An OpenVX implementation must support at least one target `VX_TARGET_ANY` as well as `VX_TARGET_STRING` enumerates. An OpenVX implementation may also support more than these two to indicate the use of specific devices. For example, an implementation may add `VX_TARGET_CPU` and `VX_TARGET_GPU` enumerates to indicate the support of two possible targets to assign a nodes to (or to excute an immediate mode function). Another way an implementation can indicate the existence of multiple targets, for example CPU and GPU, is by specifying the target as `VX_TARGET_STRING` and using strings 'CPU' and 'GPU'. Thus defining targets using names rather than enumerates. The specific naming of string or enumerates is not enforced by the specification and it is up to the vendors to document and communicate the Target naming. Once available in a given implementation Applications can assign a Target to a node to specify the target that must execute that node by using the API `vxSetNodeTarget`. For immediate mode functions the target specifies the physical or logical device where the future execution of that function will be attempted. When an immediate mode function is not supported on the selected target the execution falls back to `VX_TARGET_ANY`.

## 2.13 Base Vision Functions

OpenVX comes with a standard or *base* set of vision functions. The following table lists the supported set of vision functions, their input types (first table) and output types (second table), and the version of OpenVX in which they are supported.

### 2.13.1 Inputs

| Vision Function      | S8 | U8       | U16 | S16        | U32 | F32 | color | other |
|----------------------|----|----------|-----|------------|-----|-----|-------|-------|
| AbsDiff              |    | 1.↔<br>0 |     | 1.↔<br>0.1 |     |     |       |       |
| Accumulate           |    | 1.↔<br>0 |     |            |     |     |       |       |
| AccumulateSquared    |    | 1.↔<br>0 |     |            |     |     |       |       |
| AccumulateWeighted   |    | 1.↔<br>0 |     |            |     |     |       |       |
| Add                  |    | 1.↔<br>0 |     | 1.0        |     |     |       |       |
| And                  |    | 1.↔<br>0 |     |            |     |     |       |       |
| BilateralFilter      |    | 1.↔<br>2 |     | 1.2        |     |     |       |       |
| Box3x3               |    | 1.↔<br>0 |     |            |     |     |       |       |
| CannyEdgeDetector    |    | 1.↔<br>0 |     |            |     |     |       |       |
| ChannelCombine       |    | 1.↔<br>0 |     |            |     |     |       |       |
| ChannelExtract       |    |          |     |            |     |     | 1.0   |       |
| ColorConvert         |    |          |     |            |     |     | 1.0   |       |
| ConvertDepth         |    | 1.↔<br>0 |     | 1.0        |     |     |       |       |
| Convolve             |    | 1.↔<br>0 |     |            |     |     |       |       |
| Data Object Copy     |    |          |     |            |     |     |       | 1.2   |
| Dilate3x3            |    | 1.↔<br>0 |     |            |     |     |       |       |
| EqualizeHistogram    |    | 1.↔<br>0 |     |            |     |     |       |       |
| Erode3x3             |    | 1.↔<br>0 |     |            |     |     |       |       |
| FastCorners          |    | 1.↔<br>0 |     |            |     |     |       |       |
| Gaussian3x3          |    | 1.↔<br>0 |     |            |     |     |       |       |
| GaussianPyramid      |    | 1.↔<br>1 |     |            |     |     |       |       |
| HarrisCorners        |    | 1.↔<br>0 |     |            |     |     |       |       |
| HalfScaleGaussian    |    | 1.↔<br>0 |     |            |     |     |       |       |
| Histogram            |    | 1.↔<br>0 |     |            |     |     |       |       |
| HOGCells             |    | 1.↔<br>2 |     |            |     |     |       |       |
| HOGFeatures          |    | 1.↔<br>2 |     |            |     |     |       |       |
| HoughLinesP          |    | 1.↔<br>2 |     |            |     |     |       |       |
| IntegrallImage       |    | 1.↔<br>0 |     |            |     |     |       |       |
| LaplacianPyramid     |    | 1.↔<br>1 |     |            |     |     |       |       |
| LaplacianReconstruct |    |          |     | 1.1        |     |     |       |       |

| Vision Function      | S8      | U8      | U16 | S16 | U32 | F32 | color | other |
|----------------------|---------|---------|-----|-----|-----|-----|-------|-------|
| LBP                  |         | 1.<br>2 |     |     |     |     |       |       |
| Magnitude            |         |         |     | 1.0 |     |     |       |       |
| MatchTemplate        |         | 1.<br>2 |     |     |     |     |       |       |
| MeanStdDev           |         | 1.<br>0 |     |     |     |     |       |       |
| Median3x3            |         | 1.<br>0 |     |     |     |     |       |       |
| Max                  |         | 1.<br>2 |     | 1.2 |     |     |       |       |
| Min                  |         | 1.<br>2 |     | 1.2 |     |     |       |       |
| MinMaxLoc            |         | 1.<br>0 |     | 1.0 |     |     |       |       |
| Multiply             |         | 1.<br>0 |     | 1.0 |     |     |       |       |
| NonLinearFilter      |         | 1.<br>1 |     |     |     |     |       |       |
| NonMaximaSuppression |         | 1.<br>2 |     | 1.2 |     |     |       |       |
| Not                  |         | 1.<br>0 |     |     |     |     |       |       |
| OpticalFlowPyrLK     |         | 1.<br>0 |     |     |     |     |       |       |
| Or                   |         | 1.<br>0 |     |     |     |     |       |       |
| Phase                |         |         |     | 1.0 |     |     |       |       |
| GaussianPyramid      |         | 1.<br>0 |     |     |     |     |       |       |
| Remap                |         | 1.<br>0 |     |     |     |     |       |       |
| ScaleImage           |         | 1.<br>0 |     |     |     |     |       |       |
| Sobel3x3             |         | 1.<br>0 |     |     |     |     |       |       |
| Subtract             |         | 1.<br>0 |     | 1.0 |     |     |       |       |
| TableLookup          |         | 1.<br>0 |     | 1.1 |     |     |       |       |
| TensorMultiply       | 1.<br>2 | 1.<br>2 |     | 1.2 |     |     |       |       |
| TensorAdd            | 1.<br>2 | 1.<br>2 |     | 1.2 |     |     |       |       |
| TensorSubtract       | 1.<br>2 | 1.<br>2 |     | 1.2 |     |     |       |       |
| TensorMatrixMultiply | 1.<br>2 | 1.<br>2 |     | 1.2 |     |     |       |       |
| TensorTableLookup    | 1.<br>2 | 1.<br>2 |     | 1.2 |     |     |       |       |
| TensorTranspose      | 1.<br>2 | 1.<br>2 |     | 1.2 |     |     |       |       |
| Threshold            |         | 1.<br>0 |     |     |     |     |       |       |
| WarpAffine           |         | 1.<br>0 |     |     |     |     |       |       |

| Vision Function | S8 | U8           | U16 | S16 | U32 | F32 | color | other |
|-----------------|----|--------------|-----|-----|-----|-----|-------|-------|
| WarpPerspective |    | 1.<br>↔<br>0 |     |     |     |     |       |       |
| Xor             |    | 1.<br>↔<br>0 |     |     |     |     |       |       |

### 2.13.2 Outputs

| Vision Function    | S8           | U8           | U16 | S16            | U32 | F32 | color | other |
|--------------------|--------------|--------------|-----|----------------|-----|-----|-------|-------|
| AbsDiff            |              | 1.<br>↔<br>0 |     | 1.<br>↔<br>0.1 |     |     |       |       |
| Accumulate         |              |              |     | 1.0            |     |     |       |       |
| AccumulateSquared  |              |              |     | 1.0            |     |     |       |       |
| AccumulateWeighted |              | 1.<br>↔<br>0 |     |                |     |     |       |       |
| Add                |              | 1.<br>↔<br>0 |     | 1.0            |     |     |       |       |
| And                |              | 1.<br>↔<br>0 |     |                |     |     |       |       |
| BilateralFilter    |              | 1.<br>↔<br>2 |     | 1.2            |     |     |       |       |
| Box3x3             |              | 1.<br>↔<br>0 |     |                |     |     |       |       |
| CannyEdgeDetector  |              | 1.<br>↔<br>0 |     |                |     |     |       |       |
| ChannelCombine     |              |              |     |                |     |     | 1.0   |       |
| ChannelExtract     |              | 1.<br>↔<br>0 |     |                |     |     |       |       |
| ColorConvert       |              |              |     |                |     |     | 1.0   |       |
| ConvertDepth       |              | 1.<br>↔<br>0 |     | 1.0            |     |     |       |       |
| Convolve           |              | 1.<br>↔<br>0 |     | 1.0            |     |     |       |       |
| Data Object Copy   |              |              |     |                |     |     |       | 1.2   |
| Dilate3x3          |              | 1.<br>↔<br>0 |     |                |     |     |       |       |
| EqualizeHistogram  |              | 1.<br>↔<br>0 |     |                |     |     |       |       |
| Erode3x3           |              | 1.<br>↔<br>0 |     |                |     |     |       |       |
| FastCorners        |              | 1.<br>↔<br>0 |     |                |     |     |       |       |
| Gaussian3x3        |              | 1.<br>↔<br>0 |     |                |     |     |       |       |
| GaussianPyramid    |              | 1.<br>↔<br>1 |     |                |     |     |       |       |
| HarrisCorners      |              | 1.<br>↔<br>0 |     |                |     |     |       |       |
| HalfScaleGaussian  |              | 1.<br>↔<br>0 |     |                |     |     |       |       |
| Histogram          |              |              |     |                | 1.0 |     |       |       |
| HOGCells           | 1.<br>↔<br>2 |              |     |                |     | 1.2 |       |       |
| HOGFeatures        | 1.<br>↔<br>2 |              |     |                |     | 1.2 |       |       |
| HoughLinesP        |              |              |     |                |     |     |       | 1.2   |

| Vision Function      | S8      | U8      | U16 | S16 | U32 | F32 | color | other |
|----------------------|---------|---------|-----|-----|-----|-----|-------|-------|
| IntegrallImage       |         |         |     |     | 1.0 |     |       |       |
| LaplacianPyramid     |         |         |     | 1.1 |     |     |       |       |
| LaplacianReconstruct |         | 1.<br>1 |     |     |     |     |       |       |
| LBP                  |         | 1.<br>2 |     |     |     |     |       |       |
| Magnitude            |         |         |     | 1.0 |     |     |       |       |
| MatchTemplate        |         | 1.<br>2 |     |     |     |     |       |       |
| MeanStdDev           |         |         |     |     |     | 1.0 |       |       |
| Median3x3            |         | 1.<br>0 |     |     |     |     |       |       |
| Max                  |         | 1.<br>2 |     | 1.2 |     |     |       |       |
| Min                  |         | 1.<br>2 |     | 1.2 |     |     |       |       |
| MinMaxLoc            |         | 1.<br>0 |     | 1.0 | 1.0 |     |       |       |
| Multiply             |         | 1.<br>0 |     | 1.0 |     |     |       |       |
| NonLinearFilter      |         | 1.<br>1 |     |     |     |     |       |       |
| NonMaximaSuppression |         | 1.<br>2 |     | 1.2 |     |     |       |       |
| Not                  |         | 1.<br>0 |     |     |     |     |       |       |
| OpticalFlowPyrLK     |         |         |     |     |     |     |       |       |
| Or                   |         | 1.<br>0 |     |     |     |     |       |       |
| Phase                |         | 1.<br>0 |     |     |     |     |       |       |
| GaussianPyramid      |         | 1.<br>0 |     |     |     |     |       |       |
| Remap                |         | 1.<br>0 |     |     |     |     |       |       |
| ScaleImage           |         | 1.<br>0 |     |     |     |     |       |       |
| Sobel3x3             |         |         |     | 1.0 |     |     |       |       |
| Subtract             |         | 1.<br>0 |     | 1.0 |     |     |       |       |
| TableLookup          |         | 1.<br>0 |     | 1.1 |     |     |       |       |
| TensorMultiply       | 1.<br>2 | 1.<br>2 |     | 1.2 |     |     |       |       |
| TensorAdd            | 1.<br>2 | 1.<br>2 |     | 1.2 |     |     |       |       |
| TensorSubtract       | 1.<br>2 | 1.<br>2 |     | 1.2 |     |     |       |       |
| TensorMatrixMultiply | 1.<br>2 | 1.<br>2 |     | 1.2 |     |     |       |       |
| TensorTableLookup    | 1.<br>2 | 1.<br>2 |     | 1.2 |     |     |       |       |
| TensorTranspose      | 1.<br>2 | 1.<br>2 |     | 1.2 |     |     |       |       |
| Threshold            |         | 1.<br>0 |     |     |     |     |       |       |

| Vision Function | S8 | U8       | U16 | S16 | U32 | F32 | color | other |
|-----------------|----|----------|-----|-----|-----|-----|-------|-------|
| WarpAffine      |    | 1.↔<br>0 |     |     |     |     |       |       |
| WarpPerspective |    | 1.↔<br>0 |     |     |     |     |       |       |
| Xor             |    | 1.↔<br>0 |     |     |     |     |       |       |

### 2.13.3 Parameter ordering convention

For vision functions, the input and output parameter ordering convention is:

1. Mandatory inputs
2. Optional inputs
3. Mandatory in/outs
4. Optional in/outs
5. Mandatory outputs
6. Optional outputs

The known exceptions are:

`vxConvertDepthNode`,  
`vxuConvertDepth`,  
`vxOpticalFlowPyrLKNode`,  
`vxuOpticalFlowPyrLK`,  
`vxScaleImageNode`,  
`vxuScaleImage`.

## 2.14 Lifecycles

### 2.14.1 OpenVX Context Lifecycle

The lifecycle of the context is very simple.




Figure 2.7: The lifecycle model for an OpenVX Context.

### 2.14.2 Graph Lifecycle

OpenVX has four main phases of graph lifecycle:

- Construction - Graphs are created via `vxCreateGraph`, and Nodes are connected together by data objects.
- Verification - The graphs are checked for consistency, correctness, and other conditions. Memory allocation may occur.



- Execution - The graphs are executed via `vxProcessGraph` or `vxScheduleGraph`. Between executions data may be updated by the client or some other external mechanism. The client of OpenVX may change reference of input data to a graph, but this may require the graph to be validated again by checking `vxIsGraphVerified`.
- Deconstruction - Graphs are released via `vxReleaseGraph`. All Nodes in the Graph are released.




Figure 2.8: Graph Lifecycle

### 2.14.3 Data Object Lifecycle

All objects in OpenVX follow a similar lifecycle model. All objects are

- Created via `vxCreate<Object><Method>` or retrieved via `vxGet<Object><Method>` from the parent object if they are internally created.
- Used within Graphs or immediate functions as needed.
- Then objects must be released via `vxRelease<Object>` or via `vxReleaseContext` when all objects are released.

#### OpenVX Image Lifecycle

This is an example of the Image Lifecycle using the OpenVX Framework API. This would also apply to other data types with changes to the types and function names.




Figure 2.9: Image Object Lifecycle

## 2.15 Host Memory Data Object Access Patterns

For objects retrieved from OpenVX that are 2D in nature, such as `vx_image`, `vx_matrix`, and `vx_convolution`, the manner in which the host-side has access to these memory regions is well-defined. OpenVX uses a row-major storage (that is each unit in a column is memory-adjacent to its row adjacent unit). Two-dimensional objects are always created (using `vxCreateImage` or `vxCreateMatrix`) in width (columns) by height (rows) notation, with the arguments in that order. When accessing these structures in “C” with two-dimensional arrays of declared size, the user must therefore provide the array dimensions in the reverse of the order of the arguments to the Create function. This layout ensures *row-wise* storage in C on the host. A pointer could also be allocated for the matrix data and would have to be indexed in this row-major method.

### 2.15.1 Matrix Access Example

```

const vx_size columns = 3;
const vx_size rows = 4;
vx_matrix matrix = vxCreateMatrix(context,
 VX_TYPE_FLOAT32, columns, rows);
vx_status status = vxGetStatus((vx_reference)matrix);
if (status == VX_SUCCESS)
{
 vx_int32 j, i;
 #if defined(OPENVX_USE_C99)
 vx_float32 mat[rows][columns]; /* note: row major */
 #else
 vx_float32 *mat = (vx_float32 *)malloc(rows*columns*sizeof(
 vx_float32));
 #endif
 if (vxCopyMatrix(matrix, mat, VX_READ_ONLY,
 VX_MEMORY_TYPE_HOST) == VX_SUCCESS) {
 for (j = 0; j < (vx_int32)rows; j++)

```

```

 for (i = 0; i < (vx_int32)columns; i++)
#ifdef OPENVX_USE_C99
 mat[j][i] = (vx_float32)rand() / (vx_float32)RAND_MAX;
#else
 mat[j*columns + i] = (vx_float32)rand() / (
vx_float32)RAND_MAX;
#endif
 vxCopyMatrix(matrix, mat, VX_WRITE_ONLY,
VX_MEMORY_TYPE_HOST);
 }
#ifdef !defined(OPENVX_USE_C99)
 free(mat);
#endif
 }
}

```

## 2.15.2 Image Access Example

Images and Array differ slightly in how they are accessed due to more complex memory layout requirements.

```

vx_status status = VX_SUCCESS;
void *base_ptr = NULL;
vx_uint32 width = 640, height = 480, plane = 0;
vx_image image = vxCreateImage(context, width, height,
VX_DF_IMAGE_U8);
vx_rectangle_t rect;
vx_imagepatch_addressing_t addr;
vx_map_id map_id;

rect.start_x = rect.start_y = 0;
rect.end_x = rect.end_y = PATCH_DIM;

status = vxMapImagePatch(image, &rect, plane, &map_id,
&addr, &base_ptr,
VX_READ_AND_WRITE,
VX_MEMORY_TYPE_HOST, 0);
if (status == VX_SUCCESS)
{
 vx_uint32 x,y,i,j;
 vx_uint8 pixel = 0;

 /* a couple addressing options */

 /* use linear addressing function/macro */
 for (i = 0; i < addr.dim_x*addr.dim_y; i++) {
 vx_uint8 *ptr2 = vxFormatImagePatchAddress1d(base_ptr,
i, &addr);
 *ptr2 = pixel;
 }

 /* 2d addressing option */
 for (y = 0; y < addr.dim_y; y+=addr.step_y) {
 for (x = 0; x < addr.dim_x; x+=addr.step_x) {
 vx_uint8 *ptr2 = vxFormatImagePatchAddress2d(base_ptr,
x, y, &addr);
 *ptr2 = pixel;
 }
 }

 /* direct addressing by client
 * for subsampled planes, scale will change
 */
 for (y = 0; y < addr.dim_y; y+=addr.step_y) {
 for (x = 0; x < addr.dim_x; x+=addr.step_x) {
 vx_uint8 *tmp = (vx_uint8 *)base_ptr;
 i = ((addr.stride_y*y*addr.scale_y) /
VX_SCALE_UNITY) +
((addr.stride_x*x*addr.scale_x) /
VX_SCALE_UNITY);
 tmp[i] = pixel;
 }
 }

 /* more efficient direct addressing by client.
 * for subsampled planes, scale will change.
 */
 for (y = 0; y < addr.dim_y; y+=addr.step_y) {
 j = (addr.stride_y*y*addr.scale_y)/VX_SCALE_UNITY;
 for (x = 0; x < addr.dim_x; x+=addr.step_x) {
 vx_uint8 *tmp = (vx_uint8 *)base_ptr;
 i = j + (addr.stride_x*x*addr.scale_x) /
VX_SCALE_UNITY;
 tmp[i] = pixel;
 }
 }
}
}

```

```

 /* this commits the data back to the image.
 */
 status = vxUnmapImagePatch(image, map_id);
}
vxReleaseImage(&image);

```

### 2.15.3 Array Access Example

Arrays only require a single value, the stride, instead of the entire addressing structure that images need.

```

vx_size i, stride = sizeof(vx_size);
void *base = NULL;
vx_map_id map_id;
/* access entire array at once */
vxMapArrayRange(array, 0, num_items, &map_id, &stride, &base,
VX_READ_AND_WRITE, VX_MEMORY_TYPE_HOST, 0);
for (i = 0; i < num_items; i++)
{
 vxArrayItem(mystruct, base, i, stride).some_uint += i;
 vxArrayItem(mystruct, base, i, stride).some_double = 3.14f;
}
vxUnmapArrayRange(array, map_id);

```

Map/Unmap pairs can also be called on individual elements of array using a method similar to this:

```

/* access each array item individually */
for (i = 0; i < num_items; i++)
{
 mystruct *myptr = NULL;
 vxMapArrayRange(array, i, i+1, &map_id, &stride, (void **)&myptr,
VX_READ_AND_WRITE, VX_MEMORY_TYPE_HOST, 0);
 myptr->some_uint += 1;
 myptr->some_double = 3.14f;
 vxUnmapArrayRange(array, map_id);
}

```

## 2.16 Concurrent Data Object Access

Accessing OpenVX data-objects using the functions Map, Copy, Read concurrently to an execution of a graph that is accessing the same data objects is permitted only if all accesses are read-only. That is, for Map, Copy to have a read-only access mode and for nodes in the graph to have that data-object as an input parameter only. In all other cases, including write or read-write modes and Write access function, as well as a graph nodes having the data-object as output or bidirectional, the application must guarantee that the access is not performed concurrently with the graph execution. That can be achieved by calling un-map following a map before calling [vxScheduleGraph](#) or [vxProcessGraph](#). In addition, the application must call [vxWaitGraph](#) after [vxScheduleGraph](#) before calling Map, Read, Write or Copy to avoid restricted concurrent access. An application that fails to follow the above might encounter an undefined behavior and/or data loss without being notified by the OpenVX framework. Accessing images created from ROI ([vxCreateImageFromROI](#)) or created from a channel ([vxCreateImageFromChannel](#)) must be treated as if the entire image is being accessed.

- Setting an attribute is considered as writing to a data object in this respect.
- For concurrent execution of several graphs please see [Execution Model](#)
- Also see the graph formalism section for guidance on accessing ROIs of the same image within a graph.

## 2.17 Valid Image Region

The valid region mechanism informs the application as to which pixels of the output images of a graph's execution have valid values (see valid pixel definition below). The mechanism also applies to immediate mode (VXU) calls, and supports the communication of the valid region between different graph executions. Some vision functions, mainly those providing statistics and summarization of image information, use the valid region to ignore pixels that are not valid on their inputs (potentially bad or unstable pixel values). A good example of such a function is Min/Max Location. Formalization of the valid region mechanism is given below.

- Valid Pixels - All output pixels of an OpenVX function are considered valid by default, unless their calculation depends on input pixels that are not valid. An input pixel is not valid in one of two situations:

1. The pixel is outside of the image border and the border mode in use is `VX_BORDER_UNDEFINED`
  2. The pixel is outside the valid region of the input image.
- Valid Region - The region in the image that contains all the valid pixels. Theoretically this can be of any shape. OpenVX currently only supports rectangular valid regions. In subsequent text the term 'valid rectangle' denotes a valid region that is rectangular in shape.
  - Valid Rectangle Reset - In some cases it is not possible to calculate a valid rectangle for the output image of a vision function (for example, warps and remap). In such cases, the vision function is said to reset the valid Region to the entire image. The attribute `VX_NODE_VALID_RECT_RESET` is a read only attribute and is used to communicate valid rectangle reset behavior to the application. When it is set to `vx_true_e` for a given node the valid rectangle of the output images will reset to the full image upon execution of the node, when it is set to `vx_false_e` the valid rectangle will be calculated. All standard OpenVX functions will have this attribute set to `vx_false_e` by default, except for Warp and Remap where it will be set to `vx_true_e`.
  - Valid Rectangle Initialization - Upon the creation of an image, its valid rectangle is the entire image. One exception to this is when creating an image via `vxCreateImageFromROI`; in that case, the valid region of the ROI image is the subset of the valid region of the parent image that is within the ROI. In other words, the valid region of an image created using an ROI is the largest rectangle that contains valid pixels in the parent image.
  - Valid Rectangle Calculation - The valid rectangle of an image changes as part of the graph execution, the correct value is guaranteed only when the execution finishes. The valid rectangle of an image remains unchanged between graph executions and persists between graph executions as long as the application doesn't explicitly change the valid region via `vxSetImageValidRectangle`. Notice that using `vxMapImagePatch`, `vxUnmapImagePatch` or `vxSwapImageHandle` does not change the valid region of an image. If a non-UNDEFINED border mode is used on an image where the valid region is not the full image, the results at the border and resulting size of the valid region are implementation-dependent. This case can occur when mixing UNDEFINED and other border mode, which is not recommended.
  - Valid Rectangle for Immediate mode (VXU) - VXU is considered a single node graph execution, thus the valid rectangle of an output of VXU will be propagated for an input to a consequent VXU call (when using the same output image from one call as input to the consecutive call).
  - Valid Region Usage - For all standard OpenVX functions, the framework must guarantee that all pixel values inside the valid rectangle of the output images are valid. The framework does not guarantee that input pixels outside of the valid rectangle are processed. For the following vision functions, the framework guarantees that pixels outside of the valid rectangle do not participate in calculating the vision function result: Equalize Histogram, Integral Image, Fast Corners, Histogram, Mean and Standard Deviation, Min Max Location, Optical Flow Pyramid (LK) and Canny Edge Detector. An application can get the valid rectangle of an image by using `vxGetValidRegionImage`.
  - User kernels - User kernels may change the valid rectangles of their output images. To change the valid rectangle, the programmer of the user kernel must provide a call-back function that sets the valid rectangle. The output validator of the user kernel must provide this callback by setting the value of the `vx_meta_format` attribute `VX_VALID_RECT_CALLBACK` during the output validator. The callback function must be callable by the OpenVX framework during graph validation and execution. Assumptions must not be made regarding the order and the frequency by which the valid rectangle callback is called. The framework will recalculate the valid region when a change in the input valid regions is detected. For user nodes, the default value of `VX_NODE_VALID_RECT_RESET` is `vx_true_e`. Setting `VX_VALID_RECT_CALLBACK` during parameter validation to a value other than NULL will result in setting `VX_NODE_VALID_RECT_RESET` to `vx_false_e`. Note: the above means that when `VX_VALID_RECT_CALLBACK` is not set or set to NULL the user-node will reset the valid rectangle to the entire image.
  - In addition, valid rectangle reset occurs in the following scenarios:
    1. A reset of the valid rectangle of a parent image when a node writes to one of its ROIs. The only case where the reset does not occur is when the child ROI image is identical to the parent image.
    2. For nodes that have the `VX_NODE_VALID_RECT_RESET` set to `vx_true_e`

## 2.18 Extending OpenVX

Beyond [User Kernels](#) there are other mechanisms for vendors to extend features in OpenVX. These mechanisms are not available to User Kernels. Each OpenVX official extension has a unique identifier, comprised of capital letters, numbers and the underscore character, prefixed with "KHR\_", for example "KHR\_NEW\_FEATURE".

### 2.18.1 Extending Attributes

When extending attributes, vendors *must* use their assigned ID from [vx\\_vendor\\_id\\_e](#) in conjunction with the appropriate macros for creating new attributes with [VX\\_ATTRIBUTE\\_BASE](#). The typical mechanism to extend a new attribute for some object type (for example a [vx\\_node](#) attribute from [VX\\_ID\\_TI](#)) would look like this:

```
enum {
 VX_NODE_TI_NEWTHING = VX_ATTRIBUTE_BASE(VX_ID_TI,
 VX_TYPE_NODE) + 0x0,
}
```

### 2.18.2 Vendor Custom Kernels

Vendors wanting to add more kernels to the base set supplied to OpenVX should provide a header of the form

```
#include <VX/vx_ext_<vendor>.h>
```

that contains definitions of each of the following.

- New Node Creation Function Prototype per function.

```
vx_node vxXYZNode(vx_graph graph, vx_image input,
 vx_uint32 value, vx_image output, vx_array temp);
```

- A new Kernel Enumeration(s) and Kernel String per function.

```
#define VX_KERNEL_NAME_KHR_XYZ "org.khronos.example.xyz"

#define VX_LIBRARY_XYZ (0x3) // assigned from Khronos, vendors control their own

enum vx_kernel_xyz_ext_e {
 VX_KERNEL_KHR_XYZ = VX_KERNEL_BASE(VX_ID_DEFAULT, VX_LIBRARY_XYZ) + 0x0,
 // up to 0xFFF kernel enums can be created.
};
```

- [Optional] A new VXU Function per function.

```
vx_status vxuXYZ(vx_context context, vx_image input,
 vx_uint32 value, vx_image output, vx_array temp);
```

This should come with good documentation for each new part of the extension. Ideally, these sorts of extensions should not require linking to new objects to facilitate usage.

### 2.18.3 Vendor Custom Extensions

Some extensions affect *base* vision functions and thus may be invisible to most users. In these circumstances, the vendor must report the supported extensions to the base nodes through the [VX\\_CONTEXT\\_EXTENSIONS](#) attribute on the context.

```
vx_char *tmp, *extensions = NULL;
vx_size size = 0;
vxQueryContext(context, VX_CONTEXT_EXTENSIONS_SIZE, &size, sizeof(
 size));
extensions = malloc(size);
vxQueryContext(context, VX_CONTEXT_EXTENSIONS,
 extensions, size);
```

Extensions in this list are dependent on the extension itself; they may or may not have a header and new kernels or framework feature or data objects. The common feature is that they are implemented and supported by the implementation vendor.

#### 2.18.4 Hinting

The specification defines a Hinting API that allows Clients to feed information to the implementation for *optional* behavior changes. See [Framework: Hints](#). It is assumed that most of the hints will be vendor- or implementation-specific. Check with the OpenVX implementation vendor for information on vendor-specific extensions.

#### 2.18.5 Directives

The specification defines a Directive API to control implementation behavior. See [Framework: Directives](#). This *may* allow things like disabling parallelism for debugging, enabling cache writing-through for some buffers, or any implementation-specific optimization.

# Chapter 3

## Module Documentation

### 3.1 Vision Functions

#### 3.1.1 Detailed Description

These are the base vision functions supported in OpenVX 1.1.

These functions were chosen as a subset of a larger pool of possible functions that fall under the following criteria:

- Applicable to Acceleration Hardware
- Very Common Usage
- Encumbrance Free

#### Modules

- [Absolute Difference](#)  
*Computes the absolute difference between two images. The output image dimensions should be the same as the dimensions of the input images.*
- [Accumulate](#)  
*Accumulates an input image into output image. The accumulation image dimensions should be the same as the dimensions of the input image.*
- [Accumulate Squared](#)  
*Accumulates a squared value from an input image to an output image. The accumulation image dimensions should be the same as the dimensions of the input image.*
- [Data Object Copy](#)  
*Copy a data object to another.*
- [Accumulate Weighted](#)  
*Accumulates a weighted value from an input image to an output image. The accumulation image dimensions should be the same as the dimensions of the input image.*
- [Arithmetic Addition](#)  
*Performs addition between two images. The output image dimensions should be the same as the dimensions of the input images.*
- [Arithmetic Subtraction](#)  
*Performs subtraction between two images. The output image dimensions should be the same as the dimensions of the input images.*
- [Bitwise AND](#)  
*Performs a bitwise AND operation between two [VX\\_DF\\_IMAGE\\_U8](#) images. The output image dimensions should be the same as the dimensions of the input images.*
- [Bitwise EXCLUSIVE OR](#)  
*Performs a bitwise EXCLUSIVE OR (XOR) operation between two [VX\\_DF\\_IMAGE\\_U8](#) images. The output image dimensions should be the same as the dimensions of the input images.*



- **Bitwise INCLUSIVE OR**  
*Performs a bitwise INCLUSIVE OR operation between two `VX_DF_IMAGE_U8` images. The output image dimensions should be the same as the dimensions of the input images.*
- **Bitwise NOT**  
*Performs a bitwise NOT operation on a `VX_DF_IMAGE_U8` input image. The output image dimensions should be the same as the dimensions of the input image.*
- **Box Filter**  
*Computes a Box filter over a window of the input image. The output image dimensions should be the same as the dimensions of the input image.*
- **Non-Maxima Suppression**  
*Find local maxima in an image, or otherwise suppress pixels that are not local maxima.*
- **Canny Edge Detector**  
*Provides a Canny edge detector kernel. The output image dimensions should be the same as the dimensions of the input image.*
- **Channel Combine**  
*Implements the Channel Combine Kernel.*
- **Channel Extract**  
*Implements the Channel Extraction Kernel.*
- **Color Convert**  
*Implements the Color Conversion Kernel. The output image dimensions should be the same as the dimensions of the input image.*
- **Convert Bit depth**  
*Converts image bit depth. The output image dimensions should be the same as the dimensions of the input image.*
- **Custom Convolution**  
*Convolve the input with the client supplied convolution matrix. The output image dimensions should be the same as the dimensions of the input image.*
- **Dilate Image**  
*Implements Dilation, which grows the white space in a `VX_DF_IMAGE_U8` Boolean image. The output image dimensions should be the same as the dimensions of the input image.*
- **Equalize Histogram**  
*Equalizes the histogram of a grayscale image. The output image dimensions should be the same as the dimensions of the input image.*
- **Erode Image**  
*Implements Erosion, which shrinks the white space in a `VX_DF_IMAGE_U8` Boolean image. The output image dimensions should be the same as the dimensions of the input image.*
- **Fast Corners**  
*Computes the corners in an image using a method based upon FAST9 algorithm suggested in [?] and with some updates from [?] with modifications described below.*
- **Gaussian Filter**  
*Computes a Gaussian filter over a window of the input image. The output image dimensions should be the same as the dimensions of the input image.*
- **Non Linear Filter**  
*Computes a non-linear filter over a window of the input image. The output image dimensions should be the same as the dimensions of the input image.*
- **Harris Corners**  
*Computes the Harris Corners of an image.*
- **Histogram**  
*Generates a distribution from an image.*
- **Gaussian Image Pyramid**  
*Computes a Gaussian Image Pyramid from an input image.*
- **Laplacian Image Pyramid**  
*Computes a Laplacian Image Pyramid from an input image.*
- **Reconstruction from a Laplacian Image Pyramid**

- Reconstructs the original image from a Laplacian Image Pyramid.*
- **Integral Image**

*Computes the integral image of the input. The output image dimensions should be the same as the dimensions of the input image.*
- **Magnitude**

*Implements the Gradient Magnitude Computation Kernel. The output image dimensions should be the same as the dimensions of the input images.*
- **Mean and Standard Deviation**

*Computes the mean pixel value and the standard deviation of the pixels in the input image (which has a dimension width and height).*
- **Median Filter**

*Computes a median pixel value over a window of the input image. The output image dimensions should be the same as the dimensions of the input image.*
- **Min, Max Location**

*Finds the minimum and maximum values in an image and a location for each.*
- **Min**

*Implements a pixel-wise minimum kernel. The output image dimensions should be the same as the dimensions of the input image.*
- **Max**

*Implements a pixel-wise maximum kernel. The output image dimensions should be the same as the dimensions of the input image.*
- **Optical Flow Pyramid (LK)**

*Computes the optical flow using the Lucas-Kanade method between two pyramid images.*
- **Phase**

*Implements the Gradient Phase Computation Kernel. The output image dimensions should be the same as the dimensions of the input images.*
- **Pixel-wise Multiplication**

*Performs element-wise multiplication between two images and a scalar value. The output image dimensions should be the same as the dimensions of the input images.*
- **Remap**

*Maps output pixels in an image from input pixels in an image.*
- **Scale Image**

*Implements the Image Resizing Kernel.*
- **Sobel 3x3**

*Implements the Sobel Image Filter Kernel. The output images dimensions should be the same as the dimensions of the input image.*
- **TableLookup**

*Implements the Table Lookup Image Kernel. The output image dimensions should be the same as the dimensions of the input image.*
- **Thresholding**

*Thresholds an input image and produces an output Boolean image. The output image dimensions should be the same as the dimensions of the input image.*
- **Warp Affine**

*Performs an affine transform on an image.*
- **Warp Perspective**

*Performs a perspective transform on an image.*
- **Bilateral Filter**

*The function applies bilateral filtering to the input tensor.*
- **MatchTemplate**

*Compares an image template against overlapped image regions.*
- **LBP**

*Extracts LBP image from an input image. The output image dimensions should be the same as the dimensions of the input image.*

- [HOG](#)  
*Extracts Histogram of Oriented Gradients features from the input grayscale image.*
- [HoughLinesP](#)  
*Finds the Probabilistic Hough Lines detected in the input binary image.*
- [Tensor Multiply](#)  
*Performs element wise multiplications on element values in the input tensor data with a scale.*
- [Tensor Add](#)  
*Performs arithmetic addition on element values in the input tensor data.*
- [Tensor Subtract](#)  
*Performs arithmetic subtraction on element values in the input tensor data.*
- [Tensor TableLookUp](#)  
*Performs LUT on element values in the input tensor data.*
- [Tensor Transpose](#)  
*Performs transpose on the input tensor.*
- [Tensor Convert Bit-Depth](#)  
*Creates a bit-depth conversion node.*
- [Tensor Matrix Multiply](#)  
*Creates a generalized matrix multiplication node.*

## 3.2 Absolute Difference

### 3.2.1 Detailed Description

Computes the absolute difference between two images. The output image dimensions should be the same as the dimensions of the input images.

Absolute Difference is computed by:

$$out(x,y) = |in_1(x,y) - in_2(x,y)|$$

If one of the input images is of type `VX_DF_IMAGE_S16`, all values are converted to `vx_int32` and the overflow policy `VX_CONVERT_POLICY_SATURATE` is used.

$$out(x,y) = saturate_{int16}(|(int32)in_1(x,y) - (int32)in_2(x,y)|)$$

The output image can be `VX_DF_IMAGE_U8` only if both source images are `VX_DF_IMAGE_U8` and the output image is explicitly set to `VX_DF_IMAGE_U8`. It is otherwise `VX_DF_IMAGE_S16`.

### Functions

- `vx_node VX_API_CALL vxAbsDiffNode (vx_graph graph, vx_image in1, vx_image in2, vx_image out)`  
[Graph] Creates an AbsDiff node.
- `vx_status VX_API_CALL vxuAbsDiff (vx_context context, vx_image in1, vx_image in2, vx_image out)`  
[Immediate] Computes the absolute difference between two images.

### 3.2.2 Function Documentation

**`vx_node VX_API_CALL vxAbsDiffNode ( vx_graph graph, vx_image in1, vx_image in2, vx_image out )`**

[Graph] Creates an AbsDiff node.

#### Parameters

|     |              |                                                                                                                                                 |
|-----|--------------|-------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i> | The reference to the graph.                                                                                                                     |
| in  | <i>in1</i>   | An input image in <code>VX_DF_IMAGE_U8</code> or <code>VX_DF_IMAGE_S16</code> format.                                                           |
| in  | <i>in2</i>   | An input image in <code>VX_DF_IMAGE_U8</code> or <code>VX_DF_IMAGE_S16</code> format.                                                           |
| out | <i>out</i>   | The output image in <code>VX_DF_IMAGE_U8</code> or <code>VX_DF_IMAGE_S16</code> format, which must have the same dimensions as the input image. |

#### Return values

|                |                                                                                                                         |
|----------------|-------------------------------------------------------------------------------------------------------------------------|
| <i>vx_node</i> | A node reference. Any possible errors preventing a successful creation should be checked using <code>vxGetStatus</code> |
|----------------|-------------------------------------------------------------------------------------------------------------------------|

**`vx_status VX_API_CALL vxuAbsDiff ( vx_context context, vx_image in1, vx_image in2, vx_image out )`**

[Immediate] Computes the absolute difference between two images.

#### Parameters

|     |                |                                                                                         |
|-----|----------------|-----------------------------------------------------------------------------------------|
| in  | <i>context</i> | The reference to the overall context.                                                   |
| in  | <i>in1</i>     | An input image in <code>VX_DF_IMAGE_U8</code> or <code>VX_DF_IMAGE_S16</code> format.   |
| in  | <i>in2</i>     | An input image in <code>VX_DF_IMAGE_U8</code> or <code>VX_DF_IMAGE_S16</code> format.   |
| out | <i>out</i>     | The output image in <code>VX_DF_IMAGE_U8</code> or <code>VX_DF_IMAGE_S16</code> format. |

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                         |                                                   |
|-------------------------|---------------------------------------------------|
| <code>VX_SUCCESS</code> | Success                                           |
| *                       | An error occurred. See <code>vx_status_e</code> . |

## 3.3 Accumulate

### 3.3.1 Detailed Description

Accumulates an input image into output image. The accumulation image dimensions should be the same as the dimensions of the input image.

Accumulation is computed by:

$$accum(x,y) = accum(x,y) + input(x,y)$$

The overflow policy used is `VX_CONVERT_POLICY_SATURATE`.

### Functions

- `vx_node VX_API_CALL vxAccumulateImageNode (vx_graph graph, vx_image input, vx_image accum)`  
[Graph] Creates an accumulate node.
- `vx_status VX_API_CALL vxuAccumulateImage (vx_context context, vx_image input, vx_image accum)`  
[Immediate] Computes an accumulation.

### 3.3.2 Function Documentation

**`vx_node VX_API_CALL vxAccumulateImageNode ( vx_graph graph, vx_image input, vx_image accum )`**

[Graph] Creates an accumulate node.

#### Parameters

|         |              |                                                                                                                  |
|---------|--------------|------------------------------------------------------------------------------------------------------------------|
| in      | <i>graph</i> | The reference to the graph.                                                                                      |
| in      | <i>input</i> | The input <code>VX_DF_IMAGE_U8</code> image.                                                                     |
| in, out | <i>accum</i> | The accumulation image in <code>VX_DF_IMAGE_S16</code> , which must have the same dimensions as the input image. |

#### Returns

`vx_node`.

#### Return values

|                      |                                                                                                                         |
|----------------------|-------------------------------------------------------------------------------------------------------------------------|
| <code>vx_node</code> | A node reference. Any possible errors preventing a successful creation should be checked using <code>vxGetStatus</code> |
|----------------------|-------------------------------------------------------------------------------------------------------------------------|

**`vx_status VX_API_CALL vxuAccumulateImage ( vx_context context, vx_image input, vx_image accum )`**

[Immediate] Computes an accumulation.

#### Parameters

|         |                |                                                        |
|---------|----------------|--------------------------------------------------------|
| in      | <i>context</i> | The reference to the overall context.                  |
| in      | <i>input</i>   | The input <code>VX_DF_IMAGE_U8</code> image.           |
| in, out | <i>accum</i>   | The accumulation image in <code>VX_DF_IMAGE_S16</code> |

#### Returns

A `vx_status_e` enumeration.

**Return values**

|                         |                                                      |
|-------------------------|------------------------------------------------------|
| <code>VX_SUCCESS</code> | Success                                              |
| *                       | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.4 Accumulate Squared

### 3.4.1 Detailed Description

Accumulates a squared value from an input image to an output image. The accumulation image dimensions should be the same as the dimensions of the input image.

Accumulate squares is computed by:

$$accum(x,y) = saturate_{int16}(((uint16)accum(x,y) + (((uint16)(input(x,y)^2)) >> (shift))))$$

Where  $0 \leq shift \leq 15$

The overflow policy used is `VX_CONVERT_POLICY_SATURATE`.

### Functions

- `vx_node VX_API_CALL vxAccumulateSquareImageNode (vx_graph graph, vx_image input, vx_scalar shift, vx_image accum)`  
[Graph] Creates an accumulate square node.
- `vx_status VX_API_CALL vxuAccumulateSquareImage (vx_context context, vx_image input, vx_scalar shift, vx_image accum)`  
[Immediate] Computes a squared accumulation.

### 3.4.2 Function Documentation

**`vx_node VX_API_CALL vxAccumulateSquareImageNode ( vx_graph graph, vx_image input, vx_scalar shift, vx_image accum )`**

[Graph] Creates an accumulate square node.

#### Parameters

|         |              |                                                                                                                  |
|---------|--------------|------------------------------------------------------------------------------------------------------------------|
| in      | <i>graph</i> | The reference to the graph.                                                                                      |
| in      | <i>input</i> | The input <code>VX_DF_IMAGE_U8</code> image.                                                                     |
| in      | <i>shift</i> | The input <code>VX_TYPE_UINT32</code> with a value in the range of $0 \leq shift \leq 15$ .                      |
| in, out | <i>accum</i> | The accumulation image in <code>VX_DF_IMAGE_S16</code> , which must have the same dimensions as the input image. |

#### Returns

`vx_node`.

#### Return values

|                |                                                                                                                         |
|----------------|-------------------------------------------------------------------------------------------------------------------------|
| <i>vx_node</i> | A node reference. Any possible errors preventing a successful creation should be checked using <code>vxGetStatus</code> |
|----------------|-------------------------------------------------------------------------------------------------------------------------|

**`vx_status VX_API_CALL vxuAccumulateSquareImage ( vx_context context, vx_image input, vx_scalar shift, vx_image accum )`**

[Immediate] Computes a squared accumulation.

#### Parameters

|    |                |                                                                                             |
|----|----------------|---------------------------------------------------------------------------------------------|
| in | <i>context</i> | The reference to the overall context.                                                       |
| in | <i>input</i>   | The input <code>VX_DF_IMAGE_U8</code> image.                                                |
| in | <i>shift</i>   | A <code>VX_TYPE_UINT32</code> type, the input value with the range $0 \leq shift \leq 15$ . |



**Parameters**

|                      |                    |                                                           |
|----------------------|--------------------|-----------------------------------------------------------|
| <code>in, out</code> | <code>accum</code> | The accumulation image in <a href="#">VX_DF_IMAGE_S16</a> |
|----------------------|--------------------|-----------------------------------------------------------|

**Returns**

A [vx\\_status\\_e](#) enumeration.

**Return values**

|                         |                                                      |
|-------------------------|------------------------------------------------------|
| <code>VX_SUCCESS</code> | Success                                              |
| *                       | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.5 Data Object Copy

### 3.5.1 Detailed Description

Copy a data object to another.

Copy data from an input data object into another data object. The input and output object must have the same object type and meta data. If these objects are object arrays, or pyramids then a deep copy shall be performed.

### Functions

- `vx_node VX_API_CALL vxCopyNode` (`vx_graph` graph, `vx_reference` input, `vx_reference` output)  
*Copy data from one object to another.*
- `vx_status VX_API_CALL vxuCopy` (`vx_context` context, `vx_reference` input, `vx_reference` output)  
*[Immediate] Copy data from one object to another.*

### 3.5.2 Function Documentation

**`vx_node VX_API_CALL vxCopyNode` ( `vx_graph` *graph*, `vx_reference` *input*, `vx_reference` *output* )**

Copy data from one object to another.

Note

An implementation may optimize away the copy when virtual data objects are used.

#### Parameters

|     |               |                                                                           |
|-----|---------------|---------------------------------------------------------------------------|
| in  | <i>graph</i>  | The reference to the graph.                                               |
| in  | <i>input</i>  | The input data object.                                                    |
| out | <i>output</i> | The output data object with meta-data identical to the input data object. |

#### Returns

`vx_node`.

#### Return values

|                      |                                                                                                                         |
|----------------------|-------------------------------------------------------------------------------------------------------------------------|
| <code>vx_node</code> | A node reference. Any possible errors preventing a successful creation should be checked using <code>vxGetStatus</code> |
|----------------------|-------------------------------------------------------------------------------------------------------------------------|

**`vx_status VX_API_CALL vxuCopy` ( `vx_context` *context*, `vx_reference` *input*, `vx_reference` *output* )**

[Immediate] Copy data from one object to another.

#### Parameters

|     |                |                                       |
|-----|----------------|---------------------------------------|
| in  | <i>context</i> | The reference to the overall context. |
| in  | <i>input</i>   | The input data object.                |
| out | <i>output</i>  | The output data object.               |

#### Returns

A `vx_status_e` enumeration.

**Return values**

|                         |                                                      |
|-------------------------|------------------------------------------------------|
| <code>VX_SUCCESS</code> | Success                                              |
| *                       | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.6 Accumulate Weighted

### 3.6.1 Detailed Description

Accumulates a weighted value from an input image to an output image. The accumulation image dimensions should be the same as the dimensions of the input image.

Weighted accumulation is computed by:

$$accum(x,y) = (1 - \alpha) * accum(x,y) + \alpha * input(x,y)$$

Where  $0 \leq \alpha \leq 1$  Conceptually, the rounding for this is defined as:

$$output(x,y) = uint8((1 - \alpha) * float32(int32(output(x,y))) + \alpha * float32(int32(input(x,y))))$$

### Functions

- **`vx_node VX_API_CALL vxAccumulateWeightedImageNode (vx_graph graph, vx_image input, vx_scalar alpha, vx_image accum)`**  
[Graph] Creates a weighted accumulate node.
- **`vx_status VX_API_CALL vxuAccumulateWeightedImage (vx_context context, vx_image input, vx_scalar alpha, vx_image accum)`**  
[Immediate] Computes a weighted accumulation.

### 3.6.2 Function Documentation

**`vx_node VX_API_CALL vxAccumulateWeightedImageNode ( vx_graph graph, vx_image input, vx_scalar alpha, vx_image accum )`**

[Graph] Creates a weighted accumulate node.

#### Parameters

|         |              |                                                                                                                  |
|---------|--------------|------------------------------------------------------------------------------------------------------------------|
| in      | <i>graph</i> | The reference to the graph.                                                                                      |
| in      | <i>input</i> | The input <a href="#">VX_DF_IMAGE_U8</a> image.                                                                  |
| in      | <i>alpha</i> | The input <a href="#">VX_TYPE_FLOAT32</a> scalar value with a value in the range of $0.0 \leq \alpha \leq 1.0$ . |
| in, out | <i>accum</i> | The <a href="#">VX_DF_IMAGE_U8</a> accumulation image, which must have the same dimensions as the input image.   |

#### Returns

[vx\\_node](#).

#### Return values

|                |                                                                                                                            |
|----------------|----------------------------------------------------------------------------------------------------------------------------|
| <i>vx_node</i> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|----------------|----------------------------------------------------------------------------------------------------------------------------|

**`vx_status VX_API_CALL vxuAccumulateWeightedImage ( vx_context context, vx_image input, vx_scalar alpha, vx_image accum )`**

[Immediate] Computes a weighted accumulation.

#### Parameters

|    |                |                                                 |
|----|----------------|-------------------------------------------------|
| in | <i>context</i> | The reference to the overall context.           |
| in | <i>input</i>   | The input <a href="#">VX_DF_IMAGE_U8</a> image. |

**Parameters**

|         |              |                                                                                                     |
|---------|--------------|-----------------------------------------------------------------------------------------------------|
| in      | <i>alpha</i> | A <a href="#">VX_TYPE_FLOAT32</a> type, the input value with the range $0.0 \leq \alpha \leq 1.0$ . |
| in, out | <i>accum</i> | The <a href="#">VX_DF_IMAGE_U8</a> accumulation image.                                              |

**Returns**

A [vx\\_status\\_e](#) enumeration.

**Return values**

|                            |                                                      |
|----------------------------|------------------------------------------------------|
| <a href="#">VX_SUCCESS</a> | Success                                              |
| *                          | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.7 Control Flow

### 3.7.1 Detailed Description

Defines the predicated execution model of OpenVX.

These features allow for conditional graph flow in OpenVX, via support for a variety of operations between two scalars. The supported scalar data types `VX_TYPE_BOOL`, `VX_TYPE_INT8`, `VX_TYPE_UINT8`, `VX_TYPE_INT16`, `VX_TYPE_UINT16`, `VX_TYPE_INT32`, `VX_TYPE_UINT32`, `VX_TYPE_SIZE`, `VX_TYPE_FLOAT32` are supported.

Summary of logical operations:

| Scalar Operation               | Equation                       | Data Types                                                 |
|--------------------------------|--------------------------------|------------------------------------------------------------|
| <code>VX_SCALAR_OP_AND</code>  | $\text{output} = (a \& b)$     | <code>bool</code> = <code>bool</code> op <code>bool</code> |
| <code>VX_SCALAR_OP_OR</code>   | $\text{output} = (a   b)$      | <code>bool</code> = <code>bool</code> op <code>bool</code> |
| <code>VX_SCALAR_OP_XOR</code>  | $\text{output} = (a \wedge b)$ | <code>bool</code> = <code>bool</code> op <code>bool</code> |
| <code>VX_SCALAR_OP_NAND</code> | $\text{output} = \neg(a \& b)$ | <code>bool</code> = <code>bool</code> op <code>bool</code> |

Summary of comparison operations:

| Scalar Operation                    | Equation                     | Data Types                                               |
|-------------------------------------|------------------------------|----------------------------------------------------------|
| <code>VX_SCALAR_OP_EQUAL</code>     | $\text{output} = (a == b)$   | <code>bool</code> = <code>num</code> op <code>num</code> |
| <code>VX_SCALAR_OP_NOTEQUAL</code>  | $\text{output} = (a != b)$   | <code>bool</code> = <code>num</code> op <code>num</code> |
| <code>VX_SCALAR_OP_LESS</code>      | $\text{output} = (a < b)$    | <code>bool</code> = <code>num</code> op <code>num</code> |
| <code>VX_SCALAR_OP_LESSEQ</code>    | $\text{output} = (a \leq b)$ | <code>bool</code> = <code>num</code> op <code>num</code> |
| <code>VX_SCALAR_OP_GREATER</code>   | $\text{output} = (a > b)$    | <code>bool</code> = <code>num</code> op <code>num</code> |
| <code>VX_SCALAR_OP_GREATEREQ</code> | $\text{output} = (a \geq b)$ | <code>bool</code> = <code>num</code> op <code>num</code> |

Summary of arithmetic operations:

| Scalar Operation                   | Equation                      | Data Types                                              |
|------------------------------------|-------------------------------|---------------------------------------------------------|
| <code>VX_SCALAR_OP_ADD</code>      | $\text{output} = (a + b)$     | <code>num</code> = <code>num</code> op <code>num</code> |
| <code>VX_SCALAR_OP_SUBTRACT</code> | $\text{output} = (a - b)$     | <code>num</code> = <code>num</code> op <code>num</code> |
| <code>VX_SCALAR_OP_MULTIPLY</code> | $\text{output} = (a * b)$     | <code>num</code> = <code>num</code> op <code>num</code> |
| <code>VX_SCALAR_OP_DIVIDE</code>   | $\text{output} = (a / b)$     | <code>num</code> = <code>num</code> op <code>num</code> |
| <code>VX_SCALAR_OP_MODULUS</code>  | $\text{output} = (a \bmod b)$ | <code>num</code> = <code>num</code> op <code>num</code> |
| <code>VX_SCALAR_OP_MIN</code>      | $\text{output} = \min(a, b)$  | <code>num</code> = <code>num</code> op <code>num</code> |
| <code>VX_SCALAR_OP_MAX</code>      | $\text{output} = \max(a, b)$  | <code>num</code> = <code>num</code> op <code>num</code> |

Please note that in the above tables:

- `bool` denotes a scalar of data type `VX_TYPE_BOOL`
- `num` denotes supported scalar data types are `VX_TYPE_INT8`, `VX_TYPE_UINT8`, `VX_TYPE_INT16`, `VX_TYPE_UINT16`, `VX_TYPE_INT32`, `VX_TYPE_UINT32`, `VX_TYPE_SIZE`, and `VX_TYPE_FLOAT32`.
- The `VX_SCALAR_OP_MODULUS` operation supports integer operands.
- The results of `VX_SCALAR_OP_DIVIDE` and `VX_SCALAR_OP_MODULUS` operations with the second argument as zero, must be defined by the implementation.
- For arithmetic and comparison operations with mixed input data types, the results will be mathematically accurate without the side effects of internal data representations.
- If the operation result can not be stored in output data type without data and/or precision loss, the following rules shall be applied:

1. If the operation result is integer and output is floating-point, the operation result is promoted to floating-point.
2. If the operation result is floating-point and output is an integer, the operation result is converted to integer with rounding policy `VX_ROUND_POLICY_TO_ZERO` and conversion policy `VX_CONVERT_POLICY_SATURATE`.
3. If both operation result and output are integers, the result is converted to output data type with `VX_CONVERT_POLICY_WRAP` conversion policy.

## Functions

- `vx_node VX_API_CALL vxScalarOperationNode (vx_graph graph, vx_enum scalar_operation, vx_scalar a, vx_scalar b, vx_scalar output)`  
*[Graph] Creates a scalar operation node.*
- `vx_node VX_API_CALL vxSelectNode (vx_graph graph, vx_scalar condition, vx_reference true_value, vx_reference false_value, vx_reference output)`  
*[Graph] Selects one of two data objects depending on the the value of a condition (boolean scalar), and copies its data into another data object.*

### 3.7.2 Function Documentation

**`vx_node VX_API_CALL vxScalarOperationNode ( vx_graph graph, vx_enum scalar_operation, vx_scalar a, vx_scalar b, vx_scalar output )`**

*[Graph] Creates a scalar operation node.*

#### Parameters

|     |                         |                                                                                    |
|-----|-------------------------|------------------------------------------------------------------------------------|
| in  | <i>graph</i>            | The reference to the graph.                                                        |
| in  | <i>scalar_operation</i> | A <code>VX_TYPE_ENUM</code> of the <code>vx_scalar_operation_e</code> enumeration. |
| in  | <i>a</i>                | First scalar operand.                                                              |
| in  | <i>b</i>                | Second scalar operand.                                                             |
| out | <i>output</i>           | Result of the scalar operation.                                                    |

#### Returns

`vx_node`.

#### Return values

|                      |                                                                                                                         |
|----------------------|-------------------------------------------------------------------------------------------------------------------------|
| <code>vx_node</code> | A node reference. Any possible errors preventing a successful creation should be checked using <code>vxGetStatus</code> |
|----------------------|-------------------------------------------------------------------------------------------------------------------------|

**`vx_node VX_API_CALL vxSelectNode ( vx_graph graph, vx_scalar condition, vx_reference true_value, vx_reference false_value, vx_reference output )`**

*[Graph] Selects one of two data objects depending on the the value of a condition (boolean scalar), and copies its data into another data object.*

This node supports predicated execution flow within a graph. All the data objects passed to this kernel shall have the same object type and meta data. It is important to note that an implementation may optimize away the select and copy when virtual data objects are used.

If there is a kernel node that contribute only into virtual data objects during the graph execution due to certain data path being eliminated by not taken argument of select node, then the OpenVX implementation guarantees that there will not be any side effects to graph execution and node state.

If the path to a select node contains non-virtual objects, user nodes, or nodes with completion callbacks, then

that path may not be "optimized out" because the callback must be executed and the non-virtual objects must be modified.

#### Parameters

|     |                    |                                                  |
|-----|--------------------|--------------------------------------------------|
| in  | <i>graph</i>       | The reference to the graph.                      |
| in  | <i>condition</i>   | <a href="#">VX_TYPE_BOOL</a> predicate variable. |
| in  | <i>true_value</i>  | Data object for true.                            |
| in  | <i>false_value</i> | Data object for false.                           |
| out | <i>output</i>      | Output data object.                              |

#### Returns

[vx\\_node](#).

#### Return values

|                |                                                                                                                            |
|----------------|----------------------------------------------------------------------------------------------------------------------------|
| <i>vx_node</i> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|----------------|----------------------------------------------------------------------------------------------------------------------------|



## 3.8 Arithmetic Addition

### 3.8.1 Detailed Description

Performs addition between two images. The output image dimensions should be the same as the dimensions of the input images.

Arithmetic addition is performed between the pixel values in two `VX_DF_IMAGE_U8` or `VX_DF_IMAGE_S16` images. The output image can be `VX_DF_IMAGE_U8` only if both source images are `VX_DF_IMAGE_U8` and the output image is explicitly set to `VX_DF_IMAGE_U8`. It is otherwise `VX_DF_IMAGE_S16`. If one of the input images is of type `VX_DF_IMAGE_S16`, all values are converted to `VX_DF_IMAGE_S16`. The overflow handling is controlled by an overflow-policy parameter. For each pixel value in the two input images:

$$out(x,y) = in_1(x,y) + in_2(x,y)$$

### Functions

- `vx_node VX_API_CALL vxAddNode (vx_graph graph, vx_image in1, vx_image in2, vx_enum policy, vx_image out)`

*[Graph] Creates an arithmetic addition node.*

- `vx_status VX_API_CALL vxuAdd (vx_context context, vx_image in1, vx_image in2, vx_enum policy, vx_image out)`

*[Immediate] Performs arithmetic addition on pixel values in the input images.*

### 3.8.2 Function Documentation

**`vx_node VX_API_CALL vxAddNode ( vx_graph graph, vx_image in1, vx_image in2, vx_enum policy, vx_image out )`**

*[Graph] Creates an arithmetic addition node.*

#### Parameters

|     |               |                                                                                                                                                 |
|-----|---------------|-------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>  | The reference to the graph.                                                                                                                     |
| in  | <i>in1</i>    | An input image, <code>VX_DF_IMAGE_U8</code> or <code>VX_DF_IMAGE_S16</code> .                                                                   |
| in  | <i>in2</i>    | An input image, <code>VX_DF_IMAGE_U8</code> or <code>VX_DF_IMAGE_S16</code> .                                                                   |
| in  | <i>policy</i> | A <code>VX_TYPE_ENUM</code> of the <code>vx_convert_policy_e</code> enumeration.                                                                |
| out | <i>out</i>    | The output image, a <code>VX_DF_IMAGE_U8</code> or <code>VX_DF_IMAGE_S16</code> image, which must have the same dimensions as the input images. |

#### Returns

`vx_node`.

#### Return values

|                |                                                                                                                         |
|----------------|-------------------------------------------------------------------------------------------------------------------------|
| <i>vx_node</i> | A node reference. Any possible errors preventing a successful creation should be checked using <code>vxGetStatus</code> |
|----------------|-------------------------------------------------------------------------------------------------------------------------|

**`vx_status VX_API_CALL vxuAdd ( vx_context context, vx_image in1, vx_image in2, vx_enum policy, vx_image out )`**

*[Immediate] Performs arithmetic addition on pixel values in the input images.*

#### Parameters

|    |                |                                       |
|----|----------------|---------------------------------------|
| in | <i>context</i> | The reference to the overall context. |
|----|----------------|---------------------------------------|

**Parameters**

|     |               |                                                                                               |
|-----|---------------|-----------------------------------------------------------------------------------------------|
| in  | <i>in1</i>    | A <a href="#">VX_DF_IMAGE_U8</a> or <a href="#">VX_DF_IMAGE_S16</a> input image.              |
| in  | <i>in2</i>    | A <a href="#">VX_DF_IMAGE_U8</a> or <a href="#">VX_DF_IMAGE_S16</a> input image.              |
| in  | <i>policy</i> | A <a href="#">vx_convert_policy_e</a> enumeration.                                            |
| out | <i>out</i>    | The output image in <a href="#">VX_DF_IMAGE_U8</a> or <a href="#">VX_DF_IMAGE_S16</a> format. |

**Returns**

A [vx\\_status\\_e](#) enumeration.

**Return values**

|                            |                                                      |
|----------------------------|------------------------------------------------------|
| <a href="#">VX_SUCCESS</a> | Success                                              |
| *                          | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.9 Arithmetic Subtraction

### 3.9.1 Detailed Description

Performs subtraction between two images. The output image dimensions should be the same as the dimensions of the input images.

Arithmetic subtraction is performed between the pixel values in two `VX_DF_IMAGE_U8` or two `VX_DF_IMAGE_S16` images. The output image can be `VX_DF_IMAGE_U8` only if both source images are `VX_DF_IMAGE_U8` and the output image is explicitly set to `VX_DF_IMAGE_U8`. It is otherwise `VX_DF_IMAGE_S16`. If one of the input images is of type `VX_DF_IMAGE_S16`, all values are converted to `VX_DF_IMAGE_S16`. The overflow handling is controlled by an overflow-policy parameter. For each pixel value in the two input images:

$$out(x,y) = in_1(x,y) - in_2(x,y)$$

### Functions

- `vx_node VX_API_CALL vxSubtractNode (vx_graph graph, vx_image in1, vx_image in2, vx_enum policy, vx_image out)`  
[Graph] Creates an arithmetic subtraction node.
- `vx_status VX_API_CALL vxuSubtract (vx_context context, vx_image in1, vx_image in2, vx_enum policy, vx_image out)`  
[Immediate] Performs arithmetic subtraction on pixel values in the input images.

### 3.9.2 Function Documentation

**`vx_node VX_API_CALL vxSubtractNode ( vx_graph graph, vx_image in1, vx_image in2, vx_enum policy, vx_image out )`**

[Graph] Creates an arithmetic subtraction node.

#### Parameters

|     |               |                                                                                                                                                 |
|-----|---------------|-------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>  | The reference to the graph.                                                                                                                     |
| in  | <i>in1</i>    | An input image, <code>VX_DF_IMAGE_U8</code> or <code>VX_DF_IMAGE_S16</code> , the minuend.                                                      |
| in  | <i>in2</i>    | An input image, <code>VX_DF_IMAGE_U8</code> or <code>VX_DF_IMAGE_S16</code> , the subtrahend.                                                   |
| in  | <i>policy</i> | A <code>VX_TYPE_ENUM</code> of the <code>vx_convert_policy_e</code> enumeration.                                                                |
| out | <i>out</i>    | The output image, a <code>VX_DF_IMAGE_U8</code> or <code>VX_DF_IMAGE_S16</code> image, which must have the same dimensions as the input images. |

#### Returns

`vx_node`.

#### Return values

|                      |                                                                                                                         |
|----------------------|-------------------------------------------------------------------------------------------------------------------------|
| <code>vx_node</code> | A node reference. Any possible errors preventing a successful creation should be checked using <code>vxGetStatus</code> |
|----------------------|-------------------------------------------------------------------------------------------------------------------------|

**`vx_status VX_API_CALL vxuSubtract ( vx_context context, vx_image in1, vx_image in2, vx_enum policy, vx_image out )`**

[Immediate] Performs arithmetic subtraction on pixel values in the input images.

#### Parameters

|    |                |                                       |
|----|----------------|---------------------------------------|
| in | <i>context</i> | The reference to the overall context. |
|----|----------------|---------------------------------------|

**Parameters**

|     |               |                                                                                                  |
|-----|---------------|--------------------------------------------------------------------------------------------------|
| in  | <i>in1</i>    | A <a href="#">VX_DF_IMAGE_U8</a> or <a href="#">VX_DF_IMAGE_S16</a> input image, the minuend.    |
| in  | <i>in2</i>    | A <a href="#">VX_DF_IMAGE_U8</a> or <a href="#">VX_DF_IMAGE_S16</a> input image, the subtrahend. |
| in  | <i>policy</i> | A <a href="#">vx_convert_policy_e</a> enumeration.                                               |
| out | <i>out</i>    | The output image in <a href="#">VX_DF_IMAGE_U8</a> or <a href="#">VX_DF_IMAGE_S16</a> format.    |

**Returns**

A [vx\\_status\\_e](#) enumeration.

**Return values**

|                            |                                                      |
|----------------------------|------------------------------------------------------|
| <a href="#">VX_SUCCESS</a> | Success                                              |
| *                          | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.10 Bitwise AND

### 3.10.1 Detailed Description

Performs a *bitwise AND* operation between two [VX\\_DF\\_IMAGE\\_U8](#) images. The output image dimensions should be the same as the dimensions of the input images.

Bitwise AND is computed by the following, for each bit in each pixel in the input images:

$$out(x,y) = in_1(x,y) \wedge in_2(x,y)$$

Or expressed as C code:

```
out(x,y) = in_1(x,y) & in_2(x,y)
```

### Functions

- [vx\\_node VX\\_API\\_CALL vxAndNode](#) ([vx\\_graph](#) graph, [vx\\_image](#) in1, [vx\\_image](#) in2, [vx\\_image](#) out)  
[Graph] Creates a bitwise AND node.
- [vx\\_status VX\\_API\\_CALL vxuAnd](#) ([vx\\_context](#) context, [vx\\_image](#) in1, [vx\\_image](#) in2, [vx\\_image](#) out)  
[Immediate] Computes the bitwise and between two images.

### 3.10.2 Function Documentation

**[vx\\_node VX\\_API\\_CALL vxAndNode](#) ( [vx\\_graph](#) graph, [vx\\_image](#) in1, [vx\\_image](#) in2, [vx\\_image](#) out )**

[Graph] Creates a bitwise AND node.

#### Parameters

|     |       |                                                                                                           |
|-----|-------|-----------------------------------------------------------------------------------------------------------|
| in  | graph | The reference to the graph.                                                                               |
| in  | in1   | A <a href="#">VX_DF_IMAGE_U8</a> input image.                                                             |
| in  | in2   | A <a href="#">VX_DF_IMAGE_U8</a> input image.                                                             |
| out | out   | The <a href="#">VX_DF_IMAGE_U8</a> output image, which must have the same dimensions as the input images. |

#### Returns

[vx\\_node](#).

#### Return values

|                         |                                                                                                                            |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|
| <a href="#">vx_node</a> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|

**[vx\\_status VX\\_API\\_CALL vxuAnd](#) ( [vx\\_context](#) context, [vx\\_image](#) in1, [vx\\_image](#) in2, [vx\\_image](#) out )**

[Immediate] Computes the bitwise and between two images.

#### Parameters

|     |         |                                                  |
|-----|---------|--------------------------------------------------|
| in  | context | The reference to the overall context.            |
| in  | in1     | A <a href="#">VX_DF_IMAGE_U8</a> input image     |
| in  | in2     | A <a href="#">VX_DF_IMAGE_U8</a> input image     |
| out | out     | The <a href="#">VX_DF_IMAGE_U8</a> output image. |

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                         |                                                   |
|-------------------------|---------------------------------------------------|
| <code>VX_SUCCESS</code> | Success                                           |
| *                       | An error occurred. See <code>vx_status_e</code> . |

## 3.11 Bitwise EXCLUSIVE OR

### 3.11.1 Detailed Description

Performs a *bitwise EXCLUSIVE OR* (XOR) operation between two [VX\\_DF\\_IMAGE\\_U8](#) images. The output image dimensions should be the same as the dimensions of the input images.

Bitwise XOR is computed by the following, for each bit in each pixel in the input images:

$$out(x,y) = in_1(x,y) \oplus in_2(x,y)$$

Or expressed as C code:

```
out(x,y) = in_1(x,y) ^ in_2(x,y)
```

### Functions

- [vx\\_status VX\\_API\\_CALL vxuXor](#) ([vx\\_context](#) context, [vx\\_image](#) in1, [vx\\_image](#) in2, [vx\\_image](#) out)  
[Immediate] Computes the bitwise exclusive-or between two images.
- [vx\\_node VX\\_API\\_CALL vxXorNode](#) ([vx\\_graph](#) graph, [vx\\_image](#) in1, [vx\\_image](#) in2, [vx\\_image](#) out)  
[Graph] Creates a bitwise EXCLUSIVE OR node.

### 3.11.2 Function Documentation

**[vx\\_node VX\\_API\\_CALL vxXorNode](#) ( [vx\\_graph](#) graph, [vx\\_image](#) in1, [vx\\_image](#) in2, [vx\\_image](#) out )**

[Graph] Creates a bitwise EXCLUSIVE OR node.

#### Parameters

|     |       |                                                                                                           |
|-----|-------|-----------------------------------------------------------------------------------------------------------|
| in  | graph | The reference to the graph.                                                                               |
| in  | in1   | A <a href="#">VX_DF_IMAGE_U8</a> input image.                                                             |
| in  | in2   | A <a href="#">VX_DF_IMAGE_U8</a> input image.                                                             |
| out | out   | The <a href="#">VX_DF_IMAGE_U8</a> output image, which must have the same dimensions as the input images. |

#### Returns

[vx\\_node](#).

#### Return values

|                         |                                                                                                                            |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|
| <a href="#">vx_node</a> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|

**[vx\\_status VX\\_API\\_CALL vxuXor](#) ( [vx\\_context](#) context, [vx\\_image](#) in1, [vx\\_image](#) in2, [vx\\_image](#) out )**

[Immediate] Computes the bitwise exclusive-or between two images.

#### Parameters

|     |         |                                                  |
|-----|---------|--------------------------------------------------|
| in  | context | The reference to the overall context.            |
| in  | in1     | A <a href="#">VX_DF_IMAGE_U8</a> input image     |
| in  | in2     | A <a href="#">VX_DF_IMAGE_U8</a> input image     |
| out | out     | The <a href="#">VX_DF_IMAGE_U8</a> output image. |

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                         |                                                   |
|-------------------------|---------------------------------------------------|
| <code>VX_SUCCESS</code> | Success                                           |
| *                       | An error occurred. See <code>vx_status_e</code> . |



## 3.12 Bitwise INCLUSIVE OR

### 3.12.1 Detailed Description

Performs a *bitwise INCLUSIVE OR* operation between two [VX\\_DF\\_IMAGE\\_U8](#) images. The output image dimensions should be the same as the dimensions of the input images.

Bitwise INCLUSIVE OR is computed by the following, for each bit in each pixel in the input images:

$$out(x,y) = in_1(x,y) \vee in_2(x,y)$$

Or expressed as C code:

```
out(x,y) = in_1(x,y) | in_2(x,y)
```

### Functions

- [vx\\_node VX\\_API\\_CALL vxOrNode](#) ([vx\\_graph](#) graph, [vx\\_image](#) in1, [vx\\_image](#) in2, [vx\\_image](#) out)  
[Graph] Creates a bitwise INCLUSIVE OR node.
- [vx\\_status VX\\_API\\_CALL vxuOr](#) ([vx\\_context](#) context, [vx\\_image](#) in1, [vx\\_image](#) in2, [vx\\_image](#) out)  
[Immediate] Computes the bitwise inclusive-or between two images.

### 3.12.2 Function Documentation

**[vx\\_node VX\\_API\\_CALL vxOrNode](#) ( [vx\\_graph](#) graph, [vx\\_image](#) in1, [vx\\_image](#) in2, [vx\\_image](#) out )**

[Graph] Creates a bitwise INCLUSIVE OR node.

#### Parameters

|     |       |                                                                                                           |
|-----|-------|-----------------------------------------------------------------------------------------------------------|
| in  | graph | The reference to the graph.                                                                               |
| in  | in1   | A <a href="#">VX_DF_IMAGE_U8</a> input image.                                                             |
| in  | in2   | A <a href="#">VX_DF_IMAGE_U8</a> input image.                                                             |
| out | out   | The <a href="#">VX_DF_IMAGE_U8</a> output image, which must have the same dimensions as the input images. |

#### Returns

[vx\\_node](#).

#### Return values

|                         |                                                                                                                            |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|
| <a href="#">vx_node</a> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|

**[vx\\_status VX\\_API\\_CALL vxuOr](#) ( [vx\\_context](#) context, [vx\\_image](#) in1, [vx\\_image](#) in2, [vx\\_image](#) out )**

[Immediate] Computes the bitwise inclusive-or between two images.

#### Parameters

|     |         |                                                  |
|-----|---------|--------------------------------------------------|
| in  | context | The reference to the overall context.            |
| in  | in1     | A <a href="#">VX_DF_IMAGE_U8</a> input image     |
| in  | in2     | A <a href="#">VX_DF_IMAGE_U8</a> input image     |
| out | out     | The <a href="#">VX_DF_IMAGE_U8</a> output image. |

**Returns**

A [vx\\_status\\_e](#) enumeration.

**Return values**

|                         |                                                      |
|-------------------------|------------------------------------------------------|
| <code>VX_SUCCESS</code> | Success                                              |
| *                       | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.13 Bitwise NOT

### 3.13.1 Detailed Description

Performs a *bitwise NOT* operation on a [VX\\_DF\\_IMAGE\\_U8](#) input image. The output image dimensions should be the same as the dimensions of the input image.

Bitwise NOT is computed by the following, for each bit in each pixel in the input image:

$$out(x,y) = \overline{in(x,y)}$$

Or expressed as C code:

```
out(x,y) = ~in_1(x,y)
```

### Functions

- [vx\\_node VX\\_API\\_CALL vxNotNode](#) ([vx\\_graph](#) graph, [vx\\_image](#) input, [vx\\_image](#) output)  
[Graph] Creates a bitwise NOT node.
- [vx\\_status VX\\_API\\_CALL vxuNot](#) ([vx\\_context](#) context, [vx\\_image](#) input, [vx\\_image](#) output)  
[Immediate] Computes the bitwise not of an image.

### 3.13.2 Function Documentation

**[vx\\_node VX\\_API\\_CALL vxNotNode](#) ( [vx\\_graph](#) graph, [vx\\_image](#) input, [vx\\_image](#) output )**

[Graph] Creates a bitwise NOT node.

#### Parameters

|     |               |                                                                                                          |
|-----|---------------|----------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>  | The reference to the graph.                                                                              |
| in  | <i>input</i>  | A <a href="#">VX_DF_IMAGE_U8</a> input image.                                                            |
| out | <i>output</i> | The <a href="#">VX_DF_IMAGE_U8</a> output image, which must have the same dimensions as the input image. |

#### Returns

[vx\\_node](#).

#### Return values

|                         |                                                                                                                            |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|
| <a href="#">vx_node</a> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|

**[vx\\_status VX\\_API\\_CALL vxuNot](#) ( [vx\\_context](#) context, [vx\\_image](#) input, [vx\\_image](#) output )**

[Immediate] Computes the bitwise not of an image.

#### Parameters

|     |                |                                                  |
|-----|----------------|--------------------------------------------------|
| in  | <i>context</i> | The reference to the overall context.            |
| in  | <i>input</i>   | The <a href="#">VX_DF_IMAGE_U8</a> input image   |
| out | <i>output</i>  | The <a href="#">VX_DF_IMAGE_U8</a> output image. |

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                         |                                                   |
|-------------------------|---------------------------------------------------|
| <code>VX_SUCCESS</code> | Success                                           |
| *                       | An error occurred. See <code>vx_status_e</code> . |

## 3.14 Box Filter

### 3.14.1 Detailed Description

Computes a Box filter over a window of the input image. The output image dimensions should be the same as the dimensions of the input image.

This filter uses the following convolution matrix:

$$\mathbf{K}_{box} = \begin{bmatrix} 1 & 1 & 1 \\ 1 & 1 & 1 \\ 1 & 1 & 1 \end{bmatrix} * \frac{1}{9}$$

### Functions

- `vx_node VX_API_CALL vxBox3x3Node (vx_graph graph, vx_image input, vx_image output)`  
[Graph] Creates a Box Filter Node.
- `vx_status VX_API_CALL vxuBox3x3 (vx_context context, vx_image input, vx_image output)`  
[Immediate] Computes a box filter on the image by a 3x3 window.

### 3.14.2 Function Documentation

**vx\_node VX\_API\_CALL vxBox3x3Node ( vx\_graph *graph*, vx\_image *input*, vx\_image *output* )**

[Graph] Creates a Box Filter Node.

#### Parameters

|     |               |                                                                                                                    |
|-----|---------------|--------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>  | The reference to the graph.                                                                                        |
| in  | <i>input</i>  | The input image in <a href="#">VX_DF_IMAGE_U8</a> format.                                                          |
| out | <i>output</i> | The output image in <a href="#">VX_DF_IMAGE_U8</a> format, which must have the same dimensions as the input image. |

#### Returns

[vx\\_node](#).

#### Return values

|                         |                                                                                                                            |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|
| <a href="#">vx_node</a> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|

**vx\_status VX\_API\_CALL vxuBox3x3 ( vx\_context *context*, vx\_image *input*, vx\_image *output* )**

[Immediate] Computes a box filter on the image by a 3x3 window.

#### Parameters

|     |                |                                                            |
|-----|----------------|------------------------------------------------------------|
| in  | <i>context</i> | The reference to the overall context.                      |
| in  | <i>input</i>   | The input image in <a href="#">VX_DF_IMAGE_U8</a> format.  |
| out | <i>output</i>  | The output image in <a href="#">VX_DF_IMAGE_U8</a> format. |

#### Returns

A [vx\\_status\\_e](#) enumeration.

**Return values**

|                         |                                                      |
|-------------------------|------------------------------------------------------|
| <code>VX_SUCCESS</code> | Success                                              |
| *                       | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.15 Non-Maxima Suppression

### 3.15.1 Detailed Description

Find local maxima in an image, or otherwise suppress pixels that are not local maxima.

The input to the Non-Maxima Suppressor is either a `VX_DF_IMAGE_U8` or `VX_DF_IMAGE_S16` image. In the case of a `VX_DF_IMAGE_S16` image, suppressed pixels shall take the value of `INT16_MIN`.

An optional mask image may be used to restrict the suppression to a region-of-interest. If a mask pixel is non-zero, then the associated pixel in the input is completely ignored and not considered during suppression; that is, it is not suppressed and not considered as part of any suppression window.

A pixel with coordinates  $(x, y)$  is kept if and only if it is greater than or equal to its top left neighbours; and greater than its bottom right neighbours. For example, for a window size of 3,  $P(x, y)$  is retained if the following condition holds:

$$\begin{aligned} P(x, y) &\geq P(x-1, y-1) \text{ and } P(x, y) \geq P(x, y-1) \text{ and} \\ P(x, y) &\geq P(x+1, y-1) \text{ and } P(x, y) \geq P(x-1, y) \text{ and} \\ P(x, y) &> P(x+1, y) \text{ and } P(x, y) > P(x-1, y+1) \text{ and} \\ P(x, y) &> P(x, y+1) \text{ and } P(x, y) > P(x+1, y+1) \end{aligned}$$

### Functions

- `vx_node VX_API_CALL vxNonMaxSuppressionNode (vx_graph graph, vx_image input, vx_image mask, vx_int32 win_size, vx_image output)`

*[Graph] Creates a Non-Maxima Suppression node.*

- `vx_status VX_API_CALL vxuNonMaxSuppression (vx_context context, vx_image input, vx_image mask, vx_int32 win_size, vx_image output)`

*[Immediate] Performs Non-Maxima Suppression on an image, producing an image of the same type.*

### 3.15.2 Function Documentation

**`vx_node VX_API_CALL vxNonMaxSuppressionNode ( vx_graph graph, vx_image input, vx_image mask, vx_int32 win_size, vx_image output )`**

*[Graph] Creates a Non-Maxima Suppression node.*

#### Parameters

|     |                 |                                                                                                                                                                  |
|-----|-----------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>    | The reference to the graph.                                                                                                                                      |
| in  | <i>input</i>    | The input image in <code>VX_DF_IMAGE_U8</code> or <code>VX_DF_IMAGE_S16</code> format.                                                                           |
| in  | <i>mask</i>     | [optional] Constrict suppression to a ROI. The mask image is of type <code>VX_DF_IMAGE_U8</code> and must be the same dimensions as the input image.             |
| in  | <i>win_size</i> | The size of window over which to perform the localized non-maxima suppression. Must be odd, and less than or equal to the smallest dimension of the input image. |
| out | <i>output</i>   | The output image, of the same type and size as the input, that has been non-maxima suppressed.                                                                   |

#### Returns

`vx_node`.

#### Return values

|                      |                                                                                                                         |
|----------------------|-------------------------------------------------------------------------------------------------------------------------|
| <code>vx_node</code> | A node reference. Any possible errors preventing a successful creation should be checked using <code>vxGetStatus</code> |
|----------------------|-------------------------------------------------------------------------------------------------------------------------|

**vx\_status VX\_API\_CALL vxuNonMaxSuppression ( vx\_context context, vx\_image input, vx\_image mask, vx\_int32 win\_size, vx\_image output )**

[Immediate] Performs Non-Maxima Suppression on an image, producing an image of the same type.

#### Parameters

|     |                 |                                                                                                                                                                  |
|-----|-----------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>context</i>  | The reference to the overall context.                                                                                                                            |
| in  | <i>input</i>    | The input image in <a href="#">VX_DF_IMAGE_U8</a> or <a href="#">VX_DF_IMAGE_S16</a> format.                                                                     |
| in  | <i>mask</i>     | [optional] Constrict suppression to a ROI. The mask image is of type <a href="#">VX_DF_IMAGE_U8</a> and must be the same dimensions as the input image.          |
| in  | <i>win_size</i> | The size of window over which to perform the localized non-maxima suppression. Must be odd, and less than or equal to the smallest dimension of the input image. |
| out | <i>output</i>   | The output image, of the same type as the input, that has been non-maxima suppressed.                                                                            |

#### Returns

A [vx\\_status\\_e](#) enumeration.

#### Return values

|                            |                                                      |
|----------------------------|------------------------------------------------------|
| <a href="#">VX_SUCCESS</a> | Success                                              |
| *                          | An error occurred. See <a href="#">vx_status_e</a> . |



## 3.16 Canny Edge Detector

### 3.16.1 Detailed Description

Provides a Canny edge detector kernel. The output image dimensions should be the same as the dimensions of the input image.

This function implements an edge detection algorithm similar to that described in [?]. The main components of the algorithm are:

- Gradient magnitude and orientation computation using a noise resistant operator (Sobel).
- Non-maximum suppression of the gradient magnitude, using the gradient orientation information.
- Tracing edges in the modified gradient image using hysteresis thresholding to produce a binary result.

The details of each of these steps are described below.

- **Gradient Computation:** Conceptually, the input image is convolved with vertical and horizontal Sobel kernels of the size indicated by the *gradient\_size* parameter. The Sobel kernels used for the gradient computation shall be as shown below. The two resulting directional gradient images ( $dx$  and  $dy$ ) are then used to compute a gradient magnitude image and a gradient orientation image. The norm used to compute the gradient magnitude is indicated by the *norm\_type* parameter, so the magnitude may be  $|dx| + |dy|$  for [VX\\_NORM\\_L1](#) or  $\sqrt{dx^2 + dy^2}$  for [VX\\_NORM\\_L2](#). The gradient orientation image is quantized into 4 values: 0, 45, 90, and 135 degrees.

- For gradient size 3:

$$\mathbf{sobel}_x = \begin{bmatrix} -1 & 0 & 1 \\ -2 & 0 & 2 \\ -1 & 0 & 1 \end{bmatrix}$$

$$\mathbf{sobel}_y = \mathit{transpose}(\mathbf{sobel}_x) = \begin{bmatrix} -1 & -2 & -1 \\ 0 & 0 & 0 \\ 1 & 2 & 1 \end{bmatrix}$$

- For gradient size 5:

$$\mathbf{sobel}_x = \begin{bmatrix} -1 & -2 & 0 & 2 & 1 \\ -4 & -8 & 0 & 8 & 4 \\ -6 & -12 & 0 & 12 & 6 \\ -4 & -8 & 0 & 8 & 4 \\ -1 & -2 & 0 & 2 & 1 \end{bmatrix}$$

$$\mathbf{sobel}_y = \mathit{transpose}(\mathbf{sobel}_x)$$

- For gradient size 7:

$$\mathbf{sobel}_x = \begin{bmatrix} -1 & -4 & -5 & 0 & 5 & 4 & 1 \\ -6 & -24 & -30 & 0 & 30 & 24 & 6 \\ -15 & -60 & -75 & 0 & 75 & 60 & 15 \\ -20 & -80 & -100 & 0 & 100 & 80 & 20 \\ -15 & -60 & -75 & 0 & 75 & 60 & 15 \\ -6 & -24 & -30 & 0 & 30 & 24 & 6 \\ -1 & -4 & -5 & 0 & 5 & 4 & 1 \end{bmatrix}$$

$$\mathbf{sobel}_y = \mathit{transpose}(\mathbf{sobel}_x)$$

- **Non-Maximum Suppression:** This is then applied such that a pixel is retained as a potential edge pixel if and only if its magnitude is greater than or equal to the pixels in the direction perpendicular to its edge orientation. For example, if the pixel's orientation is 0 degrees, it is only retained if its gradient magnitude is larger than that of the pixels at 90 and 270 degrees to it. If a pixel is suppressed via this condition, it must not appear as an edge pixel in the final output, i.e., its value must be 0 in the final output.

- **Edge Tracing:** The final edge pixels in the output are identified via a double thresholded hysteresis procedure. All retained pixels with magnitude above the *high* threshold are marked as known edge pixels (valued 255) in the final output image. All pixels with magnitudes less than or equal to the *low* threshold must not be marked as edge pixels in the final output. For the pixels in between the thresholds, edges are traced and marked as edges (255) in the output. This can be done by starting at the known edge pixels and moving in all eight directions recursively until the gradient magnitude is less than or equal to the low threshold.
- **Caveats:** The intermediate results described above are conceptual only; so for example, the implementation may not actually construct the gradient images and non-maximum-suppressed images. Only the final binary (0 or 255 valued) output image must be computed so that it matches the result of a final image constructed as described above.

## Enumerations

- enum `vx_norm_type_e` {  
`VX_NORM_L1` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_NORM_TYPE` << 12)) + 0x0,  
`VX_NORM_L2` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_NORM_TYPE` << 12)) + 0x1 }  
A normalization type.

## Functions

- `vx_node VX_API_CALL vxCannyEdgeDetectorNode` (`vx_graph` graph, `vx_image` input, `vx_threshold` hyst, `vx_int32` gradient\_size, `vx_enum` norm\_type, `vx_image` output)  
[Graph] Creates a Canny Edge Detection Node.
- `vx_status VX_API_CALL vxuCannyEdgeDetector` (`vx_context` context, `vx_image` input, `vx_threshold` hyst, `vx_int32` gradient\_size, `vx_enum` norm\_type, `vx_image` output)  
[Immediate] Computes Canny Edges on the input image into the output image.

### 3.16.2 Enumeration Type Documentation

#### enum `vx_norm_type_e`

A normalization type.

See also

[Canny Edge Detector](#)

Enumerator

**`VX_NORM_L1`** The L1 normalization.

**`VX_NORM_L2`** The L2 normalization.

Definition at line 1378 of file [vx\\_types.h](#).

### 3.16.3 Function Documentation

**`vx_node VX_API_CALL vxCannyEdgeDetectorNode`** ( `vx_graph` graph, `vx_image` input, `vx_threshold` hyst, `vx_int32` gradient\_size, `vx_enum` norm\_type, `vx_image` output )

[Graph] Creates a Canny Edge Detection Node.

Parameters

|    |                      |                                                                                                                                                                                                                                   |
|----|----------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>graph</i>         | The reference to the graph.                                                                                                                                                                                                       |
| in | <i>input</i>         | The input <a href="#">VX_DF_IMAGE_U8</a> image.                                                                                                                                                                                   |
| in | <i>hyst</i>          | The double threshold for hysteresis. The <a href="#">VX_THRESHOLD_INPUT_FORMAT</a> shall be either <a href="#">VX_DF_IMAGE_U8</a> or <a href="#">VX_DF_IMAGE_S16</a> . The <a href="#">VX_THRESHOLD_OUTPUT_FORMAT</a> is ignored. |
| in | <i>gradient_size</i> | The size of the Sobel filter window, must support at least 3, 5, and 7.                                                                                                                                                           |

**Parameters**

|     |                  |                                                                                                                     |
|-----|------------------|---------------------------------------------------------------------------------------------------------------------|
| in  | <i>norm_type</i> | A flag indicating the norm used to compute the gradient, <a href="#">VX_NORM_L1</a> or <a href="#">VX_NORM_L2</a> . |
| out | <i>output</i>    | The output image in <a href="#">VX_DF_IMAGE_U8</a> format with values either 0 or 255.                              |

**Returns**

[vx\\_node](#).

**Return values**

|                |                                                                                                                            |
|----------------|----------------------------------------------------------------------------------------------------------------------------|
| <i>vx_node</i> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|----------------|----------------------------------------------------------------------------------------------------------------------------|

**vx\_status** [VX\\_API\\_CALL](#) vxuCannyEdgeDetector ( *vx\_context context*, *vx\_image input*, *vx\_threshold hyst*, *vx\_int32 gradient\_size*, *vx\_enum norm\_type*, *vx\_image output* )

[Immediate] Computes Canny Edges on the input image into the output image.

**Parameters**

|     |                      |                                                                                                                                                                                                                                   |
|-----|----------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>context</i>       | The reference to the overall context.                                                                                                                                                                                             |
| in  | <i>input</i>         | The input <a href="#">VX_DF_IMAGE_U8</a> image.                                                                                                                                                                                   |
| in  | <i>hyst</i>          | The double threshold for hysteresis. The <a href="#">VX_THRESHOLD_INPUT_FORMAT</a> shall be either <a href="#">VX_DF_IMAGE_U8</a> or <a href="#">VX_DF_IMAGE_S16</a> . The <a href="#">VX_THRESHOLD_OUTPUT_FORMAT</a> is ignored. |
| in  | <i>gradient_size</i> | The size of the Sobel filter window, must support at least 3, 5 and 7.                                                                                                                                                            |
| in  | <i>norm_type</i>     | A flag indicating the norm used to compute the gradient, <a href="#">VX_NORM_L1</a> or <a href="#">VX_NORM_L2</a> .                                                                                                               |
| out | <i>output</i>        | The output image in <a href="#">VX_DF_IMAGE_U8</a> format with values either 0 or 255.                                                                                                                                            |

**Returns**

A [vx\\_status\\_e](#) enumeration.

**Return values**

|                            |                                                      |
|----------------------------|------------------------------------------------------|
| <a href="#">VX_SUCCESS</a> | Success                                              |
| *                          | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.17 Channel Combine

### 3.17.1 Detailed Description

Implements the Channel Combine Kernel.

This kernel takes multiple [VX\\_DF\\_IMAGE\\_U8](#) planes to recombine them into a multi-planar or interleaved format from [vx\\_df\\_image\\_e](#). The user must specify only the number of channels that are appropriate for the combining operation. If a user specifies more channels than necessary, the operation results in an error. For the case where the destination image is a format with subsampling, the input channels are expected to have been subsampled before combining (by stretching and resizing).

### Functions

- [vx\\_node VX\\_API\\_CALL vxChannelCombineNode](#) ([vx\\_graph](#) graph, [vx\\_image](#) plane0, [vx\\_image](#) plane1, [vx\\_image](#) plane2, [vx\\_image](#) plane3, [vx\\_image](#) output)  
[Graph] Creates a channel combine node.
- [vx\\_status VX\\_API\\_CALL vxuChannelCombine](#) ([vx\\_context](#) context, [vx\\_image](#) plane0, [vx\\_image](#) plane1, [vx\\_image](#) plane2, [vx\\_image](#) plane3, [vx\\_image](#) output)  
[Immediate] Invokes an immediate Channel Combine.

### 3.17.2 Function Documentation

**[vx\\_node VX\\_API\\_CALL vxChannelCombineNode](#) ( [vx\\_graph](#) graph, [vx\\_image](#) plane0, [vx\\_image](#) plane1, [vx\\_image](#) plane2, [vx\\_image](#) plane3, [vx\\_image](#) output )**

[Graph] Creates a channel combine node.

#### Parameters

|     |        |                                                                                                                                            |
|-----|--------|--------------------------------------------------------------------------------------------------------------------------------------------|
| in  | graph  | The graph reference.                                                                                                                       |
| in  | plane0 | The plane that forms channel 0. Must be <a href="#">VX_DF_IMAGE_U8</a> .                                                                   |
| in  | plane1 | The plane that forms channel 1. Must be <a href="#">VX_DF_IMAGE_U8</a> .                                                                   |
| in  | plane2 | [optional] The plane that forms channel 2. Must be <a href="#">VX_DF_IMAGE_U8</a> .                                                        |
| in  | plane3 | [optional] The plane that forms channel 3. Must be <a href="#">VX_DF_IMAGE_U8</a> .                                                        |
| out | output | The output image. The format of the image must be defined, even if the image is virtual. Must have the same dimensions as the input images |

See also

[VX\\_KERNEL\\_CHANNEL\\_COMBINE](#)

Returns

[vx\\_node](#).

#### Return values

|                         |                                                                                                                            |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|
| <a href="#">vx_node</a> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|

**[vx\\_status VX\\_API\\_CALL vxuChannelCombine](#) ( [vx\\_context](#) context, [vx\\_image](#) plane0, [vx\\_image](#) plane1, [vx\\_image](#) plane2, [vx\\_image](#) plane3, [vx\\_image](#) output )**

[Immediate] Invokes an immediate Channel Combine.

**Parameters**

|     |                |                                                                                     |
|-----|----------------|-------------------------------------------------------------------------------------|
| in  | <i>context</i> | The reference to the overall context.                                               |
| in  | <i>plane0</i>  | The plane that forms channel 0. Must be <a href="#">VX_DF_IMAGE_U8</a> .            |
| in  | <i>plane1</i>  | The plane that forms channel 1. Must be <a href="#">VX_DF_IMAGE_U8</a> .            |
| in  | <i>plane2</i>  | [optional] The plane that forms channel 2. Must be <a href="#">VX_DF_IMAGE_U8</a> . |
| in  | <i>plane3</i>  | [optional] The plane that forms channel 3. Must be <a href="#">VX_DF_IMAGE_U8</a> . |
| out | <i>output</i>  | The output image.                                                                   |

**Returns**

A [vx\\_status\\_e](#) enumeration.

**Return values**

|                   |                                                      |
|-------------------|------------------------------------------------------|
| <i>VX_SUCCESS</i> | Success                                              |
| *                 | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.18 Channel Extract

### 3.18.1 Detailed Description

Implements the Channel Extraction Kernel.

This kernel removes a single `VX_DF_IMAGE_U8` channel (plane) from a multi-planar or interleaved image format from `vx_df_image_e`.

### Functions

- `vx_node VX_API_CALL vxChannelExtractNode` (`vx_graph` *graph*, `vx_image` *input*, `vx_enum` *channel*, `vx_image` *output*)  
[Graph] Creates a channel extract node.
- `vx_status VX_API_CALL vxuChannelExtract` (`vx_context` *context*, `vx_image` *input*, `vx_enum` *channel*, `vx_image` *output*)  
[Immediate] Invokes an immediate Channel Extract.

### 3.18.2 Function Documentation

**`vx_node VX_API_CALL vxChannelExtractNode` ( `vx_graph` *graph*, `vx_image` *input*, `vx_enum` *channel*, `vx_image` *output* )**

[Graph] Creates a channel extract node.

#### Parameters

|     |                |                                                                                                               |
|-----|----------------|---------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>   | The reference to the graph.                                                                                   |
| in  | <i>input</i>   | The input image. Must be one of the defined <code>vx_df_image_e</code> multi-channel formats.                 |
| in  | <i>channel</i> | The <code>vx_channel_e</code> channel to extract.                                                             |
| out | <i>output</i>  | The output image. Must be <code>VX_DF_IMAGE_U8</code> , and must have the same dimensions as the input image. |

See also

`VX_KERNEL_CHANNEL_EXTRACT`

Returns

`vx_node`.

#### Return values

|                      |                                                                                                                         |
|----------------------|-------------------------------------------------------------------------------------------------------------------------|
| <code>vx_node</code> | A node reference. Any possible errors preventing a successful creation should be checked using <code>vxGetStatus</code> |
|----------------------|-------------------------------------------------------------------------------------------------------------------------|

**`vx_status VX_API_CALL vxuChannelExtract` ( `vx_context` *context*, `vx_image` *input*, `vx_enum` *channel*, `vx_image` *output* )**

[Immediate] Invokes an immediate Channel Extract.

#### Parameters

|     |                |                                                                                               |
|-----|----------------|-----------------------------------------------------------------------------------------------|
| in  | <i>context</i> | The reference to the overall context.                                                         |
| in  | <i>input</i>   | The input image. Must be one of the defined <code>vx_df_image_e</code> multi-channel formats. |
| in  | <i>channel</i> | The <code>vx_channel_e</code> enumeration to extract.                                         |
| out | <i>output</i>  | The output image. Must be <code>VX_DF_IMAGE_U8</code> .                                       |

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                         |                                                   |
|-------------------------|---------------------------------------------------|
| <code>VX_SUCCESS</code> | Success                                           |
| *                       | An error occurred. See <code>vx_status_e</code> . |

## 3.19 Color Convert

### 3.19.1 Detailed Description

Implements the Color Conversion Kernel. The output image dimensions should be the same as the dimensions of the input image.

This kernel converts an image of a designated `vx_df_image_e` format to another `vx_df_image_e` format for those combinations listed in the below table, where the columns are output types and the rows are input types. The API version first supporting the conversion is also listed.

| I/O  | RGB | RGBX | NV12 | NV21 | UYVY | YUYV | IYUV | YUV4 |
|------|-----|------|------|------|------|------|------|------|
| RGB  |     | 1.0  | 1.0  |      |      |      | 1.0  | 1.0  |
| RGBX | 1.0 |      | 1.0  |      |      |      | 1.0  | 1.0  |
| NV12 | 1.0 | 1.0  |      |      |      |      | 1.0  | 1.0  |
| NV21 | 1.0 | 1.0  |      |      |      |      | 1.0  | 1.0  |
| UYVY | 1.0 | 1.0  | 1.0  |      |      |      | 1.0  |      |
| YUYV | 1.0 | 1.0  | 1.0  |      |      |      | 1.0  |      |
| IYUV | 1.0 | 1.0  | 1.0  |      |      |      |      | 1.0  |
| YUV4 |     |      |      |      |      |      |      |      |

The `vx_df_image_e` encoding, held in the `VX_IMAGE_FORMAT` attribute, describes the data layout. The interpretation of the colors is determined by the `VX_IMAGE_SPACE` (see `vx_color_space_e`) and `VX_IMAGE_RANGE` (see `vx_channel_range_e`) attributes of the image. OpenVX 1.1 implementations are required only to support images of `VX_COLOR_SPACE_BT709` and `VX_CHANNEL_RANGE_FULL`.

If the channel range is defined as `VX_CHANNEL_RANGE_FULL`, the conversion between the real number and integer quantizations of color channels is defined for red, green, blue, and Y as:

$$value_{real} = \frac{value_{integer}}{256.0}$$

$$value_{integer} = \max(0, \min(255, \text{floor}(value_{real} * 256.0)))$$

For the U and V channels, the conversion between real number and integer quantizations is:

$$value_{real} = \frac{(value_{integer} - 128.0)}{256.0}$$

$$value_{integer} = \max(0, \min(255, \text{floor}((value_{real} * 256.0) + 128)))$$

If the channel range is defined as `VX_CHANNEL_RANGE_RESTRICTED`, the conversion between the integer quantizations of color channels and the continuous representations is defined for red, green, blue, and Y as:

$$value_{real} = \frac{(value_{integer} - 16.0)}{219.0}$$

$$value_{integer} = \max(0, \min(255, \text{floor}((value_{real} * 219.0) + 16.5)))$$

For the U and V channels, the conversion between real number and integer quantizations is:

$$value_{real} = \frac{(value_{integer} - 128.0)}{224.0}$$

$$value_{integer} = \max(0, \min(255, \text{floor}((value_{real} * 224.0) + 128.5)))$$

The conversions between nonlinear-intensity Y'PbPr and R'G'B' real numbers are:

$$R' = Y' + 2(1 - K_r)Pr$$

$$B' = Y' + 2(1 - K_b)Pb$$

$$G' = Y' - \frac{2(K_r(1 - K_r)Pr + K_b(1 - K_b)Pb)}{1 - K_r - K_b}$$

$$Y' = (K_r * R') + (K_b * B') + (1 - K_r - K_b)G'$$



$$Pb = \frac{B'}{2} - \frac{(R' * K_r) + G'(1 - K_r - K_b)}{2(1 - K_b)}$$

$$Pr = \frac{R'}{2} - \frac{(B' * K_b) + G'(1 - K_r - K_b)}{2(1 - K_r)}$$

The means of reconstructing Pb and Pr values from chroma-downsampled formats is implementation-defined. In [VX\\_COLOR\\_SPACE\\_BT601\\_525](#) or [VX\\_COLOR\\_SPACE\\_BT601\\_625](#):

$$K_r = 0.299$$

$$K_b = 0.114$$

In [VX\\_COLOR\\_SPACE\\_BT709](#):

$$K_r = 0.2126$$

$$K_b = 0.0722$$

In all cases, for the purposes of conversion, these colour representations are interpreted as nonlinear in intensity, as defined by the BT.601, BT.709, and sRGB specifications. That is, the encoded colour channels are nonlinear R', G' and B', Y', Pb, and Pr.

Each channel of the R'G'B' representation can be converted to and from a linear-intensity RGB channel by these formulae:

$$value_{nonlinear} = 1.099 * value_{linear}^{0.45} - 0.099 \quad for \quad 1 \geq value_{linear} \geq 0.018$$

$$value_{nonlinear} = 4.500 * value_{linear} \quad for \quad 0.018 > value_{linear} \geq 0$$

$$value_{linear} = \left( \frac{value_{nonlinear} + 0.099}{1.099} \right)^{\frac{1}{0.45}} \quad for \quad 1 \geq value_{nonlinear} > 0.081$$

$$value_{linear} = \frac{value_{nonlinear}}{4.5} \quad for \quad 0.081 \geq value_{nonlinear} \geq 0$$

As the different color spaces have different RGB primaries, a conversion between them must transform the color coordinates into the new RGB space. Working with linear RGB values, the conversion formulae are:

$$R_{BT601\_525} = R_{BT601\_625} * 1.112302 + G_{BT601\_625} * -0.102441 + B_{BT601\_625} * -0.009860$$

$$G_{BT601\_525} = R_{BT601\_625} * -0.020497 + G_{BT601\_625} * 1.037030 + B_{BT601\_625} * -0.016533$$

$$B_{BT601\_525} = R_{BT601\_625} * 0.001704 + G_{BT601\_625} * 0.016063 + B_{BT601\_625} * 0.982233$$

$$R_{BT601\_525} = R_{BT709} * 1.065379 + G_{BT709} * -0.055401 + B_{BT709} * -0.009978$$

$$G_{BT601\_525} = R_{BT709} * -0.019633 + G_{BT709} * 1.036363 + B_{BT709} * -0.016731$$

$$B_{BT601\_525} = R_{BT709} * 0.001632 + G_{BT709} * 0.004412 + B_{BT709} * 0.993956$$

$$R_{BT601\_625} = R_{BT601\_525} * 0.900657 + G_{BT601\_525} * 0.088807 + B_{BT601\_525} * 0.010536$$

$$G_{BT601\_625} = R_{BT601\_525} * 0.017772 + G_{BT601\_525} * 0.965793 + B_{BT601\_525} * 0.016435$$

$$B_{BT601\_625} = R_{BT601\_525} * -0.001853 + G_{BT601\_525} * -0.015948 + B_{BT601\_525} * 1.017801$$

$$R_{BT601\_625} = R_{BT709} * 0.957815 + G_{BT709} * 0.042185$$

$$G_{BT601\_625} = G_{BT709}$$

$$B_{BT601\_625} = G_{BT709} * -0.011934 + B_{BT709} * 1.011934$$

$$R_{BT709} = R_{BT601\_525} * 0.939542 + G_{BT601\_525} * 0.050181 + B_{BT601\_525} * 0.010277$$

$$G_{BT709} = R_{BT601\_525} * 0.017772 + G_{BT601\_525} * 0.965793 + B_{BT601\_525} * 0.016435$$

$$B_{BT709} = R_{BT601\_525} * -0.001622 + G_{BT601\_525} * -0.004370 + B_{BT601\_525} * 1.005991$$

$$R_{BT709} = R_{BT601\_625} * 1.044043 + G_{BT601\_625} * -0.044043$$

$$G_{BT709} = G_{BT601\_625}$$

$$B_{BT709} = G_{BT601\_625} * 0.011793 + B_{BT601\_625} * 0.988207$$

A conversion between one YUV color space and another may therefore consist of the following transformations:

1. Convert quantized Y'CbCr ("YUV") to continuous, nonlinear Y'PbPr.
2. Convert continuous Y'PbPr to continuous, nonlinear R'G'B'.
3. Convert nonlinear R'G'B' to linear-intensity RGB (gamma-correction).
4. Convert linear RGB from the first color space to linear RGB in the second color space.
5. Convert linear RGB to nonlinear R'G'B' (gamma-conversion).
6. Convert nonlinear R'G'B' to Y'PbPr.
7. Convert continuous Y'PbPr to quantized Y'CbCr ("YUV").

The above formulae and constants are defined in the ITU [BT.601](#) and [BT.709](#) specifications. The formulae for converting between RGB primaries can be derived from the specified primary chromaticity values and the specified white point by solving for the relative intensity of the primaries.

## Functions

- [vx\\_node VX\\_API\\_CALL vxColorConvertNode](#) ([vx\\_graph](#) graph, [vx\\_image](#) input, [vx\\_image](#) output)  
[Graph] Creates a color conversion node.
- [vx\\_status VX\\_API\\_CALL vxuColorConvert](#) ([vx\\_context](#) context, [vx\\_image](#) input, [vx\\_image](#) output)  
[Immediate] Invokes an immediate Color Conversion.

### 3.19.2 Function Documentation

**[vx\\_node VX\\_API\\_CALL vxColorConvertNode](#) ( [vx\\_graph](#) graph, [vx\\_image](#) input, [vx\\_image](#) output )**

[Graph] Creates a color conversion node.

#### Parameters

|     |               |                                                                                               |
|-----|---------------|-----------------------------------------------------------------------------------------------|
| in  | <i>graph</i>  | The reference to the graph.                                                                   |
| in  | <i>input</i>  | The input image from which to convert.                                                        |
| out | <i>output</i> | The output image to which to convert, which must have the same dimensions as the input image. |

See also

[VX\\_KERNEL\\_COLOR\\_CONVERT](#)

Returns

[vx\\_node](#).

#### Return values

|                         |                                                                                                                            |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|
| <a href="#">vx_node</a> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|

**vx\_status VX\_API\_CALL vxuColorConvert ( vx\_context *context*, vx\_image *input*, vx\_image *output* )**

[Immediate] Invokes an immediate Color Conversion.

#### Parameters

|     |                |                                       |
|-----|----------------|---------------------------------------|
| in  | <i>context</i> | The reference to the overall context. |
| in  | <i>input</i>   | The input image.                      |
| out | <i>output</i>  | The output image.                     |

#### Returns

A [vx\\_status\\_e](#) enumeration.

#### Return values

|                   |                                                      |
|-------------------|------------------------------------------------------|
| <i>VX_SUCCESS</i> | Success                                              |
| *                 | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.20 Convert Bit depth

### 3.20.1 Detailed Description

Converts image bit depth. The output image dimensions should be the same as the dimensions of the input image.

This kernel converts an image from some source bit-depth to another bit-depth as described by the table below. If the input value is unsigned the shift must be in zeros. If the input value is signed, the shift used must be an arithmetic shift. The columns in the table below are the output types and the rows are the input types. The API version on which conversion is supported is also listed. (An X denotes an invalid operation.)

| I/O | U8       | U16 | S16 | U32 | S32 |
|-----|----------|-----|-----|-----|-----|
| U8  | X        |     | 1.0 |     |     |
| U16 |          | X   | X   |     |     |
| S16 | 1.↔<br>0 | X   | X   |     |     |
| U32 |          |     |     | X   | X   |
| S32 |          |     |     | X   | X   |

**Conversion Type** The table below identifies the conversion types for the allowed bith depth conversions.

| From | To  | Conversion Type |
|------|-----|-----------------|
| U8   | S16 | Up-conversion   |
| S16  | U8  | Down-conversion |

**Convert Policy** Down-conversions with `VX_CONVERT_POLICY_WRAP` follow this equation:

```
output(x,y) = ((uint8) (input(x,y) >> shift));
```

Down-conversions with `VX_CONVERT_POLICY_SATURATE` follow this equation:

```
int16 value = input(x,y) >> shift;
value = value < 0 ? 0 : value;
value = value > 255 ? 255 : value;
output(x,y) = (uint8) value;
```

Up-conversions ignore the policy and perform this operation:

```
output(x,y) = ((int16) input(x,y)) << shift;
```

The valid values for 'shift' are as specified below, all other values produce undefined behavior.

```
0 <= shift < 8;
```

## Functions

- `vx_node VX_API_CALL vxConvertDepthNode` (`vx_graph` graph, `vx_image` input, `vx_image` output, `vx_enum` policy, `vx_scalar` shift)

*[Graph] Creates a bit-depth conversion node.*

- `vx_status VX_API_CALL vxuConvertDepth` (`vx_context` context, `vx_image` input, `vx_image` output, `vx_enum` policy, `vx_int32` shift)

*[Immediate] Converts the input images bit-depth into the output image.*

### 3.20.2 Function Documentation

**`vx_node VX_API_CALL vxConvertDepthNode`** ( `vx_graph` graph, `vx_image` input, `vx_image` output, `vx_enum` policy, `vx_scalar` shift )

[Graph] Creates a bit-depth conversion node.

**Parameters**

|     |               |                                                                                        |
|-----|---------------|----------------------------------------------------------------------------------------|
| in  | <i>graph</i>  | The reference to the graph.                                                            |
| in  | <i>input</i>  | The input image.                                                                       |
| out | <i>output</i> | The output image with the same dimensions of the input image.                          |
| in  | <i>policy</i> | A <a href="#">VX_TYPE_ENUM</a> of the <a href="#">vx_convert_policy_e</a> enumeration. |
| in  | <i>shift</i>  | A scalar containing a <a href="#">VX_TYPE_INT32</a> of the shift value.                |

**Returns**

[vx\\_node](#).

**Return values**

|                |                                                                                                                            |
|----------------|----------------------------------------------------------------------------------------------------------------------------|
| <i>vx_node</i> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|----------------|----------------------------------------------------------------------------------------------------------------------------|

**vx\_status** [VX\\_API\\_CALL](#) vxuConvertDepth ( *vx\_context context*, *vx\_image input*, *vx\_image output*, *vx\_enum policy*, *vx\_int32 shift* )

[Immediate] Converts the input images bit-depth into the output image.

**Parameters**

|     |                |                                                                                        |
|-----|----------------|----------------------------------------------------------------------------------------|
| in  | <i>context</i> | The reference to the overall context.                                                  |
| in  | <i>input</i>   | The input image.                                                                       |
| out | <i>output</i>  | The output image.                                                                      |
| in  | <i>policy</i>  | A <a href="#">VX_TYPE_ENUM</a> of the <a href="#">vx_convert_policy_e</a> enumeration. |
| in  | <i>shift</i>   | A scalar containing a <a href="#">VX_TYPE_INT32</a> of the shift value.                |

**Returns**

A [vx\\_status\\_e](#) enumeration.

**Return values**

|                            |                                                       |
|----------------------------|-------------------------------------------------------|
| <a href="#">VX_SUCCESS</a> | Success                                               |
| *                          | An error occurred. See <a href="#">vx_status_e</a> .. |

## 3.21 Custom Convolution

### 3.21.1 Detailed Description

Convolve the input with the client supplied convolution matrix. The output image dimensions should be the same as the dimensions of the input image.

The client can supply a `vx_int16` typed convolution matrix  $C_{m,n}$ . Outputs will be in the `VX_DF_IMAGE_S16` format unless a `VX_DF_IMAGE_U8` image is explicitly provided. If values would have been out of range of U8 for `VX_DF_IMAGE_U8`, the values are clamped to 0 or 255.

$$k_0 = \frac{m}{2} \quad (3.1)$$

$$l_0 = \frac{n}{2} \quad (3.2)$$

$$sum = \sum_{k=0, l=0}^{k=m-1, l=n-1} input(x + k_0 - k, y + l_0 - l) C_{k,l} \quad (3.3)$$

Note

The above equation for this function is different than an equivalent operation suggested by the OpenCV `filter2D` function.

This translates into the C declaration:

```
// A horizontal Scharr gradient operator with different scale.
vx_int16 gx[3][3] = {
 { 3, 0, -3},
 {10, 0, -10},
 { 3, 0, -3},
};
vx_uint32 scale = 8;
vx_convolution scharr_x = vxCreateConvolution(context, 3, 3);
vxCopyConvolutionCoefficients(scharr_x, (
 vx_int16*)gx, VX_WRITE_ONLY, VX_MEMORY_TYPE_HOST);
vxSetConvolutionAttribute(scharr_x,
 VX_CONVOLUTION_SCALE, &scale, sizeof(scale));
```

For `VX_DF_IMAGE_U8` output, an additional step is taken:

$$output(x,y) = \begin{cases} 0 & \text{if } sum < 0 \\ 255 & \text{if } sum/scale > 255 \\ sum/scale & \text{otherwise} \end{cases}$$

For `VX_DF_IMAGE_S16` output, the summation is simply set to the output

$$output(x,y) = sum/scale$$

The overflow policy used is `VX_CONVERT_POLICY_SATURATE`.

### Functions

- `vx_node VX_API_CALL vxConvolveNode (vx_graph graph, vx_image input, vx_convolution conv, vx_image output)`  
[Graph] Creates a custom convolution node.
- `vx_status VX_API_CALL vxuConvolve (vx_context context, vx_image input, vx_convolution conv, vx_image output)`  
[Immediate] Computes a convolution on the input image with the supplied matrix.

### 3.21.2 Function Documentation

**`vx_node VX_API_CALL vxConvolveNode ( vx_graph graph, vx_image input, vx_convolution conv, vx_image output )`**

[Graph] Creates a custom convolution node.

**Parameters**

|     |               |                                                                                                                                                       |
|-----|---------------|-------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>  | The reference to the graph.                                                                                                                           |
| in  | <i>input</i>  | The input image in <a href="#">VX_DF_IMAGE_U8</a> format.                                                                                             |
| in  | <i>conv</i>   | The <a href="#">vx_int16</a> convolution matrix.                                                                                                      |
| out | <i>output</i> | The output image in <a href="#">VX_DF_IMAGE_U8</a> or <a href="#">VX_DF_IMAGE_S16</a> format, which must have the same dimensions as the input image. |

**Returns**

[vx\\_node](#).

**Return values**

|                         |                                                                                                                            |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|
| <a href="#">vx_node</a> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|

**`vx_status VX_API_CALL vxuConvolve ( vx_context context, vx_image input, vx_convolution conv, vx_image output )`**

[Immediate] Computes a convolution on the input image with the supplied matrix.

**Parameters**

|     |                |                                                                                               |
|-----|----------------|-----------------------------------------------------------------------------------------------|
| in  | <i>context</i> | The reference to the overall context.                                                         |
| in  | <i>input</i>   | The input image in <a href="#">VX_DF_IMAGE_U8</a> format.                                     |
| in  | <i>conv</i>    | The <a href="#">vx_int16</a> convolution matrix.                                              |
| out | <i>output</i>  | The output image in <a href="#">VX_DF_IMAGE_U8</a> or <a href="#">VX_DF_IMAGE_S16</a> format. |

**Returns**

A [vx\\_status\\_e](#) enumeration.

**Return values**

|                            |                                                      |
|----------------------------|------------------------------------------------------|
| <a href="#">VX_SUCCESS</a> | Success                                              |
| *                          | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.22 Dilate Image

### 3.22.1 Detailed Description

Implements Dilation, which *grows* the white space in a [VX\\_DF\\_IMAGE\\_U8](#) Boolean image. The output image dimensions should be the same as the dimensions of the input image.

This kernel uses a 3x3 box around the output pixel used to determine value.

$$dst(x,y) = \max_{\substack{x-1 \leq x' \leq x+1 \\ y-1 \leq y' \leq y+1}} src(x',y')$$

Note

For kernels that use other structuring patterns than 3x3 see [vxNonLinearFilterNode](#) or [vxuNonLinearFilter](#).

### Functions

- [vx\\_node VX\\_API\\_CALL vxDilate3x3Node](#) ([vx\\_graph](#) graph, [vx\\_image](#) input, [vx\\_image](#) output)  
[Graph] Creates a Dilation Image Node.
- [vx\\_status VX\\_API\\_CALL vxuDilate3x3](#) ([vx\\_context](#) context, [vx\\_image](#) input, [vx\\_image](#) output)  
[Immediate] Dilates an image by a 3x3 window.

### 3.22.2 Function Documentation

**[vx\\_node VX\\_API\\_CALL vxDilate3x3Node](#) ( [vx\\_graph](#) graph, [vx\\_image](#) input, [vx\\_image](#) output )**

[Graph] Creates a Dilation Image Node.

Parameters

|     |        |                                                                                                                    |
|-----|--------|--------------------------------------------------------------------------------------------------------------------|
| in  | graph  | The reference to the graph.                                                                                        |
| in  | input  | The input image in <a href="#">VX_DF_IMAGE_U8</a> format.                                                          |
| out | output | The output image in <a href="#">VX_DF_IMAGE_U8</a> format, which must have the same dimensions as the input image. |

Returns

[vx\\_node](#).

Return values

|                         |                                                                                                                            |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|
| <a href="#">vx_node</a> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|

**[vx\\_status VX\\_API\\_CALL vxuDilate3x3](#) ( [vx\\_context](#) context, [vx\\_image](#) input, [vx\\_image](#) output )**

[Immediate] Dilates an image by a 3x3 window.

Parameters

|     |         |                                                            |
|-----|---------|------------------------------------------------------------|
| in  | context | The reference to the overall context.                      |
| in  | input   | The input image in <a href="#">VX_DF_IMAGE_U8</a> format.  |
| out | output  | The output image in <a href="#">VX_DF_IMAGE_U8</a> format. |



**Returns**

A `vx_status_e` enumeration.

**Return values**

|                         |                                                   |
|-------------------------|---------------------------------------------------|
| <code>VX_SUCCESS</code> | Success                                           |
| *                       | An error occurred. See <code>vx_status_e</code> . |

## 3.23 Equalize Histogram

### 3.23.1 Detailed Description

Equalizes the histogram of a grayscale image. The output image dimensions should be the same as the dimensions of the input image.

This kernel uses Histogram Equalization to modify the values of a grayscale image so that it will automatically have a standardized brightness and contrast.

### Functions

- `vx_node VX_API_CALL vxEqualizeHistNode (vx_graph graph, vx_image input, vx_image output)`  
[Graph] Creates a Histogram Equalization node.
- `vx_status VX_API_CALL vxuEqualizeHist (vx_context context, vx_image input, vx_image output)`  
[Immediate] Equalizes the Histogram of a grayscale image.

### 3.23.2 Function Documentation

**`vx_node VX_API_CALL vxEqualizeHistNode ( vx_graph graph, vx_image input, vx_image output )`**

[Graph] Creates a Histogram Equalization node.

#### Parameters

|     |               |                                                                                                                                         |
|-----|---------------|-----------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>  | The reference to the graph.                                                                                                             |
| in  | <i>input</i>  | The grayscale input image in <code>VX_DF_IMAGE_U8</code> .                                                                              |
| out | <i>output</i> | The grayscale output image of type <code>VX_DF_IMAGE_U8</code> with equalized brightness and contrast and same size as the input image. |

#### Returns

`vx_node`.

#### Return values

|                      |                                                                                                                         |
|----------------------|-------------------------------------------------------------------------------------------------------------------------|
| <code>vx_node</code> | A node reference. Any possible errors preventing a successful creation should be checked using <code>vxGetStatus</code> |
|----------------------|-------------------------------------------------------------------------------------------------------------------------|

**`vx_status VX_API_CALL vxuEqualizeHist ( vx_context context, vx_image input, vx_image output )`**

[Immediate] Equalizes the Histogram of a grayscale image.

#### Parameters

|     |                |                                                                                                        |
|-----|----------------|--------------------------------------------------------------------------------------------------------|
| in  | <i>context</i> | The reference to the overall context.                                                                  |
| in  | <i>input</i>   | The grayscale input image in <code>VX_DF_IMAGE_U8</code>                                               |
| out | <i>output</i>  | The grayscale output image of type <code>VX_DF_IMAGE_U8</code> with equalized brightness and contrast. |

#### Returns

A `vx_status_e` enumeration.

#### Return values

|                         |                                                   |
|-------------------------|---------------------------------------------------|
| <code>VX_SUCCESS</code> | Success                                           |
| *                       | An error occurred. See <code>vx_status_e</code> . |

## 3.24 Erode Image

### 3.24.1 Detailed Description

Implements Erosion, which *shrinks* the white space in a [VX\\_DF\\_IMAGE\\_U8](#) Boolean image. The output image dimensions should be the same as the dimensions of the input image.

This kernel uses a 3x3 box around the output pixel used to determine value.

$$dst(x,y) = \min_{\substack{x-1 \leq x' \leq x+1 \\ y-1 \leq y' \leq y+1}} src(x',y')$$

Note

For kernels that use other structuring patterns than 3x3 see [vxNonLinearFilterNode](#) or [vxuNonLinearFilter](#).

### Functions

- [vx\\_node VX\\_API\\_CALL vxErode3x3Node](#) ([vx\\_graph](#) graph, [vx\\_image](#) input, [vx\\_image](#) output)  
[Graph] Creates an Erosion Image Node.
- [vx\\_status VX\\_API\\_CALL vxuErode3x3](#) ([vx\\_context](#) context, [vx\\_image](#) input, [vx\\_image](#) output)  
[Immediate] Erodes an image by a 3x3 window.

### 3.24.2 Function Documentation

**[vx\\_node VX\\_API\\_CALL vxErode3x3Node](#) ( [vx\\_graph](#) *graph*, [vx\\_image](#) *input*, [vx\\_image](#) *output* )**

[Graph] Creates an Erosion Image Node.

Parameters

|     |               |                                                                                                                    |
|-----|---------------|--------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>  | The reference to the graph.                                                                                        |
| in  | <i>input</i>  | The input image in <a href="#">VX_DF_IMAGE_U8</a> format.                                                          |
| out | <i>output</i> | The output image in <a href="#">VX_DF_IMAGE_U8</a> format, which must have the same dimensions as the input image. |

Returns

[vx\\_node](#).

Return values

|                         |                                                                                                                            |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|
| <a href="#">vx_node</a> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|

**[vx\\_status VX\\_API\\_CALL vxuErode3x3](#) ( [vx\\_context](#) *context*, [vx\\_image](#) *input*, [vx\\_image](#) *output* )**

[Immediate] Erodes an image by a 3x3 window.

Parameters

|     |                |                                                            |
|-----|----------------|------------------------------------------------------------|
| in  | <i>context</i> | The reference to the overall context.                      |
| in  | <i>input</i>   | The input image in <a href="#">VX_DF_IMAGE_U8</a> format.  |
| out | <i>output</i>  | The output image in <a href="#">VX_DF_IMAGE_U8</a> format. |

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                         |                                                   |
|-------------------------|---------------------------------------------------|
| <code>VX_SUCCESS</code> | Success                                           |
| *                       | An error occurred. See <code>vx_status_e</code> . |

## 3.25 Fast Corners

### 3.25.1 Detailed Description

Computes the corners in an image using a method based upon FAST9 algorithm suggested in [?] and with some updates from [?] with modifications described below.

It extracts corners by evaluating pixels on the Bresenham circle around a candidate point. If  $N$  contiguous pixels are brighter than the candidate point by at least a threshold value  $t$  or darker by at least  $t$ , then the candidate point is considered to be a corner. For each detected corner, its strength is computed. Optionally, a non-maxima suppression step is applied on all detected corners to remove multiple or spurious responses.

### 3.25.2 Segment Test Detector

The FAST corner detector uses the pixels on a Bresenham circle of radius 3 (16 pixels) to classify whether a candidate point  $p$  is actually a corner, given the following variables.

$I$  = input image (3.4)

$p$  = candidate point position for a corner (3.5)

$I_p$  = image intensity of the candidate point in image  $I$  (3.6)

$x$  = pixel on the Bresenham circle around the candidate point  $p$  (3.7)

$I_x$  = image intensity of the candidate point (3.8)

$t$  = intensity difference threshold for a corner (3.9)

$N$  = minimum number of contiguous pixel to detect a corner (3.10)

$S$  = set of contiguous pixel on the Bresenham circle around the candidate point (3.11)

$C_p$  = corner response at corner location  $p$  (3.12)

(3.13)

The two conditions for FAST corner detection can be expressed as:

- C1: A set of  $N$  contiguous pixels  $S$ ,  $\forall x \text{ in } S, I_x > I_p + t$
- C2: A set of  $N$  contiguous pixels  $S$ ,  $\forall x \text{ in } S, I_x < I_p - t$

So when either of these two conditions is met, the candidate  $p$  is classified as a corner.

In this version of the FAST algorithm, the minimum number of contiguous pixels  $N$  is 9 (FAST9).

The value of the intensity difference threshold *strength\_thresh.* of type `VX_TYPE_FLOAT32` must be within:

$$UINT8_{MIN} < t < UINT8_{MAX}$$

These limits are established due to the input data type `VX_DF_IMAGE_U8`.

**Corner Strength Computation** Once a corner has been detected, its strength (response, saliency, or score) shall be computed if `nonmax_suppression` is set to true, otherwise the value of strength is undefined. The corner response  $C_p$  function is defined as the largest threshold  $t$  for which the pixel  $p$  remains a corner.

**Non-maximum suppression** If the `nonmax_suppression` flag is true, a non-maxima suppression step is applied on the detected corners. The corner with coordinates  $(x, y)$  is kept if and only if

$$\begin{aligned} &C_p(x, y) \geq C_p(x-1, y-1) \text{ and } C_p(x, y) \geq C_p(x, y-1) \text{ and} \\ &C_p(x, y) \geq C_p(x+1, y-1) \text{ and } C_p(x, y) \geq C_p(x-1, y) \text{ and} \\ &C_p(x, y) > C_p(x+1, y) \text{ and } C_p(x, y) > C_p(x-1, y+1) \text{ and} \\ &C_p(x, y) > C_p(x, y+1) \text{ and } C_p(x, y) > C_p(x+1, y+1) \end{aligned}$$

See also

<http://www.edwardrosten.com/work/fast.html>

[http://en.wikipedia.org/wiki/Features\\_from\\_accelerated\\_segment\\_test](http://en.wikipedia.org/wiki/Features_from_accelerated_segment_test)

## Functions

- **vx\_node VX\_API\_CALL vxFastCornersNode** (**vx\_graph** graph, **vx\_image** input, **vx\_scalar** strength\_thresh, **vx\_bool** nonmax\_suppression, **vx\_array** corners, **vx\_scalar** num\_corners)  
[Graph] Creates a FAST Corners Node.
- **vx\_status VX\_API\_CALL vxuFastCorners** (**vx\_context** context, **vx\_image** input, **vx\_scalar** strength\_thresh, **vx\_bool** nonmax\_suppression, **vx\_array** corners, **vx\_scalar** num\_corners)  
[Immediate] Computes corners on an image using FAST algorithm and produces the array of feature points.

### 3.25.3 Function Documentation

**vx\_node VX\_API\_CALL vxFastCornersNode** ( **vx\_graph** graph, **vx\_image** input, **vx\_scalar** strength\_thresh, **vx\_bool** nonmax\_suppression, **vx\_array** corners, **vx\_scalar** num\_corners )

[Graph] Creates a FAST Corners Node.

#### Parameters

|     |                    |                                                                                                                                                                                                                                                                               |
|-----|--------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | graph              | The reference to the graph.                                                                                                                                                                                                                                                   |
| in  | input              | The input <b>VX_DF_IMAGE_U8</b> image.                                                                                                                                                                                                                                        |
| in  | strength_thresh    | Threshold on difference between intensity of the central pixel and pixels on Bresenham's circle of radius 3 ( <b>VX_TYPE_FLOAT32</b> scalar), with a value in the range of $0.0 \leq \text{strength\_thresh} < 256.0$ . Any fractional value will be truncated to an integer. |
| in  | nonmax_suppression | If true, non-maximum suppression is applied to detected corners before being placed in the <b>vx_array</b> of <b>VX_TYPE_KEYPOINT</b> objects.                                                                                                                                |
| out | corners            | Output corner <b>vx_array</b> of <b>VX_TYPE_KEYPOINT</b> . The order of the keypoints in this array is implementation dependent.                                                                                                                                              |
| out | num_corners        | [optional] The total number of detected corners in image. Use a <b>VX_TYPE_SIZE</b> scalar.                                                                                                                                                                                   |

#### Returns

**vx\_node**.

#### Return values

|                |                                                                                                                   |
|----------------|-------------------------------------------------------------------------------------------------------------------|
| <b>vx_node</b> | A node reference. Any possible errors preventing a successful creation should be checked using <b>vxGetStatus</b> |
|----------------|-------------------------------------------------------------------------------------------------------------------|

**vx\_status VX\_API\_CALL vxuFastCorners** ( **vx\_context** context, **vx\_image** input, **vx\_scalar** strength\_thresh, **vx\_bool** nonmax\_suppression, **vx\_array** corners, **vx\_scalar** num\_corners )

[Immediate] Computes corners on an image using FAST algorithm and produces the array of feature points.

#### Parameters

|    |                    |                                                                                                                                                                                                                                                                               |
|----|--------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | context            | The reference to the overall context.                                                                                                                                                                                                                                         |
| in | input              | The input <b>VX_DF_IMAGE_U8</b> image.                                                                                                                                                                                                                                        |
| in | strength_thresh    | Threshold on difference between intensity of the central pixel and pixels on Bresenham's circle of radius 3 ( <b>VX_TYPE_FLOAT32</b> scalar), with a value in the range of $0.0 \leq \text{strength\_thresh} < 256.0$ . Any fractional value will be truncated to an integer. |
| in | nonmax_suppression | If true, non-maximum suppression is applied to detected corners before being places in the <b>vx_array</b> of <b>VX_TYPE_KEYPOINT</b> structs.                                                                                                                                |

**Parameters**

|     |                    |                                                                                                                                                    |
|-----|--------------------|----------------------------------------------------------------------------------------------------------------------------------------------------|
| out | <i>corners</i>     | Output corner <a href="#">vx_array</a> of <a href="#">VX_TYPE_KEYPOINT</a> . The order of the keypoints in this array is implementation dependent. |
| out | <i>num_corners</i> | [optional] The total number of detected corners in image. Use a <a href="#">VX_TYPE_SIZE</a> scalar.                                               |

**Returns**

A [vx\\_status\\_e](#) enumeration.

**Return values**

|                            |                                                      |
|----------------------------|------------------------------------------------------|
| <a href="#">VX_SUCCESS</a> | Success                                              |
| *                          | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.26 Gaussian Filter

### 3.26.1 Detailed Description

Computes a Gaussian filter over a window of the input image. The output image dimensions should be the same as the dimensions of the input image.

This filter uses the following convolution matrix:

$$\mathbf{K}_{\text{gaussian}} = \begin{bmatrix} 1 & 2 & 1 \\ 2 & 4 & 2 \\ 1 & 2 & 1 \end{bmatrix} * \frac{1}{16}$$

### Functions

- [vx\\_node VX\\_API\\_CALL vxGaussian3x3Node](#) ([vx\\_graph](#) graph, [vx\\_image](#) input, [vx\\_image](#) output)  
[Graph] Creates a Gaussian Filter Node.
- [vx\\_status VX\\_API\\_CALL vxuGaussian3x3](#) ([vx\\_context](#) context, [vx\\_image](#) input, [vx\\_image](#) output)  
[Immediate] Computes a gaussian filter on the image by a 3x3 window.

### 3.26.2 Function Documentation

**[vx\\_node VX\\_API\\_CALL vxGaussian3x3Node](#) ( [vx\\_graph](#) graph, [vx\\_image](#) input, [vx\\_image](#) output )**

[Graph] Creates a Gaussian Filter Node.

#### Parameters

|     |               |                                                                                                                    |
|-----|---------------|--------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>  | The reference to the graph.                                                                                        |
| in  | <i>input</i>  | The input image in <a href="#">VX_DF_IMAGE_U8</a> format.                                                          |
| out | <i>output</i> | The output image in <a href="#">VX_DF_IMAGE_U8</a> format, which must have the same dimensions as the input image. |

#### Returns

[vx\\_node](#).

#### Return values

|                         |                                                                                                                            |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|
| <a href="#">vx_node</a> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|

**[vx\\_status VX\\_API\\_CALL vxuGaussian3x3](#) ( [vx\\_context](#) context, [vx\\_image](#) input, [vx\\_image](#) output )**

[Immediate] Computes a gaussian filter on the image by a 3x3 window.

#### Parameters

|     |                |                                                            |
|-----|----------------|------------------------------------------------------------|
| in  | <i>context</i> | The reference to the overall context.                      |
| in  | <i>input</i>   | The input image in <a href="#">VX_DF_IMAGE_U8</a> format.  |
| out | <i>output</i>  | The output image in <a href="#">VX_DF_IMAGE_U8</a> format. |

#### Returns

A [vx\\_status\\_e](#) enumeration.



**Return values**

|                         |                                                      |
|-------------------------|------------------------------------------------------|
| <code>VX_SUCCESS</code> | Success                                              |
| *                       | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.27 Non Linear Filter

### 3.27.1 Detailed Description

Computes a non-linear filter over a window of the input image. The output image dimensions should be the same as the dimensions of the input image.

The attribute [VX\\_CONTEXT\\_NONLINEAR\\_MAX\\_DIMENSION](#) enables the user to query the largest nonlinear filter supported by the implementation of `vxNonLinearFilterNode`. The implementation must support all dimensions (height or width, not necessarily the same) up to the value of this attribute. The lowest value that must be supported for this attribute is 9.

### Functions

- [vx\\_node VX\\_API\\_CALL vxNonLinearFilterNode](#) ([vx\\_graph](#) graph, [vx\\_enum](#) function, [vx\\_image](#) input, [vx\\_matrix](#) mask, [vx\\_image](#) output)  
[Graph] Creates a Non-linear Filter Node.
- [vx\\_status VX\\_API\\_CALL vxuNonLinearFilter](#) ([vx\\_context](#) context, [vx\\_enum](#) function, [vx\\_image](#) input, [vx\\_matrix](#) mask, [vx\\_image](#) output)  
[Immediate] Performs Non-linear Filtering.

### 3.27.2 Function Documentation

**[vx\\_node VX\\_API\\_CALL vxNonLinearFilterNode](#) ( [vx\\_graph](#) graph, [vx\\_enum](#) function, [vx\\_image](#) input, [vx\\_matrix](#) mask, [vx\\_image](#) output )**

[Graph] Creates a Non-linear Filter Node.

#### Parameters

|     |          |                                                                                                                                                                                                                           |
|-----|----------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | graph    | The reference to the graph.                                                                                                                                                                                               |
| in  | function | The non-linear filter function. See <a href="#">vx_non_linear_filter_e</a> .                                                                                                                                              |
| in  | input    | The input image in <a href="#">VX_DF_IMAGE_U8</a> format.                                                                                                                                                                 |
| in  | mask     | The mask to be applied to the Non-linear function. <a href="#">VX_MATRIX_ORIGIN</a> attribute is used to place the mask appropriately when computing the resulting image. See <a href="#">vxCreateMatrixFromPattern</a> . |
| out | output   | The output image in <a href="#">VX_DF_IMAGE_U8</a> format, which must have the same dimensions as the input image.                                                                                                        |

#### Returns

[vx\\_node](#).

#### Return values

|                         |                                                                                                                            |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|
| <a href="#">vx_node</a> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|

**[vx\\_status VX\\_API\\_CALL vxuNonLinearFilter](#) ( [vx\\_context](#) context, [vx\\_enum](#) function, [vx\\_image](#) input, [vx\\_matrix](#) mask, [vx\\_image](#) output )**

[Immediate] Performs Non-linear Filtering.

#### Parameters

|    |          |                                                                              |
|----|----------|------------------------------------------------------------------------------|
| in | context  | The reference to the overall context.                                        |
| in | function | The non-linear filter function. See <a href="#">vx_non_linear_filter_e</a> . |

**Parameters**

|     |               |                                                                                                                                                                                                                                                                                  |
|-----|---------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>input</i>  | The input image in <a href="#">VX_DF_IMAGE_U8</a> format.                                                                                                                                                                                                                        |
| in  | <i>mask</i>   | The mask to be applied to the Non-linear function. <a href="#">VX_MATRIX_ORIGIN</a> attribute is used to place the mask appropriately when computing the resulting image. See <a href="#">vxCreateMatrixFromPattern</a> and <a href="#">vxCreateMatrixFromPatternAndOrigin</a> . |
| out | <i>output</i> | The output image in <a href="#">VX_DF_IMAGE_U8</a> format.                                                                                                                                                                                                                       |

**Returns**

A [vx\\_status\\_e](#) enumeration.

**Return values**

|                            |                                                      |
|----------------------------|------------------------------------------------------|
| <a href="#">VX_SUCCESS</a> | Success                                              |
| *                          | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.28 Harris Corners

### 3.28.1 Detailed Description

Computes the Harris Corners of an image.

The Harris Corners are computed with several parameters

$$I = \text{input image} \quad (3.14)$$

$$T_c = \text{corner strength threshold} \quad (3.15)$$

$$r = \text{euclidean radius} \quad (3.16)$$

$$k = \text{sensitivity threshold} \quad (3.17)$$

$$w = \text{window size} \quad (3.18)$$

$$b = \text{block size} \quad (3.19)$$

$$(3.20)$$

The computation to find the corner values or scores can be summarized as:

$$G_x = \text{Sobel}_x(w, I) \quad (3.21)$$

$$G_y = \text{Sobel}_y(w, I) \quad (3.22)$$

$$A = \text{window}_{G_{x,y}}(x - b/2, y - b/2, x + b/2, y + b/2) \quad (3.23)$$

$$\text{trace}(A) = \sum_x^A G_x^2 + \sum_y^A G_y^2 \quad (3.24)$$

$$\det(A) = \sum_x^A G_x^2 \sum_y^A G_y^2 - \left( \sum_x^A (G_x G_y) \right)^2 \quad (3.25)$$

$$M_c(x, y) = \det(A) - k * \text{trace}(A)^2 \quad (3.26)$$

$$V_c(x, y) = \begin{cases} M_c(x, y) & \text{if } M_c(x, y) > T_c \\ 0 & \text{otherwise} \end{cases} \quad (3.27)$$

where  $V_c$  is the thresholded corner value.

The normalized Sobel kernels used for the gradient computation shall be as shown below:

- For gradient size 3:

$$\text{Sobel}_x(\text{Normalized}) = \frac{1}{4 * 255 * b} * \begin{bmatrix} -1 & 0 & 1 \\ -2 & 0 & 2 \\ -1 & 0 & 1 \end{bmatrix}$$

$$\text{Sobel}_y(\text{Normalized}) = \frac{1}{4 * 255 * b} * \text{transpose}(\text{sobel}_x) = \frac{1}{4 * 255 * b} * \begin{bmatrix} -1 & -2 & -1 \\ 0 & 0 & 0 \\ 1 & 2 & 1 \end{bmatrix}$$

- For gradient size 5:

$$\text{Sobel}_x(\text{Normalized}) = \frac{1}{16 * 255 * b} * \begin{bmatrix} -1 & -2 & 0 & 2 & 1 \\ -4 & -8 & 0 & 8 & 4 \\ -6 & -12 & 0 & 12 & 6 \\ -4 & -8 & 0 & 8 & 4 \\ -1 & -2 & 0 & 2 & 1 \end{bmatrix}$$

$$\text{Sobel}_y(\text{Normalized}) = \frac{1}{16 * 255 * b} * \text{transpose}(\text{sobel}_x)$$

- For gradient size 7:

$$\text{Sobel}_x(\text{Normalized}) = \frac{1}{64 * 255 * b} * \begin{bmatrix} -1 & -4 & -5 & 0 & 5 & 4 & 1 \\ -6 & -24 & -30 & 0 & 30 & 24 & 6 \\ -15 & -60 & -75 & 0 & 75 & 60 & 15 \\ -20 & -80 & -100 & 0 & 100 & 80 & 20 \\ -15 & -60 & -75 & 0 & 75 & 60 & 15 \\ -6 & -24 & -30 & 0 & 30 & 24 & 6 \\ -1 & -4 & -5 & 0 & 5 & 4 & 1 \end{bmatrix}$$

$$\text{Sobel}_y(\text{Normalized}) = \frac{1}{64 * 255 * b} * \text{transpose}(\text{sobel}_x)$$

$V_c$  is then non-maximally suppressed, returning the same results as using the following algorithm:

- Filter the features using the non-maximum suppression algorithm defined for `vxFastCornersNode`.
- Create an array of features sorted by  $V_c$  in descending order:  $V_c(j) > V_c(j+1)$ .
- Initialize an empty feature set  $F = \{\}$
- For each feature  $j$  in the sorted array, while  $V_c(j) > T_c$ :
  - If there is no feature  $i$  in  $F$  such that the Euclidean distance between pixels  $i$  and  $j$  is less than  $r$ , add the feature  $j$  to the feature set  $F$ .

An implementation shall support all values of Euclidean distance  $r$  that satisfy:

```
0 <= max_dist <= 30
```

The feature set  $F$  is returned as a `vx_array` of `vx_keypoint_t` structs.

## Functions

- `vx_node VX_API_CALL vxHarrisCornersNode` (`vx_graph` graph, `vx_image` input, `vx_scalar` strength\_thresh, `vx_scalar` min\_distance, `vx_scalar` sensitivity, `vx_int32` gradient\_size, `vx_int32` block\_size, `vx_array` corners, `vx_scalar` num\_corners)

*[Graph] Creates a Harris Corners Node.*

- `vx_status VX_API_CALL vxuHarrisCorners` (`vx_context` context, `vx_image` input, `vx_scalar` strength\_thresh, `vx_scalar` min\_distance, `vx_scalar` sensitivity, `vx_int32` gradient\_size, `vx_int32` block\_size, `vx_array` corners, `vx_scalar` num\_corners)

*[Immediate] Computes the Harris Corners over an image and produces the array of scored points.*

### 3.28.2 Function Documentation

**`vx_node VX_API_CALL vxHarrisCornersNode` ( `vx_graph` graph, `vx_image` input, `vx_scalar` strength\_thresh, `vx_scalar` min\_distance, `vx_scalar` sensitivity, `vx_int32` gradient\_size, `vx_int32` block\_size, `vx_array` corners, `vx_scalar` num\_corners )**

*[Graph] Creates a Harris Corners Node.*

#### Parameters

|     |                        |                                                                                                                                               |
|-----|------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>           | The reference to the graph.                                                                                                                   |
| in  | <i>input</i>           | The input <code>VX_DF_IMAGE_U8</code> image.                                                                                                  |
| in  | <i>strength_thresh</i> | The <code>VX_TYPE_FLOAT32</code> minimum threshold with which to eliminate Harris Corner scores (computed using the normalized Sobel kernel). |
| in  | <i>min_distance</i>    | The <code>VX_TYPE_FLOAT32</code> radial Euclidean distance for non-maximum suppression.                                                       |
| in  | <i>sensitivity</i>     | The <code>VX_TYPE_FLOAT32</code> scalar sensitivity threshold $k$ from the Harris-Stephens equation.                                          |
| in  | <i>gradient_size</i>   | The gradient window size to use on the input. The implementation must support at least 3, 5, and 7.                                           |
| in  | <i>block_size</i>      | The block window size used to compute the Harris Corner score. The implementation must support at least 3, 5, and 7.                          |
| out | <i>corners</i>         | The array of <code>VX_TYPE_KEYPOINT</code> objects. The order of the keypoints in this array is implementation dependent.                     |
| out | <i>num_corners</i>     | [optional] The total number of detected corners in image. Use a <code>VX_TYPE_SIZE</code> scalar.                                             |

## Returns

[vx\\_node](#).

## Return values

|                         |                                                                                                                            |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|
| <a href="#">vx_node</a> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|

**vx\_status** **VX\_API\_CALL** **vxuHarrisCorners** ( **vx\_context** *context*, **vx\_image** *input*, **vx\_scalar** *strength\_thresh*, **vx\_scalar** *min\_distance*, **vx\_scalar** *sensitivity*, **vx\_int32** *gradient\_size*, **vx\_int32** *block\_size*, **vx\_array** *corners*, **vx\_scalar** *num\_corners* )

[Immediate] Computes the Harris Corners over an image and produces the array of scored points.

## Parameters

|     |                        |                                                                                                                                             |
|-----|------------------------|---------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>context</i>         | The reference to the overall context.                                                                                                       |
| in  | <i>input</i>           | The input <a href="#">VX_DF_IMAGE_U8</a> image.                                                                                             |
| in  | <i>strength_thresh</i> | The <a href="#">VX_TYPE_FLOAT32</a> minimum threshold which to eliminate Harris Corner scores (computed using the normalized Sobel kernel). |
| in  | <i>min_distance</i>    | The <a href="#">VX_TYPE_FLOAT32</a> radial Euclidean distance for non-maximum suppression.                                                  |
| in  | <i>sensitivity</i>     | The <a href="#">VX_TYPE_FLOAT32</a> scalar sensitivity threshold $k$ from the Harris-Stephens equation.                                     |
| in  | <i>gradient_size</i>   | The gradient window size to use on the input. The implementation must support at least 3, 5, and 7.                                         |
| in  | <i>block_size</i>      | The block window size used to compute the harris corner score. The implementation must support at least 3, 5, and 7.                        |
| out | <i>corners</i>         | The array of <a href="#">VX_TYPE_KEYPOINT</a> structs. The order of the keypoints in this array is implementation dependent.                |
| out | <i>num_corners</i>     | [optional] The total number of detected corners in image. Use a <a href="#">VX_TYPE_SIZE</a> scalar                                         |

## Returns

A [vx\\_status\\_e](#) enumeration.

## Return values

|                            |                                                      |
|----------------------------|------------------------------------------------------|
| <a href="#">VX_SUCCESS</a> | Success                                              |
| *                          | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.29 Histogram

### 3.29.1 Detailed Description

Generates a distribution from an image.

This kernel counts the number of occurrences of each pixel value within the window size of a pre-calculated number of bins. A pixel with intensity 'I' will result in incrementing histogram bin 'i' where

$$i = (I - offset) * numBins / range \text{ for } I \geq offset$$

and

$$I < offset + range.$$

Pixels with intensities that don't meet these conditions will have no effect on the histogram. Here offset, range and numBins are values of histogram attributes (see [VX\\_DISTRIBUTION\\_OFFSET](#), [VX\\_DISTRIBUTION\\_RANGE](#), [VX\\_DISTRIBUTION\\_BINS](#)).

### Functions

- [vx\\_node VX\\_API\\_CALL vxHistogramNode](#) ([vx\\_graph](#) graph, [vx\\_image](#) input, [vx\\_distribution](#) distribution)  
[Graph] Creates a Histogram node.
- [vx\\_status VX\\_API\\_CALL vxuHistogram](#) ([vx\\_context](#) context, [vx\\_image](#) input, [vx\\_distribution](#) distribution)  
[Immediate] Generates a distribution from an image.

### 3.29.2 Function Documentation

**[vx\\_node VX\\_API\\_CALL vxHistogramNode](#) ( [vx\\_graph](#) graph, [vx\\_image](#) input, [vx\\_distribution](#) distribution )**

[Graph] Creates a Histogram node.

#### Parameters

|     |                     |                                                     |
|-----|---------------------|-----------------------------------------------------|
| in  | <i>graph</i>        | The reference to the graph.                         |
| in  | <i>input</i>        | The input image in <a href="#">VX_DF_IMAGE_U8</a> . |
| out | <i>distribution</i> | The output distribution.                            |

#### Returns

[vx\\_node](#).

#### Return values

|                         |                                                                                                                            |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|
| <a href="#">vx_node</a> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|

**[vx\\_status VX\\_API\\_CALL vxuHistogram](#) ( [vx\\_context](#) context, [vx\\_image](#) input, [vx\\_distribution](#) distribution )**

[Immediate] Generates a distribution from an image.

#### Parameters

|     |                     |                                                   |
|-----|---------------------|---------------------------------------------------|
| in  | <i>context</i>      | The reference to the overall context.             |
| in  | <i>input</i>        | The input image in <a href="#">VX_DF_IMAGE_U8</a> |
| out | <i>distribution</i> | The output distribution.                          |

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                         |                                                   |
|-------------------------|---------------------------------------------------|
| <code>VX_SUCCESS</code> | Success                                           |
| *                       | An error occurred. See <code>vx_status_e</code> . |



## 3.30 Gaussian Image Pyramid

### 3.30.1 Detailed Description

Computes a Gaussian Image Pyramid from an input image.

This vision function creates the Gaussian image pyramid from the input image using the particular 5x5 Gaussian Kernel:

$$\mathbf{G} = \frac{1}{256} * \begin{bmatrix} 1 & 4 & 6 & 4 & 1 \\ 4 & 16 & 24 & 16 & 4 \\ 6 & 24 & 36 & 24 & 6 \\ 4 & 16 & 24 & 16 & 4 \\ 1 & 4 & 6 & 4 & 1 \end{bmatrix}$$

on each level of the pyramid then scales the image to the next level using [VX\\_INTERPOLATION\\_NEAREST\\_NEIGHBOR](#). For the Gaussian pyramid, level 0 shall always have the same resolution and contents as the input image. Pyramids configured with one of the following level scaling must be supported:

- [VX\\_SCALE\\_PYRAMID\\_HALF](#)
- [VX\\_SCALE\\_PYRAMID\\_ORB](#)

### Functions

- [vx\\_node VX\\_API\\_CALL vxGaussianPyramidNode](#) ([vx\\_graph](#) graph, [vx\\_image](#) input, [vx\\_pyramid](#) gaussian)  
[Graph] Creates a node for a Gaussian Image Pyramid.
- [vx\\_status VX\\_API\\_CALL vxuGaussianPyramid](#) ([vx\\_context](#) context, [vx\\_image](#) input, [vx\\_pyramid](#) gaussian)  
[Immediate] Computes a Gaussian pyramid from an input image.

### 3.30.2 Function Documentation

**[vx\\_node VX\\_API\\_CALL vxGaussianPyramidNode](#) ( [vx\\_graph](#) graph, [vx\\_image](#) input, [vx\\_pyramid](#) gaussian )**

[Graph] Creates a node for a Gaussian Image Pyramid.

#### Parameters

|     |                 |                                                                        |
|-----|-----------------|------------------------------------------------------------------------|
| in  | <i>graph</i>    | The reference to the graph.                                            |
| in  | <i>input</i>    | The input image in <a href="#">VX_DF_IMAGE_U8</a> format.              |
| out | <i>gaussian</i> | The Gaussian pyramid with <a href="#">VX_DF_IMAGE_U8</a> to construct. |

See also

[Object: Pyramid](#)

Returns

[vx\\_node](#).

#### Return values

|                         |                                                                                                                            |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|
| <a href="#">vx_node</a> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|

**[vx\\_status VX\\_API\\_CALL vxuGaussianPyramid](#) ( [vx\\_context](#) context, [vx\\_image](#) input, [vx\\_pyramid](#) gaussian )**

[Immediate] Computes a Gaussian pyramid from an input image.

**Parameters**

|     |                 |                                                                        |
|-----|-----------------|------------------------------------------------------------------------|
| in  | <i>context</i>  | The reference to the overall context.                                  |
| in  | <i>input</i>    | The input image in <a href="#">VX_DF_IMAGE_U8</a>                      |
| out | <i>gaussian</i> | The Gaussian pyramid with <a href="#">VX_DF_IMAGE_U8</a> to construct. |

**Returns**

A [vx\\_status\\_e](#) enumeration.

**Return values**

|                   |                                                      |
|-------------------|------------------------------------------------------|
| <i>VX_SUCCESS</i> | Success                                              |
| *                 | An error occurred. See <a href="#">vx_status_e</a> . |

### 3.31 Laplacian Image Pyramid

#### 3.31.1 Detailed Description

Computes a Laplacian Image Pyramid from an input image.

This vision function creates the Laplacian image pyramid from the input image. First, a Gaussian pyramid is created with the scale attribute `VX_SCALE_PYRAMID_HALF` and the number of levels equal to  $N + 1$ , where  $N$  is the number of levels in the laplacian pyramid. The border mode for the Gaussian pyramid calculation should be `VX_BORDER_REPLICATE`. Then, for each  $i = 0..N - 1$ , the Laplacian level  $L_i$  is computed as:

$$L_i = G_i - UpSample(G_{i+1}).$$

Here  $G_i$  is the  $i$ -th level of the Gaussian pyramid.

The  $UpSample(I)$  is computed by injecting even zero rows and columns and then convolves the result with the Gaussian 5x5 filter multiplied by 4.

$$UpSample(I)_{x,y} = 4 \sum_{k=-2}^2 \sum_{l=-2}^2 I'_{x-k,y-l} W_{k+2,l+2}$$

$$I'_{x,y} = \begin{cases} I_{\frac{x}{2},\frac{y}{2}} & \text{if x and y are even} \\ 0 & \text{otherwise} \end{cases}$$

$$\mathbf{W} = \frac{1}{256} * \begin{bmatrix} 1 & 4 & 6 & 4 & 1 \\ 4 & 16 & 24 & 16 & 4 \\ 6 & 24 & 36 & 24 & 6 \\ 4 & 16 & 24 & 16 & 4 \\ 1 & 4 & 6 & 4 & 1 \end{bmatrix}$$

$L_0$  shall always have the same resolution as the input image. The output image is equal to  $G_N$ .

The border mode for the UpSample calculation should be `VX_BORDER_REPLICATE`.

#### Functions

- `vx_node VX_API_CALL vxLaplacianPyramidNode (vx_graph graph, vx_image input, vx_pyramid laplacian, vx_image output)`

*[Graph] Creates a node for a Laplacian Image Pyramid.*

- `vx_status VX_API_CALL vxuLaplacianPyramid (vx_context context, vx_image input, vx_pyramid laplacian, vx_image output)`

*[Immediate] Computes a Laplacian pyramid from an input image.*

#### 3.31.2 Function Documentation

**`vx_node VX_API_CALL vxLaplacianPyramidNode ( vx_graph graph, vx_image input, vx_pyramid laplacian, vx_image output )`**

*[Graph] Creates a node for a Laplacian Image Pyramid.*

##### Parameters

|     |                  |                                                                                                                                                                                                                            |
|-----|------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>     | The reference to the graph.                                                                                                                                                                                                |
| in  | <i>input</i>     | The input image in <code>VX_DF_IMAGE_U8</code> or <code>VX_DF_IMAGE_S16</code> format.                                                                                                                                     |
| out | <i>laplacian</i> | The Laplacian pyramid with <code>VX_DF_IMAGE_S16</code> to construct.                                                                                                                                                      |
| out | <i>output</i>    | The lowest resolution image in <code>VX_DF_IMAGE_U8</code> or <code>VX_DF_IMAGE_S16</code> format necessary to reconstruct the input image from the pyramid. The output image format should be same as input image format. |

See also

[Object: Pyramid](#)

Returns

[vx\\_node](#).

Return values

|                         |                                                                                                                            |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|
| <a href="#">vx_node</a> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|

**vx\_status VX\_API\_CALL vxuLaplacianPyramid ( vx\_context *context*, vx\_image *input*, vx\_pyramid *laplacian*, vx\_image *output* )**

[Immediate] Computes a Laplacian pyramid from an input image.

Parameters

|     |                  |                                                                                                                                                                                                                                  |
|-----|------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>context</i>   | The reference to the overall context.                                                                                                                                                                                            |
| in  | <i>input</i>     | The input image in <a href="#">VX_DF_IMAGE_U8</a> or <a href="#">VX_DF_IMAGE_S16</a> format.                                                                                                                                     |
| out | <i>laplacian</i> | The Laplacian pyramid with <a href="#">VX_DF_IMAGE_S16</a> to construct.                                                                                                                                                         |
| out | <i>output</i>    | The lowest resolution image in <a href="#">VX_DF_IMAGE_U8</a> or <a href="#">VX_DF_IMAGE_S16</a> format necessary to reconstruct the input image from the pyramid. The output image format should be same as input image format. |

See also

[Object: Pyramid](#)

Returns

A [vx\\_status](#) enumeration.

Return values

|                            |                                                    |
|----------------------------|----------------------------------------------------|
| <a href="#">VX_SUCCESS</a> | Success.                                           |
| *                          | An error occurred. See <a href="#">vx_status_e</a> |

## 3.32 Reconstruction from a Laplacian Image Pyramid

### 3.32.1 Detailed Description

Reconstructs the original image from a Laplacian Image Pyramid.

This vision function reconstructs the image of the highest possible resolution from a Laplacian pyramid. The upscaled input image is added to the last level of the Laplacian pyramid  $L_{N-1}$ :

$$I_{N-1} = UpSample(input) + L_{N-1}$$

For the definition of the *UpSample* function please see [vxLaplacianPyramidNode](#) . Correspondingly, for each pyramid level  $i = 0..N - 2$ :

$$I_i = UpSample(I_{i+1}) + L_i$$

Finally, the output image is:

$$output = I_0$$

### Functions

- [vx\\_node VX\\_API\\_CALL vxLaplacianReconstructNode](#) ([vx\\_graph](#) graph, [vx\\_pyramid](#) laplacian, [vx\\_image](#) input, [vx\\_image](#) output)  
[Graph] Reconstructs an image from a Laplacian Image pyramid.
- [vx\\_status VX\\_API\\_CALL vxuLaplacianReconstruct](#) ([vx\\_context](#) context, [vx\\_pyramid](#) laplacian, [vx\\_image](#) input, [vx\\_image](#) output)  
[Immediate] Reconstructs an image from a Laplacian Image pyramid.

### 3.32.2 Function Documentation

**[vx\\_node VX\\_API\\_CALL vxLaplacianReconstructNode](#) ( [vx\\_graph](#) graph, [vx\\_pyramid](#) laplacian, [vx\\_image](#) input, [vx\\_image](#) output )**

[Graph] Reconstructs an image from a Laplacian Image pyramid.

#### Parameters

|     |                  |                                                                                                                                                                                                                                           |
|-----|------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>     | The reference to the graph.                                                                                                                                                                                                               |
| in  | <i>laplacian</i> | The Laplacian pyramid with <a href="#">VX_DF_IMAGE_S16</a> format.                                                                                                                                                                        |
| in  | <i>input</i>     | The lowest resolution image in <a href="#">VX_DF_IMAGE_U8</a> or <a href="#">VX_DF_IMAGE_S16</a> format for the Laplacian pyramid.                                                                                                        |
| out | <i>output</i>    | The output image in <a href="#">VX_DF_IMAGE_U8</a> or <a href="#">VX_DF_IMAGE_S16</a> format with the highest possible resolution reconstructed from the Laplacian pyramid. The output image format should be same as input image format. |

See also

[Object: Pyramid](#)

Returns

[vx\\_node](#).

#### Return values

|   |                            |
|---|----------------------------|
| 0 | Node could not be created. |
| * | Node handle.               |

**vx\_status VX\_API\_CALL vxuLaplacianReconstruct ( vx\_context *context*, vx\_pyramid *laplacian*, vx\_image *input*, vx\_image *output* )**

[Immediate] Reconstructs an image from a Laplacian Image pyramid.

#### Parameters

|     |                  |                                                                                                                                                                                                                                           |
|-----|------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>context</i>   | The reference to the overall context.                                                                                                                                                                                                     |
| in  | <i>laplacian</i> | The Laplacian pyramid with <a href="#">VX_DF_IMAGE_S16</a> format.                                                                                                                                                                        |
| in  | <i>input</i>     | The lowest resolution image in <a href="#">VX_DF_IMAGE_U8</a> or <a href="#">VX_DF_IMAGE_S16</a> format for the Laplacian pyramid.                                                                                                        |
| out | <i>output</i>    | The output image in <a href="#">VX_DF_IMAGE_U8</a> or <a href="#">VX_DF_IMAGE_S16</a> format with the highest possible resolution reconstructed from the Laplacian pyramid. The output image format should be same as input image format. |

See also

[Object: Pyramid](#)

Returns

A [vx\\_status](#) enumeration.

#### Return values

|                            |                                                    |
|----------------------------|----------------------------------------------------|
| <a href="#">VX_SUCCESS</a> | Success.                                           |
| *                          | An error occurred. See <a href="#">vx_status_e</a> |

## 3.33 Integral Image

### 3.33.1 Detailed Description

Computes the integral image of the input. The output image dimensions should be the same as the dimensions of the input image.

Each output pixel is the sum of the corresponding input pixel and all other pixels above and to the left of it.

$$dst(x,y) = sum(x,y)$$

where, for  $x \geq 0$  and  $y \geq 0$

$$sum(x,y) = src(x,y) + sum(x-1,y) + sum(x,y-1) - sum(x-1,y-1)$$

otherwise,

$$sum(x,y) = 0$$

The overflow policy used is [VX\\_CONVERT\\_POLICY\\_WRAP](#).

### Functions

- [vx\\_node VX\\_API\\_CALL vxIntegrallImageNode](#) ([vx\\_graph](#) graph, [vx\\_image](#) input, [vx\\_image](#) output)  
[Graph] Creates an Integral Image Node.
- [vx\\_status VX\\_API\\_CALL vxuIntegrallImage](#) ([vx\\_context](#) context, [vx\\_image](#) input, [vx\\_image](#) output)  
[Immediate] Computes the integral image of the input.

### 3.33.2 Function Documentation

**[vx\\_node VX\\_API\\_CALL vxIntegrallImageNode](#) ( [vx\\_graph](#) graph, [vx\\_image](#) input, [vx\\_image](#) output )**

[Graph] Creates an Integral Image Node.

#### Parameters

|     |               |                                                                                                                     |
|-----|---------------|---------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>  | The reference to the graph.                                                                                         |
| in  | <i>input</i>  | The input image in <a href="#">VX_DF_IMAGE_U8</a> format.                                                           |
| out | <i>output</i> | The output image in <a href="#">VX_DF_IMAGE_U32</a> format, which must have the same dimensions as the input image. |

#### Returns

[vx\\_node](#).

#### Return values

|                         |                                                                                                                            |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|
| <a href="#">vx_node</a> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|

**[vx\\_status VX\\_API\\_CALL vxuIntegrallImage](#) ( [vx\\_context](#) context, [vx\\_image](#) input, [vx\\_image](#) output )**

[Immediate] Computes the integral image of the input.

#### Parameters

|     |                |                                                             |
|-----|----------------|-------------------------------------------------------------|
| in  | <i>context</i> | The reference to the overall context.                       |
| in  | <i>input</i>   | The input image in <a href="#">VX_DF_IMAGE_U8</a> format.   |
| out | <i>output</i>  | The output image in <a href="#">VX_DF_IMAGE_U32</a> format. |

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                         |                                                   |
|-------------------------|---------------------------------------------------|
| <code>VX_SUCCESS</code> | Success                                           |
| *                       | An error occurred. See <code>vx_status_e</code> . |



## 3.34 Magnitude

### 3.34.1 Detailed Description

Implements the Gradient Magnitude Computation Kernel. The output image dimensions should be the same as the dimensions of the input images.

This kernel takes two gradients in [VX\\_DF\\_IMAGE\\_S16](#) format and computes the [VX\\_DF\\_IMAGE\\_S16](#) normalized magnitude. Magnitude is computed as:

$$mag(x,y) = \sqrt{grad_x(x,y)^2 + grad_y(x,y)^2}$$

The conceptual definition describing the overflow is given as:

```
uint16 z = uint16(sqrt(double(uint32(int32(x) * int32(x)) + uint32(int32(y) * int32(y)))) + 0.5);
int16 mag = z > 32767 ? 32767 : z;
```

### Functions

- [vx\\_node VX\\_API\\_CALL vxMagnitudeNode](#) ([vx\\_graph](#) graph, [vx\\_image](#) grad\_x, [vx\\_image](#) grad\_y, [vx\\_image](#) mag)  
*[Graph] Create a Magnitude node.*
- [vx\\_status VX\\_API\\_CALL vxuMagnitude](#) ([vx\\_context](#) context, [vx\\_image](#) grad\_x, [vx\\_image](#) grad\_y, [vx\\_image](#) mag)  
*[Immediate] Invokes an immediate Magnitude.*

### 3.34.2 Function Documentation

[vx\\_node VX\\_API\\_CALL vxMagnitudeNode](#) ( [vx\\_graph](#) graph, [vx\\_image](#) grad\_x, [vx\\_image](#) grad\_y, [vx\\_image](#) mag )

[Graph] Create a Magnitude node.

#### Parameters

|     |                        |                                                                                                                           |
|-----|------------------------|---------------------------------------------------------------------------------------------------------------------------|
| in  | <a href="#">graph</a>  | The reference to the graph.                                                                                               |
| in  | <a href="#">grad_x</a> | The input x image. This must be in <a href="#">VX_DF_IMAGE_S16</a> format.                                                |
| in  | <a href="#">grad_y</a> | The input y image. This must be in <a href="#">VX_DF_IMAGE_S16</a> format.                                                |
| out | <a href="#">mag</a>    | The magnitude image. This is in <a href="#">VX_DF_IMAGE_S16</a> format. Must have the same dimensions as the input image. |

See also

[VX\\_KERNEL\\_MAGNITUDE](#)

Returns

[vx\\_node](#).

#### Return values

|                         |                                                                                                                            |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|
| <a href="#">vx_node</a> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|

**vx\_status VX\_API\_CALL vxuMagnitude ( vx\_context *context*, vx\_image *grad\_x*, vx\_image *grad\_y*, vx\_image *mag* )**

[Immediate] Invokes an immediate Magnitude.

#### Parameters

|     |                |                                                                              |
|-----|----------------|------------------------------------------------------------------------------|
| in  | <i>context</i> | The reference to the overall context.                                        |
| in  | <i>grad_x</i>  | The input x image. This must be in <a href="#">VX_DF_IMAGE_S16</a> format.   |
| in  | <i>grad_y</i>  | The input y image. This must be in <a href="#">VX_DF_IMAGE_S16</a> format.   |
| out | <i>mag</i>     | The magnitude image. This will be in <a href="#">VX_DF_IMAGE_S16</a> format. |

#### Returns

A [vx\\_status\\_e](#) enumeration.

#### Return values

|                            |                                                      |
|----------------------------|------------------------------------------------------|
| <a href="#">VX_SUCCESS</a> | Success                                              |
| *                          | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.35 Mean and Standard Deviation

### 3.35.1 Detailed Description

Computes the mean pixel value and the standard deviation of the pixels in the input image (which has a dimension width and height).

The mean value is computed as:

$$\mu = \frac{\left( \sum_{y=0}^h \sum_{x=0}^w src(x,y) \right)}{(width * height)}$$

The standard deviation is computed as:

$$\sigma = \sqrt{\frac{\left( \sum_{y=0}^h \sum_{x=0}^w (\mu - src(x,y))^2 \right)}{(width * height)}}$$

### Functions

- **`vx_node VX_API_CALL vxMeanStdDevNode`** (`vx_graph` *graph*, `vx_image` *input*, `vx_scalar` *mean*, `vx_scalar` *stddev*)  
[Graph] Creates a mean value and optionally, a standard deviation node.
- **`vx_status VX_API_CALL vxuMeanStdDev`** (`vx_context` *context*, `vx_image` *input*, `vx_float32` \**mean*, `vx_float32` \**stddev*)  
[Immediate] Computes the mean value and optionally the standard deviation.

### 3.35.2 Function Documentation

**`vx_node VX_API_CALL vxMeanStdDevNode`** ( `vx_graph` *graph*, `vx_image` *input*, `vx_scalar` *mean*, `vx_scalar` *stddev* )

[Graph] Creates a mean value and optionally, a standard deviation node.

#### Parameters

|     |               |                                                                                     |
|-----|---------------|-------------------------------------------------------------------------------------|
| in  | <i>graph</i>  | The reference to the graph.                                                         |
| in  | <i>input</i>  | The input image. <code>VX_DF_IMAGE_U8</code> is supported.                          |
| out | <i>mean</i>   | The <code>VX_TYPE_FLOAT32</code> average pixel value.                               |
| out | <i>stddev</i> | [optional] The <code>VX_TYPE_FLOAT32</code> standard deviation of the pixel values. |

#### Returns

`vx_node`.

#### Return values

|                      |                                                                                                                         |
|----------------------|-------------------------------------------------------------------------------------------------------------------------|
| <code>vx_node</code> | A node reference. Any possible errors preventing a successful creation should be checked using <code>vxGetStatus</code> |
|----------------------|-------------------------------------------------------------------------------------------------------------------------|

**`vx_status VX_API_CALL vxuMeanStdDev`** ( `vx_context` *context*, `vx_image` *input*, `vx_float32` \**mean*, `vx_float32` \**stddev* )

[Immediate] Computes the mean value and optionally the standard deviation.

#### Parameters

|    |                |                                       |
|----|----------------|---------------------------------------|
| in | <i>context</i> | The reference to the overall context. |
|----|----------------|---------------------------------------|

**Parameters**

|     |               |                                                               |
|-----|---------------|---------------------------------------------------------------|
| in  | <i>input</i>  | The input image. <a href="#">VX_DF_IMAGE_U8</a> is supported. |
| out | <i>mean</i>   | The average pixel value.                                      |
| out | <i>stddev</i> | [optional] The standard deviation of the pixel values.        |

**Returns**

A [vx\\_status\\_e](#) enumeration.

**Return values**

|                   |                                                      |
|-------------------|------------------------------------------------------|
| <i>VX_SUCCESS</i> | Success                                              |
| *                 | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.36 Median Filter

### 3.36.1 Detailed Description

Computes a median pixel value over a window of the input image. The output image dimensions should be the same as the dimensions of the input image.

The median is the middle value over an odd-numbered, sorted range of values.

Note

For kernels that use other structuring patterns than 3x3 see [vxNonLinearFilterNode](#) or [vxuNonLinearFilter](#).

### Functions

- [vx\\_node VX\\_API\\_CALL vxMedian3x3Node](#) ([vx\\_graph](#) graph, [vx\\_image](#) input, [vx\\_image](#) output)  
[Graph] Creates a Median Image Node.
- [vx\\_status VX\\_API\\_CALL vxuMedian3x3](#) ([vx\\_context](#) context, [vx\\_image](#) input, [vx\\_image](#) output)  
[Immediate] Computes a median filter on the image by a 3x3 window.

### 3.36.2 Function Documentation

**[vx\\_node VX\\_API\\_CALL vxMedian3x3Node](#) ( [vx\\_graph](#) graph, [vx\\_image](#) input, [vx\\_image](#) output )**

[Graph] Creates a Median Image Node.

Parameters

|     |               |                                                                                                                    |
|-----|---------------|--------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>  | The reference to the graph.                                                                                        |
| in  | <i>input</i>  | The input image in <a href="#">VX_DF_IMAGE_U8</a> format.                                                          |
| out | <i>output</i> | The output image in <a href="#">VX_DF_IMAGE_U8</a> format, which must have the same dimensions as the input image. |

Returns

[vx\\_node](#).

Return values

|                         |                                                                                                                            |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|
| <a href="#">vx_node</a> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|

**[vx\\_status VX\\_API\\_CALL vxuMedian3x3](#) ( [vx\\_context](#) context, [vx\\_image](#) input, [vx\\_image](#) output )**

[Immediate] Computes a median filter on the image by a 3x3 window.

Parameters

|     |                |                                                            |
|-----|----------------|------------------------------------------------------------|
| in  | <i>context</i> | The reference to the overall context.                      |
| in  | <i>input</i>   | The input image in <a href="#">VX_DF_IMAGE_U8</a> format.  |
| out | <i>output</i>  | The output image in <a href="#">VX_DF_IMAGE_U8</a> format. |

Returns

A [vx\\_status\\_e](#) enumeration.

**Return values**

|                         |                                                      |
|-------------------------|------------------------------------------------------|
| <code>VX_SUCCESS</code> | Success                                              |
| *                       | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.37 Min, Max Location

### 3.37.1 Detailed Description

Finds the minimum and maximum values in an image and a location for each.

If the input image has several minimums/maximums, the kernel returns all of them.

$$\begin{aligned} \minVal = & \min_{\substack{0 \leq x' \leq width \\ 0 \leq y' \leq height}} src(x', y') \end{aligned}$$

$$\begin{aligned} \maxVal = & \max_{\substack{0 \leq x' \leq width \\ 0 \leq y' \leq height}} src(x', y') \end{aligned}$$

### Functions

- **`vx_node VX_API_CALL vxMinMaxLocNode`** (`vx_graph` graph, `vx_image` input, `vx_scalar` minVal, `vx_scalar` maxVal, `vx_array` minLoc, `vx_array` maxLoc, `vx_scalar` minCount, `vx_scalar` maxCount)  
[Graph] Creates a min,max,loc node.
- **`vx_status VX_API_CALL vxuMinMaxLoc`** (`vx_context` context, `vx_image` input, `vx_scalar` minVal, `vx_scalar` maxVal, `vx_array` minLoc, `vx_array` maxLoc, `vx_scalar` minCount, `vx_scalar` maxCount)  
[Immediate] Computes the minimum and maximum values of the image.

### 3.37.2 Function Documentation

**`vx_node VX_API_CALL vxMinMaxLocNode`** ( `vx_graph` graph, `vx_image` input, `vx_scalar` minVal, `vx_scalar` maxVal, `vx_array` minLoc, `vx_array` maxLoc, `vx_scalar` minCount, `vx_scalar` maxCount )

[Graph] Creates a min,max,loc node.

#### Parameters

|     |                 |                                                                                                                                                                       |
|-----|-----------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>    | The reference to create the graph.                                                                                                                                    |
| in  | <i>input</i>    | The input image in <code>VX_DF_IMAGE_U8</code> or <code>VX_DF_IMAGE_S16</code> format.                                                                                |
| out | <i>minVal</i>   | The minimum value in the image, which corresponds to the type of the input.                                                                                           |
| out | <i>maxVal</i>   | The maximum value in the image, which corresponds to the type of the input.                                                                                           |
| out | <i>minLoc</i>   | [optional] The minimum <code>VX_TYPE_COORDINATES2D</code> locations. If the input image has several minimums, the kernel will return up to the capacity of the array. |
| out | <i>maxLoc</i>   | [optional] The maximum <code>VX_TYPE_COORDINATES2D</code> locations. If the input image has several maximums, the kernel will return up to the capacity of the array. |
| out | <i>minCount</i> | [optional] The total number of detected minimums in image. Use a <code>VX_TYPE_SIZE</code> scalar.                                                                    |
| out | <i>maxCount</i> | [optional] The total number of detected maximums in image. Use a <code>VX_TYPE_SIZE</code> scalar.                                                                    |

#### Returns

`vx_node`.

#### Return values

|                      |                                                                                                                         |
|----------------------|-------------------------------------------------------------------------------------------------------------------------|
| <code>vx_node</code> | A node reference. Any possible errors preventing a successful creation should be checked using <code>vxGetStatus</code> |
|----------------------|-------------------------------------------------------------------------------------------------------------------------|

**vx\_status VX\_API\_CALL vxuMinMaxLoc ( vx\_context context, vx\_image input, vx\_scalar minVal, vx\_scalar maxVal, vx\_array minLoc, vx\_array maxLoc, vx\_scalar minCount, vx\_scalar maxCount )**

[Immediate] Computes the minimum and maximum values of the image.

#### Parameters

|     |                 |                                                                                                                                                                          |
|-----|-----------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>context</i>  | The reference to the overall context.                                                                                                                                    |
| in  | <i>input</i>    | The input image in <a href="#">VX_DF_IMAGE_U8</a> or <a href="#">VX_DF_IMAGE_S16</a> format.                                                                             |
| out | <i>minVal</i>   | The minimum value in the image, which corresponds to the type of the input.                                                                                              |
| out | <i>maxVal</i>   | The maximum value in the image, which corresponds to the type of the input.                                                                                              |
| out | <i>minLoc</i>   | [optional] The minimum <a href="#">VX_TYPE_COORDINATES2D</a> locations. If the input image has several minimums, the kernel will return up to the capacity of the array. |
| out | <i>maxLoc</i>   | [optional] The maximum <a href="#">VX_TYPE_COORDINATES2D</a> locations. If the input image has several maximums, the kernel will return up to the capacity of the array. |
| out | <i>minCount</i> | [optional] The total number of detected minimums in image. Use a <a href="#">VX_TYPE_SIZE</a> scalar.                                                                    |
| out | <i>maxCount</i> | [optional] The total number of detected maximums in image. Use a <a href="#">VX_TYPE_SIZE</a> scalar.                                                                    |

#### Returns

A [vx\\_status\\_e](#) enumeration.

#### Return values

|                            |                                                      |
|----------------------------|------------------------------------------------------|
| <a href="#">VX_SUCCESS</a> | Success                                              |
| *                          | An error occurred. See <a href="#">vx_status_e</a> . |



## 3.38 Min

### 3.38.1 Detailed Description

Implements a pixel-wise minimum kernel. The output image dimensions should be the same as the dimensions of the input image.

Performing a pixel-wise minimum on a `VX_DF_IMAGE_U8` or `VX_DF_IMAGE_S16` images. All data types of the input and output images must match.

$$out[i, j] = (in1[i, j] < in2[i, j]) ? in1[i, j] : in2[i, j].$$

### Functions

- `vx_node VX_API_CALL vxMinNode (vx_graph graph, vx_image in1, vx_image in2, vx_image out)`  
[Graph] Creates a pixel-wise minimum kernel.
- `vx_status VX_API_CALL vxuMin (vx_context context, vx_image in1, vx_image in2, vx_image out)`  
[Immediate] Computes pixel-wise minimum values between two images.

### 3.38.2 Function Documentation

**`vx_node VX_API_CALL vxMinNode ( vx_graph graph, vx_image in1, vx_image in2, vx_image out )`**

[Graph] Creates a pixel-wise minimum kernel.

#### Parameters

|     |              |                                                                                                                    |
|-----|--------------|--------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i> | The reference to the graph where to create the node.                                                               |
| in  | <i>in1</i>   | The first input image. Must be of type <code>VX_DF_IMAGE_U8</code> or <code>VX_DF_IMAGE_S16</code> .               |
| in  | <i>in2</i>   | The second input image. Must be of type <code>VX_DF_IMAGE_U8</code> or <code>VX_DF_IMAGE_S16</code> .              |
| out | <i>out</i>   | The output image which will hold the result of min and will have the same type and dimensions of the input images. |

#### Returns

`vx_node`.

#### Return values

|                      |                                                                                                                         |
|----------------------|-------------------------------------------------------------------------------------------------------------------------|
| <code>vx_node</code> | A node reference. Any possible errors preventing a successful creation should be checked using <code>vxGetStatus</code> |
|----------------------|-------------------------------------------------------------------------------------------------------------------------|

**`vx_status VX_API_CALL vxuMin ( vx_context context, vx_image in1, vx_image in2, vx_image out )`**

[Immediate] Computes pixel-wise minimum values between two images.

#### Parameters

|     |                |                                                                                                       |
|-----|----------------|-------------------------------------------------------------------------------------------------------|
| in  | <i>context</i> | The reference to the overall context.                                                                 |
| in  | <i>in1</i>     | The first input image. Must be of type <code>VX_DF_IMAGE_U8</code> or <code>VX_DF_IMAGE_S16</code> .  |
| in  | <i>in2</i>     | The second input image. Must be of type <code>VX_DF_IMAGE_U8</code> or <code>VX_DF_IMAGE_S16</code> . |
| out | <i>out</i>     | The output image which will hold the result of min.                                                   |

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                         |                                                   |
|-------------------------|---------------------------------------------------|
| <code>VX_SUCCESS</code> | Success                                           |
| *                       | An error occurred. See <code>vx_status_e</code> . |

## 3.39 Max

### 3.39.1 Detailed Description

Implements a pixel-wise maximum kernel. The output image dimensions should be the same as the dimensions of the input image.

Performing a pixel-wise maximum on a [VX\\_DF\\_IMAGE\\_U8](#) images or [VX\\_DF\\_IMAGE\\_S16](#). All data types of the input and output images must match.

$$out[i, j] = out[i, j] = (in1[i, j] > in2[i, j] ? in1[i, j] : in2[i, j]).$$

### Functions

- [vx\\_node VX\\_API\\_CALL vxMaxNode](#) ([vx\\_graph](#) graph, [vx\\_image](#) in1, [vx\\_image](#) in2, [vx\\_image](#) out)  
[Graph] Creates a pixel-wise maximum kernel.
- [vx\\_status VX\\_API\\_CALL vxuMax](#) ([vx\\_context](#) context, [vx\\_image](#) in1, [vx\\_image](#) in2, [vx\\_image](#) out)  
[Immediate] Computes pixel-wise maximum values between two images.

### 3.39.2 Function Documentation

**[vx\\_node VX\\_API\\_CALL vxMaxNode](#) ( [vx\\_graph](#) graph, [vx\\_image](#) in1, [vx\\_image](#) in2, [vx\\_image](#) out )**

[Graph] Creates a pixel-wise maximum kernel.

#### Parameters

|     |       |                                                                                                                    |
|-----|-------|--------------------------------------------------------------------------------------------------------------------|
| in  | graph | The reference to the graph where to create the node.                                                               |
| in  | in1   | The first input image. Must be of type <a href="#">VX_DF_IMAGE_U8</a> or <a href="#">VX_DF_IMAGE_S16</a> .         |
| in  | in2   | The second input image. Must be of type <a href="#">VX_DF_IMAGE_U8</a> or <a href="#">VX_DF_IMAGE_S16</a> .        |
| out | out   | The output image which will hold the result of max and will have the same type and dimensions of the input images. |

#### Returns

[vx\\_node](#).

#### Return values

|                         |                                                                                                                            |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|
| <a href="#">vx_node</a> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|

**[vx\\_status VX\\_API\\_CALL vxuMax](#) ( [vx\\_context](#) context, [vx\\_image](#) in1, [vx\\_image](#) in2, [vx\\_image](#) out )**

[Immediate] Computes pixel-wise maximum values between two images.

#### Parameters

|     |         |                                                                                                             |
|-----|---------|-------------------------------------------------------------------------------------------------------------|
| in  | context | The reference to the overall context.                                                                       |
| in  | in1     | The first input image. Must be of type <a href="#">VX_DF_IMAGE_U8</a> or <a href="#">VX_DF_IMAGE_S16</a> .  |
| in  | in2     | The second input image. Must be of type <a href="#">VX_DF_IMAGE_U8</a> or <a href="#">VX_DF_IMAGE_S16</a> . |
| out | out     | The output image which will hold the result of max.                                                         |

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                         |                                                   |
|-------------------------|---------------------------------------------------|
| <code>VX_SUCCESS</code> | Success                                           |
| *                       | An error occurred. See <code>vx_status_e</code> . |

## 3.40 Optical Flow Pyramid (LK)

### 3.40.1 Detailed Description

Computes the optical flow using the Lucas-Kanade method between two pyramid images.

The function is an implementation of the algorithm described in [?]. The function inputs are two `vx_pyramid` objects, old and new, along with a `vx_array` of `vx_keypoint_t` structs to track from the old `vx_pyramid`. Both pyramids old and new pyramids must have the same dimensionality. `VX_SCALE_PYRAMID_HALF` pyramidal scaling must be supported.

The function outputs a `vx_array` of `vx_keypoint_t` structs that were tracked from the old `vx_pyramid` to the new `vx_pyramid`. Each element in the `vx_array` of `vx_keypoint_t` structs in the new array may be valid or not. The implementation shall return the same number of `vx_keypoint_t` structs in the new `vx_array` that were in the older `vx_array`.

In more detail: The Lucas-Kanade method finds the affine motion vector  $V$  for each point in the old image tracking points array, using the following equation:

$$\begin{bmatrix} V_x \\ V_y \end{bmatrix} = \begin{bmatrix} \sum_i I_x^2 & \sum_i I_x * I_y \\ \sum_i I_x * I_y & \sum_i I_y^2 \end{bmatrix}^{-1} \begin{bmatrix} -\sum_i I_x * I_t \\ -\sum_i I_y * I_t \end{bmatrix}$$

Where  $I_x$  and  $I_y$  are obtained using the Scharr gradients on the input image:

$$G_x = \begin{bmatrix} +3 & 0 & -3 \\ +10 & 0 & -10 \\ +3 & 0 & -3 \end{bmatrix}$$

$$G_y = \begin{bmatrix} +3 & +10 & +3 \\ 0 & 0 & 0 \\ -3 & -10 & -3 \end{bmatrix}$$

$I_t$  is obtained by a simple difference between the same pixel in both images.  $I$  is defined as the adjacent pixels to the point  $p(x,y)$  under consideration. With a given window size of  $M$ ,  $I$  is  $M^2$  points. The pixel  $p(x,y)$  is centered in the window. In practice, to get an accurate solution, it is necessary to iterate multiple times on this scheme (in a Newton-Raphson fashion) until:

- the residual of the affine motion vector is smaller than a threshold
- And/or maximum number of iteration achieved. Each iteration, the estimation of the previous iteration is used by changing  $I_t$  to be the difference between the old image and the pixel with the estimated coordinates in the new image. Each iteration the function checks if the pixel to track was lost. The criteria for lost tracking is that the matrix above is invertible. (The determinant of the matrix is less than a threshold :  $10^{-7}$ .) Or the minimum eigenvalue of the matrix is smaller then a threshold (  $10^{-4}$  ). Also lost tracking happens when the point tracked coordinate is outside the image coordinates. When `vx_true_e` is given as the input to `use_initial_estimates`, the algorithm starts by calculating  $I_t$  as the difference between the old image and the pixel with the initial estimated coordinates in the new image. The input `vx_array` of `vx_keypoint_t` structs with `tracking_status` set to zero (lost) are copied to the new `vx_array`.

Clients are responsible for editing the output `vx_array` of `vx_keypoint_t` structs array before applying it as the input `vx_array` of `vx_keypoint_t` structs for the next frame. For example, `vx_keypoint_t` structs with `tracking_status` set to zero may be removed by a client for efficiency.

This function changes just the `x`, `y`, and `tracking_status` members of the `vx_keypoint_t` structure and behaves as if it copied the rest from the old tracking `vx_keypoint_t` to new image `vx_keypoint_t`.

## Functions

- `vx_node VX_API_CALL vxOpticalFlowPyrLKNode` (`vx_graph` graph, `vx_pyramid` old\_images, `vx_pyramid` new\_images, `vx_array` old\_points, `vx_array` new\_points\_estimates, `vx_array` new\_points, `vx_enum` termination, `vx_scalar` epsilon, `vx_scalar` num\_iterations, `vx_scalar` use\_initial\_estimate, `vx_size` window\_dimension)

[Graph] Creates a Lucas Kanade Tracking Node.

- `vx_status VX_API_CALL vxuOpticalFlowPyrLK` (`vx_context` context, `vx_pyramid` old\_images, `vx_pyramid` new\_images, `vx_array` old\_points, `vx_array` new\_points\_estimates, `vx_array` new\_points, `vx_enum` termination, `vx_scalar` epsilon, `vx_scalar` num\_iterations, `vx_scalar` use\_initial\_estimate, `vx_size` window\_dimension)

[Immediate] Computes an optical flow on two images.

### 3.40.2 Function Documentation

**vx\_node VX\_API\_CALL vxOpticalFlowPyrLKNode ( vx\_graph graph, vx\_pyramid old\_images, vx\_pyramid new\_images, vx\_array old\_points, vx\_array new\_points\_estimates, vx\_array new\_points, vx\_enum termination, vx\_scalar epsilon, vx\_scalar num\_iterations, vx\_scalar use\_initial\_estimate, vx\_size window\_dimension )**

[Graph] Creates a Lucas Kanade Tracking Node.

#### Parameters

|     |                             |                                                                                                                                                                                                           |
|-----|-----------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>                | The reference to the graph.                                                                                                                                                                               |
| in  | <i>old_images</i>           | Input of first (old) image pyramid in <a href="#">VX_DF_IMAGE_U8</a> .                                                                                                                                    |
| in  | <i>new_images</i>           | Input of destination (new) image pyramid <a href="#">VX_DF_IMAGE_U8</a> .                                                                                                                                 |
| in  | <i>old_points</i>           | An array of key points in a <a href="#">vx_array</a> of <a href="#">VX_TYPE_KEYPOINT</a> ; those key points are defined at the <i>old_images</i> high resolution pyramid.                                 |
| in  | <i>new_points_estimates</i> | An array of estimation on what is the output key points in a <a href="#">vx_array</a> of <a href="#">VX_TYPE_KEYPOINT</a> ; those keypoints are defined at the <i>new_images</i> high resolution pyramid. |
| out | <i>new_points</i>           | An output array of key points in a <a href="#">vx_array</a> of <a href="#">VX_TYPE_KEYPOINT</a> ; those key points are defined at the <i>new_images</i> high resolution pyramid.                          |
| in  | <i>termination</i>          | The termination can be <a href="#">VX_TERM_CRITERIA_ITERATIONS</a> or <a href="#">VX_TERM_CRITERIA_EPSILON</a> or <a href="#">VX_TERM_CRITERIA_BOTH</a> .                                                 |
| in  | <i>epsilon</i>              | The <a href="#">vx_float32</a> error for terminating the algorithm.                                                                                                                                       |
| in  | <i>num_iterations</i>       | The number of iterations. Use a <a href="#">VX_TYPE_UINT32</a> scalar.                                                                                                                                    |
| in  | <i>use_initial_estimate</i> | Use a <a href="#">VX_TYPE_BOOL</a> scalar.                                                                                                                                                                |
| in  | <i>window_dimension</i>     | The size of the window on which to perform the algorithm. See <a href="#">VX_CONTEXT_OPTICAL_FLOW_MAX_WINDOW_DIMENSION</a>                                                                                |

#### Returns

[vx\\_node](#).

#### Return values

|                |                                                                                                                            |
|----------------|----------------------------------------------------------------------------------------------------------------------------|
| <i>vx_node</i> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|----------------|----------------------------------------------------------------------------------------------------------------------------|

**vx\_status VX\_API\_CALL vxuOpticalFlowPyrLK ( vx\_context context, vx\_pyramid old\_images, vx\_pyramid new\_images, vx\_array old\_points, vx\_array new\_points\_estimates, vx\_array new\_points, vx\_enum termination, vx\_scalar epsilon, vx\_scalar num\_iterations, vx\_scalar use\_initial\_estimate, vx\_size window\_dimension )**

[Immediate] Computes an optical flow on two images.

#### Parameters

|    |                             |                                                                                                                                                                                                        |
|----|-----------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>context</i>              | The reference to the overall context.                                                                                                                                                                  |
| in | <i>old_images</i>           | Input of first (old) image pyramid in <a href="#">VX_DF_IMAGE_U8</a> .                                                                                                                                 |
| in | <i>new_images</i>           | Input of destination (new) image pyramid in <a href="#">VX_DF_IMAGE_U8</a>                                                                                                                             |
| in | <i>old_points</i>           | an array of key points in a <a href="#">vx_array</a> of <a href="#">VX_TYPE_KEYPOINT</a> those key points are defined at the <i>old_images</i> high resolution pyramid                                 |
| in | <i>new_points_estimates</i> | an array of estimation on what is the output key points in a <a href="#">vx_array</a> of <a href="#">VX_TYPE_KEYPOINT</a> those keypoints are defined at the <i>new_images</i> high resolution pyramid |

**Parameters**

|     |                             |                                                                                                                                                                  |
|-----|-----------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| out | <i>new_points</i>           | an output array of key points in a <code>vx_array</code> of <code>VX_TYPE_KEYPOINT</code> those key points are defined at the new_images high resolution pyramid |
| in  | <i>termination</i>          | termination can be <code>VX_TERM_CRITERIA_ITERATIONS</code> or <code>VX_TERM_CRITERIA_EPSILON</code> or <code>VX_TERM_CRITERIA_BOTH</code>                       |
| in  | <i>epsilon</i>              | is the <code>vx_float32</code> error for terminating the algorithm                                                                                               |
| in  | <i>num_iterations</i>       | is the number of iterations. Use a <code>VX_TYPE_UINT32</code> scalar.                                                                                           |
| in  | <i>use_initial_estimate</i> | Can be set to either <code>vx_false_e</code> or <code>vx_true_e</code> .                                                                                         |
| in  | <i>window_dimension</i>     | The size of the window on which to perform the algorithm. See <code>VX_CONTEXT_OPTICAL_FLOW_MAX_WINDOW_DIMENSION</code>                                          |

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                         |                                                   |
|-------------------------|---------------------------------------------------|
| <code>VX_SUCCESS</code> | Success                                           |
| *                       | An error occurred. See <code>vx_status_e</code> . |

## 3.41 Phase

### 3.41.1 Detailed Description

Implements the Gradient Phase Computation Kernel. The output image dimensions should be the same as the dimensions of the input images.

This kernel takes two gradients in [VX\\_DF\\_IMAGE\\_S16](#) format and computes the angles for each pixel and stores this in a [VX\\_DF\\_IMAGE\\_U8](#) image.

$$\phi = \tan^{-1} \frac{\text{grad}_y(x,y)}{\text{grad}_x(x,y)}$$

Where  $\phi$  is then translated to  $0 \leq \phi < 2\pi$ . Each  $\phi$  value is then mapped to the range 0 to 255 inclusive.

### Functions

- [vx\\_node VX\\_API\\_CALL vxPhaseNode](#) ([vx\\_graph](#) graph, [vx\\_image](#) grad\_x, [vx\\_image](#) grad\_y, [vx\\_image](#) orientation)  
[Graph] Creates a Phase node.
- [vx\\_status VX\\_API\\_CALL vxuPhase](#) ([vx\\_context](#) context, [vx\\_image](#) grad\_x, [vx\\_image](#) grad\_y, [vx\\_image](#) orientation)  
[Immediate] Invokes an immediate Phase.

### 3.41.2 Function Documentation

**[vx\\_node VX\\_API\\_CALL vxPhaseNode](#) ( [vx\\_graph](#) graph, [vx\\_image](#) grad\_x, [vx\\_image](#) grad\_y, [vx\\_image](#) orientation )**

[Graph] Creates a Phase node.

#### Parameters

|     |                    |                                                                                                                           |
|-----|--------------------|---------------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>       | The reference to the graph.                                                                                               |
| in  | <i>grad_x</i>      | The input x image. This must be in <a href="#">VX_DF_IMAGE_S16</a> format.                                                |
| in  | <i>grad_y</i>      | The input y image. This must be in <a href="#">VX_DF_IMAGE_S16</a> format.                                                |
| out | <i>orientation</i> | The phase image. This is in <a href="#">VX_DF_IMAGE_U8</a> format, and must have the same dimensions as the input images. |

See also

[VX\\_KERNEL\\_PHASE](#)

Returns

[vx\\_node](#).

#### Return values

|                         |                                                                                                                            |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|
| <a href="#">vx_node</a> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|

**[vx\\_status VX\\_API\\_CALL vxuPhase](#) ( [vx\\_context](#) context, [vx\\_image](#) grad\_x, [vx\\_image](#) grad\_y, [vx\\_image](#) orientation )**

[Immediate] Invokes an immediate Phase.



**Parameters**

|     |                    |                                                                            |
|-----|--------------------|----------------------------------------------------------------------------|
| in  | <i>context</i>     | The reference to the overall context.                                      |
| in  | <i>grad_x</i>      | The input x image. This must be in <a href="#">VX_DF_IMAGE_S16</a> format. |
| in  | <i>grad_y</i>      | The input y image. This must be in <a href="#">VX_DF_IMAGE_S16</a> format. |
| out | <i>orientation</i> | The phase image. This will be in <a href="#">VX_DF_IMAGE_U8</a> format.    |

**Returns**

A [vx\\_status\\_e](#) enumeration.

**Return values**

|                            |                                                      |
|----------------------------|------------------------------------------------------|
| <a href="#">VX_SUCCESS</a> | Success                                              |
| *                          | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.42 Pixel-wise Multiplication

### 3.42.1 Detailed Description

Performs element-wise multiplication between two images and a scalar value. The output image dimensions should be the same as the dimensions of the input images.

Pixel-wise multiplication is performed between the pixel values in two `VX_DF_IMAGE_U8` or `VX_DF_IMAGE_S16` images and a scalar floating-point number *scale*. The output image can be `VX_DF_IMAGE_U8` only if both source images are `VX_DF_IMAGE_U8` and the output image is explicitly set to `VX_DF_IMAGE_U8`. It is otherwise `VX_DF_IMAGE_S16`. If one of the input images is of type `VX_DF_IMAGE_S16`, all values are converted to `VX_DF_IMAGE_S16`.

The scale with a value of  $1/2^n$ , where  $n$  is an integer and  $0 \leq n \leq 15$ , and 1/255 (0x1.010102p-8 C99 float hex) must be supported. The support for other values of scale is not prohibited. Furthermore, for scale with a value of 1/255 the rounding policy of `VX_ROUND_POLICY_TO_NEAREST_EVEN` must be supported whereas for the scale with value of  $1/2^n$  the rounding policy of `VX_ROUND_POLICY_TO_ZERO` must be supported. The support of other rounding modes for any values of scale is not prohibited.

The rounding policy `VX_ROUND_POLICY_TO_ZERO` for this function is defined as:

$$reference(x,y,scale) = truncate(((int32_t)in_1(x,y)) * ((int32_t)in_2(x,y)) * (double)scale)$$

The rounding policy `VX_ROUND_POLICY_TO_NEAREST_EVEN` for this function is defined as:

$$reference(x,y,scale) = round\_to\_nearest\_even(((int32_t)in_1(x,y)) * ((int32_t)in_2(x,y)) * (double)scale)$$

The overflow handling is controlled by an overflow-policy parameter. For each pixel value in the two input images:

$$out(x,y) = in_1(x,y) * in_2(x,y) * scale$$

### Functions

- `vx_node VX_API_CALL vxMultiplyNode (vx_graph graph, vx_image in1, vx_image in2, vx_scalar scale, vx_enum overflow_policy, vx_enum rounding_policy, vx_image out)`  
[Graph] Creates an pixelwise-multiplication node.
- `vx_status VX_API_CALL vxuMultiply (vx_context context, vx_image in1, vx_image in2, vx_float32 scale, vx_enum overflow_policy, vx_enum rounding_policy, vx_image out)`  
[Immediate] Performs elementwise multiplications on pixel values in the input images and a scale.

### 3.42.2 Function Documentation

**`vx_node VX_API_CALL vxMultiplyNode ( vx_graph graph, vx_image in1, vx_image in2, vx_scalar scale, vx_enum overflow_policy, vx_enum rounding_policy, vx_image out )`**

[Graph] Creates an pixelwise-multiplication node.

#### Parameters

|     |                        |                                                                                                                                                    |
|-----|------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>           | The reference to the graph.                                                                                                                        |
| in  | <i>in1</i>             | An input image, <code>VX_DF_IMAGE_U8</code> or <code>VX_DF_IMAGE_S16</code> .                                                                      |
| in  | <i>in2</i>             | An input image, <code>VX_DF_IMAGE_U8</code> or <code>VX_DF_IMAGE_S16</code> .                                                                      |
| in  | <i>scale</i>           | A non-negative <code>VX_TYPE_FLOAT32</code> multiplied to each product before overflow handling.                                                   |
| in  | <i>overflow_policy</i> | A <code>VX_TYPE_ENUM</code> of the <code>vx_convert_policy_e</code> enumeration.                                                                   |
| in  | <i>rounding_policy</i> | A <code>VX_TYPE_ENUM</code> of the <code>vx_round_policy_e</code> enumeration.                                                                     |
| out | <i>out</i>             | The output image, a <code>VX_DF_IMAGE_U8</code> or <code>VX_DF_IMAGE_S16</code> image. Must have the same type and dimensions of the input images. |

## Returns

[vx\\_node](#).

## Return values

|                         |                                                                                                                            |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|
| <a href="#">vx_node</a> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|

**vx\_status VX\_API\_CALL vxuMultiply ( vx\_context context, vx\_image in1, vx\_image in2, vx\_float32 scale, vx\_enum overflow\_policy, vx\_enum rounding\_policy, vx\_image out )**

[Immediate] Performs elementwise multiplications on pixel values in the input images and a scale.

## Parameters

|     |                        |                                                                                                     |
|-----|------------------------|-----------------------------------------------------------------------------------------------------|
| in  | <i>context</i>         | The reference to the overall context.                                                               |
| in  | <i>in1</i>             | A <a href="#">VX_DF_IMAGE_U8</a> or <a href="#">VX_DF_IMAGE_S16</a> input image.                    |
| in  | <i>in2</i>             | A <a href="#">VX_DF_IMAGE_U8</a> or <a href="#">VX_DF_IMAGE_S16</a> input image.                    |
| in  | <i>scale</i>           | A non-negative <a href="#">VX_TYPE_FLOAT32</a> multiplied to each product before overflow handling. |
| in  | <i>overflow_policy</i> | A <a href="#">vx_convert_policy_e</a> enumeration.                                                  |
| in  | <i>rounding_policy</i> | A <a href="#">vx_round_policy_e</a> enumeration.                                                    |
| out | <i>out</i>             | The output image in <a href="#">VX_DF_IMAGE_U8</a> or <a href="#">VX_DF_IMAGE_S16</a> format.       |

## Returns

A [vx\\_status\\_e](#) enumeration.

## Return values

|                            |                                                      |
|----------------------------|------------------------------------------------------|
| <a href="#">VX_SUCCESS</a> | Success                                              |
| *                          | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.43 Remap

### 3.43.1 Detailed Description

Maps output pixels in an image from input pixels in an image.

Remap takes a remap table object [vx\\_remap](#) to map a set of output pixels back to source input pixels. A remap is typically defined as:

$$output(x,y) = input(mapx(x,y),mapy(x,y));$$

for every (x,y) in the destination image

However, the mapping functions are contained in the [vx\\_remap](#) object.

### Functions

- [vx\\_node VX\\_API\\_CALL vxRemapNode](#) ([vx\\_graph](#) graph, [vx\\_image](#) input, [vx\\_remap](#) table, [vx\\_enum](#) policy, [vx\\_image](#) output)  
*[Graph] Creates a Remap Node.*
- [vx\\_status VX\\_API\\_CALL vxuRemap](#) ([vx\\_context](#) context, [vx\\_image](#) input, [vx\\_remap](#) table, [vx\\_enum](#) policy, [vx\\_image](#) output)  
*[Immediate] Remaps an output image from an input image.*

### 3.43.2 Function Documentation

**[vx\\_node VX\\_API\\_CALL vxRemapNode](#) ( [vx\\_graph](#) graph, [vx\\_image](#) input, [vx\\_remap](#) table, [vx\\_enum](#) policy, [vx\\_image](#) output )**

[Graph] Creates a Remap Node.

#### Parameters

|     |               |                                                                                                                              |
|-----|---------------|------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>  | The reference to the graph that will contain the node.                                                                       |
| in  | <i>input</i>  | The input <a href="#">VX_DF_IMAGE_U8</a> image.                                                                              |
| in  | <i>table</i>  | The remap table object.                                                                                                      |
| in  | <i>policy</i> | An interpolation type from <a href="#">vx_interpolation_type_e</a> . <a href="#">VX_INTERPOLATION_AREA</a> is not supported. |
| out | <i>output</i> | The output <a href="#">VX_DF_IMAGE_U8</a> image with the same dimensions as the input image.                                 |

#### Note

The border modes [VX\\_NODE\\_BORDER](#) value [VX\\_BORDER\\_UNDEFINED](#) and [VX\\_BORDER\\_CONSTANT](#) are supported.

#### Returns

A [vx\\_node](#).

#### Return values

|                         |                                                                                                                            |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|
| <a href="#">vx_node</a> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|

**[vx\\_status VX\\_API\\_CALL vxuRemap](#) ( [vx\\_context](#) context, [vx\\_image](#) input, [vx\\_remap](#) table, [vx\\_enum](#) policy, [vx\\_image](#) output )**

[Immediate] Remaps an output image from an input image.

**Parameters**

|     |                |                                                                                                                                 |
|-----|----------------|---------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>context</i> | The reference to the overall context.                                                                                           |
| in  | <i>input</i>   | The input <a href="#">VX_DF_IMAGE_U8</a> image.                                                                                 |
| in  | <i>table</i>   | The remap table object.                                                                                                         |
| in  | <i>policy</i>  | The interpolation policy from <a href="#">vx_interpolation_type_e</a> . <a href="#">VX_INTERPOLATION_AREA</a> is not supported. |
| out | <i>output</i>  | The output <a href="#">VX_DF_IMAGE_U8</a> image.                                                                                |

**Returns**

A [vx\\_status\\_e](#) enumeration.

## 3.44 Scale Image

### 3.44.1 Detailed Description

Implements the Image Resizing Kernel.

This kernel resizes an image from the source to the destination dimensions. The supported interpolation types are currently:

- `VX_INTERPOLATION_NEAREST_NEIGHBOR`
- `VX_INTERPOLATION_AREA`
- `VX_INTERPOLATION_BILINEAR`

The sample positions used to determine output pixel values are generated by scaling the outside edges of the source image pixels to the outside edges of the destination image pixels. As described in the documentation for `vx_interpolation_type_e`, samples are taken at pixel centers. This means that, unless the scale is 1:1, the sample position for the top left destination pixel typically does not fall exactly on the top left source pixel but will be generated by interpolation.

That is, the sample positions corresponding in source and destination are defined by the following equations:

$$x_{input} = \left( (x_{output} + 0.5) * \frac{width_{input}}{width_{output}} \right) - 0.5$$

$$y_{input} = \left( (y_{output} + 0.5) * \frac{height_{input}}{height_{output}} \right) - 0.5$$

$$x_{output} = \left( (x_{input} + 0.5) * \frac{width_{output}}{width_{input}} \right) - 0.5$$

$$y_{output} = \left( (y_{input} + 0.5) * \frac{height_{output}}{height_{input}} \right) - 0.5$$

- For `VX_INTERPOLATION_NEAREST_NEIGHBOR`, the output value is that of the pixel whose centre is closest to the sample point.
- For `VX_INTERPOLATION_BILINEAR`, the output value is formed by a weighted average of the nearest source pixels to the sample point. That is:

$$x_{lower} = \lfloor x_{input} \rfloor$$

$$y_{lower} = \lfloor y_{input} \rfloor$$

$$s = x_{input} - x_{lower}$$

$$t = y_{input} - y_{lower}$$

$$\begin{aligned} output(x_{input}, y_{input}) = & (1-s)(1-t) * input(x_{lower}, y_{lower}) + s(1-t) * input(x_{lower} + 1, y_{lower}) \\ & + (1-s)t * input(x_{lower}, y_{lower} + 1) + s * t * input(x_{lower} + 1, y_{lower} + 1) \end{aligned}$$


- For `VX_INTERPOLATION_AREA`, the implementation is expected to generate each output pixel by sampling all the source pixels that are at least partly covered by the area bounded by:

$$\left( x_{output} * \frac{width_{input}}{width_{output}} \right) - 0.5, \left( y_{output} * \frac{height_{input}}{height_{output}} \right) - 0.5$$

and

$$\left( (x_{output} + 1) * \frac{width_{input}}{width_{output}} \right) - 0.5, \left( (y_{output} + 1) * \frac{height_{input}}{height_{output}} \right) - 0.5$$

The details of this sampling method are implementation-defined. The implementation should perform enough sampling to avoid aliasing, but there is no requirement that the sample areas for adjacent output pixels be disjoint, nor that the pixels be weighted evenly.



The above diagram shows three sampling methods used to shrink a 7x3 image to 3x1.

The topmost image pair shows nearest-neighbor sampling, with crosses on the left image marking the sample positions in the source that are used to generate the output image on the right. As the pixel centre closest to the sample position is white in all cases, the resulting 3x1 image is white.

The middle image pair shows bilinear sampling, with black squares on the left image showing the region in the source being sampled to generate each pixel on the destination image on the right. This sample area is always the size of an input pixel. The outer destination pixels partly sample from the outermost green pixels, so their resulting value is a weighted average of white and green.

The bottom image pair shows area sampling. The black rectangles in the source image on the left show the bounds of the projection of the destination pixels onto the source. The destination pixels on the right are formed by averaging at least those source pixels whose areas are wholly or partly contained within those rectangles. The manner of this averaging is implementation-defined; the example shown here weights the contribution of each source pixel by the amount of that pixel's area contained within the black rectangle.

## Functions

- `vx_node VX_API_CALL vxHalfScaleGaussianNode (vx_graph graph, vx_image input, vx_image output, vx_int32 kernel_size)`  
*[Graph] Performs a Gaussian Blur on an image then half-scales it. The interpolation mode used is nearest-neighbor.*
- `vx_node VX_API_CALL vxScaleImageNode (vx_graph graph, vx_image src, vx_image dst, vx_enum type)`  
*[Graph] Creates a Scale Image Node.*
- `vx_status VX_API_CALL vxuHalfScaleGaussian (vx_context context, vx_image input, vx_image output, vx_int32 kernel_size)`  
*[Immediate] Performs a Gaussian Blur on an image then half-scales it. The interpolation mode used is nearest-neighbor.*
- `vx_status VX_API_CALL vxuScaleImage (vx_context context, vx_image src, vx_image dst, vx_enum type)`  
*[Immediate] Scales an input image to an output image.*

### 3.44.2 Function Documentation

**vx\_node VX\_API\_CALL vxScaleImageNode ( vx\_graph *graph*, vx\_image *src*, vx\_image *dst*, vx\_enum *type* )**

[Graph] Creates a Scale Image Node.

#### Parameters

|     |              |                                                                |
|-----|--------------|----------------------------------------------------------------|
| in  | <i>graph</i> | The reference to the graph.                                    |
| in  | <i>src</i>   | The source image of type <a href="#">VX_DF_IMAGE_U8</a> .      |
| out | <i>dst</i>   | The destination image of type <a href="#">VX_DF_IMAGE_U8</a> . |
| in  | <i>type</i>  | The interpolation type to use.                                 |

See also

[vx\\_interpolation\\_type\\_e](#).

Note

The destination image must have a defined size and format. The border modes [VX\\_NODE\\_BORDER](#) value [VX\\_BORDER\\_UNDEFINED](#), [VX\\_BORDER\\_REPLICATE](#) and [VX\\_BORDER\\_CONSTANT](#) are supported.

Returns

[vx\\_node](#).

#### Return values

|                |                                                                                                                            |
|----------------|----------------------------------------------------------------------------------------------------------------------------|
| <i>vx_node</i> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|----------------|----------------------------------------------------------------------------------------------------------------------------|

**vx\_node VX\_API\_CALL vxHalfScaleGaussianNode ( vx\_graph *graph*, vx\_image *input*, vx\_image *output*, vx\_int32 *kernel\_size* )**

[Graph] Performs a Gaussian Blur on an image then half-scales it. The interpolation mode used is nearest-neighbor. The output image size is determined by:

$$W_{output} = \frac{W_{input} + 1}{2}, H_{output} = \frac{H_{input} + 1}{2}$$

#### Parameters

|     |                    |                                                                         |
|-----|--------------------|-------------------------------------------------------------------------|
| in  | <i>graph</i>       | The reference to the graph.                                             |
| in  | <i>input</i>       | The input <a href="#">VX_DF_IMAGE_U8</a> image.                         |
| out | <i>output</i>      | The output <a href="#">VX_DF_IMAGE_U8</a> image.                        |
| in  | <i>kernel_size</i> | The input size of the Gaussian filter. Supported values are 1, 3 and 5. |

Returns

[vx\\_node](#).



## Return values

|                      |                                                                                                                            |
|----------------------|----------------------------------------------------------------------------------------------------------------------------|
| <code>vx_node</code> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|----------------------|----------------------------------------------------------------------------------------------------------------------------|

**vx\_status VX\_API\_CALL vxuScaleImage ( vx\_context context, vx\_image src, vx\_image dst, vx\_enum type )**

[Immediate] Scales an input image to an output image.

## Parameters

|     |                |                                                                |
|-----|----------------|----------------------------------------------------------------|
| in  | <i>context</i> | The reference to the overall context.                          |
| in  | <i>src</i>     | The source image of type <a href="#">VX_DF_IMAGE_U8</a> .      |
| out | <i>dst</i>     | The destination image of type <a href="#">VX_DF_IMAGE_U8</a> . |
| in  | <i>type</i>    | The interpolation type.                                        |

See also

[vx\\_interpolation\\_type\\_e](#).

Returns

A [vx\\_status\\_e](#) enumeration.

## Return values

|                         |                                                      |
|-------------------------|------------------------------------------------------|
| <code>VX_SUCCESS</code> | Success                                              |
| *                       | An error occurred. See <a href="#">vx_status_e</a> . |

**vx\_status VX\_API\_CALL vxuHalfScaleGaussian ( vx\_context context, vx\_image input, vx\_image output, vx\_int32 kernel\_size )**

[Immediate] Performs a Gaussian Blur on an image then half-scales it. The interpolation mode used is nearest-neighbor.

## Parameters

|     |                    |                                                                         |
|-----|--------------------|-------------------------------------------------------------------------|
| in  | <i>context</i>     | The reference to the overall context.                                   |
| in  | <i>input</i>       | The input <a href="#">VX_DF_IMAGE_U8</a> image.                         |
| out | <i>output</i>      | The output <a href="#">VX_DF_IMAGE_U8</a> image.                        |
| in  | <i>kernel_size</i> | The input size of the Gaussian filter. Supported values are 1, 3 and 5. |

Returns

A [vx\\_status\\_e](#) enumeration.

## Return values

|                         |                                                      |
|-------------------------|------------------------------------------------------|
| <code>VX_SUCCESS</code> | Success                                              |
| *                       | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.45 Sobel 3x3

### 3.45.1 Detailed Description

Implements the Sobel Image Filter Kernel. The output images dimensions should be the same as the dimensions of the input image.

This kernel produces two output planes (one can be omitted) in the x and y plane. The Sobel Operators  $G_x, G_y$  are defined as:

$$\mathbf{G}_x = \begin{bmatrix} -1 & 0 & +1 \\ -2 & 0 & +2 \\ -1 & 0 & +1 \end{bmatrix}, \mathbf{G}_y = \begin{bmatrix} -1 & -2 & -1 \\ 0 & 0 & 0 \\ +1 & +2 & +1 \end{bmatrix}$$

### Functions

- **`vx_node VX_API_CALL vxSobel3x3Node`** (`vx_graph` *graph*, `vx_image` *input*, `vx_image` *output\_x*, `vx_image` *output\_y*)  
[Graph] Creates a Sobel3x3 node.
- **`vx_status VX_API_CALL vxuSobel3x3`** (`vx_context` *context*, `vx_image` *input*, `vx_image` *output\_x*, `vx_image` *output\_y*)  
[Immediate] Invokes an immediate Sobel 3x3.

### 3.45.2 Function Documentation

**`vx_node VX_API_CALL vxSobel3x3Node`** ( `vx_graph` *graph*, `vx_image` *input*, `vx_image` *output\_x*, `vx_image` *output\_y* )

[Graph] Creates a Sobel3x3 node.

#### Parameters

|     |                 |                                                                                                                                       |
|-----|-----------------|---------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>    | The reference to the graph.                                                                                                           |
| in  | <i>input</i>    | The input image in <code>VX_DF_IMAGE_U8</code> format.                                                                                |
| out | <i>output_x</i> | [optional] The output gradient in the x direction in <code>VX_DF_IMAGE_S16</code> . Must have the same dimensions as the input image. |
| out | <i>output_y</i> | [optional] The output gradient in the y direction in <code>VX_DF_IMAGE_S16</code> . Must have the same dimensions as the input image. |

See also

`VX_KERNEL_SOBEL_3x3`

Returns

`vx_node`.

#### Return values

|                      |                                                                                                                         |
|----------------------|-------------------------------------------------------------------------------------------------------------------------|
| <code>vx_node</code> | A node reference. Any possible errors preventing a successful creation should be checked using <code>vxGetStatus</code> |
|----------------------|-------------------------------------------------------------------------------------------------------------------------|

**`vx_status VX_API_CALL vxuSobel3x3`** ( `vx_context` *context*, `vx_image` *input*, `vx_image` *output\_x*, `vx_image` *output\_y* )

[Immediate] Invokes an immediate Sobel 3x3.

**Parameters**

|     |                            |                                                                                        |
|-----|----------------------------|----------------------------------------------------------------------------------------|
| in  | <i>context</i>             | The reference to the overall context.                                                  |
| in  | <i>input</i>               | The input image in <a href="#">VX_DF_IMAGE_U8</a> format.                              |
| out | <i>output</i><br><i>_x</i> | [optional] The output gradient in the x direction in <a href="#">VX_DF_IMAGE_S16</a> . |
| out | <i>output</i><br><i>_y</i> | [optional] The output gradient in the y direction in <a href="#">VX_DF_IMAGE_S16</a> . |

**Returns**

A [vx\\_status\\_e](#) enumeration.

**Return values**

|                   |                                                      |
|-------------------|------------------------------------------------------|
| <i>VX_SUCCESS</i> | Success                                              |
| *                 | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.46 TableLookup

### 3.46.1 Detailed Description

Implements the Table Lookup Image Kernel. The output image dimensions should be the same as the dimensions of the input image.

This kernel uses each pixel in an image to index into a LUT and put the indexed LUT value into the output image. The formats supported are `VX_DF_IMAGE_U8` and `VX_DF_IMAGE_S16`.

### Functions

- `vx_node VX_API_CALL vxTableLookupNode` (`vx_graph` graph, `vx_image` input, `vx_lut` lut, `vx_image` output)  
[Graph] Creates a Table Lookup node. If a value from the input image is not present in the lookup table, the result is undefined.
- `vx_status VX_API_CALL vxuTableLookup` (`vx_context` context, `vx_image` input, `vx_lut` lut, `vx_image` output)  
[Immediate] Processes the image through the LUT.

### 3.46.2 Function Documentation

**`vx_node VX_API_CALL vxTableLookupNode` ( `vx_graph` graph, `vx_image` input, `vx_lut` lut, `vx_image` output )**

[Graph] Creates a Table Lookup node. If a value from the input image is not present in the lookup table, the result is undefined.

#### Parameters

|     |        |                                                                                                                                                                                  |
|-----|--------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | graph  | The reference to the graph.                                                                                                                                                      |
| in  | input  | The input image in <code>VX_DF_IMAGE_U8</code> or <code>VX_DF_IMAGE_S16</code> .                                                                                                 |
| in  | lut    | The LUT which is of type <code>VX_TYPE_UINT8</code> if input image is <code>VX_DF_IMAGE_U8</code> or <code>VX_TYPE_INT16</code> if input image is <code>VX_DF_IMAGE_S16</code> . |
| out | output | The output image of the same type and size as the input image.                                                                                                                   |

#### Returns

`vx_node`.

#### Return values

|                      |                                                                                                                           |
|----------------------|---------------------------------------------------------------------------------------------------------------------------|
| <code>vx_node</code> | A node reference. Any possible errors preventing a successful creation should be checked using <code>vxGetStatus</code> . |
|----------------------|---------------------------------------------------------------------------------------------------------------------------|

**`vx_status VX_API_CALL vxuTableLookup` ( `vx_context` context, `vx_image` input, `vx_lut` lut, `vx_image` output )**

[Immediate] Processes the image through the LUT.

#### Parameters

|     |         |                                                                                                                                                                                  |
|-----|---------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | context | The reference to the overall context.                                                                                                                                            |
| in  | input   | The input image in <code>VX_DF_IMAGE_U8</code> or <code>VX_DF_IMAGE_S16</code> .                                                                                                 |
| in  | lut     | The LUT which is of type <code>VX_TYPE_UINT8</code> if input image is <code>VX_DF_IMAGE_U8</code> or <code>VX_TYPE_INT16</code> if input image is <code>VX_DF_IMAGE_S16</code> . |
| out | output  | The output image of the same type as the input image.                                                                                                                            |

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                         |                                                   |
|-------------------------|---------------------------------------------------|
| <code>VX_SUCCESS</code> | Success                                           |
| *                       | An error occurred. See <code>vx_status_e</code> . |

## 3.47 Thresholding

### 3.47.1 Detailed Description

Thresholds an input image and produces an output Boolean image. The output image dimensions should be the same as the dimensions of the input image.

In `VX_THRESHOLD_TYPE_BINARY`, the output is determined by:

$$dst(x,y) = \begin{cases} true\ value & \text{if } src(x,y) > threshold \\ false\ value & \text{otherwise} \end{cases}$$

In `VX_THRESHOLD_TYPE_RANGE`, the output is determined by:

$$dst(x,y) = \begin{cases} false\ value & \text{if } src(x,y) > upper \\ false\ value & \text{if } src(x,y) < lower \\ true\ value & \text{otherwise} \end{cases}$$

Where 'false value' and 'true value' are defined by the of the *thresh* parameter dependent upon the threshold output format with default values as discussed in the description of `vxCreateThresholdForImage` or as set by a call to `vxCopyThresholdOutput` with the *thresh* parameter as the first argument.

## Functions

- `vx_node VX_API_CALL vxThresholdNode (vx_graph graph, vx_image input, vx_threshold thresh, vx_image output)`  
[Graph] Creates a Threshold node and returns a reference to it.
- `vx_status VX_API_CALL vxuThreshold (vx_context context, vx_image input, vx_threshold thresh, vx_image output)`  
[Immediate] Threshold's an input image and produces a `VX_DF_IMAGE_U8` boolean image.

### 3.47.2 Function Documentation

**`vx_node VX_API_CALL vxThresholdNode ( vx_graph graph, vx_image input, vx_threshold thresh, vx_image output )`**

[Graph] Creates a Threshold node and returns a reference to it.

#### Parameters

|     |               |                                                                                                                                                                                                                                                          |
|-----|---------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>  | The reference to the graph in which the node is created.                                                                                                                                                                                                 |
| in  | <i>input</i>  | The input image. Only images with format <code>VX_DF_IMAGE_U8</code> and <code>VX_DF_IMAGE_S16</code> are supported.                                                                                                                                     |
| in  | <i>thresh</i> | The thresholding object that defines the parameters of the operation. The <code>VX_THRESHOLD_INPUT_FORMAT</code> must be the same as the input image format and the <code>VX_THRESHOLD_OUTPUT_FORMAT</code> must be the same as the output image format. |
| out | <i>output</i> | The output image, that will contain as pixel value true and false values defined by <i>thresh</i> . Only images with format <code>VX_DF_IMAGE_U8</code> are supported. The dimensions are the same as the input image.                                   |

#### Returns

`vx_node`.

#### Return values

|                      |                                                                                                                         |
|----------------------|-------------------------------------------------------------------------------------------------------------------------|
| <code>vx_node</code> | A node reference. Any possible errors preventing a successful creation should be checked using <code>vxGetStatus</code> |
|----------------------|-------------------------------------------------------------------------------------------------------------------------|

**vx\_status VX\_API\_CALL vxuThreshold ( vx\_context *context*, vx\_image *input*, vx\_threshold *thresh*, vx\_image *output* )**

[Immediate] Threshold's an input image and produces a [VX\\_DF\\_IMAGE\\_U8](#) boolean image.

#### Parameters

|     |                |                                                                                                                                                                                                                                                                |
|-----|----------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>context</i> | The reference to the overall context.                                                                                                                                                                                                                          |
| in  | <i>input</i>   | The input image. Only images with format <a href="#">VX_DF_IMAGE_U8</a> and <a href="#">VX_DF_IMAGE_S16</a> are supported.                                                                                                                                     |
| in  | <i>thresh</i>  | The thresholding object that defines the parameters of the operation. The <a href="#">VX_THRESHOLD_INPUT_FORMAT</a> must be the same as the input image format and the <a href="#">VX_THRESHOLD_OUTPUT_FORMAT</a> must be the same as the output image format. |
| out | <i>output</i>  | The output image, that will contain as pixel value true and false values defined by <i>thresh</i> . Only images with format <a href="#">VX_DF_IMAGE_U8</a> are supported.                                                                                      |

#### Returns

A [vx\\_status\\_e](#) enumeration.

#### Return values

|                            |                                                      |
|----------------------------|------------------------------------------------------|
| <a href="#">VX_SUCCESS</a> | Success                                              |
| *                          | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.48 Warp Affine

### 3.48.1 Detailed Description

Performs an affine transform on an image.

This kernel performs an affine transform with a 2x3 Matrix  $M$  with this method of pixel coordinate translation:

$$x0 = M_{1,1} * x + M_{1,2} * y + M_{1,3} \quad (3.28)$$

$$y0 = M_{2,1} * x + M_{2,2} * y + M_{2,3} \quad (3.29)$$

$$out\ put(x,y) = in\ put(x0,y0) \quad (3.30)$$

This translates into the C declaration:

```
// x0 = a x + b y + c;
// y0 = d x + e y + f;
vx_float32 mat[3][2] = {
 {a, d}, // 'x' coefficients
 {b, e}, // 'y' coefficients
 {c, f}, // 'offsets'
};
vx_matrix matrix = vxCreateMatrix(context,
 VX_TYPE_FLOAT32, 2, 3);
vxCopyMatrix(matrix, mat, VX_WRITE_ONLY,
 VX_MEMORY_TYPE_HOST);
```

## Functions

- `vx_status VX_API_CALL vxuWarpAffine` (`vx_context` context, `vx_image` input, `vx_matrix` matrix, `vx_enum` type, `vx_image` output)

*[Immediate] Performs an Affine warp on an image.*

- `vx_node VX_API_CALL vxWarpAffineNode` (`vx_graph` graph, `vx_image` input, `vx_matrix` matrix, `vx_enum` type, `vx_image` output)

*[Graph] Creates an Affine Warp Node.*

### 3.48.2 Function Documentation

`vx_node VX_API_CALL vxWarpAffineNode` ( `vx_graph` *graph*, `vx_image` *input*, `vx_matrix` *matrix*, `vx_enum` *type*, `vx_image` *output* )

[Graph] Creates an Affine Warp Node.

#### Parameters

|     |               |                                                                                                                         |
|-----|---------------|-------------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>  | The reference to the graph.                                                                                             |
| in  | <i>input</i>  | The input <code>VX_DF_IMAGE_U8</code> image.                                                                            |
| in  | <i>matrix</i> | The affine matrix. Must be 2x3 of type <code>VX_TYPE_FLOAT32</code> .                                                   |
| in  | <i>type</i>   | The interpolation type from <code>vx_interpolation_type_e</code> . <code>VX_INTERPOLATION_AREA</code> is not supported. |
| out | <i>output</i> | The output <code>VX_DF_IMAGE_U8</code> image and the same dimensions as the input image.                                |

#### Note

The border modes `VX_NODE_BORDER` value `VX_BORDER_UNDEFINED` and `VX_BORDER_CONSTANT` are supported.

#### Returns

`vx_node`.



## Return values

|                      |                                                                                                                            |
|----------------------|----------------------------------------------------------------------------------------------------------------------------|
| <code>vx_node</code> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|----------------------|----------------------------------------------------------------------------------------------------------------------------|

**`vx_status VX_API_CALL vxuWarpAffine ( vx_context context, vx_image input, vx_matrix matrix, vx_enum type, vx_image output )`**

[Immediate] Performs an Affine warp on an image.

## Parameters

|     |                |                                                                                                                               |
|-----|----------------|-------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>context</i> | The reference to the overall context.                                                                                         |
| in  | <i>input</i>   | The input <a href="#">VX_DF_IMAGE_U8</a> image.                                                                               |
| in  | <i>matrix</i>  | The affine matrix. Must be 2x3 of type <a href="#">VX_TYPE_FLOAT32</a> .                                                      |
| in  | <i>type</i>    | The interpolation type from <a href="#">vx_interpolation_type_e</a> . <a href="#">VX_INTERPOLATION_AREA</a> is not supported. |
| out | <i>output</i>  | The output <a href="#">VX_DF_IMAGE_U8</a> image.                                                                              |

## Returns

A [vx\\_status\\_e](#) enumeration.

## Return values

|                         |                                                      |
|-------------------------|------------------------------------------------------|
| <code>VX_SUCCESS</code> | Success                                              |
| *                       | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.49 Warp Perspective

### 3.49.1 Detailed Description

Performs a perspective transform on an image.

This kernel performs an perspective transform with a 3x3 Matrix  $M$  with this method of pixel coordinate translation:

$$x0 = M_{1,1} * x + M_{1,2} * y + M_{1,3} \quad (3.31)$$

$$y0 = M_{2,1} * x + M_{2,2} * y + M_{2,3} \quad (3.32)$$

$$z0 = M_{3,1} * x + M_{3,2} * y + M_{3,3} \quad (3.33)$$

$$out\ put(x,y) = input\left(\frac{x0}{z0}, \frac{y0}{z0}\right) \quad (3.34)$$

This translates into the C declaration:

```
// x0 = a x + b y + c;
// y0 = d x + e y + f;
// z0 = g x + h y + i;
vx_float32 mat[3][3] = {
 {a, d, g}, // 'x' coefficients
 {b, e, h}, // 'y' coefficients
 {c, f, i}, // 'offsets'
};
vx_matrix matrix = vxCreateMatrix(context,
 VX_TYPE_FLOAT32, 3, 3);
vxCopyMatrix(matrix, mat, VX_WRITE_ONLY,
 VX_MEMORY_TYPE_HOST);
```

## Functions

- `vx_status VX_API_CALL vxuWarpPerspective` (`vx_context` context, `vx_image` input, `vx_matrix` matrix, `vx_enum` type, `vx_image` output)  
*[Immediate] Performs an Perspective warp on an image.*
- `vx_node VX_API_CALL vxWarpPerspectiveNode` (`vx_graph` graph, `vx_image` input, `vx_matrix` matrix, `vx_enum` type, `vx_image` output)  
*[Graph] Creates a Perspective Warp Node.*

### 3.49.2 Function Documentation

**`vx_node VX_API_CALL vxWarpPerspectiveNode` ( `vx_graph` *graph*, `vx_image` *input*, `vx_matrix` *matrix*, `vx_enum` *type*, `vx_image` *output* )**

[Graph] Creates a Perspective Warp Node.

#### Parameters

|     |               |                                                                                                                            |
|-----|---------------|----------------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>  | The reference to the graph.                                                                                                |
| in  | <i>input</i>  | The input <code>VX_DF_IMAGE_U8</code> image.                                                                               |
| in  | <i>matrix</i> | The perspective matrix. Must be 3x3 of type <code>VX_TYPE_FLOAT32</code> .                                                 |
| in  | <i>type</i>   | The interpolation type from <code>vx_interpolation_type_e</code> .<br><code>VX_INTERPOLATION_AREA</code> is not supported. |
| out | <i>output</i> | The output <code>VX_DF_IMAGE_U8</code> image with the same dimensions as the input image.                                  |

#### Note

The border modes `VX_NODE_BORDER` value `VX_BORDER_UNDEFINED` and `VX_BORDER_CONSTANT` are supported.

## Returns

[vx\\_node](#).

## Return values

|                         |                                                                                                                            |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|
| <a href="#">vx_node</a> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|

**vx\_status VX\_API\_CALL vxuWarpPerspective ( vx\_context *context*, vx\_image *input*, vx\_matrix *matrix*, vx\_enum *type*, vx\_image *output* )**

[Immediate] Performs an Perspective warp on an image.

## Parameters

|     |                |                                                                                                                               |
|-----|----------------|-------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>context</i> | The reference to the overall context.                                                                                         |
| in  | <i>input</i>   | The input <a href="#">VX_DF_IMAGE_U8</a> image.                                                                               |
| in  | <i>matrix</i>  | The perspective matrix. Must be 3x3 of type <a href="#">VX_TYPE_FLOAT32</a> .                                                 |
| in  | <i>type</i>    | The interpolation type from <a href="#">vx_interpolation_type_e</a> . <a href="#">VX_INTERPOLATION_AREA</a> is not supported. |
| out | <i>output</i>  | The output <a href="#">VX_DF_IMAGE_U8</a> image.                                                                              |

## Returns

A [vx\\_status\\_e](#) enumeration.

## Return values

|                            |                                                      |
|----------------------------|------------------------------------------------------|
| <a href="#">VX_SUCCESS</a> | Success                                              |
| *                          | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.50 Bilateral Filter

### 3.50.1 Detailed Description

The function applies bilateral filtering to the input tensor.

A bilateral filter is a non-linear, edge-preserving and noise-reducing smoothing filter. The input and output are tensors with the same dimensions and data type. The tensor dimensions are divided to spatial and non spatial dimensions. The spatial dimensions are isometric distance which is Cartesian. And they are the last 2. The non spatial dimension is the first, and we call him the radiometric. The radiometric value at each spatial position is replaced by a weighted average of radiometric values from nearby pixels. This weight can be based on a Gaussian distribution. Crucially, the weights depend not only on Euclidean distance of spatial dimensions, but also on the radiometric differences (e.g. range differences, such as color intensity, depth distance, etc.). This preserves sharp edges by systematically looping through each pixel and adjusting weights to the adjacent pixels accordingly. The equations are as follows:

$$h(x, \tau) = \sum f(y, t) g_1(y - x) g_2(t - \tau) dy dt$$

$$g_1 = \frac{1}{\sqrt{2\pi}\sigma_y} \exp\left(-\frac{1}{2} \left(\frac{y^2}{\sigma_y^2}\right)\right)$$

$$g_2(t) = \frac{1}{\sqrt{2\pi}\sigma_t} \exp\left(-\frac{1}{2} \left(\frac{t^2}{\sigma_t^2}\right)\right)$$

where  $x, y$  are in the spatial euclidean space.  $t, \tau$  are vectors in radiometric space. Can be color, depth or movement. In case of 3 dimensions the 1st dimension of the `vx_tensor`. Which can be of size 1 or 2. Or the value in the tensor in the case of tensor with 2 dimensions.

### Functions

- `vx_node VX_API_CALL vxBilateralFilterNode` (`vx_graph` graph, `vx_tensor` src, `vx_int32` diameter, `vx_float32` sigmaSpace, `vx_float32` sigmaValues, `vx_tensor` dst)  
[Graph] The function applies bilateral filtering to the input tensor.
- `vx_status VX_API_CALL vxuBilateralFilter` (`vx_context` context, `vx_tensor` src, `vx_int32` diameter, `vx_float32` sigmaSpace, `vx_float32` sigmaValues, `vx_tensor` dst)  
[Immediate] The function applies bilateral filtering to the input tensor.

### 3.50.2 Function Documentation

**`vx_node VX_API_CALL vxBilateralFilterNode` ( `vx_graph` graph, `vx_tensor` src, `vx_int32` diameter, `vx_float32` sigmaSpace, `vx_float32` sigmaValues, `vx_tensor` dst )**

[Graph] The function applies bilateral filtering to the input tensor.

#### Parameters

|     |                    |                                                                                                                                                                                                                                                                                                     |
|-----|--------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>       | The reference to the graph.                                                                                                                                                                                                                                                                         |
| in  | <i>src</i>         | The input data a <code>vx_tensor</code> . maximum 3 dimension and minimum 2. The tensor is of type <code>VX_TYPE_UINT8</code> or <code>VX_TYPE_INT16</code> . dimensions are [radiometric ,width,height] or [width,height].See <code>vxCreateTensor</code> and <code>vxCreateVirtualTensor</code> . |
| in  | <i>diameter</i>    | of each pixel neighbourhood that is used during filtering. Values of diameter must be odd. Bigger then 3 and smaller then 10.                                                                                                                                                                       |
| in  | <i>sigmaValues</i> | Filter sigma in the radiometric space. Supported values are bigger then 0 and smaller or equal 20.                                                                                                                                                                                                  |
| in  | <i>sigmaSpace</i>  | Filter sigma in the spatial space. Supported values are bigger then 0 and smaller or equal 20.                                                                                                                                                                                                      |
| out | <i>dst</i>         | The output data a <code>vx_tensor</code> .Of type <code>VX_TYPE_UINT8</code> or <code>VX_TYPE_INT16</code> . And must be the same type and size of the input.                                                                                                                                       |

**Note**

The border modes `VX_NODE_BORDER` value `VX_BORDER_REPLICATE` and `VX_BORDER_CONSTANT` are supported.

**Returns**

`vx_node`.

**Return values**

|                      |                                                                                                                         |
|----------------------|-------------------------------------------------------------------------------------------------------------------------|
| <code>vx_node</code> | A node reference. Any possible errors preventing a successful creation should be checked using <code>vxGetStatus</code> |
|----------------------|-------------------------------------------------------------------------------------------------------------------------|

**`vx_status VX_API_CALL vxuBilateralFilter ( vx_context context, vx_tensor src, vx_int32 diameter, vx_float32 sigmaSpace, vx_float32 sigmaValues, vx_tensor dst )`**

[Immediate] The function applies bilateral filtering to the input tensor.

**Parameters**

|     |                          |                                                                                                                                                                                                                            |
|-----|--------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <code>context</code>     | The reference to the overall context.                                                                                                                                                                                      |
| in  | <code>src</code>         | The input data a <code>vx_tensor</code> . maximum 3 dimension and minimum 2. The tensor is of type <code>VX_TYPE_UINT8</code> or <code>VX_TYPE_INT16</code> . dimensions are [radiometric ,width,height] or [width,height] |
| in  | <code>diameter</code>    | of each pixel neighbourhood that is used during filtering. Values of diameter must be odd. Bigger then 3 and smaller then 10.                                                                                              |
| in  | <code>sigmaValues</code> | Filter sigma in the radiometric space. Supported values are bigger then 0 and smaller or equal 20.                                                                                                                         |
| in  | <code>sigmaSpace</code>  | Filter sigma in the spatial space. Supported values are bigger then 0 and smaller or equal 20.                                                                                                                             |
| out | <code>dst</code>         | The output data a <code>vx_tensor</code> ,Of type <code>VX_TYPE_UINT8</code> or <code>VX_TYPE_INT16</code> . And must be the same type and size of the input.                                                              |

**Note**

The border modes `VX_NODE_BORDER` value `VX_BORDER_REPLICATE` and `VX_BORDER_CONSTANT` are supported.

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                         |                                                   |
|-------------------------|---------------------------------------------------|
| <code>VX_SUCCESS</code> | Success                                           |
| *                       | An error occurred. See <code>vx_status_e</code> . |

## 3.51 MatchTemplate

### 3.51.1 Detailed Description

Compares an image template against overlapped image regions.

The detailed equation to the matching can be found in [vx\\_comp\\_metric\\_e](#). The output of the template matching node is a comparison map. The output comparison map should be the same size as the input image. The template image size (width\*height) shall not be larger than 65535. If the valid region of the template image is smaller than the entire template image, the result in the destination image is implementation-dependent.

### Enumerations

- enum [vx\\_comp\\_metric\\_e](#) {  
[VX\\_COMPARE\\_HAMMING](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_ENUM\\_COMP\\_METRIC](#) << 12)) + 0x0,  
[VX\\_COMPARE\\_L1](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_ENUM\\_COMP\\_METRIC](#) << 12)) + 0x1,  
[VX\\_COMPARE\\_L2](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_ENUM\\_COMP\\_METRIC](#) << 12)) + 0x2,  
[VX\\_COMPARE\\_CCORR](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_ENUM\\_COMP\\_METRIC](#) << 12)) + 0x3,  
[VX\\_COMPARE\\_L2\\_NORM](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_ENUM\\_COMP\\_METRIC](#) << 12)) + 0x4,  
[VX\\_COMPARE\\_CCORR\\_NORM](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_ENUM\\_COMP\\_METRIC](#) << 12)) + 0x5 }  
 comparing metrics.

### Functions

- [vx\\_node VX\\_API\\_CALL vxMatchTemplateNode](#) ([vx\\_graph](#) graph, [vx\\_image](#) src, [vx\\_image](#) templateImage, [vx\\_enum](#) matchingMethod, [vx\\_image](#) output)  
*[Graph] The Node Compares an image template against overlapped image regions.*
- [vx\\_status VX\\_API\\_CALL vxuMatchTemplate](#) ([vx\\_context](#) context, [vx\\_image](#) src, [vx\\_image](#) templateImage, [vx\\_enum](#) matchingMethod, [vx\\_image](#) output)  
*[Immediate] The function compares an image template against overlapped image regions.*

### 3.51.2 Enumeration Type Documentation

#### enum [vx\\_comp\\_metric\\_e](#)

comparing metrics.

In all the equations below  $w$  and  $h$  are width and height of the template image respectively.  $R$  is the compare map.  $T$  is the template image.  $I$  is the image on which the template is searched.

Enumerator

**[VX\\_COMPARE\\_HAMMING](#)** hamming distance  $R(x, y) = \frac{1}{w \cdot h} \sum_{\hat{x}, \hat{y}}^{w, h} XOR(T(\hat{x}, \hat{y}), I(x + \hat{x}, y + \hat{y}))$

**[VX\\_COMPARE\\_L1](#)** L1 distance  $R(x, y) = \frac{1}{w \cdot h} \sum_{\hat{x}, \hat{y}}^{w, h} ABS(T(\hat{x}, \hat{y}) - I(x + \hat{x}, y + \hat{y}))$ .

**[VX\\_COMPARE\\_L2](#)** L2 distance normalized by image size  $R(x, y) = \frac{1}{w \cdot h} \sum_{\hat{x}, \hat{y}}^{w, h} (T(\hat{x}, \hat{y}) - I(x + \hat{x}, y + \hat{y}))^2$ .

**[VX\\_COMPARE\\_CCORR](#)** cross correlation distance  $R(x, y) = \frac{1}{w \cdot h} \sum_{\hat{x}, \hat{y}}^{w, h} (T(\hat{x}, \hat{y}) * I(x + \hat{x}, y + \hat{y}))$

**[VX\\_COMPARE\\_L2\\_NORM](#)** L2 normalized distance  $R(x, y) = \frac{\sum_{\hat{x}, \hat{y}}^{w, h} (T(\hat{x}, \hat{y}) - I(x + \hat{x}, y + \hat{y}))^2}{\sqrt{\sum_{\hat{x}, \hat{y}}^{w, h} T(\hat{x}, \hat{y})^2 * I(x + \hat{x}, y + \hat{y})^2}}$ .

**[VX\\_COMPARE\\_CCORR\\_NORM](#)** cross correlation normalized distance  $R(x, y) = \frac{\sum_{\hat{x}, \hat{y}}^{w, h} T(\hat{x}, \hat{y}) * I(x + \hat{x}, y + \hat{y}) * 2^{15}}{\sqrt{\sum_{\hat{x}, \hat{y}}^{w, h} T(\hat{x}, \hat{y})^2 * I(x + \hat{x}, y + \hat{y})^2}}$

Definition at line 1447 of file [vx\\_types.h](#).

### 3.51.3 Function Documentation

**vx\_node VX\_API\_CALL vxMatchTemplateNode ( vx\_graph graph, vx\_image src, vx\_image templateImage, vx\_enum matchingMethod, vx\_image output )**

[Graph] The Node Compares an image template against overlapped image regions.

The detailed equation to the matching can be found in [vx\\_comp\\_metric\\_e](#). The output of the template matching node is a comparison map as described in [vx\\_comp\\_metric\\_e](#). The Node have a limitation on the template image size (width\*height). It should not be larger then 65535. If the valid region of the template image is smaller than the entire template image, the result in the destination image is implementation-dependent.

#### Parameters

|     |                       |                                                                                                                                                                                    |
|-----|-----------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>          | The reference to the graph.                                                                                                                                                        |
| in  | <i>src</i>            | The input image of type <a href="#">VX_DF_IMAGE_U8</a> .                                                                                                                           |
| in  | <i>templateImage</i>  | Searched template of type <a href="#">VX_DF_IMAGE_U8</a> .                                                                                                                         |
| in  | <i>matchingMethod</i> | attribute specifying the comparison method <a href="#">vx_comp_metric_e</a> . This function support only <a href="#">VX_COMPARE_CCORR_NORM</a> and <a href="#">VX_COMPARE_L2</a> . |
| out | <i>output</i>         | Map of comparison results. The output is an image of type <a href="#">VX_DF_IMAGE_S16</a>                                                                                          |

#### Returns

[vx\\_node](#).

#### Return values

|                |                                                                                                                            |
|----------------|----------------------------------------------------------------------------------------------------------------------------|
| <i>vx_node</i> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|----------------|----------------------------------------------------------------------------------------------------------------------------|

**vx\_status VX\_API\_CALL vxuMatchTemplate ( vx\_context context, vx\_image src, vx\_image templateImage, vx\_enum matchingMethod, vx\_image output )**

[Immediate] The function compares an image template against overlapped image regions.

The detailed equation to the matching can be found in [vx\\_comp\\_metric\\_e](#). The output of the template matching node is a comparison map as described in [vx\\_comp\\_metric\\_e](#). The Node have a limitation on the template image size (width\*height). It should not be larger then 65535. If the valid region of the template image is smaller than the entire template image, the result in the destination image is implementation-dependent.

#### Parameters

|     |                       |                                                                                                                                                                                    |
|-----|-----------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>context</i>        | The reference to the overall context.                                                                                                                                              |
| in  | <i>src</i>            | The input image of type <a href="#">VX_DF_IMAGE_U8</a> .                                                                                                                           |
| in  | <i>templateImage</i>  | Searched template of type <a href="#">VX_DF_IMAGE_U8</a> .                                                                                                                         |
| in  | <i>matchingMethod</i> | attribute specifying the comparison method <a href="#">vx_comp_metric_e</a> . This function support only <a href="#">VX_COMPARE_CCORR_NORM</a> and <a href="#">VX_COMPARE_L2</a> . |
| out | <i>output</i>         | Map of comparison results. The output is an image of type <a href="#">VX_DF_IMAGE_S16</a>                                                                                          |

#### Returns

A [vx\\_status\\_e](#) enumeration.

#### Return values

|                            |                                                      |
|----------------------------|------------------------------------------------------|
| <a href="#">VX_SUCCESS</a> | Success                                              |
| *                          | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.52 LBP

### 3.52.1 Detailed Description

Extracts LBP image from an input image. The output image dimensions should be the same as the dimensions of the input image.

The function calculates one of the following LBP descriptors: Local Binary Pattern, Modified Local Binary Pattern, or Uniform Local Binary Pattern.

local binary pattern is defined as: Each pixel (y,x) generate an 8 bit value describing the local binary pattern around the pixel, by comparing the pixel value with its 8 neighbours (selected neighbours of the 3x3 or 5x5 window).

We will define the pixels for the 3x3 neighbourhood as:

$$\begin{aligned}
 g_0 &= \text{SrcImg}[y-1, x-1] \\
 g_1 &= \text{SrcImg}[y-1, x] \\
 g_2 &= \text{SrcImg}[y-1, x+1] \\
 g_3 &= \text{SrcImg}[y, x+1] \\
 g_4 &= \text{SrcImg}[y+1, x+1] \\
 g_5 &= \text{SrcImg}[y+1, x] \\
 g_6 &= \text{SrcImg}[y+1, x-1] \\
 g_7 &= \text{SrcImg}[y, x-1] \\
 g_c &= \text{SrcImg}[y, x]
 \end{aligned} \tag{3.35}$$

and the pixels in a 5x5 neighbourhood as:

$$\begin{aligned}
 g_0 &= \text{SrcImg}[y-1, x-1] \\
 g_1 &= \text{SrcImg}[y-2, x] \\
 g_2 &= \text{SrcImg}[y-1, x+1] \\
 g_3 &= \text{SrcImg}[y, x+2] \\
 g_4 &= \text{SrcImg}[y+1, x+1] \\
 g_5 &= \text{SrcImg}[y+2, x] \\
 g_6 &= \text{SrcImg}[y+1, x-1] \\
 g_7 &= \text{SrcImg}[y, x-2] \\
 g_c &= \text{SrcImg}[y, x]
 \end{aligned} \tag{3.36}$$

We also define the sign difference function:

$$s(x) = \begin{cases} 1 & x \geq 0 \\ 0 & x < 0 \end{cases} \tag{3.37}$$

Using the above definitions. The LBP image is defined in the following equation:

$$\text{DstImg}[y, x] = \sum_{p=0}^7 s(g_p - g_c) 2^p$$

For modified local binary pattern. Each pixel (y,x) generate an 8 bit value describing the modified local binary pattern around the pixel, by comparing the average of 8 neighbour pixels with its 8 neighbours (5x5 window).

$$\begin{aligned}
 \text{Avg}[y, x] &= ((\text{SrcImg}[y-2, x-2]) \\
 &+ (\text{SrcImg}[y-2, x]) \\
 &+ (\text{SrcImg}[y-2, x+2]) \\
 &+ (\text{SrcImg}[y, x+2]) \\
 &+ (\text{SrcImg}[y+2, x+2]) \\
 &+ (\text{SrcImg}[y+2, x]) \\
 &+ (\text{SrcImg}[y+2, x-2]) \\
 &+ (\text{SrcImg}[y, x-2]) + 1) / 8
 \end{aligned} \tag{3.38}$$



$$\begin{aligned}
DstImg[y,x] = & ((SrcImg[y-2,x-2] > Avg[y,x])) \\
& | \\
& ((SrcImg[y-2,x] > Avg[y,x]) << 1) \\
& | \\
& ((SrcImg[y-2,x+2] > Avg[y,x]) << 2) \\
& | \\
& ((SrcImg[y,x+2] > Avg[y,x]) << 3) \\
& | \\
& ((SrcImg[y+2,x+2] > Avg[y,x]) << 4) \\
& | \\
& ((SrcImg[y+2,x] > Avg[y,x]) << 5) \\
& | \\
& ((SrcImg[y+2,x-2] > Avg[y,x]) << 6) \\
& | \\
& ((SrcImg[y,x-2] > Avg[y,x]) << 7)
\end{aligned} \tag{3.39}$$

The uniform LBP patterns refer to the patterns which have limited transition or discontinuities (smaller then 2 or equal) in the circular binary presentation.

For each pixel (y,x) a value is generated, describing the transition around the pixel (If there are up to 2 transitions between 0 to 1 or 1 to 0). And an additional value for all other local binary pattern values. We can define the function that measure transition as:

$$U = |s(g_7 - g_c) - s(g_0 - g_c)| + \sum_{p=1}^7 |s(g_p - g_c) - s(g_{p-1} - g_c)|$$

With the above definitions, the unified LBP equation is defined as.

$$DstImg[y,x] = \begin{cases} \sum_{p=0}^7 s(g_p - g_c) 2^p & U \leq 2 \\ 9 & otherwise \end{cases}$$

## Enumerations

- enum `vx_lbp_format_e` {  
`VX_LBP` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_LBP_FORMAT` << 12)) + 0x0,  
`VX_MLBP` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_LBP_FORMAT` << 12)) + 0x1,  
`VX_ULBP` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_LBP_FORMAT` << 12)) + 0x2 }

*Local binary pattern supported.*

## Functions

- `vx_node VX_API_CALL vxLBPNode` (`vx_graph` graph, `vx_image` in, `vx_enum` format, `vx_int8` kernel\_size, `vx_image` out)  
*[Graph]* Creates a node that extracts LBP image from an input image
- `vx_status VX_API_CALL vxuLBP` (`vx_context` context, `vx_image` in, `vx_enum` format, `vx_int8` kernel\_size, `vx_image` out)

*[Immediate]* The function extracts LBP image from an input image

### 3.52.2 Enumeration Type Documentation

#### enum `vx_lbp_format_e`

Local binary pattern supported.

Enumerator

- `VX_LBP`** local binary pattern
- `VX_MLBP`** Modified Local Binary Patterns.
- `VX_ULBP`** Uniform local binary pattern.

Definition at line 1428 of file `vx_types.h`.

### 3.52.3 Function Documentation

**vx\_node** **VX\_API\_CALL** vxLBPNode ( vx\_graph *graph*, vx\_image *in*, vx\_enum *format*, vx\_int8 *kernel\_size*, vx\_image *out* )

[Graph] Creates a node that extracts LBP image from an input image

#### Parameters

|     |                    |                                                                                                                                                                 |
|-----|--------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>       | The reference to the graph.                                                                                                                                     |
| in  | <i>in</i>          | An input image in vx_image. Or <i>SrcImg</i> in the equations. the image is of type <a href="#">VX_DF_IMAGE_U8</a>                                              |
| in  | <i>format</i>      | A variation of LBP like original LBP and mLBP. see <a href="#">vx_lbp_format_e</a>                                                                              |
| in  | <i>kernel_size</i> | Kernel size. Only size of 3 and 5 are supported                                                                                                                 |
| out | <i>out</i>         | An output image in vx_image.Or <i>DstImg</i> in the equations. the image is of type <a href="#">VX_DF_IMAGE_U8</a> with the same dimensions as the input image. |

#### Returns

[vx\\_node](#).

#### Return values

|                |                                                                                                                            |
|----------------|----------------------------------------------------------------------------------------------------------------------------|
| <i>vx_node</i> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|----------------|----------------------------------------------------------------------------------------------------------------------------|

**vx\_status** **VX\_API\_CALL** vxuLBP ( vx\_context *context*, vx\_image *in*, vx\_enum *format*, vx\_int8 *kernel\_size*, vx\_image *out* )

[Immediate] The function extracts LBP image from an input image

#### Parameters

|     |                    |                                                                                                                    |
|-----|--------------------|--------------------------------------------------------------------------------------------------------------------|
| in  | <i>context</i>     | The reference to the overall context.                                                                              |
| in  | <i>in</i>          | An input image in vx_image. Or <i>SrcImg</i> in the equations. the image is of type <a href="#">VX_DF_IMAGE_U8</a> |
| in  | <i>format</i>      | A variation of LBP like original LBP and mLBP. see <a href="#">vx_lbp_format_e</a>                                 |
| in  | <i>kernel_size</i> | Kernel size. Only size of 3 and 5 are supported                                                                    |
| out | <i>out</i>         | An output image in vx_image.Or <i>DstImg</i> in the equations. the image is of type <a href="#">VX_DF_IMAGE_U8</a> |

#### Returns

A [vx\\_status\\_e](#) enumeration.

#### Return values

|                   |                                                      |
|-------------------|------------------------------------------------------|
| <i>VX_SUCCESS</i> | Success                                              |
| *                 | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.53 HOG

### 3.53.1 Detailed Description

Extracts Histogram of Oriented Gradients features from the input grayscale image.

The Histogram of Oriented Gradients (HOG) vision function is split into two nodes `vxHOGCellsNode` and `vxHOGFeaturesNode`. The specification of these nodes cover a subset of possible HOG implementations. The `vxHOGCellsNode` calculates the gradient orientation histograms and average gradient magnitudes for each of the cells. The `vxHOGFeaturesNode` uses the cell histograms and optionally the average gradient magnitude of the cells to produce a HOG feature vector. This involves grouping up the cell histograms into blocks which are then normalized. A moving window is applied to the input image and for each location the block data associated with the window is concatenated to the HOG feature vector.

### Data Structures

- struct `vx_hog_t`

The HOG descriptor structure. [More...](#)

### Functions

- `vx_node VX_API_CALL vxHOGCellsNode` (`vx_graph` graph, `vx_image` input, `vx_int32` cell\_width, `vx_int32` cell\_height, `vx_int32` num\_bins, `vx_tensor` magnitudes, `vx_tensor` bins)  
*[Graph] Performs cell calculations for the average gradient magnitude and gradient orientation histograms.*
- `vx_node VX_API_CALL vxHOGFeaturesNode` (`vx_graph` graph, `vx_image` input, `vx_tensor` magnitudes, `vx_tensor` bins, const `vx_hog_t` \*params, `vx_size` hog\_param\_size, `vx_tensor` features)  
*[Graph] The node produces HOG features for the W1xW2 window in a sliding window fashion over the whole input image. Each position produces a HOG feature vector.*
- `vx_status VX_API_CALL vxuHOGCells` (`vx_context` context, `vx_image` input, `vx_int32` cell\_width, `vx_int32` cell\_height, `vx_int32` num\_bins, `vx_tensor` magnitudes, `vx_tensor` bins)  
*[Immediate] Performs cell calculations for the average gradient magnitude and gradient orientation histograms.*
- `vx_status VX_API_CALL vxuHOGFeatures` (`vx_context` context, `vx_image` input, `vx_tensor` magnitudes, `vx_tensor` bins, const `vx_hog_t` \*params, `vx_size` hog\_param\_size, `vx_tensor` features)  
*[Immediate] Computes Histogram of Oriented Gradients features for the W1xW2 window in a sliding window fashion over the whole input image.*

### 3.53.2 Data Structure Documentation

#### struct `vx_hog_t`

The HOG descriptor structure.

Definition at line 1699 of file `vx_types.h`.

#### Data Fields

|                       |               |                                                                                                                                             |
|-----------------------|---------------|---------------------------------------------------------------------------------------------------------------------------------------------|
| <code>vx_int32</code> | cell_width    | The histogram cell width of type <code>VX_TYPE_INT32</code> .                                                                               |
| <code>vx_int32</code> | cell_height   | The histogram cell height of type <code>VX_TYPE_INT32</code> .                                                                              |
| <code>vx_int32</code> | block_width   | The histogram block width of type <code>VX_TYPE_INT32</code> . Must be divisible by cell_width.                                             |
| <code>vx_int32</code> | block_height  | The histogram block height of type <code>VX_TYPE_INT32</code> . Must be divisible by cell_height.                                           |
| <code>vx_int32</code> | block_stride  | The histogram block stride within the window of type <code>VX_TYPE_INT32</code> . Must be an integral number of cell_width and cell_height. |
| <code>vx_int32</code> | num_bins      | The histogram size of type <code>VX_TYPE_INT32</code> .                                                                                     |
| <code>vx_int32</code> | window_width  | The feature descriptor window width of type <code>VX_TYPE_INT32</code>                                                                      |
| <code>vx_int32</code> | window_height | The feature descriptor window height of type <code>VX_TYPE_INT32</code>                                                                     |
| <code>vx_int32</code> | window_stride | The feature descriptor window stride of type <code>VX_TYPE_INT32</code>                                                                     |

## Data Fields

|                            |           |                                                                                                                                 |
|----------------------------|-----------|---------------------------------------------------------------------------------------------------------------------------------|
| <a href="#">vx_float32</a> | threshold | The threshold for the maximum L2-norm value for a histogram bin. It is used as part of block normalization. It defaults to 0.2. |
|----------------------------|-----------|---------------------------------------------------------------------------------------------------------------------------------|

## 3.53.3 Function Documentation

**vx\_node VX\_API\_CALL vxHOGCellsNode ( vx\_graph graph, vx\_image input, vx\_int32 cell\_width, vx\_int32 cell\_height, vx\_int32 num\_bins, vx\_tensor magnitudes, vx\_tensor bins )**

[Graph] Performs cell calculations for the average gradient magnitude and gradient orientation histograms.

Firstly, the gradient magnitude and gradient orientation are computed for each pixel in the input image. Two 1-D centred, point discrete derivative masks are applied to the input image in the horizontal and vertical directions.

$$M_h = [-1, 0, 1]$$

and

$$M_v = [-1, 0, 1]^T$$

$G_v$  is the result of applying mask  $M_v$  to the input image, and  $G_h$  is the result of applying mask  $M_h$  to the input image. The border mode used for the gradient calculation is implementation dependent. Its behavior should be similar to [VX\\_BORDER\\_UNDEFINED](#). The gradient magnitudes and gradient orientations for each pixel are then calculated in the following manner.

$$G(x, y) = \sqrt{G_v(x, y)^2 + G_h(x, y)^2}$$

$$\theta(x, y) = \arctan(G_v(x, y), G_h(x, y))$$

where  $\arctan(v, h)$  is  $\tan^{-1}(v/h)$  when  $h \neq 0$ ,

$-pi/2$  if  $v < 0$  and  $h == 0$ ,

$pi/2$  if  $v > 0$  and  $h == 0$

and 0 if  $v == 0$  and  $h == 0$

Secondly, the gradient magnitudes and orientations are used to compute the bins output tensor and optional magnitudes output tensor. These tensors are computed on a cell level where the cells are rectangular in shape. The magnitudes tensor contains the average gradient magnitude for each cell.

$$magnitudes(c) = \frac{1}{(cell\_width * cell\_height)} \sum_{w=0}^{cell\_width} \sum_{h=0}^{cell\_height} G_c(w, h)$$

where  $G_c$  is the gradient magnitudes related to cell  $c$ . The bins tensor contains histograms of gradient orientations for each cell. The gradient orientations at each pixel range from 0 to 360 degrees. These are quantised into a set of histogram bins based on the `num_bins` parameter. Each pixel votes for a specific cell histogram bin based on its gradient orientation. The vote itself is the pixel's gradient magnitude.

$$bins(c, n) = \sum_{w=0}^{cell\_width} \sum_{h=0}^{cell\_height} G_c(w, h) * 1[B_c(w, h, num\_bins) == n]$$

where  $B_c$  produces the histogram bin number based on the gradient orientation of the pixel at location  $(w, h)$  in cell  $c$  based on the `num_bins` and

$$1[B_c(w, h, num\_bins) == n]$$

is a delta-function with value 1 when  $B_c(w, h, num\_bins) == n$  or 0 otherwise.

## Parameters

|    |                    |                                                                   |
|----|--------------------|-------------------------------------------------------------------|
| in | <i>graph</i>       | The reference to the graph.                                       |
| in | <i>input</i>       | The input image of type <a href="#">VX_DF_IMAGE_U8</a> .          |
| in | <i>cell_width</i>  | The histogram cell width of type <a href="#">VX_TYPE_INT32</a> .  |
| in | <i>cell_height</i> | The histogram cell height of type <a href="#">VX_TYPE_INT32</a> . |
| in | <i>num_bins</i>    | The histogram size of type <a href="#">VX_TYPE_INT32</a> .        |

## Parameters

|     |                   |                                                                                                                                                                                                                   |
|-----|-------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| out | <i>magnitudes</i> | (Optional) The output average gradient magnitudes per cell of <code>vx_tensor</code> of type <code>VX_TYPE_INT16</code> of size $[floor(image_{width}/cell_{width}), floor(image_{height}/cell_{height})]$ .      |
| out | <i>bins</i>       | The output gradient orientation histograms per cell of <code>vx_tensor</code> of type <code>VX_TYPE_INT16</code> of size $[floor(image_{width}/cell_{width}), floor(image_{height}/cell_{height}), num_{bins}]$ . |

## Returns

`vx_node`.

## Return values

|   |                            |
|---|----------------------------|
| 0 | Node could not be created. |
| * | Node handle.               |

**vx\_node VX\_API\_CALL vxHOGFeaturesNode ( vx\_graph graph, vx\_image input, vx\_tensor magnitudes, vx\_tensor bins, const vx\_hog\_t \* params, vx\_size hog\_param\_size, vx\_tensor features )**

[Graph] The node produces HOG features for the W1xW2 window in a sliding window fashion over the whole input image. Each position produces a HOG feature vector.

Firstly if a magnitudes tensor is provided the cell histograms in the bins tensor are normalised by the average cell gradient magnitudes.

$$bins(c, n) = \frac{bins(c, n)}{magnitudes(c)}$$

To account for changes in illumination and contrast the cell histograms must be locally normalized which requires grouping the cell histograms together into larger spatially connected blocks. Blocks are rectangular grids represented by three parameters: the number of cells per block, the number of pixels per cell, and the number of bins per cell histogram. These blocks typically overlap, meaning that each cell histogram contributes more than once to the final descriptor. To normalize a block its cell histograms  $h$  are grouped together to form a vector  $v = [h_1, h_2, h_3, \dots, h_n]$ . This vector is normalised using L2-Hys which means performing L2-norm on this vector; clipping the result (by limiting the maximum values of  $v$  to be threshold) and renormalizing again. If the threshold is equal to zero then L2-Hys normalization is not performed.

$$L2norm(v) = \frac{v}{\sqrt{\|v\|_2^2 + \epsilon^2}}$$

where  $\|v\|_k$  be its k-norm for  $k=1, 2$ , and  $\epsilon$  be a small constant. For a specific window its HOG descriptor is then the concatenated vector of the components of the normalized cell histograms from all of the block regions contained in the window. The W1xW2 window starting position is at coordinates 0x0. If the input image has dimensions that are not an integer multiple of W1xW2 blocks with the specified stride, then the last positions that contain only a partial W1xW2 window will be calculated with the remaining part of the W1xW2 window padded with zeroes. The Window W1xW2 must also have a size so that it contains an integer number of cells, otherwise the node is not well-defined. The final output tensor will contain HOG descriptors equal to the number of windows in the input image. The output features tensor has 3 dimensions, given by:

$$\begin{aligned} & [(floor((image_{width} - window_{width})/window_{stride}) + 1), \\ & (floor((image_{height} - window_{height})/window_{stride}) + 1), \\ & floor((window_{width} - block_{width})/block_{stride} + 1) * floor((window_{height} - block_{height})/block_{stride} + 1) * \\ & (((block_{width} * block_{height})/(cell_{width} * cell_{height})) * num_{bins})] \end{aligned}$$

See `vxCreateTensor` and `vxCreateVirtualTensor`. We recommend the output tensors always be *virtual* objects, with this node connected directly to the classifier. The output tensor will be very large, and using non-virtual tensors will result in a poorly optimized implementation. Merging of this node with a classifier node such as that described in the classifier extension will result in better performance. Notice that this node creation function has

more parameters than the corresponding kernel. Numbering of kernel parameters (required if you create this node using the generic interface) is explicitly specified here.

#### Parameters

|     |                       |                                                                                                                                                                                              |
|-----|-----------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>          | The reference to the graph.                                                                                                                                                                  |
| in  | <i>input</i>          | The input image of type <a href="#">VX_DF_IMAGE_U8</a> . (Kernel parameter #0)                                                                                                               |
| in  | <i>magnitudes</i>     | (Optional) The gradient magnitudes per cell of <a href="#">vx_tensor</a> of type <a href="#">VX_TYPE_INT16</a> . It is the output of <a href="#">vxHOGCellsNode</a> . (Kernel parameter #1)  |
| in  | <i>bins</i>           | The gradient orientation histograms per cell of <a href="#">vx_tensor</a> of type <a href="#">VX_TYPE_INT16</a> . It is the output of <a href="#">vxHOGCellsNode</a> . (Kernel parameter #2) |
| in  | <i>params</i>         | The parameters of type <a href="#">vx_hog_t</a> . (Kernel parameter #3)                                                                                                                      |
| in  | <i>hog_param_size</i> | Size of <a href="#">vx_hog_t</a> in bytes. Note that this parameter is not counted as one of the kernel parameters.                                                                          |
| out | <i>features</i>       | The output HOG features of <a href="#">vx_tensor</a> of type <a href="#">VX_TYPE_INT16</a> . (Kernel parameter #4)                                                                           |

#### Returns

[vx\\_node](#).

#### Return values

|   |                            |
|---|----------------------------|
| 0 | Node could not be created. |
| * | Node handle.               |

**vx\_status VX\_API\_CALL vxuHOGCells ( vx\_context context, vx\_image input, vx\_int32 cell\_width, vx\_int32 cell\_height, vx\_int32 num\_bins, vx\_tensor magnitudes, vx\_tensor bins )**

[Immediate] Performs cell calculations for the average gradient magnitude and gradient orientation histograms.

Firstly, the gradient magnitude and gradient orientation are computed for each pixel in the input image. Two 1-D centred, point discrete derivative masks are applied to the input image in the horizontal and vertical directions.

$$M_h = [-1, 0, 1]$$

and

$$M_v = [-1, 0, 1]^T$$

$G_v$  is the result of applying mask  $M_v$  to the input image, and  $G_h$  is the result of applying mask  $M_h$  to the input image. The border mode used for the gradient calculation is implementation dependent. Its behavior should be similar to [VX\\_BORDER\\_UNDEFINED](#). The gradient magnitudes and gradient orientations for each pixel are then calculated in the following manner.

$$G(x, y) = \sqrt{G_v(x, y)^2 + G_h(x, y)^2}$$

$$\theta(x, y) = \arctan(G_v(x, y), G_h(x, y))$$

where  $\arctan(v, h)$  is  $\tan^{-1}(v/h)$  when  $h \neq 0$ ,

$-\pi/2$  if  $v < 0$  and  $h == 0$ ,

$\pi/2$  if  $v > 0$  and  $h == 0$

and 0 if  $v == 0$  and  $h == 0$

Secondly, the gradient magnitudes and orientations are used to compute the bins output tensor and optional magnitudes output tensor. These tensors are computed on a cell level where the cells are rectangular in shape. The magnitudes tensor contains the average gradient magnitude for each cell.

$$\text{magnitudes}(c) = \frac{1}{(\text{cell\_width} * \text{cell\_height})} \sum_{w=0}^{\text{cell\_width}-1} \sum_{h=0}^{\text{cell\_height}-1} G_c(w, h)$$

where  $G_c$  is the gradient magnitudes related to cell  $c$ . The bins tensor contains histograms of gradient orientations for each cell. The gradient orientations at each pixel range from 0 to 360 degrees. These are quantised into a set of histogram bins based on the `num_bins` parameter. Each pixel votes for a specific cell histogram bin based on its gradient orientation. The vote itself is the pixel's gradient magnitude.

$$bins(c, n) = \sum_{w=0}^{cell\_width} \sum_{h=0}^{cell\_height} G_c(w, h) * 1[B_c(w, h, num\_bins) == n]$$

where  $B_c$  produces the histogram bin number based on the gradient orientation of the pixel at location  $(w, h)$  in cell  $c$  based on the `num_bins` and

$$1[B_c(w, h, num\_bins) == n]$$

is a delta-function with value 1 when  $B_c(w, h, num\_bins) == n$  or 0 otherwise.

#### Parameters

|     |                          |                                                                                                                                                                                                              |
|-----|--------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <code>context</code>     | The reference to the overall context.                                                                                                                                                                        |
| in  | <code>input</code>       | The input image of type <code>VX_DF_IMAGE_U8</code> .                                                                                                                                                        |
| in  | <code>cell_width</code>  | The histogram cell width of type <code>VX_TYPE_INT32</code> .                                                                                                                                                |
| in  | <code>cell_height</code> | The histogram cell height of type <code>VX_TYPE_INT32</code> .                                                                                                                                               |
| in  | <code>num_bins</code>    | The histogram size of type <code>VX_TYPE_INT32</code> .                                                                                                                                                      |
| out | <code>magnitudes</code>  | The output average gradient magnitudes per cell of <code>vx_tensor</code> of type <code>VX_TYPE_INT16</code> of size $[floor(image\_width/cell\_width), floor(image\_height/cell\_height)]$ .                |
| out | <code>bins</code>        | The output gradient orientation histograms per cell of <code>vx_tensor</code> of type <code>VX_TYPE_INT16</code> of size $[floor(image\_width/cell\_width), floor(image\_height/cell\_height), num\_bins]$ . |

#### Returns

A `vx_status_e` enumeration.

#### Return values

|                         |                                                   |
|-------------------------|---------------------------------------------------|
| <code>VX_SUCCESS</code> | Success                                           |
| *                       | An error occurred. See <code>vx_status_e</code> . |

**`vx_status VX_API_CALL vxuHOGFeatures ( vx_context context, vx_image input, vx_tensor magnitudes, vx_tensor bins, const vx_hog_t * params, vx_size hog_param_size, vx_tensor features )`**

[Immediate] Computes Histogram of Oriented Gradients features for the W1xW2 window in a sliding window fashion over the whole input image.

Firstly if a `magnitudes` tensor is provided the cell histograms in the `bins` tensor are normalised by the average cell gradient magnitudes.

$$bins(c, n) = \frac{bins(c, n)}{magnitudes(c)}$$

To account for changes in illumination and contrast the cell histograms must be locally normalized which requires grouping the cell histograms together into larger spatially connected blocks. Blocks are rectangular grids represented by three parameters: the number of cells per block, the number of pixels per cell, and the number of bins per cell histogram. These blocks typically overlap, meaning that each cell histogram contributes more than once to the final descriptor. To normalize a block its cell histograms  $h$  are grouped together to form a vector  $v = [h_1, h_2, h_3, \dots, h_n]$ . This vector is normalised using L2-Hys which means performing L2-norm on this vector; clipping the result (by limiting the maximum values of  $v$  to be threshold) and renormalizing again. If the threshold is equal to zero then L2-Hys normalization is not performed.

$$L2norm(v) = \frac{v}{\sqrt{\|v\|_2^2 + \epsilon^2}}$$

where  $\|v\|_k$  be its k-norm for  $k=1, 2$ , and  $\epsilon$  be a small constant. For a specific window its HOG descriptor is then the concatenated vector of the components of the normalized cell histograms from all of the block regions contained in the window. The  $W1 \times W2$  window starting position is at coordinates  $0 \times 0$ . If the input image has dimensions that are not an integer multiple of  $W1 \times W2$  blocks with the specified stride, then the last positions that contain only a partial  $W1 \times W2$  window will be calculated with the remaining part of the  $W1 \times W2$  window padded with zeroes. The Window  $W1 \times W2$  must also have a size so that it contains an integer number of cells, otherwise the node is not well-defined. The final output tensor will contain HOG descriptors equal to the number of windows in the input image. The output features tensor has 3 dimensions, given by:

$$\begin{aligned} &[(\text{floor}((\text{image}_{\text{width}} - \text{window}_{\text{width}})/\text{window}_{\text{stride}}) + 1), \\ &(\text{floor}((\text{image}_{\text{height}} - \text{window}_{\text{height}})/\text{window}_{\text{stride}}) + 1), \\ &\text{floor}((\text{window}_{\text{width}} - \text{block}_{\text{width}})/\text{block}_{\text{stride}} + 1) * \text{floor}((\text{window}_{\text{height}} - \text{block}_{\text{height}})/\text{block}_{\text{stride}} + 1) * \\ &(((\text{block}_{\text{width}} * \text{block}_{\text{height}})/(\text{cell}_{\text{width}} * \text{cell}_{\text{height}})) * \text{num}_{\text{bins}})] \end{aligned}$$

See [vxCreateTensor](#) and [vxCreateVirtualTensor](#). The output tensor from this function may be very large. For this reason, is it not recommended that this "immediate mode" version of the function be used. The preferred method to perform this function is as graph node with a virtual tensor as the output.

#### Parameters

|     |                       |                                                                                                                                                                    |
|-----|-----------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>context</i>        | The reference to the overall context.                                                                                                                              |
| in  | <i>input</i>          | The input image of type <a href="#">VX_DF_IMAGE_U8</a> .                                                                                                           |
| in  | <i>magnitudes</i>     | The average gradient magnitudes per cell of <a href="#">vx_tensor</a> of type <a href="#">VX_TYPE_INT16</a> . It is the output of <a href="#">vxuHOGCells</a> .    |
| in  | <i>bins</i>           | The gradient orientation histogram per cell of <a href="#">vx_tensor</a> of type <a href="#">VX_TYPE_INT16</a> . It is the output of <a href="#">vxuHOGCells</a> . |
| in  | <i>params</i>         | The parameters of type <a href="#">vx_hog_t</a> .                                                                                                                  |
| in  | <i>hog_param_size</i> | Size of <a href="#">vx_hog_t</a> in bytes.                                                                                                                         |
| out | <i>features</i>       | The output HOG features of <a href="#">vx_tensor</a> of type <a href="#">VX_TYPE_INT16</a> .                                                                       |

#### Returns

A [vx\\_status\\_e](#) enumeration.

#### Return values

|                            |                                                      |
|----------------------------|------------------------------------------------------|
| <a href="#">VX_SUCCESS</a> | Success                                              |
| *                          | An error occurred. See <a href="#">vx_status_e</a> . |



## 3.54 HoughLinesP

### 3.54.1 Detailed Description

Finds the Probabilistic Hough Lines detected in the input binary image.

The node implement the Progressive Probabilistic Hough Transform described in Matas, J. and Galambos, C. and Kittler, J.V., Robust Detection of Lines Using the Progressive Probabilistic Hough Transform. CVIU 78 1, pp 119-137 (2000) The linear Hough transform algorithm uses a two-dimensional array, called an accumulator, to detect the existence of a line described by  $r = x \cos \theta + y \sin \theta$ . The dimension of the accumulator equals the number of unknown parameters, i.e., two, considering quantized values of  $r$  and  $\theta$  in the pair  $(r, \theta)$ . For each pixel at  $(x, y)$  and its neighbourhood, the Hough transform algorithm determines if there is enough evidence of a straight line at that pixel. If so, it will calculate the parameters  $(r, \theta)$  of that line, and then look for the accumulator's bin that the parameters fall into, and increment the value of that bin./n Algorithm Outline:

1. Check the input image; if it is empty then finish.
2. Update the accumulator with a single pixel randomly selected from the input image.
3. Remove the selected pixel from input image.
4. Check if the highest peak in the accumulator that was modified by the new pixel is higher than threshold. If not then goto 1.
5. Look along a corridor specified by the peak in the accumulator, and find the longest segment that either is continuous or exhibits a gap not exceeding a given threshold.
6. Remove the pixels in the segment from input image.
7. "Unvote" from the accumulator all the pixels from the line that have previously voted.
8. If the line segment is longer than the minimum length add it into the output list.
9. Goto 1 each line is stored in `vx_line2d_t` struct. Such that `start_x <= end_x`.

### Data Structures

- struct `vx_hough_lines_p_t`  
Hough lines probability parameters. [More...](#)

### Functions

- `vx_node VX_API_CALL vxHoughLinesPNode` (`vx_graph` graph, `vx_image` input, const `vx_hough_lines_p_t` \*params, `vx_array` lines\_array, `vx_scalar` num\_lines)  
[Graph] Finds the Probabilistic Hough Lines detected in the input binary image, each line is stored in the output array as a set of points  $(x1, y1, x2, y2)$ .
- `vx_status VX_API_CALL vxuHoughLinesP` (`vx_context` context, `vx_image` input, const `vx_hough_lines_p_t` \*params, `vx_array` lines\_array, `vx_scalar` num\_lines)  
[Immediate] Finds the Probabilistic Hough Lines detected in the input binary image, each line is stored in the output array as a set of points  $(x1, y1, x2, y2)$ .

### 3.54.2 Data Structure Documentation

#### struct `vx_hough_lines_p_t`

Hough lines probability parameters.

Definition at line 1552 of file `vx_types.h`.

#### Data Fields

|                         |       |                                                 |
|-------------------------|-------|-------------------------------------------------|
| <code>vx_float32</code> | rho   | Distance resolution of the parameter in pixels. |
| <code>vx_float32</code> | theta | Angle resolution of the parameter in radians.   |

## Data Fields

|                            |             |                                                                                                  |
|----------------------------|-------------|--------------------------------------------------------------------------------------------------|
| <a href="#">vx_int32</a>   | threshold   | The minimum number of intersections to detect a line.                                            |
| <a href="#">vx_int32</a>   | line_length | The minimum number of points that can form a line. Line segments shorter than that are rejected. |
| <a href="#">vx_int32</a>   | line_gap    | The maximum allowed gap between points on the same line to link them.                            |
| <a href="#">vx_float32</a> | theta_max   | Optional restriction on theta. The max allowed value.                                            |
| <a href="#">vx_float32</a> | theta_min   | Optional restriction on theta. The min allowed value.                                            |

## 3.54.3 Function Documentation

**`vx_node VX_API_CALL vxHoughLinesPNode ( vx_graph graph, vx_image input, const vx_hough_lines_p_t * params, vx_array lines_array, vx_scalar num_lines )`**

[Graph] Finds the Probabilistic Hough Lines detected in the input binary image, each line is stored in the output array as a set of points (x1, y1, x2, y2) .

Some implementations of the algorithm may have a random or non-deterministic element. If the target application is in a safety-critical environment this should be borne in mind and steps taken in the implementation, the application or both to achieve the level of determinism required by the system design.

## Parameters

|     |                    |                                                                                                                     |
|-----|--------------------|---------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>       | graph handle                                                                                                        |
| in  | <i>input</i>       | 8 bit, single channel binary source image                                                                           |
| in  | <i>params</i>      | parameters of the struct <a href="#">vx_hough_lines_p_t</a>                                                         |
| out | <i>lines_array</i> | lines_array contains array of lines, see <a href="#">vx_line2d_t</a> The order of lines in implementation dependent |
| out | <i>num_lines</i>   | [optional] The total number of detected lines in image. Use a VX_TYPE_SIZE scalar                                   |

## Returns

[vx\\_node](#).

## Return values

|                         |                                                                                                                            |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|
| <a href="#">vx_node</a> | A node reference. Any possible errors preventing a successful creation should be checked using <a href="#">vxGetStatus</a> |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------|

**`vx_status VX_API_CALL vxuHoughLinesP ( vx_context context, vx_image input, const vx_hough_lines_p_t * params, vx_array lines_array, vx_scalar num_lines )`**

[Immediate] Finds the Probabilistic Hough Lines detected in the input binary image, each line is stored in the output array as a set of points (x1, y1, x2, y2) .

Some implementations of the algorithm may have a random or non-deterministic element. If the target application is in a safety-critical environment this should be borne in mind and steps taken in the implementation, the application or both to achieve the level of determinism required by the system design.

## Parameters

|     |                    |                                                                                                                     |
|-----|--------------------|---------------------------------------------------------------------------------------------------------------------|
| in  | <i>context</i>     | The reference to the overall context.                                                                               |
| in  | <i>input</i>       | 8 bit, single channel binary source image                                                                           |
| in  | <i>params</i>      | parameters of the struct <a href="#">vx_hough_lines_p_t</a>                                                         |
| out | <i>lines_array</i> | lines_array contains array of lines, see <a href="#">vx_line2d_t</a> The order of lines in implementation dependent |

**Parameters**

|     |                  |                                                                                                |
|-----|------------------|------------------------------------------------------------------------------------------------|
| out | <i>num_lines</i> | [optional] The total number of detected lines in image. Use a <code>VX_TYPE_SIZE</code> scalar |
|-----|------------------|------------------------------------------------------------------------------------------------|

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                         |                                                   |
|-------------------------|---------------------------------------------------|
| <code>VX_SUCCESS</code> | Success                                           |
| *                       | An error occurred. See <code>vx_status_e</code> . |

## 3.55 Tensor Multiply

### 3.55.1 Detailed Description

Performs element wise multiplications on element values in the input tensor data with a scale.

Pixel-wise multiplication is performed between the pixel values in two tensors and a scalar floating-point number *scale*. The scale with a value of  $1/2^n$ , where  $n$  is an integer and  $0 \leq n \leq 15$ , and 1/255 (0x1.010102p-8 C99 float hex) must be supported. The support for other values of scale is not prohibited. Furthermore, for scale with a value of 1/255 the rounding policy of `VX_ROUND_POLICY_TO_NEAREST_EVEN` must be supported whereas for the scale with value of  $1/2^n$  the rounding policy of `VX_ROUND_POLICY_TO_ZERO` must be supported. The support of other rounding modes for any values of scale is not prohibited.

### Functions

- `vx_node VX_API_CALL vxTensorMultiplyNode` (`vx_graph` graph, `vx_tensor` input1, `vx_tensor` input2, `vx_scalar` scale, `vx_enum` overflow\_policy, `vx_enum` rounding\_policy, `vx_tensor` output)  
[Graph] Performs element wise multiplications on element values in the input tensor data with a scale.
- `vx_status VX_API_CALL vxuTensorMultiply` (`vx_context` context, `vx_tensor` input1, `vx_tensor` input2, `vx_scalar` scale, `vx_enum` overflow\_policy, `vx_enum` rounding\_policy, `vx_tensor` output)  
[Immediate] Performs element wise multiplications on element values in the input tensor data with a scale.

### 3.55.2 Function Documentation

**`vx_node VX_API_CALL vxTensorMultiplyNode` ( `vx_graph` graph, `vx_tensor` input1, `vx_tensor` input2, `vx_scalar` scale, `vx_enum` overflow\_policy, `vx_enum` rounding\_policy, `vx_tensor` output )**

[Graph] Performs element wise multiplications on element values in the input tensor data with a scale.

#### Parameters

|     |                 |                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
|-----|-----------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | graph           | The handle to the graph.                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| in  | input1          | Input tensor data. Implementations must support input tensor data type <code>VX_TYPE_INT16</code> with fixed_point_position 8, and tensor data types <code>VX_TYPE_UINT8</code> and <code>VX_TYPE_INT8</code> , with fixed_point_position 0.                                                                                                                                                                                                                 |
| in  | input2          | Input tensor data. The dimensions and sizes of input2 match those of input1, unless the <code>vx_tensor</code> of one or more dimensions in input2 is 1. In this case, those dimensions are treated as if this tensor was expanded to match the size of the corresponding dimension of input1, and data was duplicated on all terms in that dimension. After this expansion, the dimensions will be equal. The data type must match the data type of Input1. |
| in  | scale           | A non-negative <code>VX_TYPE_FLOAT32</code> multiplied to each product before overflow handling.                                                                                                                                                                                                                                                                                                                                                             |
| in  | overflow_policy | A <code>vx_convert_policy_e</code> enumeration.                                                                                                                                                                                                                                                                                                                                                                                                              |
| in  | rounding_policy | A <code>vx_round_policy_e</code> enumeration.                                                                                                                                                                                                                                                                                                                                                                                                                |
| out | output          | The output tensor data with the same dimensions as the input tensor data.                                                                                                                                                                                                                                                                                                                                                                                    |

#### Returns

`vx_node`.

A node reference `vx_node`. Any possible errors preventing a successful creation should be checked using `vxGetStatus`.

**`vx_status VX_API_CALL vxuTensorMultiply` ( `vx_context` context, `vx_tensor` input1, `vx_tensor` input2, `vx_scalar` scale, `vx_enum` overflow\_policy, `vx_enum` rounding\_policy, `vx_tensor` output )**

[Immediate] Performs element wise multiplications on element values in the input tensor data with a scale.

**Parameters**

|     |                        |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
|-----|------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>context</i>         | The reference to the overall context.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
| in  | <i>input1</i>          | Input tensor data. Implementations must support input tensor data type <a href="#">VX_TYPE_INT16</a> with <code>fixed_point_position</code> 8, and tensor data types <a href="#">VX_TYPE_UINT8</a> and <a href="#">VX_TYPE_INT8</a> , with <code>fixed_point_position</code> 0.                                                                                                                                                                                                                                                  |
| in  | <i>input2</i>          | Input tensor data. The dimensions and sizes of <code>input2</code> match those of <code>input1</code> , unless the <code>vx_tensor</code> of one or more dimensions in <code>input2</code> is 1. In this case, those dimensions are treated as if this tensor was expanded to match the size of the corresponding dimension of <code>input1</code> , and data was duplicated on all terms in that dimension. After this expansion, the dimensions will be equal. The data type must match the data type of <code>input1</code> . |
| in  | <i>scale</i>           | A non-negative <a href="#">VX_TYPE_FLOAT32</a> multiplied to each product before overflow handling.                                                                                                                                                                                                                                                                                                                                                                                                                              |
| in  | <i>overflow_policy</i> | A <a href="#">vx_convert_policy_e</a> enumeration.                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
| in  | <i>rounding_policy</i> | A <a href="#">vx_round_policy_e</a> enumeration.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| out | <i>output</i>          | The output tensor data with the same dimensions as the input tensor data.                                                                                                                                                                                                                                                                                                                                                                                                                                                        |

**Returns**

A [vx\\_status\\_e](#) enumeration.

**Return values**

|                            |                                                      |
|----------------------------|------------------------------------------------------|
| <a href="#">VX_SUCCESS</a> | Success                                              |
| *                          | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.56 Tensor Add

### 3.56.1 Detailed Description

Performs arithmetic addition on element values in the input tensor data.

#### Functions

- `vx_node VX_API_CALL vxTensorAddNode` (`vx_graph` *graph*, `vx_tensor` *input1*, `vx_tensor` *input2*, `vx_enum` *policy*, `vx_tensor` *output*)  
*[Graph]* Performs arithmetic addition on element values in the input tensor data.
- `vx_status VX_API_CALL vxuTensorAdd` (`vx_context` *context*, `vx_tensor` *input1*, `vx_tensor` *input2*, `vx_enum` *policy*, `vx_tensor` *output*)  
*[Immediate]* Performs arithmetic addition on element values in the input tensor data.

### 3.56.2 Function Documentation

**`vx_node VX_API_CALL vxTensorAddNode` ( `vx_graph` *graph*, `vx_tensor` *input1*, `vx_tensor` *input2*, `vx_enum` *policy*, `vx_tensor` *output* )**

*[Graph]* Performs arithmetic addition on element values in the input tensor data.

#### Parameters

|     |               |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
|-----|---------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>  | The handle to the graph.                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
| in  | <i>input1</i> | Input tensor data. Implementations must support input tensor data type <code>VX_TYPE_INT16</code> with <code>fixed_point_position</code> 8, and tensor data types <code>VX_TYPE_UINT8</code> and <code>VX_TYPE_INT8</code> , with <code>fixed_point_position</code> 0.                                                                                                                                                                                                                             |
| in  | <i>input2</i> | Input tensor data. The dimensions and sizes of <i>input2</i> match those of <i>input1</i> , unless the <code>vx_tensor</code> of one or more dimensions in <i>input2</i> is 1. In this case, those dimensions are treated as if this tensor was expanded to match the size of the corresponding dimension of <i>input1</i> , and data was duplicated on all terms in that dimension. After this expansion, the dimensions will be equal. The data type must match the data type of <i>Input1</i> . |
| in  | <i>policy</i> | A <code>vx_convert_policy_e</code> enumeration.                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
| out | <i>output</i> | The output tensor data with the same dimensions as the input tensor data.                                                                                                                                                                                                                                                                                                                                                                                                                          |

#### Returns

`vx_node`.

A node reference `vx_node`. Any possible errors preventing a successful creation should be checked using `vxGetStatus`.

**`vx_status VX_API_CALL vxuTensorAdd` ( `vx_context` *context*, `vx_tensor` *input1*, `vx_tensor` *input2*, `vx_enum` *policy*, `vx_tensor` *output* )**

*[Immediate]* Performs arithmetic addition on element values in the input tensor data.

#### Parameters

|    |                |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
|----|----------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>context</i> | The reference to the overall context.                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
| in | <i>input1</i>  | Input tensor data. Implementations must support input tensor data type <code>VX_TYPE_INT16</code> with <code>fixed_point_position</code> 8, and tensor data types <code>VX_TYPE_UINT8</code> and <code>VX_TYPE_INT8</code> , with <code>fixed_point_position</code> 0.                                                                                                                                                                                                                             |
| in | <i>input2</i>  | Input tensor data. The dimensions and sizes of <i>input2</i> match those of <i>input1</i> , unless the <code>vx_tensor</code> of one or more dimensions in <i>input2</i> is 1. In this case, those dimensions are treated as if this tensor was expanded to match the size of the corresponding dimension of <i>input1</i> , and data was duplicated on all terms in that dimension. After this expansion, the dimensions will be equal. The data type must match the data type of <i>Input1</i> . |

**Parameters**

|     |               |                                                                           |
|-----|---------------|---------------------------------------------------------------------------|
| in  | <i>policy</i> | A <a href="#">vx_convert_policy_e</a> enumeration.                        |
| out | <i>output</i> | The output tensor data with the same dimensions as the input tensor data. |

**Returns**

A [vx\\_status\\_e](#) enumeration.

**Return values**

|                            |                                                      |
|----------------------------|------------------------------------------------------|
| <a href="#">VX_SUCCESS</a> | Success                                              |
| *                          | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.57 Tensor Subtract

### 3.57.1 Detailed Description

Performs arithmetic subtraction on element values in the input tensor data.

#### Functions

- `vx_node VX_API_CALL vxTensorSubtractNode` (`vx_graph` *graph*, `vx_tensor` *input1*, `vx_tensor` *input2*, `vx_enum` *policy*, `vx_tensor` *output*)  
*[Graph] Performs arithmetic subtraction on element values in the input tensor data.*
- `vx_status VX_API_CALL vxuTensorSubtract` (`vx_context` *context*, `vx_tensor` *input1*, `vx_tensor` *input2*, `vx_enum` *policy*, `vx_tensor` *output*)  
*[Immediate] Performs arithmetic subtraction on element values in the input tensor data.*

### 3.57.2 Function Documentation

**`vx_node VX_API_CALL vxTensorSubtractNode` ( `vx_graph` *graph*, `vx_tensor` *input1*, `vx_tensor` *input2*, `vx_enum` *policy*, `vx_tensor` *output* )**

*[Graph] Performs arithmetic subtraction on element values in the input tensor data.*

#### Parameters

|     |               |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
|-----|---------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>  | The handle to the graph.                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
| in  | <i>input1</i> | Input tensor data. Implementations must support input tensor data type <code>VX_TYPE_INT16</code> with <code>fixed_point_position</code> 8, and tensor data types <code>VX_TYPE_UINT8</code> and <code>VX_TYPE_INT8</code> , with <code>fixed_point_position</code> 0.                                                                                                                                                                                                                             |
| in  | <i>input2</i> | Input tensor data. The dimensions and sizes of <i>input2</i> match those of <i>input1</i> , unless the <code>vx_tensor</code> of one or more dimensions in <i>input2</i> is 1. In this case, those dimensions are treated as if this tensor was expanded to match the size of the corresponding dimension of <i>input1</i> , and data was duplicated on all terms in that dimension. After this expansion, the dimensions will be equal. The data type must match the data type of <i>input1</i> . |
| in  | <i>policy</i> | A <code>vx_convert_policy_e</code> enumeration.                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
| out | <i>output</i> | The output tensor data with the same dimensions as the input tensor data.                                                                                                                                                                                                                                                                                                                                                                                                                          |

#### Returns

`vx_node`.

A node reference `vx_node`. Any possible errors preventing a successful creation should be checked using `vxGetStatus`.

**`vx_status VX_API_CALL vxuTensorSubtract` ( `vx_context` *context*, `vx_tensor` *input1*, `vx_tensor` *input2*, `vx_enum` *policy*, `vx_tensor` *output* )**

*[Immediate] Performs arithmetic subtraction on element values in the input tensor data.*

#### Parameters

|    |                |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
|----|----------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>context</i> | The reference to the overall context.                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
| in | <i>input1</i>  | Input tensor data. Implementations must support input tensor data type <code>VX_TYPE_INT16</code> with <code>fixed_point_position</code> 8, and tensor data types <code>VX_TYPE_UINT8</code> and <code>VX_TYPE_INT8</code> , with <code>fixed_point_position</code> 0.                                                                                                                                                                                                                             |
| in | <i>input2</i>  | Input tensor data. The dimensions and sizes of <i>input2</i> match those of <i>input1</i> , unless the <code>vx_tensor</code> of one or more dimensions in <i>input2</i> is 1. In this case, those dimensions are treated as if this tensor was expanded to match the size of the corresponding dimension of <i>input1</i> , and data was duplicated on all terms in that dimension. After this expansion, the dimensions will be equal. The data type must match the data type of <i>input1</i> . |



**Parameters**

|     |               |                                                                           |
|-----|---------------|---------------------------------------------------------------------------|
| in  | <i>policy</i> | A <a href="#">vx_convert_policy_e</a> enumeration.                        |
| out | <i>output</i> | The output tensor data with the same dimensions as the input tensor data. |

**Returns**

A [vx\\_status\\_e](#) enumeration.

**Return values**

|                            |                                                      |
|----------------------------|------------------------------------------------------|
| <a href="#">VX_SUCCESS</a> | Success                                              |
| *                          | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.58 TensorTableLookup

### 3.58.1 Detailed Description

Performs LUT on element values in the input tensor data.

This kernel uses each element in a tensor to index into a LUT and put the indexed LUT value into the output tensor. The tensor types supported are `VX_TYPE_UINT8` and `VX_TYPE_INT16`. Signed inputs are cast to unsigned before used as input indexes to the LUT.

### Functions

- `vx_node VX_API_CALL vxTensorTableLookupNode` (`vx_graph` *graph*, `vx_tensor` *input1*, `vx_lut` *lut*, `vx_tensor` *output*)  
*[Graph] Performs LUT on element values in the input tensor data.*
- `vx_status VX_API_CALL vxuTensorTableLookup` (`vx_context` *context*, `vx_tensor` *input1*, `vx_lut` *lut*, `vx_tensor` *output*)  
*[Immediate] Performs LUT on element values in the input tensor data.*

### 3.58.2 Function Documentation

**`vx_node VX_API_CALL vxTensorTableLookupNode` ( `vx_graph` *graph*, `vx_tensor` *input1*, `vx_lut` *lut*, `vx_tensor` *output* )**

*[Graph] Performs LUT on element values in the input tensor data.*

#### Parameters

|     |               |                                                                                                                                                                                                                                                            |
|-----|---------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>  | The handle to the graph.                                                                                                                                                                                                                                   |
| in  | <i>input1</i> | Input tensor data. Implementations must support input tensor data type <code>VX_TYPE_INT16</code> with <code>fixed_point_position</code> 8, and tensor data types <code>VX_TYPE_UINT8</code> , with <code>fixed_point_position</code> 0.                   |
| in  | <i>lut</i>    | The look-up table to use, of type <code>vx_lut</code> . The elements of <i>input1</i> are treated as unsigned integers to determine an index into the look-up table. The data type of the items in the look-up table must match that of the output tensor. |
| out | <i>output</i> | The output tensor data with the same dimensions as the input tensor data.                                                                                                                                                                                  |

#### Returns

`vx_node`.

A node reference `vx_node`. Any possible errors preventing a successful creation should be checked using `vxGetStatus`.

**`vx_status VX_API_CALL vxuTensorTableLookup` ( `vx_context` *context*, `vx_tensor` *input1*, `vx_lut` *lut*, `vx_tensor` *output* )**

*[Immediate] Performs LUT on element values in the input tensor data.*

#### Parameters

|     |                |                                                                                                                                                                                                                                                            |
|-----|----------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>context</i> | The reference to the overall context.                                                                                                                                                                                                                      |
| in  | <i>input1</i>  | Input tensor data. Implementations must support input tensor data type <code>VX_TYPE_INT16</code> with <code>fixed_point_position</code> 8, and tensor data types <code>VX_TYPE_UINT8</code> , with <code>fixed_point_position</code> 0.                   |
| in  | <i>lut</i>     | The look-up table to use, of type <code>vx_lut</code> . The elements of <i>input1</i> are treated as unsigned integers to determine an index into the look-up table. The data type of the items in the look-up table must match that of the output tensor. |
| out | <i>output</i>  | The output tensor data with the same dimensions as the input tensor data.                                                                                                                                                                                  |

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                         |                                                   |
|-------------------------|---------------------------------------------------|
| <code>VX_SUCCESS</code> | Success                                           |
| *                       | An error occurred. See <code>vx_status_e</code> . |

## 3.59 Tensor Transpose

### 3.59.1 Detailed Description

Performs transpose on the input tensor.

#### Functions

- **`vx_node VX_API_CALL vxTensorTransposeNode`** (`vx_graph` *graph*, `vx_tensor` *input*, `vx_tensor` *output*, `vx_size` *dimension1*, `vx_size` *dimension2*)  
*[Graph]* Performs transpose on the input tensor. The node transpose the tensor according to a specified 2 indexes in the tensor (0-based indexing)
- **`vx_status VX_API_CALL vxuTensorTranspose`** (`vx_context` *context*, `vx_tensor` *input*, `vx_tensor` *output*, `vx_size` *dimension1*, `vx_size` *dimension2*)  
*[Immediate]* Performs transpose on the input tensor. The tensor is transposed according to a specified 2 indexes in the tensor (0-based indexing)

### 3.59.2 Function Documentation

**`vx_node VX_API_CALL vxTensorTransposeNode`** ( `vx_graph` *graph*, `vx_tensor` *input*, `vx_tensor` *output*, `vx_size` *dimension1*, `vx_size` *dimension2* )

*[Graph]* Performs transpose on the input tensor. The node transpose the tensor according to a specified 2 indexes in the tensor (0-based indexing)

#### Parameters

|     |                   |                                                                                                                                                                                                                                                                        |
|-----|-------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>      | The handle to the graph.                                                                                                                                                                                                                                               |
| in  | <i>input</i>      | Input tensor data, Implementations must support input tensor data type <code>VX_TYPE_INT16</code> with <code>fixed_point_position</code> 8, and tensor data types <code>VX_TYPE_UINT8</code> and <code>VX_TYPE_INT8</code> , with <code>fixed_point_position</code> 0. |
| out | <i>output</i>     | output tensor data,                                                                                                                                                                                                                                                    |
| in  | <i>dimension1</i> | Dimension index that is transposed with dim 2.                                                                                                                                                                                                                         |
| in  | <i>dimension2</i> | Dimension index that is transposed with dim 1.                                                                                                                                                                                                                         |

#### Returns

`vx_node`.

A node reference `vx_node`. Any possible errors preventing a successful creation should be checked using `vxGetStatus`.

**`vx_status VX_API_CALL vxuTensorTranspose`** ( `vx_context` *context*, `vx_tensor` *input*, `vx_tensor` *output*, `vx_size` *dimension1*, `vx_size` *dimension2* )

*[Immediate]* Performs transpose on the input tensor. The tensor is transposed according to a specified 2 indexes in the tensor (0-based indexing)

#### Parameters

|     |                   |                                                                                                                                                                                                                                                                        |
|-----|-------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>context</i>    | The reference to the overall context.                                                                                                                                                                                                                                  |
| in  | <i>input</i>      | Input tensor data, Implementations must support input tensor data type <code>VX_TYPE_INT16</code> with <code>fixed_point_position</code> 8, and tensor data types <code>VX_TYPE_UINT8</code> and <code>VX_TYPE_INT8</code> , with <code>fixed_point_position</code> 0. |
| out | <i>output</i>     | output tensor data,                                                                                                                                                                                                                                                    |
| in  | <i>dimension1</i> | Dimension index that is transposed with dim 2.                                                                                                                                                                                                                         |
| in  | <i>dimension2</i> | Dimension index that is transposed with dim 1.                                                                                                                                                                                                                         |

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                         |                                                   |
|-------------------------|---------------------------------------------------|
| <code>VX_SUCCESS</code> | Success                                           |
| *                       | An error occurred. See <code>vx_status_e</code> . |

## 3.60 Tensor Convert Bit-Depth

### 3.60.1 Detailed Description

Creates a bit-depth conversion node.

Convert tensor from a specific data type and fixed point position to another data type and fixed point position. The equation for the conversion is as follows:

$$out\ put = \frac{\left(\frac{input}{2^{input\_fixed\_point\_position}} - offset\right)}{norm} * 2^{out\ put\_fixed\_point\_position}$$

Where offset and norm are the input parameters in `vx_float32`. `input_fixed_point_position` and `output_fixed_point_position` are the fixed point positions of the input and output respectively. In case input or output tensors are of `VX_TYPE_FLOAT32` fixed point position 0 is used.

### Functions

- `vx_node VX_API_CALL vxTensorConvertDepthNode (vx_graph graph, vx_tensor input, vx_enum policy, vx_scalar norm, vx_scalar offset, vx_tensor output)`  
[Graph] Creates a bit-depth conversion node.
- `vx_status VX_API_CALL vxuTensorConvertDepth (vx_context context, vx_tensor input, vx_enum policy, vx_scalar norm, vx_scalar offset, vx_tensor output)`  
[Immediate] Performs a bit-depth conversion.

### 3.60.2 Function Documentation

**`vx_node VX_API_CALL vxTensorConvertDepthNode ( vx_graph graph, vx_tensor input, vx_enum policy, vx_scalar norm, vx_scalar offset, vx_tensor output )`**

[Graph] Creates a bit-depth conversion node.

#### Parameters

|     |               |                                                                                                                                                                                                                                                                       |
|-----|---------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>  | The reference to the graph.                                                                                                                                                                                                                                           |
| in  | <i>input</i>  | The input tensor. Implementations must support input tensor data type <code>VX_TYPE_INT16</code> with <code>fixed_point_position</code> 8, and tensor data types <code>VX_TYPE_UINT8</code> and <code>VX_TYPE_INT8</code> , with <code>fixed_point_position</code> 0. |
| in  | <i>policy</i> | A <code>VX_TYPE_ENUM</code> of the <code>vx_convert_policy_e</code> enumeration.                                                                                                                                                                                      |
| in  | <i>norm</i>   | A scalar containing a <code>VX_TYPE_FLOAT32</code> of the normalization value.                                                                                                                                                                                        |
| in  | <i>offset</i> | A scalar containing a <code>VX_TYPE_FLOAT32</code> of the offset value subtracted before normalization.                                                                                                                                                               |
| out | <i>output</i> | The output tensor. Implementations must support input tensor data type <code>VX_TYPE_INT16</code> with <code>fixed_point_position</code> 8. And <code>VX_TYPE_UINT8</code> with <code>fixed_point_position</code> 0.                                                  |

#### Returns

`vx_node`.

#### Return values

|                      |                                                                                                                         |
|----------------------|-------------------------------------------------------------------------------------------------------------------------|
| <code>vx_node</code> | A node reference. Any possible errors preventing a successful creation should be checked using <code>vxGetStatus</code> |
|----------------------|-------------------------------------------------------------------------------------------------------------------------|

**vx\_status VX\_API\_CALL vxuTensorConvertDepth ( vx\_context context, vx\_tensor input, vx\_enum policy, vx\_scalar norm, vx\_scalar offset, vx\_tensor output )**

[Immediate] Performs a bit-depth conversion.

#### Parameters

|     |                |                                                                                                                                                                                                                                                      |
|-----|----------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>context</i> | The reference to the overall context.                                                                                                                                                                                                                |
| in  | <i>input</i>   | The input tensor. Implementations must support input tensor data type <a href="#">VX_TYPE_INT16</a> with fixed_point_position 8, and tensor data types <a href="#">VX_TYPE_UINT8</a> and <a href="#">VX_TYPE_INT8</a> , with fixed_point_position 0. |
| in  | <i>policy</i>  | A <a href="#">VX_TYPE_ENUM</a> of the <a href="#">vx_convert_policy_e</a> enumeration.                                                                                                                                                               |
| in  | <i>norm</i>    | A scalar containing a <a href="#">VX_TYPE_FLOAT32</a> of the normalization value.                                                                                                                                                                    |
| in  | <i>offset</i>  | A scalar containing a <a href="#">VX_TYPE_FLOAT32</a> of the offset value subtracted before normalization.                                                                                                                                           |
| out | <i>output</i>  | The output tensor. Implementations must support input tensor data type <a href="#">VX_TYPE_INT16</a> . with fixed_point_position 8. And <a href="#">VX_TYPE_UINT8</a> with fixed_point_position 0.                                                   |

#### Returns

A [vx\\_status\\_e](#) enumeration.

#### Return values

|                            |                                                      |
|----------------------------|------------------------------------------------------|
| <a href="#">VX_SUCCESS</a> | Success                                              |
| *                          | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.61 Tensor Matrix Multiply

### 3.61.1 Detailed Description

Creates a generalized matrix multiplication node.

Performs:

$$output = T1(input1) * T2(input2) + T3(input3)$$

Where matrix multiplication is defined as:

$$C[i * L + j] = saturate(truncate(round(\sum_{k=1}^M (C[i * L + j] + ((int)A[i * M + k]) * ((int)B[k * L + j]))))))$$

where i,j are indexes from 1 to N,L respectively. C matrix is of size NxL. A matrix is of size NxM and B matrix is of size MxL. For signed integers, a fixed point calculation is performed with round, truncate and saturate according to the number of accumulator bits. round: rounding to nearest on the fractional part. truncate: at every multiplication result of 32bit is truncated after rounding. saturate: a saturation if performed on the accumulation and after the truncation, meaning no saturation is performed on the multiplication result.

### Data Structures

- struct [vx\\_tensor\\_matrix\\_multiply\\_params\\_t](#)  
Matrix Multiply Parameters. [More...](#)

### Functions

- [vx\\_node VX\\_API\\_CALL vxTensorMatrixMultiplyNode](#) ([vx\\_graph](#) graph, [vx\\_tensor](#) input1, [vx\\_tensor](#) input2, [vx\\_tensor](#) input3, const [vx\\_tensor\\_matrix\\_multiply\\_params\\_t](#) \*matrix\_multiply\_params, [vx\\_tensor](#) output)  
[Graph] Creates a generalized matrix multiplication node.
- [vx\\_status VX\\_API\\_CALL vxuTensorMatrixMultiply](#) ([vx\\_context](#) context, [vx\\_tensor](#) input1, [vx\\_tensor](#) input2, [vx\\_tensor](#) input3, const [vx\\_tensor\\_matrix\\_multiply\\_params\\_t](#) \*matrix\_multiply\_params, [vx\\_tensor](#) output)  
[Immediate] Performs a generalized matrix multiplication.

### 3.61.2 Data Structure Documentation

#### struct vx\_tensor\_matrix\_multiply\_params\_t

Matrix Multiply Parameters.

transpose\_input1/input2/input3 : if True the matrix is transposed before the operation, otherwise the matrix is used as is.

Definition at line 1590 of file [vx\\_types.h](#).

#### Data Fields

|                         |                  |                                                                                           |
|-------------------------|------------------|-------------------------------------------------------------------------------------------|
| <a href="#">vx_bool</a> | transpose_input1 | if True the matrix is transposed before the operation, otherwise the matrix is used as is |
| <a href="#">vx_bool</a> | transpose_input2 | if True the matrix is transposed before the operation, otherwise the matrix is used as is |
| <a href="#">vx_bool</a> | transpose_input3 | if True the matrix is transposed before the operation, otherwise the matrix is used as is |



### 3.61.3 Function Documentation

**vx\_node** **VX\_API\_CALL** vxTensorMatrixMultiplyNode ( vx\_graph *graph*, vx\_tensor *input1*, vx\_tensor *input2*, vx\_tensor *input3*, const vx\_tensor\_matrix\_multiply\_params\_t \* *matrix\_multiply\_params*, vx\_tensor *output* )

[Graph] Creates a generalized matrix multiplication node.

#### Parameters

|     |                               |                                                                                                                                                                                                      |
|-----|-------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>graph</i>                  | The reference to the graph.                                                                                                                                                                          |
| in  | <i>input1</i>                 | The first input 2D tensor of type <a href="#">VX_TYPE_INT16</a> with fixed_point_pos 8, or tensor data types <a href="#">VX_TYPE_UINT8</a> or <a href="#">VX_TYPE_INT8</a> , with fixed_point_pos 0. |
| in  | <i>input2</i>                 | The second 2D tensor. Must be in the same data type as input1.                                                                                                                                       |
| in  | <i>input3</i>                 | The third 2D tensor. Must be in the same data type as input1. [optional].                                                                                                                            |
| in  | <i>matrix_multiply_params</i> | Matrix multiply parameters, see <a href="#">vx_tensor_matrix_multiply_params_t</a> .                                                                                                                 |
| out | <i>output</i>                 | The output 2D tensor. Must be in the same data type as input1. Output dimension must agree the formula in the description.                                                                           |

#### Returns

[vx\\_node](#).

A node reference [vx\\_node](#). Any possible errors preventing a successful creation should be checked using [vxGetStatus](#).

**vx\_status** **VX\_API\_CALL** vxuTensorMatrixMultiply ( vx\_context *context*, vx\_tensor *input1*, vx\_tensor *input2*, vx\_tensor *input3*, const vx\_tensor\_matrix\_multiply\_params\_t \* *matrix\_multiply\_params*, vx\_tensor *output* )

[Immediate] Performs a generalized matrix multiplication.

#### Parameters

|     |                               |                                                                                                                                                                                                      |
|-----|-------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>context</i>                | The reference to the overall context.                                                                                                                                                                |
| in  | <i>input1</i>                 | The first input 2D tensor of type <a href="#">VX_TYPE_INT16</a> with fixed_point_pos 8, or tensor data types <a href="#">VX_TYPE_UINT8</a> or <a href="#">VX_TYPE_INT8</a> , with fixed_point_pos 0. |
| in  | <i>input2</i>                 | The second 2D tensor. Must be in the same data type as input1.                                                                                                                                       |
| in  | <i>input3</i>                 | The third 2D tensor. Must be in the same data type as input1. [optional].                                                                                                                            |
| in  | <i>matrix_multiply_params</i> | Matrix multiply parameters, see <a href="#">vx_tensor_matrix_multiply_params_t</a> .                                                                                                                 |
| out | <i>output</i>                 | The output 2D tensor. Must be in the same data type as input1. Output dimension must agree the formula in the description.                                                                           |

#### Returns

A [vx\\_status\\_e](#) enumeration.

#### Return values

|                            |                                                      |
|----------------------------|------------------------------------------------------|
| <a href="#">VX_SUCCESS</a> | Success                                              |
| *                          | An error occurred. See <a href="#">vx_status_e</a> . |

## 3.62 Basic Features

### 3.62.1 Detailed Description

The basic parts of OpenVX needed for computation.

Types in OpenVX intended to be derived from the C99 Section 7.18 standard definition of fixed width types.

#### Modules

- [Objects](#)

*Defines the basic objects within OpenVX.*

#### Data Structures

- struct [vx\\_coordinates2d\\_t](#)

*The 2D Coordinates structure. [More...](#)*

- struct [vx\\_coordinates2df\\_t](#)

*The floating-point 2D Coordinates structure. [More...](#)*

- struct [vx\\_coordinates3d\\_t](#)

*The 3D Coordinates structure. [More...](#)*

- struct [vx\\_keypoint\\_t](#)

*The keypoint data structure. [More...](#)*

- struct [vx\\_line2d\\_t](#)

*line struct [More...](#)*

- struct [vx\\_rectangle\\_t](#)

*The rectangle data structure that is shared with the users. The area of the rectangle can be computed as  $(end\_x - start\_x) * (end\_y - start\_y)$ . [More...](#)*

#### Macros

- [#define VX\\_API\\_CALL](#)

*Defines calling convention for OpenVX API.*

- [#define VX\\_ATTRIBUTE\\_BASE](#)(vendor, object) (((vendor) << 20) | (object << 8))

*Defines the manner in which to combine the Vendor and Object IDs to get the base value of the enumeration.*

- [#define VX\\_ATTRIBUTE\\_ID\\_MASK](#) (0x000000FF)

*An object's attribute ID is within the range of  $[0, 2^8 - 1]$  (inclusive).*

- [#define VX\\_CALLBACK](#)

*Defines calling convention for user callbacks.*

- [#define VX\\_DF\\_IMAGE](#)(a, b, c, d) ((a) | (b << 8) | (c << 16) | (d << 24))

*Converts a set of four chars into a `uint32_t` container of a `VX_DF_IMAGE` code.*

- [#define VX\\_ENUM\\_BASE](#)(vendor, id) (((vendor) << 20) | (id << 12))

*Defines the manner in which to combine the Vendor and Object IDs to get the base value of the enumeration.*

- [#define VX\\_ENUM\\_MASK](#) (0x0000FFFF)

*A generic enumeration list can have values between  $[0, 2^{12} - 1]$  (inclusive).*

- [#define VX\\_ENUM\\_TYPE](#)(e) (((vx\_uint32)e & VX\_ENUM\_TYPE\_MASK) >> 12)

*A macro to extract the enum type from an enumerated value.*

- [#define VX\\_ENUM\\_TYPE\\_MASK](#) (0x000FF000)

*A type of enumeration. The valid range is between  $[0, 2^8 - 1]$  (inclusive).*

- [#define VX\\_FMT\\_REF](#) "%p"

*Use to aid in debugging values in OpenVX.*

- [#define VX\\_FMT\\_SIZE](#) "%zu"

*Use to aid in debugging values in OpenVX.*

- [#define VX\\_KERNEL\\_BASE](#)(vendor, lib) (((vendor) << 20) | (lib << 12))

- Defines the manner in which to combine the Vendor and Library IDs to get the base value of the enumeration.*

  - #define `VX_KERNEL_MASK` (0x00000FFF)
  - An individual kernel in a library has its own unique ID within  $[0, 2^{12} - 1]$  (inclusive).*
  - #define `VX_LIBRARY(e)` (((`vx_uint32`)e & `VX_LIBRARY_MASK`) >> 12)
  - A macro to extract the kernel library enumeration from a enumerated kernel value.*
  - #define `VX_LIBRARY_MASK` (0x000FF000)
  - A library is a set of vision kernels with its own ID supplied by a vendor. The vendor defines the library ID. The range is  $[0, 2^8 - 1]$  inclusive.*
  - #define `VX_MAX_LOG_MESSAGE_LEN` (1024)
  - Defines the length of a message buffer to copy from the log, including the trailing zero.*
  - #define `VX_SCALE_UNITY` (1024u)
  - Use to indicate the 1:1 ratio in Q22.10 format.*
  - #define `VX_TYPE(e)` (((`vx_uint32`)e & `VX_TYPE_MASK`) >> 8)
  - A macro to extract the type from an enumerated attribute value.*
  - #define `VX_TYPE_MASK` (0x000FFF00)
  - A type mask removes the scalar/object type from the attribute. It is 3 nibbles in size and is contained between the third and second byte.*
  - #define `VX_VENDOR(e)` (((`vx_uint32`)e & `VX_VENDOR_MASK`) >> 20)
  - A macro to extract the vendor ID from the enumerated value.*
  - #define `VX_VENDOR_MASK` (0xFFFF0000)
  - Vendor IDs are 2 nibbles in size and are located in the upper byte of the 4 bytes of an enumeration.*
  - #define `VX_VERSION VX_VERSION_1_2`
  - Defines the OpenVX Version Number.*
  - #define `VX_VERSION_1_0` (`VX_VERSION_MAJOR`(1) | `VX_VERSION_MINOR`(0))
  - Defines the predefined version number for 1.0.*
  - #define `VX_VERSION_1_1` (`VX_VERSION_MAJOR`(1) | `VX_VERSION_MINOR`(1))
  - Defines the predefined version number for 1.1.*
  - #define `VX_VERSION_1_2` (`VX_VERSION_MAJOR`(1) | `VX_VERSION_MINOR`(2))
  - Defines the predefined version number for 1.2.*
  - #define `VX_VERSION_MAJOR(x)` ((x & 0xFF) << 8)
  - Defines the major version number macro.*
  - #define `VX_VERSION_MINOR(x)` ((x & 0xFF) << 0)
  - Defines the minor version number macro.*

## Typedefs

- typedef `vx_enum vx_bool`
- A formal boolean type with known fixed size.*
- typedef char `vx_char`
- An 8 bit ASCII character.*
- typedef uint32\_t `vx_df_image`
- Used to hold a `VX_DF_IMAGE` code to describe the pixel format and color space.*
- typedef int32\_t `vx_enum`
- Sets the standard enumeration type size to be a fixed quantity.*
- typedef float `vx_float32`
- A 32-bit float value.*
- typedef double `vx_float64`
- A 64-bit float value (aka double).*
- typedef int16\_t `vx_int16`
- A 16-bit signed value.*
- typedef int32\_t `vx_int32`

- `typedef int64_t vx_int64`  
A 32-bit signed value.
- `typedef int8_t vx_int8`  
A 64-bit signed value.
- `typedef size_t vx_size`  
An 8-bit signed value.
- `typedef vx_enum vx_status`  
A wrapper of `size_t` to keep the naming convention uniform.
- `typedef vx_enum vx_status`  
A formal status type with known fixed size.
- `typedef uint16_t vx_uint16`  
A 16-bit unsigned value.
- `typedef uint32_t vx_uint32`  
A 32-bit unsigned value.
- `typedef uint64_t vx_uint64`  
A 64-bit unsigned value.
- `typedef uint8_t vx_uint8`  
An 8-bit unsigned value.

## Enumerations

- `enum vx_bool_e {`  
  `vx_false_e = 0,`  
  `vx_true_e }`  
A Boolean value. This allows 0 to be FALSE, as it is in C, and any non-zero to be TRUE.
- `enum vx_channel_e {`  
  `VX_CHANNEL_0 = ((( VX_ID_KHRONOS ) << 20) | ( VX_ENUM_CHANNEL << 12)) + 0x0,`  
  `VX_CHANNEL_1 = ((( VX_ID_KHRONOS ) << 20) | ( VX_ENUM_CHANNEL << 12)) + 0x1,`  
  `VX_CHANNEL_2 = ((( VX_ID_KHRONOS ) << 20) | ( VX_ENUM_CHANNEL << 12)) + 0x2,`  
  `VX_CHANNEL_3 = ((( VX_ID_KHRONOS ) << 20) | ( VX_ENUM_CHANNEL << 12)) + 0x3,`  
  `VX_CHANNEL_R = ((( VX_ID_KHRONOS ) << 20) | ( VX_ENUM_CHANNEL << 12)) + 0x10,`  
  `VX_CHANNEL_G = ((( VX_ID_KHRONOS ) << 20) | ( VX_ENUM_CHANNEL << 12)) + 0x11,`  
  `VX_CHANNEL_B = ((( VX_ID_KHRONOS ) << 20) | ( VX_ENUM_CHANNEL << 12)) + 0x12,`  
  `VX_CHANNEL_A = ((( VX_ID_KHRONOS ) << 20) | ( VX_ENUM_CHANNEL << 12)) + 0x13,`  
  `VX_CHANNEL_Y = ((( VX_ID_KHRONOS ) << 20) | ( VX_ENUM_CHANNEL << 12)) + 0x14,`  
  `VX_CHANNEL_U = ((( VX_ID_KHRONOS ) << 20) | ( VX_ENUM_CHANNEL << 12)) + 0x15,`  
  `VX_CHANNEL_V = ((( VX_ID_KHRONOS ) << 20) | ( VX_ENUM_CHANNEL << 12)) + 0x16 }`  
The channel enumerations for channel extractions.
- `enum vx_convert_policy_e {`  
  `VX_CONVERT_POLICY_WRAP = ((( VX_ID_KHRONOS ) << 20) | ( VX_ENUM_CONVERT_POLICY << 12)) + 0x0,`  
  `VX_CONVERT_POLICY_SATURATE = ((( VX_ID_KHRONOS ) << 20) | ( VX_ENUM_CONVERT_POLICY << 12)) + 0x1 }`  
The Conversion Policy Enumeration.
- `enum vx_df_image_e {`

```

VX_DF_IMAGE_VIRT = (('V') | ('I' << 8) | ('R' << 16) | ('T' << 24)),
VX_DF_IMAGE_RGB = (('R') | ('G' << 8) | ('B' << 16) | ('2' << 24)),
VX_DF_IMAGE_RGBX = (('R') | ('G' << 8) | ('B' << 16) | ('A' << 24)),
VX_DF_IMAGE_NV12 = (('N') | ('V' << 8) | ('1' << 16) | ('2' << 24)),
VX_DF_IMAGE_NV21 = (('N') | ('V' << 8) | ('2' << 16) | ('1' << 24)),
VX_DF_IMAGE_UYVY = (('U') | ('Y' << 8) | ('V' << 16) | ('Y' << 24)),
VX_DF_IMAGE_YUYV = (('Y') | ('U' << 8) | ('Y' << 16) | ('V' << 24)),
VX_DF_IMAGE_IYUV = (('I') | ('Y' << 8) | ('U' << 16) | ('V' << 24)),
VX_DF_IMAGE_YUV4 = (('Y') | ('U' << 8) | ('V' << 16) | ('4' << 24)),
VX_DF_IMAGE_U8 = (('U') | ('0' << 8) | ('0' << 16) | ('8' << 24)),
VX_DF_IMAGE_U16 = (('U') | ('0' << 8) | ('1' << 16) | ('6' << 24)),
VX_DF_IMAGE_S16 = (('S') | ('0' << 8) | ('1' << 16) | ('6' << 24)),
VX_DF_IMAGE_U32 = (('U') | ('0' << 8) | ('3' << 16) | ('2' << 24)),
VX_DF_IMAGE_S32 = (('S') | ('0' << 8) | ('3' << 16) | ('2' << 24)) }

```

*Based on the VX\_DF\_IMAGE definition.*

- enum vx\_enum\_e {
 VX\_ENUM\_DIRECTION = 0x00,
 VX\_ENUM\_ACTION = 0x01,
 VX\_ENUM\_HINT = 0x02,
 VX\_ENUM\_DIRECTIVE = 0x03,
 VX\_ENUM\_INTERPOLATION = 0x04,
 VX\_ENUM\_OVERFLOW = 0x05,
 VX\_ENUM\_COLOR\_SPACE = 0x06,
 VX\_ENUM\_COLOR\_RANGE = 0x07,
 VX\_ENUM\_PARAMETER\_STATE = 0x08,
 VX\_ENUM\_CHANNEL = 0x09,
 VX\_ENUM\_CONVERT\_POLICY = 0x0A,
 VX\_ENUM\_THRESHOLD\_TYPE = 0x0B,
 VX\_ENUM\_BORDER = 0x0C,
 VX\_ENUM\_COMPARISON = 0x0D,
 VX\_ENUM\_MEMORY\_TYPE = 0x0E,
 VX\_ENUM\_TERM\_CRITERIA = 0x0F,
 VX\_ENUM\_NORM\_TYPE = 0x10,
 VX\_ENUM\_ACCESSOR = 0x11,
 VX\_ENUM\_ROUND\_POLICY = 0x12,
 VX\_ENUM\_TARGET = 0x13,
 VX\_ENUM\_BORDER\_POLICY = 0x14,
 VX\_ENUM\_GRAPH\_STATE = 0x15,
 VX\_ENUM\_NONLINEAR = 0x16,
 VX\_ENUM\_PATTERN = 0x17,
 VX\_ENUM\_LBP\_FORMAT = 0x18,
 VX\_ENUM\_COMP\_METRIC = 0x19,
 VX\_ENUM\_SCALAR\_OPERATION = 0x20 }

*The set of supported enumerations in OpenVX.*

- enum vx\_interpolation\_type\_e {
 VX\_INTERPOLATION\_NEAREST\_NEIGHBOR = ((( VX\_ID\_KHRONOS ) << 20 ) | ( VX\_ENUM\_INTERPOLATION << 12 )) + 0x0,
 VX\_INTERPOLATION\_BILINEAR = ((( VX\_ID\_KHRONOS ) << 20 ) | ( VX\_ENUM\_INTERPOLATION << 12 )) + 0x1,
 VX\_INTERPOLATION\_AREA = ((( VX\_ID\_KHRONOS ) << 20 ) | ( VX\_ENUM\_INTERPOLATION << 12 )) + 0x2 }

*The image reconstruction filters supported by image resampling operations.*

- enum vx\_non\_linear\_filter\_e {
 VX\_NONLINEAR\_FILTER\_MEDIAN = ((( VX\_ID\_KHRONOS ) << 20 ) | ( VX\_ENUM\_NONLINEAR << 12 )) + 0x0,
 VX\_NONLINEAR\_FILTER\_MIN = ((( VX\_ID\_KHRONOS ) << 20 ) | ( VX\_ENUM\_NONLINEAR << 12 )) + 0x1,
 VX\_NONLINEAR\_FILTER\_MAX = ((( VX\_ID\_KHRONOS ) << 20 ) | ( VX\_ENUM\_NONLINEAR << 12 )) +

0x2 }

*An enumeration of non-linear filter functions.*

- enum `vx_pattern_e` {  
`VX_PATTERN_BOX` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_PATTERN` << 12)) + 0x0,  
`VX_PATTERN_CROSS` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_PATTERN` << 12)) + 0x1,  
`VX_PATTERN_DISK` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_PATTERN` << 12)) + 0x2,  
`VX_PATTERN_OTHER` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_PATTERN` << 12)) + 0x3 }

*An enumeration of matrix patterns. See `vxCreateMatrixFromPattern` and `vxCreateMatrixFromPatternAndOrigin`*

- enum `vx_status_e` {  
`VX_STATUS_MIN` = -25,  
`VX_ERROR_REFERENCE_NONZERO` = -24,  
`VX_ERROR_MULTIPLE_WRITERS` = -23,  
`VX_ERROR_GRAPH_ABANDONED` = -22,  
`VX_ERROR_GRAPH_SCHEDULED` = -21,  
`VX_ERROR_INVALID_SCOPE` = -20,  
`VX_ERROR_INVALID_NODE` = -19,  
`VX_ERROR_INVALID_GRAPH` = -18,  
`VX_ERROR_INVALID_TYPE` = -17,  
`VX_ERROR_INVALID_VALUE` = -16,  
`VX_ERROR_INVALID_DIMENSION` = -15,  
`VX_ERROR_INVALID_FORMAT` = -14,  
`VX_ERROR_INVALID_LINK` = -13,  
`VX_ERROR_INVALID_REFERENCE` = -12,  
`VX_ERROR_INVALID_MODULE` = -11,  
`VX_ERROR_INVALID_PARAMETERS` = -10,  
`VX_ERROR_OPTIMIZED_AWAY` = -9,  
`VX_ERROR_NO_MEMORY` = -8,  
`VX_ERROR_NO_RESOURCES` = -7,  
`VX_ERROR_NOT_COMPATIBLE` = -6,  
`VX_ERROR_NOT_ALLOCATED` = -5,  
`VX_ERROR_NOT_SUFFICIENT` = -4,  
`VX_ERROR_NOT_SUPPORTED` = -3,  
`VX_ERROR_NOT_IMPLEMENTED` = -2,  
`VX_FAILURE` = -1,  
`VX_SUCCESS` = 0 }

*The enumeration of all status codes.*

- enum `vx_target_e` {  
`VX_TARGET_ANY` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_TARGET` << 12)) + 0x0000,  
`VX_TARGET_STRING` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_TARGET` << 12)) + 0x0001,  
`VX_TARGET_VENDOR_BEGIN` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_TARGET` << 12)) + 0x1000 }

*The Target Enumeration.*

- enum `vx_type_e` {

```

VX_TYPE_INVALID = 0x000,
VX_TYPE_CHAR = 0x001,
VX_TYPE_INT8 = 0x002,
VX_TYPE_UINT8 = 0x003,
VX_TYPE_INT16 = 0x004,
VX_TYPE_UINT16 = 0x005,
VX_TYPE_INT32 = 0x006,
VX_TYPE_UINT32 = 0x007,
VX_TYPE_INT64 = 0x008,
VX_TYPE_UINT64 = 0x009,
VX_TYPE_FLOAT32 = 0x00A,
VX_TYPE_FLOAT64 = 0x00B,
VX_TYPE_ENUM = 0x00C,
VX_TYPE_SIZE = 0x00D,
VX_TYPE_DF_IMAGE = 0x00E,
VX_TYPE_BOOL = 0x010,
VX_TYPE_RECTANGLE = 0x020,
VX_TYPE_KEYPOINT = 0x021,
VX_TYPE_COORDINATES2D = 0x022,
VX_TYPE_COORDINATES3D = 0x023,
VX_TYPE_COORDINATES2DF = 0x024,
VX_TYPE_HOG_PARAMS = 0x028,
VX_TYPE_HOUGH_LINES_PARAMS = 0x029,
VX_TYPE_LINE_2D = 0x02A,
VX_TYPE_TENSOR_MATRIX_MULTIPLY_PARAMS = 0x02B,
VX_TYPE_USER_STRUCT_START = 0x100,
VX_TYPE_VENDOR_STRUCT_START = 0x400,
VX_TYPE_KHRONOS_OBJECT_START = 0x800,
VX_TYPE_VENDOR_OBJECT_START = 0xC00,
VX_TYPE_KHRONOS_STRUCT_MAX = VX_TYPE_USER_STRUCT_START - 1,
VX_TYPE_USER_STRUCT_END = VX_TYPE_VENDOR_STRUCT_START - 1,
VX_TYPE_VENDOR_STRUCT_END = VX_TYPE_KHRONOS_OBJECT_START - 1,
VX_TYPE_KHRONOS_OBJECT_END = VX_TYPE_VENDOR_OBJECT_START - 1,
VX_TYPE_VENDOR_OBJECT_END = 0xFFFF,
VX_TYPE_REFERENCE = 0x800,
VX_TYPE_CONTEXT = 0x801,
VX_TYPE_GRAPH = 0x802,
VX_TYPE_NODE = 0x803,
VX_TYPE_KERNEL = 0x804,
VX_TYPE_PARAMETER = 0x805,
VX_TYPE_DELAY = 0x806,
VX_TYPE_LUT = 0x807,
VX_TYPE_DISTRIBUTION = 0x808,
VX_TYPE_PYRAMID = 0x809,
VX_TYPE_THRESHOLD = 0x80A,
VX_TYPE_MATRIX = 0x80B,
VX_TYPE_CONVOLUTION = 0x80C,
VX_TYPE_SCALAR = 0x80D,
VX_TYPE_ARRAY = 0x80E,
VX_TYPE_IMAGE = 0x80F,
VX_TYPE_REMAP = 0x810,
VX_TYPE_ERROR = 0x811,
VX_TYPE_META_FORMAT = 0x812,
VX_TYPE_OBJECT_ARRAY = 0x813,
VX_TYPE_TENSOR = 0x815 }

```

*The type enumeration lists all the known types in OpenVX.*

- enum `vx_vendor_id_e` {

```

VX_ID_KHRONOS = 0x000,
VX_ID_TI = 0x001,
VX_ID_QUALCOMM = 0x002,
VX_ID_NVIDIA = 0x003,
VX_ID_ARM = 0x004,
VX_ID_BDTI = 0x005,
VX_ID_RENESAS = 0x006,
VX_ID_VIVANTE = 0x007,
VX_ID_XILINX = 0x008,
VX_ID_AXIS = 0x009,
VX_ID_MOVIDIUS = 0x00A,
VX_ID_SAMSUNG = 0x00B,
VX_ID_FREESCALE = 0x00C,
VX_ID_AMD = 0x00D,
VX_ID_BROADCOM = 0x00E,
VX_ID_INTEL = 0x00F,
VX_ID_MARVELL = 0x010,
VX_ID_MEDIATEK = 0x011,
VX_ID_ST = 0x012,
VX_ID_CEVA = 0x013,
VX_ID_ITSEEZ = 0x014,
VX_ID_IMAGINATION = 0x015,
VX_ID_NXP = 0x016,
VX_ID_VIDEANTIS = 0x017,
VX_ID_SYNOPSYS = 0x018,
VX_ID_CADENCE = 0x019,
VX_ID_HUAWEI = 0x01A,
VX_ID_SOCIONEXT = 0x01B,
VX_ID_USER = 0xFFE,
VX_ID_MAX = 0xFFF,
VX_ID_DEFAULT = VX_ID_MAX }

```

*The Vendor ID of the Implementation. As new vendors submit their implementations, this enumeration will grow.*

## Functions

- `vx_status VX_API_CALL vxGetStatus(vx_reference reference)`

*Provides a generic API to return status values from Object constructors if they fail.*

### 3.62.2 Data Structure Documentation

#### **struct vx\_coordinates2d\_t**

The 2D Coordinates structure.

Definition at line 1658 of file `vx_types.h`.

##### Data Fields

|                        |   |                   |
|------------------------|---|-------------------|
| <code>vx_uint32</code> | x | The X coordinate. |
| <code>vx_uint32</code> | y | The Y coordinate. |

#### **struct vx\_coordinates2df\_t**

The floating-point 2D Coordinates structure.

Definition at line 1666 of file `vx_types.h`.

##### Data Fields

|                         |   |                   |
|-------------------------|---|-------------------|
| <code>vx_float32</code> | x | The X coordinate. |
|-------------------------|---|-------------------|



## Data Fields

|                            |   |                   |
|----------------------------|---|-------------------|
| <a href="#">vx_float32</a> | y | The Y coordinate. |
|----------------------------|---|-------------------|

**struct vx\_coordinates3d\_t**

The 3D Coordinates structure.

Definition at line 1674 of file [vx\\_types.h](#).

## Data Fields

|                           |   |                   |
|---------------------------|---|-------------------|
| <a href="#">vx_uint32</a> | x | The X coordinate. |
| <a href="#">vx_uint32</a> | y | The Y coordinate. |
| <a href="#">vx_uint32</a> | z | The Z coordinate. |

**struct vx\_keypoint\_t**

The keypoint data structure.

Definition at line 1635 of file [vx\\_types.h](#).

## Data Fields

|                            |                 |                                                                                  |
|----------------------------|-----------------|----------------------------------------------------------------------------------|
| <a href="#">vx_int32</a>   | x               | The x coordinate.                                                                |
| <a href="#">vx_int32</a>   | y               | The y coordinate.                                                                |
| <a href="#">vx_float32</a> | strength        | The strength of the keypoint. Its definition is specific to the corner detector. |
| <a href="#">vx_float32</a> | scale           | Initialized to 0 by corner detectors.                                            |
| <a href="#">vx_float32</a> | orientation     | Initialized to 0 by corner detectors.                                            |
| <a href="#">vx_int32</a>   | tracking_status | A zero indicates a lost point. Initialized to 1 by corner detectors.             |
| <a href="#">vx_float32</a> | error           | A tracking method specific error. Initialized to 0 by corner detectors.          |

**struct vx\_line2d\_t**

line struct

Definition at line 1573 of file [vx\\_types.h](#).

## Data Fields

|                            |                               |                       |
|----------------------------|-------------------------------|-----------------------|
| <a href="#">vx_float32</a> | start $\leftrightarrow$<br>_x | x index of line start |
| <a href="#">vx_float32</a> | start $\leftrightarrow$<br>_y | y index of line start |
| <a href="#">vx_float32</a> | end $\leftrightarrow$<br>_x   | x index of line end   |
| <a href="#">vx_float32</a> | end $\leftrightarrow$<br>_y   | y index of line end   |

**struct vx\_rectangle\_t**

The rectangle data structure that is shared with the users. The area of the rectangle can be computed as  $(end\_x - start\_x) * (end\_y - start\_y)$ .

Definition at line 1648 of file [vx\\_types.h](#).

## Data Fields

|                           |              |                         |
|---------------------------|--------------|-------------------------|
| <a href="#">vx_uint32</a> | start↔<br>_x | The Start X coordinate. |
| <a href="#">vx_uint32</a> | start↔<br>_y | The Start Y coordinate. |
| <a href="#">vx_uint32</a> | end↔<br>_x   | The End X coordinate.   |
| <a href="#">vx_uint32</a> | end↔<br>_y   | The End Y coordinate.   |

### 3.62.3 Macro Definition Documentation

#### **#define VX\_TYPE\_MASK (0x000FFF00)**

A type mask removes the scalar/object type from the attribute. It is 3 nibbles in size and is contained between the third and second byte.

See also

[vx\\_type\\_e](#)

Definition at line 473 of file [vx\\_types.h](#).

#### **#define VX\_DF\_IMAGE( a, b, c, d ) ((a) | (b << 8) | (c << 16) | (d << 24))**

Converts a set of four chars into a `uint32_t` container of a `VX_DF_IMAGE` code.

Note

Use a [vx\\_df\\_image](#) variable to hold the value.

Definition at line 526 of file [vx\\_types.h](#).

#### **#define VX\_ENUM\_BASE( vendor, id ) (((vendor) << 20) | (id << 12))**

Defines the manner in which to combine the Vendor and Object IDs to get the base value of the enumeration.

From any enumerated value (with exceptions), the vendor, and enumeration type should be extractable. Those types that are exceptions are [vx\\_vendor\\_id\\_e](#), [vx\\_type\\_e](#), [vx\\_enum\\_e](#), [vx\\_df\\_image\\_e](#), and `vx_↔bool`.

Definition at line 550 of file [vx\\_types.h](#).

### 3.62.4 Typedef Documentation

#### **typedef int32\_t vx\_enum**

Sets the standard enumeration type size to be a fixed quantity.

All enumerable fields must use this type as the container to enforce enumeration ranges and `sizeof()` operations.

Definition at line 149 of file [vx\\_types.h](#).

#### **typedef vx\_enum vx\_bool**

A formal boolean type with known fixed size.

See also

[vx\\_bool\\_e](#)

Definition at line 309 of file [vx\\_types.h](#).

**typedef vx\_enum vx\_status**

A formal status type with known fixed size.

See also

[vx\\_status\\_e](#)

Definition at line [445](#) of file [vx\\_types.h](#).

**3.62.5 Enumeration Type Documentation****enum vx\_bool\_e**

A Boolean value. This allows 0 to be FALSE, as it is in C, and any non-zero to be TRUE.

```
00001 vx_bool ret = vx_true_e;
00002 if (ret) printf("true!\n");
00003 ret = vx_false_e;
00004 if (!ret) printf("false!\n");
```

This would print both strings.

See also

[vx\\_bool](#)

Enumerator

***vx\_false\_e*** The "false" value.

***vx\_true\_e*** The "true" value.

Definition at line [298](#) of file [vx\\_types.h](#).

**enum vx\_type\_e**

The type enumeration lists all the known types in OpenVX.

Enumerator

***VX\_TYPE\_INVALID*** An invalid type value. When passed an error must be returned.

***VX\_TYPE\_CHAR*** A [vx\\_char](#).

***VX\_TYPE\_INT8*** A [vx\\_int8](#).

***VX\_TYPE\_UINT8*** A [vx\\_uint8](#).

***VX\_TYPE\_INT16*** A [vx\\_int16](#).

***VX\_TYPE\_UINT16*** A [vx\\_uint16](#).

***VX\_TYPE\_INT32*** A [vx\\_int32](#).

***VX\_TYPE\_UINT32*** A [vx\\_uint32](#).

***VX\_TYPE\_INT64*** A [vx\\_int64](#).

***VX\_TYPE\_UINT64*** A [vx\\_uint64](#).

***VX\_TYPE\_FLOAT32*** A [vx\\_float32](#).

***VX\_TYPE\_FLOAT64*** A [vx\\_float64](#).

***VX\_TYPE\_ENUM*** A [vx\\_enum](#). Equivalent in size to a [vx\\_int32](#).

***VX\_TYPE\_SIZE*** A [vx\\_size](#).

***VX\_TYPE\_DF\_IMAGE*** A [vx\\_df\\_image](#).

***VX\_TYPE\_BOOL*** A [vx\\_bool](#).

***VX\_TYPE\_RECTANGLE*** A [vx\\_rectangle\\_t](#).

***VX\_TYPE\_KEYPOINT*** A [vx\\_keypoint\\_t](#).

***VX\_TYPE\_COORDINATES2D*** A [vx\\_coordinates2d\\_t](#).

**VX\_TYPE\_COORDINATES3D** A [vx\\_coordinates3d\\_t](#).  
**VX\_TYPE\_COORDINATES2DF** A [vx\\_coordinates2df\\_t](#).  
**VX\_TYPE\_HOG\_PARAMS** A [vx\\_hog\\_t](#).  
**VX\_TYPE\_HOUGH\_LINES\_PARAMS** A [vx\\_hough\\_lines\\_p\\_t](#).  
**VX\_TYPE\_LINE\_2D** A [vx\\_line2d\\_t](#).  
**VX\_TYPE\_TENSOR\_MATRIX\_MULTIPLY\_PARAMS** A [vx\\_tensor\\_matrix\\_multiply\\_params\\_t](#).  
**VX\_TYPE\_USER\_STRUCT\_START** A user-defined struct base index.  
**VX\_TYPE\_VENDOR\_STRUCT\_START** A vendor-defined struct base index.  
**VX\_TYPE\_KHRONOS\_OBJECT\_START** A Khronos defined object base index.  
**VX\_TYPE\_VENDOR\_OBJECT\_START** A vendor defined object base index.  
**VX\_TYPE\_KHRONOS\_STRUCT\_MAX** A value for comparison between Khronos defined structs and user structs.  
**VX\_TYPE\_USER\_STRUCT\_END** A value for comparison between user structs and vendor structs.  
**VX\_TYPE\_VENDOR\_STRUCT\_END** A value for comparison between vendor structs and Khronos defined objects.  
**VX\_TYPE\_KHRONOS\_OBJECT\_END** A value for comparison between Khronos defined objects and vendor structs.  
**VX\_TYPE\_VENDOR\_OBJECT\_END** A value used for bound checking of vendor objects.  
**VX\_TYPE\_REFERENCE** A [vx\\_reference](#).  
**VX\_TYPE\_CONTEXT** A [vx\\_context](#).  
**VX\_TYPE\_GRAPH** A [vx\\_graph](#).  
**VX\_TYPE\_NODE** A [vx\\_node](#).  
**VX\_TYPE\_KERNEL** A [vx\\_kernel](#).  
**VX\_TYPE\_PARAMETER** A [vx\\_parameter](#).  
**VX\_TYPE\_DELAY** A [vx\\_delay](#).  
**VX\_TYPE\_LUT** A [vx\\_lut](#).  
**VX\_TYPE\_DISTRIBUTION** A [vx\\_distribution](#).  
**VX\_TYPE\_PYRAMID** A [vx\\_pyramid](#).  
**VX\_TYPE\_THRESHOLD** A [vx\\_threshold](#).  
**VX\_TYPE\_MATRIX** A [vx\\_matrix](#).  
**VX\_TYPE\_CONVOLUTION** A [vx\\_convolution](#).  
**VX\_TYPE\_SCALAR** A [vx\\_scalar](#). when needed to be completely generic for kernel validation.  
**VX\_TYPE\_ARRAY** A [vx\\_array](#).  
**VX\_TYPE\_IMAGE** A [vx\\_image](#).  
**VX\_TYPE\_REMAP** A [vx\\_remap](#).  
**VX\_TYPE\_ERROR** An error object which has no type.  
**VX\_TYPE\_META\_FORMAT** A [vx\\_meta\\_format](#).  
**VX\_TYPE\_OBJECT\_ARRAY** A [vx\\_object\\_array](#).  
**VX\_TYPE\_TENSOR** A [vx\\_tensor](#).

Definition at line 325 of file [vx\\_types.h](#).

**enum vx\_status\_e**

The enumeration of all status codes.

See also

[vx\\_status](#).

Enumerator

**VX\_STATUS\_MIN** Indicates the lower bound of status codes in VX. Used for bounds checks only.

**VX\_ERROR\_REFERENCE\_NONZERO** Indicates that an operation did not complete due to a reference count being non-zero.

**VX\_ERROR\_MULTIPLE\_WRITERS** Indicates that the graph has more than one node outputting to the same data object. This is an invalid graph structure.

**VX\_ERROR\_GRAPH\_ABANDONED** Indicates that the graph is stopped due to an error or a callback that abandoned execution.

**VX\_ERROR\_GRAPH\_SCHEDULED** Indicates that the supplied graph already has been scheduled and may be currently executing.

**VX\_ERROR\_INVALID\_SCOPE** Indicates that the supplied parameter is from another scope and cannot be used in the current scope.

**VX\_ERROR\_INVALID\_NODE** Indicates that the supplied node could not be created.

**VX\_ERROR\_INVALID\_GRAPH** Indicates that the supplied graph has invalid connections (cycles).

**VX\_ERROR\_INVALID\_TYPE** Indicates that the supplied type parameter is incorrect.

**VX\_ERROR\_INVALID\_VALUE** Indicates that the supplied parameter has an incorrect value.

**VX\_ERROR\_INVALID\_DIMENSION** Indicates that the supplied parameter is too big or too small in dimension.

**VX\_ERROR\_INVALID\_FORMAT** Indicates that the supplied parameter is in an invalid format.

**VX\_ERROR\_INVALID\_LINK** Indicates that the link is not possible as specified. The parameters are incompatible.

**VX\_ERROR\_INVALID\_REFERENCE** Indicates that the reference provided is not valid.

**VX\_ERROR\_INVALID\_MODULE** This is returned from [vxLoadKernels](#) when the module does not contain the entry point.

**VX\_ERROR\_INVALID\_PARAMETERS** Indicates that the supplied parameter information does not match the kernel contract.

**VX\_ERROR\_OPTIMIZED\_AWAY** Indicates that the object referred to has been optimized out of existence.

**VX\_ERROR\_NO\_MEMORY** Indicates that an internal or implicit allocation failed. Typically catastrophic. After detection, deconstruct the context.

See also

[vxVerifyGraph](#).

**VX\_ERROR\_NO\_RESOURCES** Indicates that an internal or implicit resource can not be acquired (not memory). This is typically catastrophic. After detection, deconstruct the context.

See also

[vxVerifyGraph](#).

**VX\_ERROR\_NOT\_COMPATIBLE** Indicates that the attempt to link two parameters together failed due to type incompatibility.

**VX\_ERROR\_NOT\_ALLOCATED** Indicates to the system that the parameter must be allocated by the system.

**VX\_ERROR\_NOT\_SUFFICIENT** Indicates that the given graph has failed verification due to an insufficient number of required parameters, which cannot be automatically created. Typically this indicates required atomic parameters.

See also

[vxVerifyGraph](#).

**VX\_ERROR\_NOT\_SUPPORTED** Indicates that the requested set of parameters produce a configuration that cannot be supported. Refer to the supplied documentation on the configured kernels.

See also

[vx\\_kernel\\_e](#). This is also returned if a function to set an attribute is called on a Read-only attribute.

**VX\_ERROR\_NOT\_IMPLEMENTED** Indicates that the requested kernel is missing.

See also

[vx\\_kernel\\_e vxGetKernelByName](#).

**VX\_FAILURE** Indicates a generic error code, used when no other describes the error.

**VX\_SUCCESS** No error.

Definition at line 411 of file [vx\\_types.h](#).

## enum vx\_enum\_e

The set of supported enumerations in OpenVX.

These can be extracted from enumerated values using [VX\\_ENUM\\_TYPE](#).

Enumerator

**VX\_ENUM\_DIRECTION** Parameter Direction.  
**VX\_ENUM\_ACTION** Action Codes.  
**VX\_ENUM\_HINT** Hint Values.  
**VX\_ENUM\_DIRECTIVE** Directive Values.  
**VX\_ENUM\_INTERPOLATION** Interpolation Types.  
**VX\_ENUM\_OVERFLOW** Overflow Policies.  
**VX\_ENUM\_COLOR\_SPACE** Color Space.  
**VX\_ENUM\_COLOR\_RANGE** Color Space Range.  
**VX\_ENUM\_PARAMETER\_STATE** Parameter State.  
**VX\_ENUM\_CHANNEL** Channel Name.  
**VX\_ENUM\_CONVERT\_POLICY** Convert Policy.  
**VX\_ENUM\_THRESHOLD\_TYPE** Threshold Type List.  
**VX\_ENUM\_BORDER** Border Mode List.  
**VX\_ENUM\_COMPARISON** Comparison Values.  
**VX\_ENUM\_MEMORY\_TYPE** The memory type enumeration.  
**VX\_ENUM\_TERM\_CRITERIA** A termination criteria.  
**VX\_ENUM\_NORM\_TYPE** A norm type.  
**VX\_ENUM\_ACCESSOR** An accessor flag type.  
**VX\_ENUM\_ROUND\_POLICY** Rounding Policy.  
**VX\_ENUM\_TARGET** Target.  
**VX\_ENUM\_BORDER\_POLICY** Unsupported Border Mode Policy List.  
**VX\_ENUM\_GRAPH\_STATE** Graph attribute states.  
**VX\_ENUM\_NONLINEAR** Non-linear function list.  
**VX\_ENUM\_PATTERN** Matrix pattern enumeration.  
**VX\_ENUM\_LBP\_FORMAT** Lbp format.  
**VX\_ENUM\_COMP\_METRIC** Compare metric.  
**VX\_ENUM\_SCALAR\_OPERATION** Scalar operation list.

Definition at line 556 of file [vx\\_types.h](#).

**enum vx\_convert\_policy\_e**

The Conversion Policy Enumeration.

Enumerator

**VX\_CONVERT\_POLICY\_WRAP** Results are the least significant bits of the output operand, as if stored in two's complement binary format in the size of its bit-depth.

**VX\_CONVERT\_POLICY\_SATURATE** Results are saturated to the bit depth of the output operand.

Definition at line 694 of file [vx\\_types.h](#).

**enum vx\_df\_image\_e**

Based on the VX\_DF\_IMAGE definition.

Note

Use [vx\\_df\\_image](#) to contain these values.

Enumerator

**VX\_DF\_IMAGE\_VIRT** A virtual image of no defined type.

**VX\_DF\_IMAGE\_RGB** A single plane of 24-bit pixel as 3 interleaved 8-bit units of R then G then B data. This uses the BT709 full range by default.

**VX\_DF\_IMAGE\_RGBX** A single plane of 32-bit pixel as 4 interleaved 8-bit units of R then G then B data, then a *don't care* byte. This uses the BT709 full range by default.

**VX\_DF\_IMAGE\_NV12** A 2-plane YUV format of Luma (Y) and interleaved UV data at 4:2:0 sampling. This uses the BT709 full range by default.

**VX\_DF\_IMAGE\_NV21** A 2-plane YUV format of Luma (Y) and interleaved VU data at 4:2:0 sampling. This uses the BT709 full range by default.

**VX\_DF\_IMAGE\_UYVY** A single plane of 32-bit macro pixel of U0, Y0, V0, Y1 bytes. This uses the BT709 full range by default.

**VX\_DF\_IMAGE\_YUYV** A single plane of 32-bit macro pixel of Y0, U0, Y1, V0 bytes. This uses the BT709 full range by default.

**VX\_DF\_IMAGE\_IYUV** A 3 plane of 8-bit 4:2:0 sampled Y, U, V planes. This uses the BT709 full range by default.

**VX\_DF\_IMAGE\_YUV4** A 3 plane of 8 bit 4:4:4 sampled Y, U, V planes. This uses the BT709 full range by default.

**VX\_DF\_IMAGE\_U8** A single plane of unsigned 8-bit data. The range of data is not specified, as it may be extracted from a YUV or generated.

**VX\_DF\_IMAGE\_U16** A single plane of unsigned 16-bit data. The range of data is not specified, as it may be extracted from a YUV or generated.

**VX\_DF\_IMAGE\_S16** A single plane of signed 16-bit data. The range of data is not specified, as it may be extracted from a YUV or generated.

**VX\_DF\_IMAGE\_U32** A single plane of unsigned 32-bit data. The range of data is not specified, as it may be extracted from a YUV or generated.

**VX\_DF\_IMAGE\_S32** A single plane of unsigned 32-bit data. The range of data is not specified, as it may be extracted from a YUV or generated.

Definition at line 707 of file [vx\\_types.h](#).

**enum vx\_target\_e**

The Target Enumeration.

Enumerator

**VX\_TARGET\_ANY** Any available target. An OpenVX implementation must support at least one target associated with this value.

**VX\_TARGET\_STRING** Target, explicitly specified by its (case-insensitive) name string.

**VX\_TARGET\_VENDOR\_BEGIN** Start of Vendor specific target enumerates.

Definition at line 773 of file [vx\\_types.h](#).

#### enum vx\_channel\_e

The channel enumerations for channel extractions.

See also

[vxChannelExtractNode](#)  
[vxuChannelExtract](#)  
[VX\\_KERNEL\\_CHANNEL\\_EXTRACT](#)

Enumerator

**VX\_CHANNEL\_0** Used by formats with unknown channel types.

**VX\_CHANNEL\_1** Used by formats with unknown channel types.

**VX\_CHANNEL\_2** Used by formats with unknown channel types.

**VX\_CHANNEL\_3** Used by formats with unknown channel types.

**VX\_CHANNEL\_R** Use to extract the RED channel, no matter the byte or packing order.

**VX\_CHANNEL\_G** Use to extract the GREEN channel, no matter the byte or packing order.

**VX\_CHANNEL\_B** Use to extract the BLUE channel, no matter the byte or packing order.

**VX\_CHANNEL\_A** Use to extract the ALPHA channel, no matter the byte or packing order.

**VX\_CHANNEL\_Y** Use to extract the LUMA channel, no matter the byte or packing order.

**VX\_CHANNEL\_U** Use to extract the Cb/U channel, no matter the byte or packing order.

**VX\_CHANNEL\_V** Use to extract the Cr/V/Value channel, no matter the byte or packing order.

Definition at line 1194 of file [vx\\_types.h](#).

#### enum vx\_interpolation\_type\_e

The image reconstruction filters supported by image resampling operations.

The edge of a pixel is interpreted as being aligned to the edge of the image. The value for an output pixel is evaluated at the center of that pixel.

This means, for example, that an even enlargement of a factor of two in nearest-neighbor interpolation will replicate every source pixel into a 2x2 quad in the destination, and that an even shrink by a factor of two in bilinear interpolation will create each destination pixel by average a 2x2 quad of source pixels.

Samples that cross the boundary of the source image have values determined by the border mode - see [vx↔\\_border\\_e](#) and [VX\\_NODE\\_BORDER](#).

See also

[vxuScaleImage](#)  
[vxScaleImageNode](#)  
[VX\\_KERNEL\\_SCALE\\_IMAGE](#)  
[vxuWarpAffine](#)  
[vxWarpAffineNode](#)  
[VX\\_KERNEL\\_WARP\\_AFFINE](#)  
[vxuWarpPerspective](#)  
[vxWarpPerspectiveNode](#)  
[VX\\_KERNEL\\_WARP\\_PERSPECTIVE](#)

Enumerator

**VX\_INTERPOLATION\_NEAREST\_NEIGHBOR** Output values are defined to match the source pixel whose center is nearest to the sample position.



**VX\_INTERPOLATION\_BILINEAR** Output values are defined by bilinear interpolation between the pixels whose centers are closest to the sample position, weighted linearly by the distance of the sample from the pixel centers.

**VX\_INTERPOLATION\_AREA** Output values are determined by averaging the source pixels whose areas fall under the area of the destination pixel, projected onto the source image.

Definition at line 1254 of file [vx\\_types.h](#).

#### **enum vx\_non\_linear\_filter\_e**

An enumeration of non-linear filter functions.

Enumerator

**VX\_NONLINEAR\_FILTER\_MEDIAN** Nonlinear median filter.

**VX\_NONLINEAR\_FILTER\_MIN** Nonlinear Erode.

**VX\_NONLINEAR\_FILTER\_MAX** Nonlinear Dilate.

Definition at line 1268 of file [vx\\_types.h](#).

#### **enum vx\_pattern\_e**

An enumeration of matrix patterns. See [vxCreateMatrixFromPattern](#) and [vxCreateMatrixFromPatternAndOrigin](#)

Enumerator

**VX\_PATTERN\_BOX** Box pattern matrix.

**VX\_PATTERN\_CROSS** Cross pattern matrix.

**VX\_PATTERN\_DISK** A square matrix (rows = columns = size)

**VX\_PATTERN\_OTHER** Matrix with any pattern other than above.

Definition at line 1281 of file [vx\\_types.h](#).

#### **enum vx\_vendor\_id\_e**

The Vendor ID of the Implementation. As new vendors submit their implementations, this enumeration will grow.

Enumerator

**VX\_ID\_KHRONOS** The Khronos Group.

**VX\_ID\_TI** Texas Instruments, Inc.

**VX\_ID\_QUALCOMM** Qualcomm, Inc.

**VX\_ID\_NVIDIA** NVIDIA Corporation.

**VX\_ID\_ARM** ARM Ltd.

**VX\_ID\_BDTI** Berkley Design Technology, Inc.

**VX\_ID\_RENESAS** Renesas Electronics.

**VX\_ID\_VIVANTE** Vivante Corporation.

**VX\_ID\_XILINX** Xilinx Inc.

**VX\_ID\_AXIS** Axis Communications.

**VX\_ID\_MOVIDIUS** Movidius Ltd.

**VX\_ID\_SAMSUNG** Samsung Electronics.

**VX\_ID\_FREESCALE** Freescale Semiconductor.

**VX\_ID\_AMD** Advanced Micro Devices.

**VX\_ID\_BROADCOM** Broadcom Corporation.

**VX\_ID\_INTEL** Intel Corporation.

**VX\_ID\_MARVELL** Marvell Technology Group Ltd.  
**VX\_ID\_MEDIATEK** MediaTek, Inc.  
**VX\_ID\_ST** STMicroelectronics.  
**VX\_ID\_CEVA** CEVA DSP.  
**VX\_ID\_ITSEEZ** Itseez, Inc.  
**VX\_ID\_IMAGINATION** Imagination Technologies.  
**VX\_ID\_NXP** NXP Semiconductors.  
**VX\_ID\_VIDEANTIS** Videantis.  
**VX\_ID\_SYNOPSYS** Synopsys.  
**VX\_ID\_CADENCE** Cadence.  
**VX\_ID\_HUAWEI** Huawei.  
**VX\_ID\_SOCIONEXT** Socionext.  
**VX\_ID\_USER** For use by vxAllocateUserKernelId and vxAllocateUserKernelLibraryId.  
**VX\_ID\_DEFAULT** For use by all Kernel authors until they can obtain an assigned ID.

Definition at line 30 of file [vx\\_vendors.h](#).

### 3.62.6 Function Documentation

#### **vx\_status VX\_API\_CALL vxGetStatus ( vx\_reference reference )**

Provides a generic API to return status values from Object constructors if they fail.

##### Note

Users do not need to strictly check every object creator as the errors should properly propagate and be detected during verification time or run-time.

```
00001 vx_image img = vxCreateImage(context, 639, 480, VX_DF_IMAGE_UYVY);
00002 vx_status status = vxGetStatus((vx_reference)img);
00003 // status == VX_ERROR_INVALID_DIMENSIONS
00004 vxReleaseImage(&img);
```

##### Precondition

Appropriate Object Creator function.

##### Postcondition

Appropriate Object Release function.

##### Parameters

|    |                  |                                                 |
|----|------------------|-------------------------------------------------|
| in | <i>reference</i> | The reference to check for construction errors. |
|----|------------------|-------------------------------------------------|

##### Returns

A [vx\\_status\\_e](#) enumeration.

##### Return values

|                   |                                                                     |
|-------------------|---------------------------------------------------------------------|
| <b>VX_SUCCESS</b> | No errors; any other value indicates failure.                       |
| *                 | Some error occurred, please check enumeration list and constructor. |

## 3.63 Objects

### 3.63.1 Detailed Description

Defines the basic objects within OpenVX.

All objects in OpenVX derive from a [vx\\_reference](#) and contain a reference to the [vx\\_context](#) from which they were made, except the [vx\\_context](#) itself.

#### Modules

- [Object: Reference](#)  
*Defines the Reference Object interface.*
- [Object: Context](#)  
*Defines the Context Object Interface.*
- [Object: Graph](#)  
*Defines the Graph Object interface.*
- [Object: Node](#)  
*Defines the Node Object interface.*
- [Object: Array](#)  
*Defines the Array Object Interface.*
- [Object: Convolution](#)  
*Defines the Image Convolution Object interface.*
- [Object: Distribution](#)  
*Defines the Distribution Object Interface.*
- [Object: Image](#)  
*Defines the Image Object interface.*
- [Object: LUT](#)  
*Defines the Look-Up Table Interface.*
- [Object: Matrix](#)  
*Defines the Matrix Object Interface.*
- [Object: Pyramid](#)  
*Defines the Image Pyramid Object Interface.*
- [Object: Remap](#)  
*Defines the Remap Object Interface.*
- [Object: Scalar](#)  
*Defines the Scalar Object interface.*
- [Object: Threshold](#)  
*Defines the Threshold Object Interface.*
- [Object: ObjectArray](#)  
*An opaque array object that could be an array of any data-object (not data-type) of OpenVX except Delay and Object↔Array objects.*
- [Object: Tensor](#)  
*Defines The Tensor Object Interface.*

## 3.64 Object: Reference

### 3.64.1 Detailed Description

Defines the Reference Object interface.

All objects in OpenVX are derived (in the object-oriented sense) from `vx_reference`. All objects shall be able to be cast back to this type safely.

#### Macros

- `#define VX_MAX_REFERENCE_NAME (64)`  
*Defines the length of the reference name string, including the trailing zero.*

#### Typedefs

- `typedef struct _vx_reference * vx_reference`  
*A generic opaque reference to any object within OpenVX.*

#### Enumerations

- `enum vx_reference_attribute_e {`  
`VX_REFERENCE_COUNT = ((( VX_ID_KHRONOS ) << 20) | ( VX_TYPE_REFERENCE << 8)) + 0x0,`  
`VX_REFERENCE_TYPE = ((( VX_ID_KHRONOS ) << 20) | ( VX_TYPE_REFERENCE << 8)) + 0x1,`  
`VX_REFERENCE_NAME = ((( VX_ID_KHRONOS ) << 20) | ( VX_TYPE_REFERENCE << 8)) + 0x2 }`  
*The reference attributes list.*

#### Functions

- `vx_status VX_API_CALL vxQueryReference (vx_reference ref, vx_enum attribute, void *ptr, vx_size size)`  
*Queries any reference type for some basic information like count or type.*
- `vx_status VX_API_CALL vxReleaseReference (vx_reference *ref_ptr)`  
*Releases a reference. The reference may potentially refer to multiple OpenVX objects of different types. This function can be used instead of calling a specific release function for each individual object type (e.g. vxRelease<object>). The object will not be destroyed until its total reference count is zero.*
- `vx_status VX_API_CALL vxRetainReference (vx_reference ref)`  
*Increments the reference counter of an object. This function is used to express the fact that the OpenVX object is referenced multiple times by an application. Each time this function is called for an object, the application will need to release the object one additional time before it can be destructed.*
- `vx_status VX_API_CALL vxSetReferenceName (vx_reference ref, const vx_char *name)`  
*Name a reference*  
*This function is used to associate a name to a referenced object. This name can be used by the OpenVX implementation in log messages and any other reporting mechanisms.*

### 3.64.2 Macro Definition Documentation

#### `#define VX_MAX_REFERENCE_NAME (64)`

Defines the length of the reference name string, including the trailing zero.

See also

`vxSetReferenceName`

Definition at line 45 of file `vx.h`.

### 3.64.3 Typedef Documentation

**typedef struct \_vx\_reference\* vx\_reference**

A generic opaque reference to any object within OpenVX.

A user of OpenVX should not assume that this can be cast directly to anything; however, any object in OpenVX can be cast back to this for the purposes of querying attributes of the object or for passing the object as a parameter to functions that take a [vx\\_reference](#) type. If the API does not take that specific type but may take others, an error may be returned from the API.

Definition at line 142 of file [vx\\_types.h](#).

### 3.64.4 Enumeration Type Documentation

**enum vx\_reference\_attribute\_e**

The reference attributes list.

Enumerator

**VX\_REFERENCE\_COUNT** Returns the reference count of the object. Read-only. Use a [vx\\_uint32](#) parameter.

**VX\_REFERENCE\_TYPE** Returns the [vx\\_type\\_e](#) of the reference. Read-only. Use a [vx\\_enum](#) parameter.

**VX\_REFERENCE\_NAME** Used to query the reference for its name. Read-write. Use a [\\*vx\\_char](#) parameter.

Definition at line 785 of file [vx\\_types.h](#).

### 3.64.5 Function Documentation

**vx\_status VX\_API\_CALL vxQueryReference ( vx\_reference ref, vx\_enum attribute, void \* ptr, vx\_size size )**

Queries any reference type for some basic information like count or type.

Parameters

|     |                  |                                                                              |
|-----|------------------|------------------------------------------------------------------------------|
| in  | <i>ref</i>       | The reference to query.                                                      |
| in  | <i>attribute</i> | The value for which to query. Use <a href="#">vx_reference_attribute_e</a> . |
| out | <i>ptr</i>       | The location at which to store the resulting value.                          |
| in  | <i>size</i>      | The size in bytes of the container to which ptr points.                      |

Returns

A [vx\\_status\\_e](#) enumeration.

Return values

|                                   |                                                            |
|-----------------------------------|------------------------------------------------------------|
| <b>VX_SUCCESS</b>                 | No errors; any other value indicates failure.              |
| <b>VX_ERROR_INVALID_REFERENCE</b> | ref is not a valid <a href="#">vx_reference</a> reference. |

**vx\_status VX\_API\_CALL vxReleaseReference ( vx\_reference \* ref\_ptr )**

Releases a reference. The reference may potentially refer to multiple OpenVX objects of different types. This function can be used instead of calling a specific release function for each individual object type (e.g. `vxRelease<object>`). The object will not be destroyed until its total reference count is zero.

**Note**

After returning from this function the reference is zeroed.

**Parameters**

|    |                |                                                        |
|----|----------------|--------------------------------------------------------|
| in | <i>ref_ptr</i> | The pointer to the reference of the object to release. |
|----|----------------|--------------------------------------------------------|

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                                         |                                                                    |
|-----------------------------------------|--------------------------------------------------------------------|
| <code>VX_SUCCESS</code>                 | No errors; any other value indicates failure.                      |
| <code>VX_ERROR_INVALID_REFERENCE</code> | <i>ref_ptr</i> is not a valid <code>vx_reference</code> reference. |

**`vx_status VX_API_CALL vxRetainReference ( vx_reference ref )`**

Increments the reference counter of an object. This function is used to express the fact that the OpenVX object is referenced multiple times by an application. Each time this function is called for an object, the application will need to release the object one additional time before it can be destructed.

**Parameters**

|    |            |                          |
|----|------------|--------------------------|
| in | <i>ref</i> | The reference to retain. |
|----|------------|--------------------------|

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                                         |                                                                |
|-----------------------------------------|----------------------------------------------------------------|
| <code>VX_SUCCESS</code>                 | No errors; any other value indicates failure.                  |
| <code>VX_ERROR_INVALID_REFERENCE</code> | <i>ref</i> is not a valid <code>vx_reference</code> reference. |

**`vx_status VX_API_CALL vxSetReferenceName ( vx_reference ref, const vx_char * name )`****Name a reference**

This function is used to associate a name to a referenced object. This name can be used by the OpenVX implementation in log messages and any other reporting mechanisms.

The OpenVX implementation will not check if the name is unique in the reference scope (context or graph). Several references can then have the same name.

**Parameters**

|    |             |                                                                                                                                                                                                                                                                                                   |
|----|-------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>ref</i>  | The reference to the object to be named.                                                                                                                                                                                                                                                          |
| in | <i>name</i> | Pointer to the '\0' terminated string that identifies the referenced object. The string is copied by the function so that it stays the property of the caller. NULL means that the reference is not named. The length of the string shall be lower than <code>VX_MAX_REFERENCE_NAME</code> bytes. |

## Returns

A `vx_status_e` enumeration.

## Return values

|                                         |                                                         |
|-----------------------------------------|---------------------------------------------------------|
| <code>VX_SUCCESS</code>                 | No errors; any other value indicates failure.           |
| <code>VX_ERROR_INVALID_REFERENCE</code> | ref is not a valid <code>vx_reference</code> reference. |

## 3.65 Object: Context

### 3.65.1 Detailed Description

Defines the Context Object Interface.

The OpenVX context is the object domain for all OpenVX objects. All data objects *live* in the context as well as all framework objects. The OpenVX context keeps reference counts on all objects and must do garbage collection during its deconstruction to free lost references. While multiple clients may connect to the OpenVX context, all data are private in that the references referring to data objects are given only to the creating party.

### Macros

- `#define VX_MAX_IMPLEMENTATION_NAME (64)`  
*Defines the length of the implementation name string, including the trailing zero.*

### Typedefs

- `typedef struct _vx_context * vx_context`  
*An opaque reference to the implementation context.*

### Enumerations

- `enum vx_accessor_e {`  
`VX_READ_ONLY = ((( VX_ID_KHRONOS ) << 20) | ( VX_ENUM_ACCESSOR << 12)) + 0x1,`  
`VX_WRITE_ONLY = ((( VX_ID_KHRONOS ) << 20) | ( VX_ENUM_ACCESSOR << 12)) + 0x2,`  
`VX_READ_AND_WRITE = ((( VX_ID_KHRONOS ) << 20) | ( VX_ENUM_ACCESSOR << 12)) + 0x3 }`  
*The memory accessor hint flags. These enumeration values are used to indicate desired system behavior, not the **User** intent. For example: these can be interpreted as hints to the system about cache operations or marshalling operations.*
- `enum vx_context_attribute_e {`  
`VX_CONTEXT_VENDOR_ID = ((( VX_ID_KHRONOS ) << 20) | ( VX_TYPE_CONTEXT << 8)) + 0x0,`  
`VX_CONTEXT_VERSION = ((( VX_ID_KHRONOS ) << 20) | ( VX_TYPE_CONTEXT << 8)) + 0x1,`  
`VX_CONTEXT_UNIQUE_KERNELS = ((( VX_ID_KHRONOS ) << 20) | ( VX_TYPE_CONTEXT << 8)) +`  
`0x2,`  
`VX_CONTEXT_MODULES = ((( VX_ID_KHRONOS ) << 20) | ( VX_TYPE_CONTEXT << 8)) + 0x3,`  
`VX_CONTEXT_REFERENCES = ((( VX_ID_KHRONOS ) << 20) | ( VX_TYPE_CONTEXT << 8)) + 0x4,`  
`VX_CONTEXT_IMPLEMENTATION = ((( VX_ID_KHRONOS ) << 20) | ( VX_TYPE_CONTEXT << 8)) +`  
`0x5,`  
`VX_CONTEXT_EXTENSIONS_SIZE = ((( VX_ID_KHRONOS ) << 20) | ( VX_TYPE_CONTEXT << 8)) +`  
`0x6,`  
`VX_CONTEXT_EXTENSIONS = ((( VX_ID_KHRONOS ) << 20) | ( VX_TYPE_CONTEXT << 8)) + 0x7,`  
`VX_CONTEXT_CONVOLUTION_MAX_DIMENSION = ((( VX_ID_KHRONOS ) << 20) | ( VX_TYPE_CO↵`  
`NTEXT << 8)) + 0x8,`  
`VX_CONTEXT_OPTICAL_FLOW_MAX_WINDOW_DIMENSION = ((( VX_ID_KHRONOS ) << 20) | ( VX↵`  
`_TYPE_CONTEXT << 8)) + 0x9,`  
`VX_CONTEXT_IMMEDIATE_BORDER = ((( VX_ID_KHRONOS ) << 20) | ( VX_TYPE_CONTEXT << 8))`  
`+ 0xA,`  
`VX_CONTEXT_UNIQUE_KERNEL_TABLE = ((( VX_ID_KHRONOS ) << 20) | ( VX_TYPE_CONTEXT <<`  
`8)) + 0xB,`  
`VX_CONTEXT_IMMEDIATE_BORDER_POLICY = ((( VX_ID_KHRONOS ) << 20) | ( VX_TYPE_CONTE↵`  
`XT << 8)) + 0xC,`  
`VX_CONTEXT_NONLINEAR_MAX_DIMENSION = ((( VX_ID_KHRONOS ) << 20) | ( VX_TYPE_CONT↵`  
`EXT << 8)) + 0xD,`  
`VX_CONTEXT_MAX_TENSOR_DIMS = ((( VX_ID_KHRONOS ) << 20) | ( VX_TYPE_CONTEXT << 8))`  
`+ 0xE }`  
*A list of context attributes.*



- enum `vx_memory_type_e` {  
`VX_MEMORY_TYPE_NONE` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_MEMORY_TYPE` << 12)) + 0x0,  
`VX_MEMORY_TYPE_HOST` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_MEMORY_TYPE` << 12)) + 0x1 }

*An enumeration of memory import types.*

- enum `vx_round_policy_e` {  
`VX_ROUND_POLICY_TO_ZERO` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_ROUND_POLICY` << 12)) + 0x1,  
`VX_ROUND_POLICY_TO_NEAREST_EVEN` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_ROUND_POLICY` << 12)) + 0x2 }

*The Round Policy Enumeration.*

- enum `vx_termination_criteria_e` {  
`VX_TERM_CRITERIA_ITERATIONS` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_TERM_CRITERIA` << 12)) + 0x0,  
`VX_TERM_CRITERIA_EPSILON` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_TERM_CRITERIA` << 12)) + 0x1,  
`VX_TERM_CRITERIA_BOTH` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_TERM_CRITERIA` << 12)) + 0x2 }

*The termination criteria list.*

## Functions

- `vx_context VX_API_CALL vxCreateContext` (void)  
*Creates a `vx_context`.*
- `vx_context VX_API_CALL vxGetContext` (`vx_reference` reference)  
*Retrieves the context from any reference from within a context.*
- `vx_status VX_API_CALL vxQueryContext` (`vx_context` context, `vx_enum` attribute, void \*ptr, `vx_size` size)  
*Queries the context for some specific information.*
- `vx_status VX_API_CALL vxReleaseContext` (`vx_context` \*context)  
*Releases the OpenVX object context.*
- `vx_status VX_API_CALL vxSetContextAttribute` (`vx_context` context, `vx_enum` attribute, const void \*ptr, `vx_size` size)  
*Sets an attribute on the context.*
- `vx_status VX_API_CALL vxSetImmediateModeTarget` (`vx_context` context, `vx_enum` target\_enum, const char \*target\_string)  
*Sets the default target of the immediate mode. Upon successful execution of this function any future execution of immediate mode function is attempted on the new default target of the context.*

### 3.65.2 Typedef Documentation

**typedef struct \_vx\_context\* vx\_context**

An opaque reference to the implementation context.

See also

[vxCreateContext](#)

Definition at line 215 of file [vx\\_types.h](#).

### 3.65.3 Enumeration Type Documentation

**enum vx\_context\_attribute\_e**

A list of context attributes.

## Enumerator

- VX\_CONTEXT\_VENDOR\_ID** Queries the unique vendor ID. Read-only. Use a [vx\\_uint16](#).
- VX\_CONTEXT\_VERSION** Queries the OpenVX Version Number. Read-only. Use a [vx\\_uint16](#).
- VX\_CONTEXT\_UNIQUE\_KERNELS** Queries the context for the number of *unique* kernels. Read-only. Use a [vx\\_uint32](#) parameter.
- VX\_CONTEXT\_MODULES** Queries the context for the number of active modules. Read-only. Use a [vx\\_uint32](#) parameter.
- VX\_CONTEXT\_REFERENCES** Queries the context for the number of active references. Read-only. Use a [vx\\_uint32](#) parameter.
- VX\_CONTEXT\_IMPLEMENTATION** Queries the context for its implementation name. Read-only. Use a [vx\\_char\[VX\\_MAX\\_IMPLEMENTATION\\_NAME\]](#) array.
- VX\_CONTEXT\_EXTENSIONS\_SIZE** Queries the number of bytes in the extensions string. Read-only. Use a [vx\\_size](#) parameter.
- VX\_CONTEXT\_EXTENSIONS** Retrieves the extensions string. Read-only. This is a space-separated string of extension names. Each OpenVX official extension has a unique identifier, comprised of capital letters, numbers and the underscore character, prefixed with "KHR\_", for example "KHR\_NEW\_FEATURE". Use a [vx\\_char](#) pointer allocated to the size returned from [VX\\_CONTEXT\\_EXTENSIONS\\_SIZE](#).
- VX\_CONTEXT\_CONVOLUTION\_MAX\_DIMENSION** The maximum width or height of a convolution matrix. Read-only. Use a [vx\\_size](#) parameter. Each vendor must support centered kernels of size  $w \times h$ , where both  $w$  and  $h$  are odd numbers,  $3 \leq w \leq n$  and  $3 \leq h \leq n$ , where  $n$  is the value of the [VX\\_CONTEXT\\_CONVOLUTION\\_MAX\\_DIMENSION](#) attribute.  $n$  is an odd number that should not be smaller than 9.  $w$  and  $h$  may or may not be equal to each other. All combinations of  $w$  and  $h$  meeting the conditions above must be supported. The behavior of [vxCreateConvolution](#) is undefined for values larger than the value returned by this attribute.
- VX\_CONTEXT\_OPTICAL\_FLOW\_MAX\_WINDOW\_DIMENSION** The maximum window dimension of the OpticalFlowPyrLK kernel. The value of this attribute shall be equal to or greater than '9'.  
See also [VX\\_KERNEL\\_OPTICAL\\_FLOW\\_PYR\\_LK](#). Read-only. Use a [vx\\_size](#) parameter.
- VX\_CONTEXT\_IMMEDIATE\_BORDER** The border mode for immediate mode functions. Graph mode functions are unaffected by this attribute. Read-write. Use a pointer to a [vx\\_border\\_t](#) structure as parameter.  
Note  
The assumed default value for immediate mode functions is [VX\\_BORDER\\_UNDEFINED](#).
- VX\_CONTEXT\_UNIQUE\_KERNEL\_TABLE** Returns the table of all unique the kernels that exist in the context. Read-only. Use a [vx\\_kernel\\_info\\_t](#) array.  
Precondition  
You must call [vxQueryContext](#) with [VX\\_CONTEXT\\_UNIQUE\\_KERNELS](#) to compute the necessary size of the array.
- VX\_CONTEXT\_IMMEDIATE\_BORDER\_POLICY** The unsupported border mode policy for immediate mode functions. Read-Write. Graph mode functions are unaffected by this attribute. Use a [vx\\_enum](#) as parameter. Will contain a [vx\\_border\\_policy\\_e](#).  
Note  
The assumed default value for immediate mode functions is [VX\\_BORDER\\_POLICY\\_DEFAULT\\_TO\\_UNDEFINED](#). Users should refer to the documentation of their implementation to determine what border modes are supported by each kernel.
- VX\_CONTEXT\_NONLINEAR\_MAX\_DIMENSION** The dimension of the largest nonlinear filter supported. See [vxNonLinearFilterNode](#). The implementation must support all dimensions (height or width, not necessarily the same) up to the value of this attribute. The lowest value that must be supported for this attribute is 9. Read-only. Use a [vx\\_size](#) parameter.
- VX\_CONTEXT\_MAX\_TENSOR\_DIMS** tensor Data maximal number of dimensions supported by the implementation.

Definition at line 797 of file [vx\\_types.h](#).

**enum vx\_memory\_type\_e**

An enumeration of memory import types.

Enumerator

**VX\_MEMORY\_TYPE\_NONE** For memory allocated through OpenVX, this is the import type.

**VX\_MEMORY\_TYPE\_HOST** The default memory type to import from the Host.

Definition at line 1223 of file [vx\\_types.h](#).

**enum vx\_termination\_criteria\_e**

The termination criteria list.

See also

[Optical Flow Pyramid \(LK\)](#)

Enumerator

**VX\_TERM\_CRITERIA\_ITERATIONS** Indicates a termination after a set number of iterations.

**VX\_TERM\_CRITERIA\_EPSILON** Indicates a termination after matching against the value of epsilon provided to the function.

**VX\_TERM\_CRITERIA\_BOTH** Indicates that both an iterations and epsilon method are employed. Whichever one matches first causes the termination.

Definition at line 1363 of file [vx\\_types.h](#).

**enum vx\_accessor\_e**

The memory accessor hint flags. These enumeration values are used to indicate desired *system* behavior, not the **User** intent. For example: these can be interpreted as hints to the system about cache operations or marshalling operations.

Enumerator

**VX\_READ\_ONLY** The memory shall be treated by the system as if it were read-only. If the User writes to this memory, the results are implementation defined.

**VX\_WRITE\_ONLY** The memory shall be treated by the system as if it were write-only. If the User reads from this memory, the results are implementation defined.

**VX\_READ\_AND\_WRITE** The memory shall be treated by the system as if it were readable and writeable.

Definition at line 1401 of file [vx\\_types.h](#).

**enum vx\_round\_policy\_e**

The Round Policy Enumeration.

Enumerator

**VX\_ROUND\_POLICY\_TO\_ZERO** When scaling, this truncates the least significant values that are lost in operations.

**VX\_ROUND\_POLICY\_TO\_NEAREST\_EVEN** When scaling, this rounds to nearest even output value.

Definition at line 1418 of file [vx\\_types.h](#).

### 3.65.4 Function Documentation

**vx\_context VX\_API\_CALL vxCreateContext ( void )**

Creates a [vx\\_context](#).

This creates a top-level object context for OpenVX.

Note

This is required to do anything else.

Returns

The reference to the implementation context [vx\\_context](#). Any possible errors preventing a successful creation should be checked using [vxGetStatus](#).

Postcondition

[vxReleaseContext](#)

**vx\_status VX\_API\_CALL vxReleaseContext ( vx\_context \* context )**

Releases the OpenVX object context.

All reference counted objects are garbage-collected by the return of this call. No calls are possible using the parameter context after the context has been released until a new reference from [vxCreateContext](#) is returned. All outstanding references to OpenVX objects from this context are invalid after this call.

Parameters

|    |                |                                              |
|----|----------------|----------------------------------------------|
| in | <i>context</i> | The pointer to the reference to the context. |
|----|----------------|----------------------------------------------|

Postcondition

After returning from this function the reference is zeroed.

Returns

A [vx\\_status\\_e](#) enumeration.

Return values

|                                   |                                                              |
|-----------------------------------|--------------------------------------------------------------|
| <i>VX_SUCCESS</i>                 | No errors; any other value indicates failure.                |
| <i>VX_ERROR_INVALID_REFERENCE</i> | context is not a valid <a href="#">vx_context</a> reference. |

Precondition

[vxCreateContext](#)

**vx\_context VX\_API\_CALL vxGetContext ( vx\_reference reference )**

Retrieves the context from any reference from within a context.

Parameters

|    |                  |                                                  |
|----|------------------|--------------------------------------------------|
| in | <i>reference</i> | The reference from which to extract the context. |
|----|------------------|--------------------------------------------------|

## Returns

The overall context that created the particular reference. Any possible errors preventing a successful completion of this function should be checked using [vxGetStatus](#).

**vx\_status VX\_API\_CALL vxQueryContext ( vx\_context context, vx\_enum attribute, void \* ptr, vx\_size size )**

Queries the context for some specific information.

## Parameters

|     |                  |                                                                        |
|-----|------------------|------------------------------------------------------------------------|
| in  | <i>context</i>   | The reference to the context.                                          |
| in  | <i>attribute</i> | The attribute to query. Use a <a href="#">vx_context_attribute_e</a> . |
| out | <i>ptr</i>       | The location at which to store the resulting value.                    |
| in  | <i>size</i>      | The size in bytes of the container to which <i>ptr</i> points.         |

## Returns

A [vx\\_status\\_e](#) enumeration.

## Return values

|                                    |                                                              |
|------------------------------------|--------------------------------------------------------------|
| <i>VX_SUCCESS</i>                  | No errors; any other value indicates failure.                |
| <i>VX_ERROR_INVALID_REFERENCE</i>  | context is not a valid <a href="#">vx_context</a> reference. |
| <i>VX_ERROR_INVALID_PARAMETERS</i> | If any of the other parameters are incorrect.                |
| <i>VX_ERROR_NOT_SUPPORTED</i>      | If the attribute is not supported on this implementation.    |

**vx\_status VX\_API\_CALL vxSetContextAttribute ( vx\_context context, vx\_enum attribute, const void \* ptr, vx\_size size )**

Sets an attribute on the context.

## Parameters

|    |                  |                                                                    |
|----|------------------|--------------------------------------------------------------------|
| in | <i>context</i>   | The handle to the overall context.                                 |
| in | <i>attribute</i> | The attribute to set from <a href="#">vx_context_attribute_e</a> . |
| in | <i>ptr</i>       | The pointer to the data to which to set the attribute.             |
| in | <i>size</i>      | The size in bytes of the data to which <i>ptr</i> points.          |

## Returns

A [vx\\_status\\_e](#) enumeration.

## Return values

|                                    |                                                              |
|------------------------------------|--------------------------------------------------------------|
| <i>VX_SUCCESS</i>                  | No errors; any other value indicates failure.                |
| <i>VX_ERROR_INVALID_REFERENCE</i>  | context is not a valid <a href="#">vx_context</a> reference. |
| <i>VX_ERROR_INVALID_PARAMETERS</i> | If any of the other parameters are incorrect.                |
| <i>VX_ERROR_NOT_SUPPORTED</i>      | If the attribute is not settable.                            |

**vx\_status VX\_API\_CALL vxSetImmediateModeTarget ( vx\_context *context*, vx\_enum *target\_enum*, const char \* *target\_string* )**

Sets the default target of the immediate mode. Upon successful execution of this function any future execution of immediate mode function is attempted on the new default target of the context.

#### Parameters

|    |                      |                                                                                                                                                         |
|----|----------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>context</i>       | The reference to the implementation context.                                                                                                            |
| in | <i>target_enum</i>   | The default immediate mode target enum to be set to the <a href="#">vx_context</a> object. Use a <a href="#">vx_target_e</a> .                          |
| in | <i>target_string</i> | The target name ASCII string. This contains a valid value when <i>target_enum</i> is set to <a href="#">VX_TARGET_STRING</a> , otherwise it is ignored. |

#### Returns

A [vx\\_status\\_e](#) enumeration.

#### Return values

|                                            |                                                                     |
|--------------------------------------------|---------------------------------------------------------------------|
| <a href="#">VX_SUCCESS</a>                 | Default target set; any other value indicates failure.              |
| <a href="#">VX_ERROR_INVALID_REFERENCE</a> | If the context is not a valid <a href="#">vx_context</a> reference. |
| <a href="#">VX_ERROR_NOT_SUPPORTED</a>     | If the specified target is not supported in this context.           |

## 3.66 Object: Graph

### 3.66.1 Detailed Description

Defines the Graph Object interface.

A set of nodes connected in a directed (only goes one-way) acyclic (does not loop back) fashion. A Graph may have sets of Nodes that are unconnected to other sets of Nodes within the same Graph. See [Graph Formalisms](#). Figure below shows the Graph state transition diagram. Also see [vx\\_graph\\_state\\_e](#).




Figure 3.1: Graph State Transition

### Typedefs

- typedef struct \_vx\_graph \* [vx\\_graph](#)  
An opaque reference to a graph.

### Enumerations

- enum [vx\\_graph\\_attribute\\_e](#) {  
[VX\\_GRAPH\\_NUMNODES](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_TYPE\\_GRAPH](#) << 8)) + 0x0,  
[VX\\_GRAPH\\_PERFORMANCE](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_TYPE\\_GRAPH](#) << 8)) + 0x2,  
[VX\\_GRAPH\\_NUMPARAMETERS](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_TYPE\\_GRAPH](#) << 8)) + 0x3,  
[VX\\_GRAPH\\_STATE](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_TYPE\\_GRAPH](#) << 8)) + 0x4 }  
The graph attributes list.
- enum [vx\\_graph\\_state\\_e](#) {  
[VX\\_GRAPH\\_STATE\\_UNVERIFIED](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_ENUM\\_GRAPH\\_STATE](#) << 12)) + 0x0,  
[VX\\_GRAPH\\_STATE\\_VERIFIED](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_ENUM\\_GRAPH\\_STATE](#) << 12)) + 0x1,  
[VX\\_GRAPH\\_STATE\\_RUNNING](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_ENUM\\_GRAPH\\_STATE](#) << 12)) + 0x2,  
[VX\\_GRAPH\\_STATE\\_ABANDONED](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_ENUM\\_GRAPH\\_STATE](#) << 12)) + 0x3,  
[VX\\_GRAPH\\_STATE\\_COMPLETED](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_ENUM\\_GRAPH\\_STATE](#) << 12)) + 0x4 }  
The Graph State Enumeration.

## Functions

- [vx\\_graph VX\\_API\\_CALL vxCreateGraph \(vx\\_context context\)](#)  
*Creates an empty graph.*
- [vx\\_bool VX\\_API\\_CALL vxIsGraphVerified \(vx\\_graph graph\)](#)  
*Returns a Boolean to indicate the state of graph verification.*
- [vx\\_status VX\\_API\\_CALL vxProcessGraph \(vx\\_graph graph\)](#)  
*This function causes the synchronous processing of a graph. If the graph has not been verified, then the implementation verifies the graph immediately. If verification fails this function returns a status identical to what [vxVerifyGraph](#) would return. After the graph verifies successfully then processing occurs. If the graph was previously verified via [vxVerifyGraph](#) or [vxProcessGraph](#) then the graph is processed. This function blocks until the graph is completed.*
- [vx\\_status VX\\_API\\_CALL vxQueryGraph \(vx\\_graph graph, vx\\_enum attribute, void \\*ptr, vx\\_size size\)](#)  
*Allows the user to query attributes of the Graph.*
- [vx\\_status VX\\_API\\_CALL vxRegisterAutoAging \(vx\\_graph graph, vx\\_delay delay\)](#)  
*Register a delay for auto-aging.*
- [vx\\_status VX\\_API\\_CALL vxReleaseGraph \(vx\\_graph \\*graph\)](#)  
*Releases a reference to a graph. The object may not be garbage collected until its total reference count is zero. Once the reference count is zero, all node references in the graph are automatically released as well. Releasing the graph will only release the nodes if the nodes were not previously released by the application. Data referenced by those nodes may not be released as the user may still have references to the data.*
- [vx\\_status VX\\_API\\_CALL vxScheduleGraph \(vx\\_graph graph\)](#)  
*Schedules a graph for future execution. If the graph has not been verified, then the implementation verifies the graph immediately. If verification fails this function returns a status identical to what [vxVerifyGraph](#) would return. After the graph verifies successfully then processing occurs. If the graph was previously verified via [vxVerifyGraph](#) or [vxProcessGraph](#) then the graph is processed.*
- [vx\\_status VX\\_API\\_CALL vxSetGraphAttribute \(vx\\_graph graph, vx\\_enum attribute, const void \\*ptr, vx\\_size size\)](#)  
*Allows the attributes of the Graph to be set to the provided value.*
- [vx\\_status VX\\_API\\_CALL vxVerifyGraph \(vx\\_graph graph\)](#)  
*Verifies the state of the graph before it is executed. This is useful to catch programmer errors and contract errors. If not verified, the graph verifies before being processed.*
- [vx\\_status VX\\_API\\_CALL vxWaitGraph \(vx\\_graph graph\)](#)  
*Waits for a specific graph to complete. If the graph has been scheduled multiple times since the last call to [vxWaitGraph](#), then [vxWaitGraph](#) returns only when the last scheduled execution completes.*

### 3.66.2 Typedef Documentation

**typedef struct \_vx\_graph\* vx\_graph**

An opaque reference to a graph.

See also

[vxCreateGraph](#)

Definition at line 208 of file [vx\\_types.h](#).

### 3.66.3 Enumeration Type Documentation

**enum vx\_graph\_state\_e**

The Graph State Enumeration.

Enumerator

**VX\_GRAPH\_STATE\_UNVERIFIED** The graph should be verified before execution.

**VX\_GRAPH\_STATE\_VERIFIED** The graph has been verified and has not been executed or scheduled for execution yet.



**VX\_GRAPH\_STATE\_RUNNING** The graph either has been scheduled and not completed, or is being executed.

**VX\_GRAPH\_STATE\_ABANDONED** The graph execution was abandoned.

**VX\_GRAPH\_STATE\_COMPLETED** The graph execution is completed and the graph is not scheduled for execution.

Definition at line 661 of file [vx\\_types.h](#).

#### enum vx\_graph\_attribute\_e

The graph attributes list.

Enumerator

**VX\_GRAPH\_NUMNODES** Returns the number of nodes in a graph. Read-only. Use a [vx\\_uint32](#) parameter.

**VX\_GRAPH\_PERFORMANCE** Returns the overall performance of the graph. Read-only. Use a [vx\\_perf\\_t](#) parameter. The accuracy of timing information is platform dependent.

Note

Performance tracking must have been enabled. See [vx\\_directive\\_e](#)

**VX\_GRAPH\_NUMPARAMETERS** Returns the number of explicitly declared parameters on the graph. Read-only. Use a [vx\\_uint32](#) parameter.

**VX\_GRAPH\_STATE** Returns the state of the graph. See [vx\\_graph\\_state\\_e](#) enum.

Definition at line 677 of file [vx\\_types.h](#).

### 3.66.4 Function Documentation

#### vx\_graph VX\_API\_CALL vxCreateGraph ( vx\_context context )

Creates an empty graph.

Parameters

|    |                |                                              |
|----|----------------|----------------------------------------------|
| in | <i>context</i> | The reference to the implementation context. |
|----|----------------|----------------------------------------------|

Returns

A graph reference [vx\\_graph](#). Any possible errors preventing a successful creation should be checked using [vxGetStatus](#).

#### vx\_status VX\_API\_CALL vxReleaseGraph ( vx\_graph \* graph )

Releases a reference to a graph. The object may not be garbage collected until its total reference count is zero. Once the reference count is zero, all node references in the graph are automatically released as well. Releasing the graph will only release the nodes if the nodes were not previously released by the application. Data referenced by those nodes may not be released as the user may still have references to the data.

Parameters

|    |              |                                      |
|----|--------------|--------------------------------------|
| in | <i>graph</i> | The pointer to the graph to release. |
|----|--------------|--------------------------------------|

Postcondition

After returning from this function the reference is zeroed.

## Returns

A [vx\\_status\\_e](#) enumeration.

## Return values

|                                         |                                                          |
|-----------------------------------------|----------------------------------------------------------|
| <code>VX_SUCCESS</code>                 | No errors; any other value indicates failure.            |
| <code>VX_ERROR_INVALID_REFERENCE</code> | graph is not a valid <a href="#">vx_graph</a> reference. |

**vx\_status VX\_API\_CALL vxVerifyGraph ( vx\_graph graph )**

Verifies the state of the graph before it is executed. This is useful to catch programmer errors and contract errors. If not verified, the graph verifies before being processed.

## Precondition

Memory for data objects is not guaranteed to exist before this call.

## Postcondition

After this call data objects exist unless the implementation optimized them out.

## Parameters

|    |              |                                       |
|----|--------------|---------------------------------------|
| in | <i>graph</i> | The reference to the graph to verify. |
|----|--------------|---------------------------------------|

## Returns

A status code for graphs with more than one error; it is undefined which error will be returned. Register a log callback using [vxRegisterLogCallback](#) to receive each specific error in the graph.

A [vx\\_status\\_e](#) enumeration.

## Return values

|                                         |                                                                  |
|-----------------------------------------|------------------------------------------------------------------|
| <code>VX_SUCCESS</code>                 | No errors; any other value indicates failure.                    |
| <code>VX_ERROR_INVALID_REFERENCE</code> | graph is not a valid <a href="#">vx_graph</a> reference.         |
| <code>VX_ERROR_MULTIPLE_WRITERS</code>  | If the graph contains more than one writer to any data object.   |
| <code>VX_ERROR_INVALID_NODE</code>      | If a node in the graph is invalid or failed to be created.       |
| <code>VX_ERROR_INVALID_GRAPH</code>     | If the graph contains cycles or some other invalid topology.     |
| <code>VX_ERROR_INVALID_TYPE</code>      | If any parameter on a node is given the wrong type.              |
| <code>VX_ERROR_INVALID_VALUE</code>     | If any value of any parameter is out of bounds of specification. |
| <code>VX_ERROR_INVALID_FORMAT</code>    | If the image format is not compatible.                           |

## See also

[vxProcessGraph](#)

**vx\_status VX\_API\_CALL vxProcessGraph ( vx\_graph graph )**

This function causes the synchronous processing of a graph. If the graph has not been verified, then the implementation verifies the graph immediately. If verification fails this function returns a status identical to what [vxVerifyGraph](#) would return. After the graph verifies successfully then processing occurs. If the graph was previously verified via [vxVerifyGraph](#) or [vxProcessGraph](#) then the graph is processed. This function blocks until the graph is completed.

**Parameters**

|    |              |                       |
|----|--------------|-----------------------|
| in | <i>graph</i> | The graph to execute. |
|----|--------------|-----------------------|

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                                         |                                                              |
|-----------------------------------------|--------------------------------------------------------------|
| <code>VX_SUCCESS</code>                 | Graph has been processed; any other value indicates failure. |
| <code>VX_ERROR_INVALID_REFERENCE</code> | graph is not a valid <code>vx_graph</code> reference.        |
| <code>VX_FAILURE</code>                 | A catastrophic error occurred during processing.             |

**`vx_status VX_API_CALL vxScheduleGraph ( vx_graph graph )`**

Schedules a graph for future execution. If the graph has not been verified, then the implementation verifies the graph immediately. If verification fails this function returns a status identical to what `vxVerifyGraph` would return. After the graph verifies successfully then processing occurs. If the graph was previously verified via `vxVerifyGraph` or `vxProcessGraph` then the graph is processed.

**Parameters**

|    |              |                        |
|----|--------------|------------------------|
| in | <i>graph</i> | The graph to schedule. |
|----|--------------|------------------------|

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                                         |                                                                  |
|-----------------------------------------|------------------------------------------------------------------|
| <code>VX_SUCCESS</code>                 | The graph has been scheduled; any other value indicates failure. |
| <code>VX_ERROR_INVALID_REFERENCE</code> | graph is not a valid <code>vx_graph</code> reference.            |
| <code>VX_ERROR_NO_RESOURCES</code>      | The graph cannot be scheduled now.                               |
| <code>VX_ERROR_NOT_SUFFICIENT</code>    | The graph is not verified and has failed forced verification.    |

**`vx_status VX_API_CALL vxWaitGraph ( vx_graph graph )`**

Waits for a specific graph to complete. If the graph has been scheduled multiple times since the last call to `vxWaitGraph`, then `vxWaitGraph` returns only when the last scheduled execution completes.

**Parameters**

|    |              |                       |
|----|--------------|-----------------------|
| in | <i>graph</i> | The graph to wait on. |
|----|--------------|-----------------------|

**Returns**

A `vx_status_e` enumeration.

## Return values

|                                   |                                                                                                                                                       |
|-----------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------|
| <i>VX_SUCCESS</i>                 | The graph has successfully completed execution and its outputs are the valid results of the most recent execution; any other value indicates failure. |
| <i>VX_ERROR_INVALID_REFERENCE</i> | graph is not a valid <a href="#">vx_graph</a> reference.                                                                                              |
| <i>VX_FAILURE</i>                 | An error occurred or the graph was never scheduled. Output data of the graph is undefined.                                                            |

## Precondition

[vxScheduleGraph](#)

**vx\_status VX\_API\_CALL vxQueryGraph ( vx\_graph graph, vx\_enum attribute, void \* ptr, vx\_size size )**

Allows the user to query attributes of the Graph.

## Parameters

|     |                  |                                                                |
|-----|------------------|----------------------------------------------------------------|
| in  | <i>graph</i>     | The reference to the created graph.                            |
| in  | <i>attribute</i> | The <a href="#">vx_graph_attribute_e</a> type needed.          |
| out | <i>ptr</i>       | The location at which to store the resulting value.            |
| in  | <i>size</i>      | The size in bytes of the container to which <i>ptr</i> points. |

## Returns

A [vx\\_status\\_e](#) enumeration.

## Return values

|                                   |                                                          |
|-----------------------------------|----------------------------------------------------------|
| <i>VX_SUCCESS</i>                 | No errors; any other value indicates failure.            |
| <i>VX_ERROR_INVALID_REFERENCE</i> | graph is not a valid <a href="#">vx_graph</a> reference. |

**vx\_status VX\_API\_CALL vxSetGraphAttribute ( vx\_graph graph, vx\_enum attribute, const void \* ptr, vx\_size size )**

Allows the attributes of the Graph to be set to the provided value.

## Parameters

|    |                  |                                                                |
|----|------------------|----------------------------------------------------------------|
| in | <i>graph</i>     | The reference to the graph.                                    |
| in | <i>attribute</i> | The <a href="#">vx_graph_attribute_e</a> type needed.          |
| in | <i>ptr</i>       | The location from which to read the value.                     |
| in | <i>size</i>      | The size in bytes of the container to which <i>ptr</i> points. |

## Returns

A [vx\\_status\\_e](#) enumeration.

## Return values

|                                   |                                                          |
|-----------------------------------|----------------------------------------------------------|
| <i>VX_SUCCESS</i>                 | No errors; any other value indicates failure.            |
| <i>VX_ERROR_INVALID_REFERENCE</i> | graph is not a valid <a href="#">vx_graph</a> reference. |

**vx\_bool VX\_API\_CALL vxIsGraphVerified ( vx\_graph graph )**

Returns a Boolean to indicate the state of graph verification.

**Parameters**

|    |              |                                      |
|----|--------------|--------------------------------------|
| in | <i>graph</i> | The reference to the graph to check. |
|----|--------------|--------------------------------------|

**Returns**

A [vx\\_bool](#) value.

**Return values**

|                            |                                                                                                                                                                                                           |
|----------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <a href="#">vx_true_e</a>  | The graph is verified.                                                                                                                                                                                    |
| <a href="#">vx_false_e</a> | The graph is not verified. It must be verified before execution either through <a href="#">vxVerifyGraph</a> or automatically through <a href="#">vxProcessGraph</a> or <a href="#">vxScheduleGraph</a> . |

**vx\_status VX\_API\_CALL vxRegisterAutoAging ( vx\_graph graph, vx\_delay delay )**

Register a delay for auto-aging.

This function registers a delay object to be auto-aged by the graph. This delay object will be automatically aged after each successful completion of this graph. Aging of a delay object cannot be called during graph execution. A graph abandoned due to a node callback will trigger an auto-aging.

If a delay is registered for auto-aging multiple times in a same graph, the delay will be only aged a single time at each graph completion. If a delay is registered for auto-aging in multiple graphs, this delay will aged automatically after each successful completion of any of these graphs.

**Parameters**

|    |              |                                                            |
|----|--------------|------------------------------------------------------------|
| in | <i>graph</i> | The graph to which the delay is registered for auto-aging. |
| in | <i>delay</i> | The delay to automatically age.                            |

**Returns**

A [vx\\_status\\_e](#) enumeration.

**Return values**

|                                            |                                                                                                                      |
|--------------------------------------------|----------------------------------------------------------------------------------------------------------------------|
| <a href="#">VX_SUCCESS</a>                 | No errors; any other value indicates failure.                                                                        |
| <a href="#">VX_ERROR_INVALID_REFERENCE</a> | graph is not a valid <a href="#">vx_graph</a> reference, or delay is not a valid <a href="#">vx_delay</a> reference. |

## 3.67 Object: Node

### 3.67.1 Detailed Description

Defines the Node Object interface.

A node is an instance of a kernel that will be paired with a specific set of references (the parameters). Nodes are created from and associated with a single graph only. When a `vx_parameter` is extracted from a Node, an additional attribute can be accessed:

- *Reference* - The `vx_reference` assigned to this parameter index from the Node creation function (e.g., `vxSobel13x3Node`).

### Typedefs

- typedef struct \_vx\_node \* `vx_node`  
*An opaque reference to a kernel node.*

### Enumerations

- enum `vx_node_attribute_e` {  
`VX_NODE_STATUS` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_TYPE_NODE` << 8)) + 0x0,  
`VX_NODE_PERFORMANCE` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_TYPE_NODE` << 8)) + 0x1,  
`VX_NODE_BORDER` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_TYPE_NODE` << 8)) + 0x2,  
`VX_NODE_LOCAL_DATA_SIZE` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_TYPE_NODE` << 8)) + 0x3,  
`VX_NODE_LOCAL_DATA_PTR` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_TYPE_NODE` << 8)) + 0x4,  
`VX_NODE_PARAMETERS` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_TYPE_NODE` << 8)) + 0x5,  
`VX_NODE_IS_REPLICATED` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_TYPE_NODE` << 8)) + 0x6,  
`VX_NODE_REPLICATE_FLAGS` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_TYPE_NODE` << 8)) + 0x7,  
`VX_NODE_VALID_RECT_RESET` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_TYPE_NODE` << 8)) + 0x8 }

*The node attributes list.*

### Functions

- `vx_status VX_API_CALL vxQueryNode` (`vx_node` node, `vx_enum` attribute, void \*ptr, `vx_size` size)  
*Allows a user to query information out of a node.*
- `vx_status VX_API_CALL vxReleaseNode` (`vx_node` \*node)  
*Releases a reference to a Node object. The object may not be garbage collected until its total reference count is zero.*
- `vx_status VX_API_CALL vxRemoveNode` (`vx_node` \*node)  
*Removes a Node from its parent Graph and releases it.*
- `vx_status VX_API_CALL vxReplicateNode` (`vx_graph` graph, `vx_node` first\_node, `vx_bool` replicate[], `vx_uint32` number\_of\_parameters)  
*Creates replicas of the same node first\_node to process a set of objects stored in vx\_pyramid or vx\_object\_array. first\_node needs to have as parameter levels 0 of a vx\_pyramid or the index 0 of a vx\_object\_array. Replica nodes are not accessible by the application through any means. An application request for removal of first\_node from the graph will result in removal of all replicas. Any change of parameter or attribute of first\_node will be propagated to the replicas. vxVerifyGraph shall enforce consistency of parameters and attributes in the replicas.*
- `vx_status VX_API_CALL vxSetNodeAttribute` (`vx_node` node, `vx_enum` attribute, const void \*ptr, `vx_size` size)  
*Allows a user to set attribute of a node before Graph Validation.*
- `vx_status VX_API_CALL vxSetNodeTarget` (`vx_node` node, `vx_enum` target\_enum, const char \*target\_string)  
*Sets the node target to the provided value. A success invalidates the graph that the node belongs to (vxVerifyGraph must be called before the next execution)*

### 3.67.2 Typedef Documentation

**typedef struct \_vx\_node\* vx\_node**

An opaque reference to a kernel node.

See also

[vxCreateGenericNode](#)

Definition at line 201 of file [vx\\_types.h](#).

### 3.67.3 Enumeration Type Documentation

**enum vx\_node\_attribute\_e**

The node attributes list.

Enumerator

**VX\_NODE\_STATUS** Queries the status of node execution. Read-only. Use a [vx\\_status](#) parameter.

**VX\_NODE\_PERFORMANCE** Queries the performance of the node execution. The accuracy of timing information is platform dependent and also depends on the graph optimizations. Read-only.

Note

Performance tracking must have been enabled. See [vx\\_directive\\_e](#).

**VX\_NODE\_BORDER** Gets or sets the border mode of the node. Read-write. Use a [vx\\_border\\_t](#) structure with a default value of VX\_BORDER\_UNDEFINED.

**VX\_NODE\_LOCAL\_DATA\_SIZE** Indicates the size of the kernel local memory area. Read-only. Can be written only at user-node (de)initialization if VX\_KERNEL\_LOCAL\_DATA\_SIZE==0. Use a [vx\\_size](#) parameter.

**VX\_NODE\_LOCAL\_DATA\_PTR** Indicates the pointer kernel local memory area. Read-Write. Can be written only at user-node (de)initialization if VX\_KERNEL\_LOCAL\_DATA\_SIZE==0. Use a void \* parameter.

**VX\_NODE\_PARAMETERS** Indicates the number of node parameters, including optional parameters that are not passed. Read-only. Use a [vx\\_uint32](#) parameter.

**VX\_NODE\_IS\_REPLICATED** Indicates whether the node is replicated. Read-only. Use a [vx\\_bool](#) parameter.

**VX\_NODE\_REPLICATE\_FLAGS** Indicates the replicated parameters. Read-only. Use a [vx\\_bool\\*](#) parameter.

**VX\_NODE\_VALID\_RECT\_RESET** Indicates the behavior with respect to the valid rectangle. Read-only. Use a [vx\\_bool](#) parameter.

Definition at line 886 of file [vx\\_types.h](#).

### 3.67.4 Function Documentation

**vx\_status VX\_API\_CALL vxQueryNode ( vx\_node node, vx\_enum attribute, void \* ptr, vx\_size size )**

Allows a user to query information out of a node.

Parameters

|     |                  |                                                                         |
|-----|------------------|-------------------------------------------------------------------------|
| in  | <i>node</i>      | The reference to the node to query.                                     |
| in  | <i>attribute</i> | Use <a href="#">vx_node_attribute_e</a> value to query for information. |
| out | <i>ptr</i>       | The location at which to store the resulting value.                     |
| in  | <i>size</i>      | The size in bytes of the container to which <i>ptr</i> points.          |

## Returns

A `vx_status_e` enumeration.

## Return values

|                                          |                                                     |
|------------------------------------------|-----------------------------------------------------|
| <code>VX_SUCCESS</code>                  | No errors; any other value indicates failure.       |
| <code>VX_ERROR_INVALID_REFERENCE</code>  | node is not a valid <code>vx_node</code> reference. |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | The type or size is incorrect.                      |

**`vx_status VX_API_CALL vxSetNodeAttribute ( vx_node node, vx_enum attribute, const void * ptr, vx_size size )`**

Allows a user to set attribute of a node before Graph Validation.

## Parameters

|    |                        |                                                                          |
|----|------------------------|--------------------------------------------------------------------------|
| in | <code>node</code>      | The reference to the node to set.                                        |
| in | <code>attribute</code> | Use <code>vx_node_attribute_e</code> value to set the desired attribute. |
| in | <code>ptr</code>       | The pointer to the desired value of the attribute.                       |
| in | <code>size</code>      | The size in bytes of the objects to which <code>ptr</code> points.       |

## Note

Some attributes are inherited from the `vx_kernel`, which was used to create the node. Some of these can be overridden using this API, notably `VX_NODE_LOCAL_DATA_SIZE` and `VX_NODE_LOCAL_DATA_PTR`.

## Returns

A `vx_status_e` enumeration.

## Return values

|                                          |                                                           |
|------------------------------------------|-----------------------------------------------------------|
| <code>VX_SUCCESS</code>                  | The attribute was set; any other value indicates failure. |
| <code>VX_ERROR_INVALID_REFERENCE</code>  | node is not a valid <code>vx_node</code> reference.       |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | size is not correct for the type needed.                  |

**`vx_status VX_API_CALL vxReleaseNode ( vx_node * node )`**

Releases a reference to a Node object. The object may not be garbage collected until its total reference count is zero.

## Parameters

|    |                   |                                                      |
|----|-------------------|------------------------------------------------------|
| in | <code>node</code> | The pointer to the reference of the node to release. |
|----|-------------------|------------------------------------------------------|

## Postcondition

After returning from this function the reference is zeroed.

## Returns

A `vx_status_e` enumeration.



## Return values

|                                   |                                                        |
|-----------------------------------|--------------------------------------------------------|
| <i>VX_SUCCESS</i>                 | No errors; any other value indicates failure.          |
| <i>VX_ERROR_INVALID_REFERENCE</i> | node is not a valid <a href="#">vx_node</a> reference. |

**vx\_status VX\_API\_CALL vxRemoveNode ( vx\_node \* *node* )**

Removes a Node from its parent Graph and releases it.

## Parameters

|    |             |                                                |
|----|-------------|------------------------------------------------|
| in | <i>node</i> | The pointer to the node to remove and release. |
|----|-------------|------------------------------------------------|

## Postcondition

After returning from this function the reference is zeroed.

## Returns

A [vx\\_status\\_e](#) enumeration.

## Return values

|                                   |                                                        |
|-----------------------------------|--------------------------------------------------------|
| <i>VX_SUCCESS</i>                 | No errors; any other value indicates failure.          |
| <i>VX_ERROR_INVALID_REFERENCE</i> | node is not a valid <a href="#">vx_node</a> reference. |

**vx\_status VX\_API\_CALL vxSetNodeTarget ( vx\_node *node*, vx\_enum *target\_enum*, const char \* *target\_string* )**

Sets the node target to the provided value. A success invalidates the graph that the node belongs to ([vxVerifyGraph](#) must be called before the next execution)

## Parameters

|    |                      |                                                                                                                                                         |
|----|----------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>node</i>          | The reference to the <a href="#">vx_node</a> object.                                                                                                    |
| in | <i>target_enum</i>   | The target enum to be set to the <a href="#">vx_node</a> object. Use a <a href="#">vx_target_e</a> .                                                    |
| in | <i>target_string</i> | The target name ASCII string. This contains a valid value when <i>target_enum</i> is set to <a href="#">VX_TARGET_STRING</a> , otherwise it is ignored. |

## Returns

A [vx\\_status\\_e](#) enumeration.

## Return values

|                                   |                                                              |
|-----------------------------------|--------------------------------------------------------------|
| <i>VX_SUCCESS</i>                 | Node target set; any other value indicates failure.          |
| <i>VX_ERROR_INVALID_REFERENCE</i> | node is not a valid <a href="#">vx_node</a> reference.       |
| <i>VX_ERROR_NOT_SUPPORTED</i>     | If the node kernel is not supported by the specified target. |

**vx\_status VX\_API\_CALL vxReplicateNode ( vx\_graph *graph*, vx\_node *first\_node*, vx\_bool *replicate*[], vx\_uint32 *number\_of\_parameters* )**

Creates replicas of the same node *first\_node* to process a set of objects stored in [vx\\_pyramid](#) or [vx\\_object\\_array](#). *first\_node* needs to have as parameter levels 0 of a [vx\\_pyramid](#) or the index 0 of a [vx\\_object\\_array](#). Replica nodes are not accessible by the application through any means. An application request for removal of *first\_node* from the graph will result in removal of all replicas. Any change of parameter or attribute of *first\_node* will be propagated to the replicas. [vxVerifyGraph](#) shall enforce consistency of parameters and attributes in the replicas.

#### Parameters

|    |                             |                                                                                                                                                                                                                                                                                                                                                                                |
|----|-----------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>graph</i>                | The reference to the graph.                                                                                                                                                                                                                                                                                                                                                    |
| in | <i>first_node</i>           | The reference to the node in the graph that will be replicated.                                                                                                                                                                                                                                                                                                                |
| in | <i>replicate</i>            | an array of size equal to the number of node parameters, vx_true_e for the parameters that should be iterated over (should be a reference to a vx_pyramid or a vx_object_array), vx_false_e for the parameters that should be the same across replicated nodes and for optional parameters that are not used. Should be vx_true_e for all output and bidirectional parameters. |
| in | <i>number_of_parameters</i> | number of elements in the replicate array                                                                                                                                                                                                                                                                                                                                      |

#### Returns

A [vx\\_status\\_e](#) enumeration.

#### Return values

|                                   |                                                                                                                                 |
|-----------------------------------|---------------------------------------------------------------------------------------------------------------------------------|
| <i>VX_SUCCESS</i>                 | No errors; any other value indicates failure.                                                                                   |
| <i>VX_ERROR_INVALID_REFERENCE</i> | graph is not a valid <a href="#">vx_graph</a> reference, or <i>first_node</i> is not a valid <a href="#">vx_node</a> reference. |
| <i>VX_ERROR_NOT_COMPATIBLE</i>    | At least one of replicated parameters is not of level 0 of a pyramid or at index 0 of an object array.                          |
| <i>VX_FAILURE</i>                 | If the node does not belong to the graph, or the number of objects in the parent objects of inputs and output are not the same. |

## 3.68 Object: Array

### 3.68.1 Detailed Description

Defines the Array Object Interface.

Array is a strongly-typed container, which provides random access by index to its elements in constant time. It uses value semantics for its own elements and holds copies of data. This is an example `for` loop over an Array:

```
vx_size i, stride = sizeof(vx_size);
void *base = NULL;
vx_map_id map_id;
/* access entire array at once */
vxMapArrayRange(array, 0, num_items, &map_id, &stride, &base,
VX_READ_AND_WRITE, VX_MEMORY_TYPE_HOST, 0);
for (i = 0; i < num_items; i++)
{
 vxArrayItem(mystruct, base, i, stride).some_uint += i;
 vxArrayItem(mystruct, base, i, stride).some_double = 3.14f;
}
vxUnmapArrayRange(array, map_id);
```

### Macros

- `#define vxArrayItem(type, ptr, index, stride) (*(type *) (vxFormatArrayPointer((ptr), (index), (stride))))`  
*Allows access to an array item as a typecast pointer deference.*
- `#define vxFormatArrayPointer(ptr, index, stride) (&(((vx_uint8*)(ptr))[(index) * (stride)]))`  
*Accesses a specific indexed element in an array.*

### Typedefs

- `typedef struct _vx_array * vx_array`  
*The Array Object. Array is a strongly-typed container for other data structures.*

### Enumerations

- `enum vx_array_attribute_e {`  
`VX_ARRAY_ITEMTYPE = ((( VX_ID_KHRONOS ) << 20) | ( VX_TYPE_ARRAY << 8)) + 0x0,`  
`VX_ARRAY_NUMITEMS = ((( VX_ID_KHRONOS ) << 20) | ( VX_TYPE_ARRAY << 8)) + 0x1,`  
`VX_ARRAY_CAPACITY = ((( VX_ID_KHRONOS ) << 20) | ( VX_TYPE_ARRAY << 8)) + 0x2,`  
`VX_ARRAY_ITEMSIZE = ((( VX_ID_KHRONOS ) << 20) | ( VX_TYPE_ARRAY << 8)) + 0x3 }`  
*The array object attributes.*

### Functions

- `vx_status VX_API_CALL vxAddArrayItems (vx_array arr, vx_size count, const void *ptr, vx_size stride)`  
*Adds items to the Array.*
- `vx_status VX_API_CALL vxCopyArrayRange (vx_array array, vx_size range_start, vx_size range_end, vx_size user_stride, void *user_ptr, vx_enum usage, vx_enum user_mem_type)`  
*Allows the application to copy a range from/into an array object.*
- `vx_array VX_API_CALL vxCreateArray (vx_context context, vx_enum item_type, vx_size capacity)`  
*Creates a reference to an Array object.*
- `vx_array VX_API_CALL vxCreateVirtualArray (vx_graph graph, vx_enum item_type, vx_size capacity)`  
*Creates an opaque reference to a virtual Array with no direct user access.*
- `vx_status VX_API_CALL vxMapArrayRange (vx_array array, vx_size range_start, vx_size range_end, vx_map_id *map_id, vx_size *stride, void **ptr, vx_enum usage, vx_enum mem_type, vx_uint32 flags)`  
*Allows the application to get direct access to a range of an array object.*
- `vx_status VX_API_CALL vxQueryArray (vx_array arr, vx_enum attribute, void *ptr, vx_size size)`  
*Queries the Array for some specific information.*
- `vx_status VX_API_CALL vxReleaseArray (vx_array *arr)`

*Releases a reference of an Array object. The object may not be garbage collected until its total reference count is zero. After returning from this function the reference is zeroed.*

- `vx_status VX_API_CALL vxTruncateArray (vx_array arr, vx_size new_num_items)`

*Truncates an Array (remove items from the end).*

- `vx_status VX_API_CALL vxUnmapArrayRange (vx_array array, vx_map_id map_id)`

*Unmap and commit potential changes to an array object range that was previously mapped. Unmapping an array range invalidates the memory location from which the range could be accessed by the application. Accessing this memory location after the unmap function completes has an undefined behavior.*

### 3.68.2 Macro Definition Documentation

```
#define vxFormatArrayPointer(ptr, index, stride) (&(((vx_uint8*)(ptr))[(index) * (stride)]))
```

Accesses a specific indexed element in an array.

#### Parameters

|    |               |                                                                          |
|----|---------------|--------------------------------------------------------------------------|
| in | <i>ptr</i>    | The base pointer for the array range.                                    |
| in | <i>index</i>  | The index of the element, not byte, to access.                           |
| in | <i>stride</i> | The 'number of bytes' between the beginning of two consecutive elements. |

Definition at line 2876 of file `vx_api.h`.

```
#define vxArrayItem(type, ptr, index, stride) (*(type*)(vxFormatArrayPointer((ptr), (index), (stride))))
```

Allows access to an array item as a typecast pointer deference.

#### Parameters

|    |               |                                                                          |
|----|---------------|--------------------------------------------------------------------------|
| in | <i>type</i>   | The type of the item to access.                                          |
| in | <i>ptr</i>    | The base pointer for the array range.                                    |
| in | <i>index</i>  | The index of the element, not byte, to access.                           |
| in | <i>stride</i> | The 'number of bytes' between the beginning of two consecutive elements. |

Definition at line 2887 of file `vx_api.h`.

### 3.68.3 Enumeration Type Documentation

```
enum vx_array_attribute_e
```

The array object attributes.

Enumerator

**VX\_ARRAY\_ITEMTYPE** The type of the Array items. Read-only. Use a `vx_enum` parameter.

**VX\_ARRAY\_NUMITEMS** The number of items in the Array. Read-only. Use a `vx_size` parameter.

**VX\_ARRAY\_CAPACITY** The maximal number of items that the Array can hold. Read-only. Use a `vx_size` parameter.

**VX\_ARRAY\_ITEMSIZE** Queries an array item size. Read-only. Use a `vx_size` parameter.

Definition at line 1145 of file `vx_types.h`.

### 3.68.4 Function Documentation

```
vx_array VX_API_CALL vxCreateArray (vx_context context, vx_enum item_type, vx_size capacity)
```

Creates a reference to an Array object.

User must specify the Array capacity (i.e., the maximal number of items that the array can hold).

**Parameters**

|    |                  |                                                                                                                                                                                                                                                |
|----|------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>context</i>   | The reference to the overall Context.                                                                                                                                                                                                          |
| in | <i>item_type</i> | The type of data to hold. Must be greater than <a href="#">VX_TYPE_INVALID</a> and less than or equal to <a href="#">VX_TYPE_VENDOR_STRUCT_END</a> . Or must be a <a href="#">vx_enum</a> returned from <a href="#">vxRegisterUserStruct</a> . |
| in | <i>capacity</i>  | The maximal number of items that the array can hold. This value must be greater than zero.                                                                                                                                                     |

**Returns**

An array reference [vx\\_array](#). Any possible errors preventing a successful creation should be checked using [vxGetStatus](#).

**vx\_array VX\_API\_CALL vxCreateVirtualArray ( vx\_graph graph, vx\_enum item\_type, vx\_size capacity )**

Creates an opaque reference to a virtual Array with no direct user access.

Virtual Arrays are useful when item type or capacity are unknown ahead of time and the Array is used as internal graph edge. Virtual arrays are scoped within the parent graph only.

All of the following constructions are allowed.

```
00001 vx_context context = vxCreateContext();
00002 vx_graph graph = vxCreateGraph(context);
00003 vx_array virt[] = {
00004 vxCreateVirtualArray(graph, 0, 0), // totally unspecified
00005 vxCreateVirtualArray(graph, VX_TYPE_KEYPOINT, 0), // unspecified capacity
00006 vxCreateVirtualArray(graph, VX_TYPE_KEYPOINT, 1000), // no access
00007 };
```

**Parameters**

|    |                  |                                                                                                                                                                                                                                                                                                              |
|----|------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>graph</i>     | The reference to the parent graph.                                                                                                                                                                                                                                                                           |
| in | <i>item_type</i> | The type of data to hold. Must be greater than <a href="#">VX_TYPE_INVALID</a> and less than or equal to <a href="#">VX_TYPE_VENDOR_STRUCT_END</a> . Or must be a <a href="#">vx_enum</a> returned from <a href="#">vxRegisterUserStruct</a> . This may be set to zero to indicate an unspecified item type. |
| in | <i>capacity</i>  | The maximal number of items that the array can hold. This may be set to zero to indicate an unspecified capacity.                                                                                                                                                                                            |

**See also**

[vxCreateArray](#) for a type list.

**Returns**

A array reference [vx\\_array](#). Any possible errors preventing a successful creation should be checked using [vxGetStatus](#).

**vx\_status VX\_API\_CALL vxReleaseArray ( vx\_array \* arr )**

Releases a reference of an Array object. The object may not be garbage collected until its total reference count is zero. After returning from this function the reference is zeroed.

**Parameters**

|    |            |                                      |
|----|------------|--------------------------------------|
| in | <i>arr</i> | The pointer to the Array to release. |
|----|------------|--------------------------------------|

## Returns

A `vx_status_e` enumeration.

## Return values

|                                         |                                                     |
|-----------------------------------------|-----------------------------------------------------|
| <code>VX_SUCCESS</code>                 | No errors; any other value indicates failure.       |
| <code>VX_ERROR_INVALID_REFERENCE</code> | arr is not a valid <code>vx_array</code> reference. |

**`vx_status VX_API_CALL vxQueryArray ( vx_array arr, vx_enum attribute, void * ptr, vx_size size )`**

Queries the Array for some specific information.

## Parameters

|     |                  |                                                                   |
|-----|------------------|-------------------------------------------------------------------|
| in  | <i>arr</i>       | The reference to the Array.                                       |
| in  | <i>attribute</i> | The attribute to query. Use a <code>vx_array_attribute_e</code> . |
| out | <i>ptr</i>       | The location at which to store the resulting value.               |
| in  | <i>size</i>      | The size in bytes of the container to which <i>ptr</i> points.    |

## Returns

A `vx_status_e` enumeration.

## Return values

|                                          |                                                                          |
|------------------------------------------|--------------------------------------------------------------------------|
| <code>VX_SUCCESS</code>                  | No errors; any other value indicates failure.                            |
| <code>VX_ERROR_INVALID_REFERENCE</code>  | arr is not a valid <code>vx_array</code> reference.                      |
| <code>VX_ERROR_NOT_SUPPORTED</code>      | If the <i>attribute</i> is not a value supported on this implementation. |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | If any of the other parameters are incorrect.                            |

**`vx_status VX_API_CALL vxAddArrayItems ( vx_array arr, vx_size count, const void * ptr, vx_size stride )`**

Adds items to the Array.

This function increases the container size.

By default, the function does not reallocate memory, so if the container is already full (number of elements is equal to capacity) or it doesn't have enough space, the function returns `VX_FAILURE` error code.

## Parameters

|    |               |                                                                        |
|----|---------------|------------------------------------------------------------------------|
| in | <i>arr</i>    | The reference to the Array.                                            |
| in | <i>count</i>  | The total number of elements to insert.                                |
| in | <i>ptr</i>    | The location from which to read the input values.                      |
| in | <i>stride</i> | The number of bytes between the beginning of two consecutive elements. |

## Returns

A `vx_status_e` enumeration.

## Return values

|                         |                                               |
|-------------------------|-----------------------------------------------|
| <code>VX_SUCCESS</code> | No errors; any other value indicates failure. |
|-------------------------|-----------------------------------------------|

## Return values

|                                          |                                                     |
|------------------------------------------|-----------------------------------------------------|
| <code>VX_ERROR_INVALID_REFERENCE</code>  | arr is not a valid <code>vx_array</code> reference. |
| <code>VX_FAILURE</code>                  | If the Array is full.                               |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | If any of the other parameters are incorrect.       |

**vx\_status VX\_API\_CALL vxTruncateArray ( vx\_array arr, vx\_size new\_num\_items )**

Truncates an Array (remove items from the end).

## Parameters

|         |                      |                                        |
|---------|----------------------|----------------------------------------|
| in, out | <i>arr</i>           | The reference to the Array.            |
| in      | <i>new_num_items</i> | The new number of items for the Array. |

## Returns

A `vx_status_e` enumeration.

## Return values

|                                          |                                                       |
|------------------------------------------|-------------------------------------------------------|
| <code>VX_SUCCESS</code>                  | No errors; any other value indicates failure.         |
| <code>VX_ERROR_INVALID_REFERENCE</code>  | arr is not a valid <code>vx_array</code> reference.   |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | The <i>new_size</i> is greater than the current size. |

**vx\_status VX\_API\_CALL vxCopyArrayRange ( vx\_array array, vx\_size range\_start, vx\_size range\_end, vx\_size user\_stride, void \* user\_ptr, vx\_enum usage, vx\_enum user\_mem\_type )**

Allows the application to copy a range from/into an array object.

## Parameters

|    |                    |                                                                                                                                                                                                                                                                                                                                                                                                                                    |
|----|--------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>array</i>       | The reference to the array object that is the source or the destination of the copy.                                                                                                                                                                                                                                                                                                                                               |
| in | <i>range_start</i> | The index of the first item of the array object to copy.                                                                                                                                                                                                                                                                                                                                                                           |
| in | <i>range_end</i>   | The index of the item following the last item of the array object to copy. (range_end range_start) items are copied from index range_start included. The range must be within the bounds of the array: $0 \leq \text{range\_start} < \text{range\_end} \leq \text{number of items in the array}$ .                                                                                                                                 |
| in | <i>user_stride</i> | The number of bytes between the beginning of two consecutive items in the user memory pointed by user_ptr. The layout of the user memory must follow an item major order: $\text{user\_stride} \geq \text{element size in bytes}$ .                                                                                                                                                                                                |
| in | <i>user_ptr</i>    | The address of the memory location where to store the requested data if the copy was requested in read mode, or from where to get the data to store into the array object if the copy was requested in write mode. The accessible memory must be large enough to contain the specified range with the specified stride: $\text{accessible memory in bytes} \geq (\text{range\_end} - \text{range\_start}) * \text{user\_stride}$ . |

## Parameters

|    |                      |                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
|----|----------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>usage</i>         | This declares the effect of the copy with regard to the array object using the <code>vx_accessor_e</code> enumeration. Only <code>VX_READ_ONLY</code> and <code>VX_WRITE_ONLY</code> are supported: <ul style="list-style-type: none"> <li>• <code>VX_READ_ONLY</code> means that data are copied from the array object into the user memory.</li> <li>• <code>VX_WRITE_ONLY</code> means that data are copied into the array object from the user memory.</li> </ul> |
| in | <i>user_mem_type</i> | A <code>vx_memory_type_e</code> enumeration that specifies the memory type of the memory referenced by the <code>user_addr</code> .                                                                                                                                                                                                                                                                                                                                   |

## Returns

A `vx_status_e` enumeration.

## Return values

|                                          |                                                                                    |
|------------------------------------------|------------------------------------------------------------------------------------|
| <code>VX_SUCCESS</code>                  | No errors; any other value indicates failure.                                      |
| <code>VX_ERROR_OPTIMIZED_AWAY</code>     | This is a reference to a virtual array that cannot be accessed by the application. |
| <code>VX_ERROR_INVALID_REFERENCE</code>  | array is not a valid <code>vx_array</code> reference.                              |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | An other parameter is incorrect.                                                   |

**vx\_status VX\_API\_CALL vxMapArrayRange ( vx\_array array, vx\_size range\_start, vx\_size range\_end, vx\_map\_id \* map\_id, vx\_size \* stride, void \*\* ptr, vx\_enum usage, vx\_enum mem\_type, vx\_uint32 flags )**

Allows the application to get direct access to a range of an array object.

## Parameters

|     |                    |                                                                                                                                                                                                                                                                                                                                                                                                                       |
|-----|--------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>array</i>       | The reference to the array object that contains the range to map.                                                                                                                                                                                                                                                                                                                                                     |
| in  | <i>range_start</i> | The index of the first item of the array object to map.                                                                                                                                                                                                                                                                                                                                                               |
| in  | <i>range_end</i>   | The index of the item following the last item of the array object to map. (range_end range_start) items are mapped, starting from index range_start included. The range must be within the bounds of the array: Must be 0 <= range_start < range_end <= number of items.                                                                                                                                              |
| out | <i>map_id</i>      | The address of a <code>vx_map_id</code> variable where the function returns a map identifier. <ul style="list-style-type: none"> <li>• (*map_id) must eventually be provided as the map_id parameter of a call to <code>vxUnmapArrayRange</code>.</li> </ul>                                                                                                                                                          |
| out | <i>stride</i>      | The address of a <code>vx_size</code> variable where the function returns the memory layout of the mapped array range. The function sets (*stride) to the number of bytes between the beginning of two consecutive items. The application must consult (*stride) to access the array items starting from address (*ptr). The layout of the mapped array follows an item major order: (*stride) >= item size in bytes. |
| out | <i>ptr</i>         | The address of a pointer that the function sets to the address where the requested data can be accessed. The returned (*ptr) address is only valid between the call to the function and the corresponding call to <code>vxUnmapArrayRange</code> .                                                                                                                                                                    |



## Parameters

|    |                 |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
|----|-----------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>usage</i>    | <p>This declares the access mode for the array range, using the <code>vx_accessor_e</code> enumeration.</p> <ul style="list-style-type: none"> <li>• <code>VX_READ_ONLY</code>: after the function call, the content of the memory location pointed by (*ptr) contains the array range data. Writing into this memory location is forbidden and its behavior is undefined.</li> <li>• <code>VX_READ_AND_WRITE</code>: after the function call, the content of the memory location pointed by (*ptr) contains the array range data; writing into this memory is allowed only for the location of items and will result in a modification of the affected items in the array object once the range is unmapped. Writing into a gap between items (when (*stride) &gt; item size in bytes) is forbidden and its behavior is undefined.</li> <li>• <code>VX_WRITE_ONLY</code>: after the function call, the memory location pointed by (*ptr) contains undefined data; writing each item of the range is required prior to unmapping. Items not written by the application before unmap will become undefined after unmap, even if they were well defined before map. Like for <code>VX_READ_AND_WRITE</code>, writing into a gap between items is forbidden and its behavior is undefined.</li> </ul> |
| in | <i>mem_type</i> | A <code>vx_memory_type_e</code> enumeration that specifies the type of the memory where the array range is requested to be mapped.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| in | <i>flags</i>    | An integer that allows passing options to the map operation. Use the <code>vx_map_flag_e</code> enumeration.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |

## Returns

A `vx_status_e` enumeration.

## Return values

|                                          |                                                                                    |
|------------------------------------------|------------------------------------------------------------------------------------|
| <code>VX_SUCCESS</code>                  | No errors; any other value indicates failure.                                      |
| <code>VX_ERROR_OPTIMIZED_AWAY</code>     | This is a reference to a virtual array that cannot be accessed by the application. |
| <code>VX_ERROR_INVALID_REFERENCE</code>  | array is not a valid <code>vx_array</code> reference.                              |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | An other parameter is incorrect.                                                   |

## Postcondition

`vxUnmapArrayRange` with same (\*map\_id) value.

**`vx_status VX_API_CALL vxUnmapArrayRange ( vx_array array, vx_map_id map_id )`**

Unmap and commit potential changes to an array object range that was previously mapped. Unmapping an array range invalidates the memory location from which the range could be accessed by the application. Accessing this memory location after the unmap function completes has an undefined behavior.

## Parameters

|     |               |                                                                                         |
|-----|---------------|-----------------------------------------------------------------------------------------|
| in  | <i>array</i>  | The reference to the array object to unmap.                                             |
| out | <i>map_id</i> | The unique map identifier that was returned when calling <code>vxMapArrayRange</code> . |

## Returns

A `vx_status_e` enumeration.

## Return values

|                                          |                                                       |
|------------------------------------------|-------------------------------------------------------|
| <code>VX_SUCCESS</code>                  | No errors; any other value indicates failure.         |
| <code>VX_ERROR_INVALID_REFERENCE</code>  | array is not a valid <code>vx_array</code> reference. |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | An other parameter is incorrect.                      |

## Precondition

`vxMapArrayRange` returning the same `map_id` value

## 3.69 Object: Convolution

### 3.69.1 Detailed Description

Defines the Image Convolution Object interface.

#### Typedefs

- typedef struct \_vx\_convolution \* [vx\\_convolution](#)  
*The Convolution Object. A user-defined convolution kernel of MxM elements.*

#### Enumerations

- enum [vx\\_convolution\\_attribute\\_e](#) {  
[VX\\_CONVOLUTION\\_ROWS](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_TYPE\\_CONVOLUTION](#) << 8)) + 0x0,  
[VX\\_CONVOLUTION\\_COLUMNS](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_TYPE\\_CONVOLUTION](#) << 8)) + 0x1,  
[VX\\_CONVOLUTION\\_SCALE](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_TYPE\\_CONVOLUTION](#) << 8)) + 0x2,  
[VX\\_CONVOLUTION\\_SIZE](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_TYPE\\_CONVOLUTION](#) << 8)) + 0x3 }  
*The convolution attributes.*

#### Functions

- [vx\\_status VX\\_API\\_CALL vxCopyConvolutionCoefficients](#) ([vx\\_convolution](#) conv, void \*user\_ptr, [vx\\_enum](#) usage, [vx\\_enum](#) user\_mem\_type)  
*Allows the application to copy coefficients from/into a convolution object.*
- [vx\\_convolution VX\\_API\\_CALL vxCreateConvolution](#) ([vx\\_context](#) context, [vx\\_size](#) columns, [vx\\_size](#) rows)  
*Creates a reference to a convolution matrix object.*
- [vx\\_convolution VX\\_API\\_CALL vxCreateVirtualConvolution](#) ([vx\\_graph](#) graph, [vx\\_size](#) columns, [vx\\_size](#) rows)  
*Creates an opaque reference to a convolution matrix object without direct user access.*
- [vx\\_status VX\\_API\\_CALL vxQueryConvolution](#) ([vx\\_convolution](#) conv, [vx\\_enum](#) attribute, void \*ptr, [vx\\_size](#) size)  
*Queries an attribute on the convolution matrix object.*
- [vx\\_status VX\\_API\\_CALL vxReleaseConvolution](#) ([vx\\_convolution](#) \*conv)  
*Releases the reference to a convolution matrix. The object may not be garbage collected until its total reference count is zero.*
- [vx\\_status VX\\_API\\_CALL vxSetConvolutionAttribute](#) ([vx\\_convolution](#) conv, [vx\\_enum](#) attribute, const void \*ptr, [vx\\_size](#) size)  
*Sets attributes on the convolution object.*

### 3.69.2 Enumeration Type Documentation

#### enum [vx\\_convolution\\_attribute\\_e](#)

The convolution attributes.

Enumerator

- [VX\\_CONVOLUTION\\_ROWS](#)** The number of rows of the convolution matrix. Read-only. Use a [vx\\_size](#) parameter.
- [VX\\_CONVOLUTION\\_COLUMNS](#)** The number of columns of the convolution matrix. Read-only. Use a [vx\\_size](#) parameter.
- [VX\\_CONVOLUTION\\_SCALE](#)** The scale of the convolution matrix. Read-write. Use a [vx\\_uint32](#) parameter.

## Note

For 1.0, only powers of 2 are supported up to  $2^{31}$ .

**VX\_CONVOLUTION\_SIZE** The total size of the convolution matrix in bytes. Read-only. Use a [vx\\_size](#) parameter.

Definition at line [1097](#) of file [vx\\_types.h](#).

### 3.69.3 Function Documentation

**vx\_convolution VX\_API\_CALL vxCreateConvolution ( vx\_context context, vx\_size columns, vx\_size rows )**

Creates a reference to a convolution matrix object.

## Parameters

|    |                |                                                                                                                                                                                   |
|----|----------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>context</i> | The reference to the overall context.                                                                                                                                             |
| in | <i>columns</i> | The columns dimension of the convolution. Must be odd and greater than or equal to 3 and less than the value returned from <a href="#">VX_CONTEXT_CONVOLUTION_MAX_DIMENSION</a> . |
| in | <i>rows</i>    | The rows dimension of the convolution. Must be odd and greater than or equal to 3 and less than the value returned from <a href="#">VX_CONTEXT_CONVOLUTION_MAX_DIMENSION</a> .    |

## Returns

A convolution reference [vx\\_convolution](#). Any possible errors preventing a successful creation should be checked using [vxGetStatus](#).

**vx\_convolution VX\_API\_CALL vxCreateVirtualConvolution ( vx\_graph graph, vx\_size columns, vx\_size rows )**

Creates an opaque reference to a convolution matrix object without direct user access.

## Parameters

|    |                |                                                                                                                                                                                   |
|----|----------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>graph</i>   | The reference to the parent graph.                                                                                                                                                |
| in | <i>columns</i> | The columns dimension of the convolution. Must be odd and greater than or equal to 3 and less than the value returned from <a href="#">VX_CONTEXT_CONVOLUTION_MAX_DIMENSION</a> . |
| in | <i>rows</i>    | The rows dimension of the convolution. Must be odd and greater than or equal to 3 and less than the value returned from <a href="#">VX_CONTEXT_CONVOLUTION_MAX_DIMENSION</a> .    |

## See also

[vxCreateConvolution](#)

## Returns

A convolution reference [vx\\_convolution](#). Any possible errors preventing a successful creation should be checked using [vxGetStatus](#).

**vx\_status VX\_API\_CALL vxReleaseConvolution ( vx\_convolution \* conv )**

Releases the reference to a convolution matrix. The object may not be garbage collected until its total reference count is zero.

## Parameters

|    |             |                                                   |
|----|-------------|---------------------------------------------------|
| in | <i>conv</i> | The pointer to the convolution matrix to release. |
|----|-------------|---------------------------------------------------|

## Postcondition

After returning from this function the reference is zeroed.

## Returns

A `vx_status_e` enumeration.

## Return values

|                                         |                                                            |
|-----------------------------------------|------------------------------------------------------------|
| <code>VX_SUCCESS</code>                 | No errors; any other value indicates failure.              |
| <code>VX_ERROR_INVALID_REFERENCE</code> | conv is not a valid <code>vx_convolution</code> reference. |

**`vx_status VX_API_CALL vxQueryConvolution ( vx_convolution conv, vx_enum attribute, void * ptr, vx_size size )`**

Queries an attribute on the convolution matrix object.

## Parameters

|     |                        |                                                                                    |
|-----|------------------------|------------------------------------------------------------------------------------|
| in  | <code>conv</code>      | The convolution matrix object to set.                                              |
| in  | <code>attribute</code> | The attribute to query. Use a <code>vx_convolution_attribute_e</code> enumeration. |
| out | <code>ptr</code>       | The location at which to store the resulting value.                                |
| in  | <code>size</code>      | The size in bytes of the container to which <code>ptr</code> points.               |

## Returns

A `vx_status_e` enumeration.

## Return values

|                                         |                                                            |
|-----------------------------------------|------------------------------------------------------------|
| <code>VX_SUCCESS</code>                 | No errors; any other value indicates failure.              |
| <code>VX_ERROR_INVALID_REFERENCE</code> | conv is not a valid <code>vx_convolution</code> reference. |

**`vx_status VX_API_CALL vxSetConvolutionAttribute ( vx_convolution conv, vx_enum attribute, const void * ptr, vx_size size )`**

Sets attributes on the convolution object.

## Parameters

|    |                        |                                                                                     |
|----|------------------------|-------------------------------------------------------------------------------------|
| in | <code>conv</code>      | The coordinates object to set.                                                      |
| in | <code>attribute</code> | The attribute to modify. Use a <code>vx_convolution_attribute_e</code> enumeration. |
| in | <code>ptr</code>       | The pointer to the value to which to set the attribute.                             |
| in | <code>size</code>      | The size in bytes of the data pointed to by <code>ptr</code> .                      |

## Returns

A `vx_status_e` enumeration.

## Return values

|                         |                                               |
|-------------------------|-----------------------------------------------|
| <code>VX_SUCCESS</code> | No errors; any other value indicates failure. |
|-------------------------|-----------------------------------------------|

## Return values

|                                         |                                                            |
|-----------------------------------------|------------------------------------------------------------|
| <code>VX_ERROR_INVALID_REFERENCE</code> | conv is not a valid <code>vx_convolution</code> reference. |
|-----------------------------------------|------------------------------------------------------------|

**vx\_status VX\_API\_CALL vxCopyConvolutionCoefficients ( vx\_convolution conv, void \* user\_ptr, vx\_enum usage, vx\_enum user\_mem\_type )**

Allows the application to copy coefficients from/into a convolution object.

## Parameters

|    |                            |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
|----|----------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <code>conv</code>          | The reference to the convolution object that is the source or the destination of the copy.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
| in | <code>user_ptr</code>      | The address of the memory location where to store the requested coefficient data if the copy was requested in read mode, or from where to get the coefficient data to store into the convolution object if the copy was requested in write mode. In the user memory, the convolution coefficient data is structured as a row-major 2D array with elements of the type corresponding to <code>VX_TYPE_CONVOLUTION</code> , with a number of rows corresponding to <code>VX_CONVOLUTION_ROWS</code> and a number of columns corresponding to <code>VX_CONVOLUTION_COLUMNS</code> . The accessible memory must be large enough to contain this 2D array: accessible memory in bytes $\geq$ <code>sizeof(data_element) * rows * columns</code> . |
| in | <code>usage</code>         | This declares the effect of the copy with regard to the convolution object using the <code>vx_accessor_e</code> enumeration. Only <code>VX_READ_ONLY</code> and <code>VX_WRITE_ONLY</code> are supported: <ul style="list-style-type: none"> <li><code>VX_READ_ONLY</code> means that data are copied from the convolution object into the user memory.</li> <li><code>VX_WRITE_ONLY</code> means that data are copied into the convolution object from the user memory.</li> </ul>                                                                                                                                                                                                                                                          |
| in | <code>user_mem_type</code> | A <code>vx_memory_type_e</code> enumeration that specifies the memory type of the memory referenced by the <code>user_addr</code> .                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |

## Returns

A `vx_status_e` enumeration.

## Return values

|                                          |                                                            |
|------------------------------------------|------------------------------------------------------------|
| <code>VX_SUCCESS</code>                  | No errors; any other value indicates failure.              |
| <code>VX_ERROR_INVALID_REFERENCE</code>  | conv is not a valid <code>vx_convolution</code> reference. |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | An other parameter is incorrect.                           |

## 3.70 Object: Distribution

### 3.70.1 Detailed Description

Defines the Distribution Object Interface.

#### Typedefs

- typedef struct \_vx\_distribution \* [vx\\_distribution](#)

*The Distribution object. This has a user-defined number of bins over a user-defined range (within a uint32\_t range).*

#### Enumerations

- enum [vx\\_distribution\\_attribute\\_e](#) {  
[VX\\_DISTRIBUTION\\_DIMENSIONS](#) = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_TYPE\_DISTRIBUTION << 8)) + 0x0,  
[VX\\_DISTRIBUTION\\_OFFSET](#) = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_TYPE\_DISTRIBUTION << 8)) + 0x1,  
[VX\\_DISTRIBUTION\\_RANGE](#) = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_TYPE\_DISTRIBUTION << 8)) + 0x2,  
[VX\\_DISTRIBUTION\\_BINS](#) = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_TYPE\_DISTRIBUTION << 8)) + 0x3,  
[VX\\_DISTRIBUTION\\_WINDOW](#) = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_TYPE\_DISTRIBUTION << 8)) + 0x4,  
[VX\\_DISTRIBUTION\\_SIZE](#) = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_TYPE\_DISTRIBUTION << 8)) + 0x5 }

*The distribution attribute list.*

#### Functions

- [vx\\_status VX\\_API\\_CALL vxCopyDistribution](#) ([vx\\_distribution](#) distribution, void \*user\_ptr, [vx\\_enum](#) usage, [vx\\_enum](#) user\_mem\_type)  
*Allows the application to copy from/into a distribution object.*
- [vx\\_distribution VX\\_API\\_CALL vxCreateDistribution](#) ([vx\\_context](#) context, [vx\\_size](#) numBins, [vx\\_int32](#) offset, [vx\\_uint32](#) range)  
*Creates a reference to a 1D Distribution of a consecutive interval [offset, offset + range - 1] defined by a start offset and valid range, divided equally into numBins parts.*
- [vx\\_distribution VX\\_API\\_CALL vxCreateVirtualDistribution](#) ([vx\\_graph](#) graph, [vx\\_size](#) numBins, [vx\\_int32](#) offset, [vx\\_uint32](#) range)  
*Creates an opaque reference to a 1D Distribution object without direct user access.*
- [vx\\_status VX\\_API\\_CALL vxMapDistribution](#) ([vx\\_distribution](#) distribution, [vx\\_map\\_id](#) \*map\_id, void \*\*ptr, [vx\\_enum](#) usage, [vx\\_enum](#) mem\_type, [vx\\_bitfield](#) flags)  
*Allows the application to get direct access to distribution object.*
- [vx\\_status VX\\_API\\_CALL vxQueryDistribution](#) ([vx\\_distribution](#) distribution, [vx\\_enum](#) attribute, void \*ptr, [vx\\_size](#) size)  
*Queries a Distribution object.*
- [vx\\_status VX\\_API\\_CALL vxReleaseDistribution](#) ([vx\\_distribution](#) \*distribution)  
*Releases a reference to a distribution object. The object may not be garbage collected until its total reference count is zero.*
- [vx\\_status VX\\_API\\_CALL vxUnmapDistribution](#) ([vx\\_distribution](#) distribution, [vx\\_map\\_id](#) map\_id)  
*Unmap and commit potential changes to distribution object that was previously mapped. Unmapping a distribution invalidates the memory location from which the distribution data could be accessed by the application. Accessing this memory location after the unmap function completes has an undefined behavior.*

### 3.70.2 Enumeration Type Documentation

#### enum [vx\\_distribution\\_attribute\\_e](#)

The distribution attribute list.

## Enumerator

**VX\_DISTRIBUTION\_DIMENSIONS** Indicates the number of dimensions in the distribution. Read-only. Use a `vx_size` parameter.

**VX\_DISTRIBUTION\_OFFSET** Indicates the start of the values to use (inclusive). Read-only. Use a `vx_int32` parameter.

**VX\_DISTRIBUTION\_RANGE** Indicates the total number of the consecutive values of the distribution interval.

**VX\_DISTRIBUTION\_BINS** Indicates the number of bins. Read-only. Use a `vx_size` parameter.

**VX\_DISTRIBUTION\_WINDOW** Indicates the width of a bin. Equal to the range divided by the number of bins. If the range is not a multiple of the number of bins, it is not valid. Read-only. Use a `vx_uint32` parameter.

**VX\_DISTRIBUTION\_SIZE** Indicates the total size of the distribution in bytes. Read-only. Use a `vx_size` parameter.

Definition at line 1034 of file `vx_types.h`.

### 3.70.3 Function Documentation

**vx\_distribution VX\_API\_CALL vxCreateDistribution ( vx\_context context, vx\_size numBins, vx\_int32 offset, vx\_uint32 range )**

Creates a reference to a 1D Distribution of a consecutive interval [offset, offset + range - 1] defined by a start offset and valid range, divided equally into numBins parts.

#### Parameters

|    |                |                                                                                        |
|----|----------------|----------------------------------------------------------------------------------------|
| in | <i>context</i> | The reference to the overall context.                                                  |
| in | <i>numBins</i> | The number of bins in the distribution.                                                |
| in | <i>offset</i>  | The start offset into the range value that marks the beginning of the 1D Distribution. |
| in | <i>range</i>   | The total number of the consecutive values of the distribution interval.               |

#### Returns

A distribution reference `vx_distribution`. Any possible errors preventing a successful creation should be checked using `vxGetStatus`.

**vx\_distribution VX\_API\_CALL vxCreateVirtualDistribution ( vx\_graph graph, vx\_size numBins, vx\_int32 offset, vx\_uint32 range )**

Creates an opaque reference to a 1D Distribution object without direct user access.

#### Parameters

|    |                |                                                                                        |
|----|----------------|----------------------------------------------------------------------------------------|
| in | <i>graph</i>   | The reference to the parent graph.                                                     |
| in | <i>numBins</i> | The number of bins in the distribution.                                                |
| in | <i>offset</i>  | The start offset into the range value that marks the beginning of the 1D Distribution. |
| in | <i>range</i>   | The total number of the consecutive values of the distribution interval.               |

#### See also

`vxCreateDistribution`

#### Returns

A distribution reference `vx_distribution`. Any possible errors preventing a successful creation should be checked using `vxGetStatus`.



**vx\_status VX\_API\_CALL vxReleaseDistribution ( vx\_distribution \* *distribution* )**

Releases a reference to a distribution object. The object may not be garbage collected until its total reference count is zero.

**Parameters**

|    |                     |                                               |
|----|---------------------|-----------------------------------------------|
| in | <i>distribution</i> | The reference to the distribution to release. |
|----|---------------------|-----------------------------------------------|

**Postcondition**

After returning from this function the reference is zeroed.

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                                         |                                                                     |
|-----------------------------------------|---------------------------------------------------------------------|
| <code>VX_SUCCESS</code>                 | No errors; any other value indicates failure.                       |
| <code>VX_ERROR_INVALID_REFERENCE</code> | distribution is not a valid <code>vx_distribution</code> reference. |

**vx\_status VX\_API\_CALL vxQueryDistribution ( vx\_distribution *distribution*, vx\_enum *attribute*, void \* *ptr*, vx\_size *size* )**

Queries a Distribution object.

**Parameters**

|     |                     |                                                                                     |
|-----|---------------------|-------------------------------------------------------------------------------------|
| in  | <i>distribution</i> | The reference to the distribution to query.                                         |
| in  | <i>attribute</i>    | The attribute to query. Use a <code>vx_distribution_attribute_e</code> enumeration. |
| out | <i>ptr</i>          | The location at which to store the resulting value.                                 |
| in  | <i>size</i>         | The size in bytes of the container to which <i>ptr</i> points.                      |

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                                         |                                                                     |
|-----------------------------------------|---------------------------------------------------------------------|
| <code>VX_SUCCESS</code>                 | No errors; any other value indicates failure.                       |
| <code>VX_ERROR_INVALID_REFERENCE</code> | distribution is not a valid <code>vx_distribution</code> reference. |

**vx\_status VX\_API\_CALL vxCopyDistribution ( vx\_distribution *distribution*, void \* *user\_ptr*, vx\_enum *usage*, vx\_enum *user\_mem\_type* )**

Allows the application to copy from/into a distribution object.

**Parameters**

|    |                     |                                                                                             |
|----|---------------------|---------------------------------------------------------------------------------------------|
| in | <i>distribution</i> | The reference to the distribution object that is the source or the destination of the copy. |
|----|---------------------|---------------------------------------------------------------------------------------------|

## Parameters

|    |                      |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |
|----|----------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>user_ptr</i>      | The address of the memory location where to store the requested data if the copy was requested in read mode, or from where to get the data to store into the distribution object if the copy was requested in write mode. In the user memory, the distribution is represented as a <code>vx_uint32</code> array with a number of elements equal to the value returned via <code>VX_DISTRIBUTION_BINS</code> . The accessible memory must be large enough to contain this <code>vx_uint32</code> array: accessible memory in bytes $\geq \text{sizeof}(\text{vx\_uint32}) * \text{num\_bins}$ . |
| in | <i>usage</i>         | This declares the effect of the copy with regard to the distribution object using the <code>vx_accessor_e</code> enumeration. Only <code>VX_READ_ONLY</code> and <code>VX_WRITE_ONLY</code> are supported: <ul style="list-style-type: none"> <li>• <code>VX_READ_ONLY</code> means that data are copied from the distribution object into the user memory.</li> <li>• <code>VX_WRITE_ONLY</code> means that data are copied into the distribution object from the user memory.</li> </ul>                                                                                                     |
| in | <i>user_mem_type</i> | A <code>vx_memory_type_e</code> enumeration that specifies the memory type of the memory referenced by the <code>user_addr</code> .                                                                                                                                                                                                                                                                                                                                                                                                                                                            |

## Returns

A `vx_status_e` enumeration.

## Return values

|                                          |                                                                     |
|------------------------------------------|---------------------------------------------------------------------|
| <code>VX_SUCCESS</code>                  | No errors; any other value indicates failure.                       |
| <code>VX_ERROR_INVALID_REFERENCE</code>  | distribution is not a valid <code>vx_distribution</code> reference. |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | An other parameter is incorrect.                                    |

**`vx_status VX_API_CALL vxMapDistribution ( vx_distribution distribution, vx_map_id * map_id, void ** ptr, vx_enum usage, vx_enum mem_type, vx_bitfield flags )`**

Allows the application to get direct access to distribution object.

## Parameters

|     |                     |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
|-----|---------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>distribution</i> | The reference to the distribution object to map.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| out | <i>map_id</i>       | The address of a <code>vx_map_id</code> variable where the function returns a map identifier. <ul style="list-style-type: none"> <li>• (<code>*map_id</code>) must eventually be provided as the <code>map_id</code> parameter of a call to <code>vxUnmapDistribution</code>.</li> </ul>                                                                                                                                                                                                                                                                                                                                                             |
| out | <i>ptr</i>          | The address of a pointer that the function sets to the address where the requested data can be accessed. In the mapped memory area, data are structured as a <code>vx_uint32</code> array with a number of elements equal to the value returned via <code>VX_DISTRIBUTION_BINS</code> . Each element of this array corresponds to a bin of the distribution, with a range-major ordering. Accessing the memory out of the bound of this array is forbidden and has an undefined behavior. The returned ( <code>*ptr</code> ) address is only valid between the call to the function and the corresponding call to <code>vxUnmapDistribution</code> . |

**Parameters**

|    |                 |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
|----|-----------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>usage</i>    | <p>This declares the access mode for the distribution, using the <code>vx_accessor_e</code> enumeration.</p> <ul style="list-style-type: none"> <li>• <code>VX_READ_ONLY</code>: after the function call, the content of the memory location pointed by (*ptr) contains the distribution data. Writing into this memory location is forbidden and its behavior is undefined.</li> <li>• <code>VX_READ_AND_WRITE</code>: after the function call, the content of the memory location pointed by (*ptr) contains the distribution data; writing into this memory is allowed only for the location of bins and will result in a modification of the affected bins in the distribution object once the distribution is unmapped.</li> <li>• <code>VX_WRITE_ONLY</code>: after the function call, the memory location pointed by (*ptr) contains undefined data; writing each bin of distribution is required prior to unmapping. Bins not written by the application before unmap will become undefined after unmap, even if they were well defined before map.</li> </ul> |
| in | <i>mem_type</i> | A <code>vx_memory_type_e</code> enumeration that specifies the type of the memory where the distribution is requested to be mapped.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
| in | <i>flags</i>    | An integer that allows passing options to the map operation. Use 0 for this option.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                                          |                                                                                |
|------------------------------------------|--------------------------------------------------------------------------------|
| <code>VX_SUCCESS</code>                  | No errors; any other value indicates failure.                                  |
| <code>VX_ERROR_INVALID_REFERENCE</code>  | distribution is not a valid <code>vx_distribution</code> reference. reference. |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | An other parameter is incorrect.                                               |

**Postcondition**

`vxUnmapDistribution` with same (\*map\_id) value.

**vx\_status VX\_API\_CALL vxUnmapDistribution ( vx\_distribution *distribution*, vx\_map\_id *map\_id* )**

Unmap and commit potential changes to distribution object that was previously mapped. Unmapping a distribution invalidates the memory location from which the distribution data could be accessed by the application. Accessing this memory location after the unmap function completes has an undefined behavior.

**Parameters**

|     |                     |                                                                                           |
|-----|---------------------|-------------------------------------------------------------------------------------------|
| in  | <i>distribution</i> | The reference to the distribution object to unmap.                                        |
| out | <i>map_id</i>       | The unique map identifier that was returned when calling <code>vxMapDistribution</code> . |

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                                          |                                                                     |
|------------------------------------------|---------------------------------------------------------------------|
| <code>VX_SUCCESS</code>                  | No errors; any other value indicates failure.                       |
| <code>VX_ERROR_INVALID_REFERENCE</code>  | distribution is not a valid <code>vx_distribution</code> reference. |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | An other parameter is incorrect.                                    |

Precondition

`vxMapDistribution` returning the same `map_id` value

## 3.71 Object: Image

### 3.71.1 Detailed Description

Defines the Image Object interface.

#### Data Structures

- struct `vx_imagepatch_addressing_t`  
*The addressing image patch structure is used by the Host only to address pixels in an image patch. The fields of the structure are defined as: [More...](#)*
- union `vx_pixel_value_t`  
*Union that describes the value of a pixel for any image format. Use the field corresponding to the image format. [More...](#)*

#### Macros

- #define `VX_IMAGEPATCH_ADDR_INIT` {0u, 0u, 0, 0, 0u, 0u, 0u, 0u}  
*Use to initialize a `vx_imagepatch_addressing_t` structure on the stack.*

#### Typedefs

- typedef struct \_vx\_image \* `vx_image`  
*An opaque reference to an image.*
- typedef uintptr\_t `vx_map_id`  
*Holds the address of a variable where the map/unmap functions return a map identifier.*

#### Enumerations

- enum `vx_channel_range_e` {  
`VX_CHANNEL_RANGE_FULL` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_COLOR_RANGE` << 12)) + 0x0,  
`VX_CHANNEL_RANGE_RESTRICTED` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_COLOR_RANGE` << 12)) + 0x1 }  
*The image channel range list used by the `VX_IMAGE_RANGE` attribute of a `vx_image`.*
- enum `vx_color_space_e` {  
`VX_COLOR_SPACE_NONE` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_COLOR_SPACE` << 12)) + 0x0,  
`VX_COLOR_SPACE_BT601_525` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_COLOR_SPACE` << 12)) + 0x1,  
`VX_COLOR_SPACE_BT601_625` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_COLOR_SPACE` << 12)) + 0x2,  
`VX_COLOR_SPACE_BT709` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_COLOR_SPACE` << 12)) + 0x3,  
`VX_COLOR_SPACE_DEFAULT` = `VX_COLOR_SPACE_BT709` }  
*The image color space list used by the `VX_IMAGE_SPACE` attribute of a `vx_image`.*
- enum `vx_image_attribute_e` {  
`VX_IMAGE_WIDTH` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_TYPE_IMAGE` << 8)) + 0x0,  
`VX_IMAGE_HEIGHT` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_TYPE_IMAGE` << 8)) + 0x1,  
`VX_IMAGE_FORMAT` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_TYPE_IMAGE` << 8)) + 0x2,  
`VX_IMAGE_PLANES` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_TYPE_IMAGE` << 8)) + 0x3,  
`VX_IMAGE_SPACE` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_TYPE_IMAGE` << 8)) + 0x4,  
`VX_IMAGE_RANGE` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_TYPE_IMAGE` << 8)) + 0x5,  
`VX_IMAGE_MEMORY_TYPE` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_TYPE_IMAGE` << 8)) + 0x7,  
`VX_IMAGE_IS_UNIFORM` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_TYPE_IMAGE` << 8)) + 0x8,  
`VX_IMAGE_UNIFORM_VALUE` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_TYPE_IMAGE` << 8)) + 0x9 }  
*The image attributes list.*

- enum `vx_map_flag_e` { `VX_NOGAP_X` = 1 }

*The Map/Unmap operation enumeration.*

## Functions

- `vx_status VX_API_CALL vxCopyImagePatch` (`vx_image` image, const `vx_rectangle_t` \*image\_rect, `vx_uint32` image\_plane\_index, const `vx_imagepatch_addressing_t` \*user\_addr, void \*user\_ptr, `vx_enum` usage, `vx_enum` user\_mem\_type)  
*Allows the application to copy a rectangular patch from/into an image object plane.*
- `vx_image VX_API_CALL vxCreateImage` (`vx_context` context, `vx_uint32` width, `vx_uint32` height, `vx_df_image` color)  
*Creates an opaque reference to an image buffer.*
- `vx_image VX_API_CALL vxCreateImageFromChannel` (`vx_image` img, `vx_enum` channel)  
*Create a sub-image from a single plane channel of another image.*
- `vx_image VX_API_CALL vxCreateImageFromHandle` (`vx_context` context, `vx_df_image` color, const `vx_imagepatch_addressing_t` \*addrs[], void \*const ptrs[], `vx_enum` memory\_type)  
*Creates a reference to an image object that was externally allocated.*
- `vx_image VX_API_CALL vxCreateImageFromROI` (`vx_image` img, const `vx_rectangle_t` \*rect)  
*Creates an image from another image given a rectangle. This second reference refers to the data in the original image. Updates to this image updates the parent image. The rectangle must be defined within the pixel space of the parent image.*
- `vx_image VX_API_CALL vxCreateUniformImage` (`vx_context` context, `vx_uint32` width, `vx_uint32` height, `vx_df_image` color, const `vx_pixel_value_t` \*value)  
*Creates a reference to an image object that has a singular, uniform value in all pixels. The uniform image created is read-only.*
- `vx_image VX_API_CALL vxCreateVirtualImage` (`vx_graph` graph, `vx_uint32` width, `vx_uint32` height, `vx_df_image` color)  
*Creates an opaque reference to an image buffer with no direct user access. This function allows setting the image width, height, or format.*
- `void *VX_API_CALL vxFormatImagePatchAddress1d` (void \*ptr, `vx_uint32` index, const `vx_imagepatch_addressing_t` \*addr)  
*Accesses a specific indexed pixel in an image patch.*
- `void *VX_API_CALL vxFormatImagePatchAddress2d` (void \*ptr, `vx_uint32` x, `vx_uint32` y, const `vx_imagepatch_addressing_t` \*addr)  
*Accesses a specific pixel at a 2d coordinate in an image patch.*
- `vx_status VX_API_CALL vxGetValidRegionImage` (`vx_image` image, `vx_rectangle_t` \*rect)  
*Retrieves the valid region of the image as a rectangle.*
- `vx_status VX_API_CALL vxMapImagePatch` (`vx_image` image, const `vx_rectangle_t` \*rect, `vx_uint32` plane\_index, `vx_map_id` \*map\_id, `vx_imagepatch_addressing_t` \*addr, void \*\*ptr, `vx_enum` usage, `vx_enum` mem\_type, `vx_uint32` flags)  
*Allows the application to get direct access to a rectangular patch of an image object plane.*
- `vx_status VX_API_CALL vxQueryImage` (`vx_image` image, `vx_enum` attribute, void \*ptr, `vx_size` size)  
*Retrieves various attributes of an image.*
- `vx_status VX_API_CALL vxReleaseImage` (`vx_image` \*image)  
*Releases a reference to an image object. The object may not be garbage collected until its total reference count is zero.*
- `vx_status VX_API_CALL vxSetImageAttribute` (`vx_image` image, `vx_enum` attribute, const void \*ptr, `vx_size` size)  
*Allows setting attributes on the image.*
- `vx_status VX_API_CALL vxSetImagePixelValues` (`vx_image` image, const `vx_pixel_value_t` \*pixel\_value)  
*Initialize an image with the given pixel value.*
- `vx_status VX_API_CALL vxSetImageValidRectangle` (`vx_image` image, const `vx_rectangle_t` \*rect)  
*Sets the valid rectangle for an image according to a supplied rectangle.*

- [vx\\_status VX\\_API\\_CALL vxSwapImageHandle](#) ([vx\\_image](#) image, void \*const new\_ptrs[], void \*prev\_ptrs[], [vx\\_size](#) num\_planes)

*Swaps the image handle of an image previously created from handle.*

- [vx\\_status VX\\_API\\_CALL vxUnmapImagePatch](#) ([vx\\_image](#) image, [vx\\_map\\_id](#) map\_id)

*Unmap and commit potential changes to a image object patch that were previously mapped. Unmapping an image patch invalidates the memory location from which the patch could be accessed by the application. Accessing this memory location after the unmap function completes has an undefined behavior.*

### 3.71.2 Data Structure Documentation

#### struct vx\_imagepatch\_addressing\_t

The addressing image patch structure is used by the Host only to address pixels in an image patch. The fields of the structure are defined as:

- dim - The dimensions of the image in logical pixel units in the x & y direction.
- stride - The physical byte distance from a logical pixel to the next logically adjacent pixel in the positive x or y direction.
- scale - The relationship of scaling from the primary plane (typically the zero indexed plane) to this plane. An integer down-scaling factor of  $f$  shall be set to a value equal to  $scale = \frac{unity}{f}$  and an integer up-scaling factor of  $f$  shall be set to a value of  $scale = unity * f$ . *unity* is defined as [VX\\_SCALE\\_UNITY](#).
- step - The step is the number of logical pixel units to skip to arrive at the next physically unique pixel. For example, on a plane that is half-scaled in a dimension, the step in that dimension is 2 to indicate that every other pixel in that dimension is an alias. This is useful in situations where iteration over unique pixels is required, such as in serializing or de-serializing the image patch information.

See also

[vxMapImagePatch](#)

Definition at line 1519 of file [vx\\_types.h](#).

#### Data Fields

|                           |               |                                                                                                                                                                                           |
|---------------------------|---------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <a href="#">vx_uint32</a> | dim_x         | Width of patch in X dimension in pixels.                                                                                                                                                  |
| <a href="#">vx_uint32</a> | dim_y         | Height of patch in Y dimension in pixels.                                                                                                                                                 |
| <a href="#">vx_int32</a>  | stride↔<br>_x | Stride in X dimension in bytes.                                                                                                                                                           |
| <a href="#">vx_int32</a>  | stride↔<br>_y | Stride in Y dimension in bytes.                                                                                                                                                           |
| <a href="#">vx_uint32</a> | scale↔<br>_x  | Scale of X dimension. For sub-sampled planes this is the scaling factor of the dimension of the plane in relation to the zero plane. Use <a href="#">VX_SCALE_UNITY</a> in the numerator. |
| <a href="#">vx_uint32</a> | scale↔<br>_y  | Scale of Y dimension. For sub-sampled planes this is the scaling factor of the dimension of the plane in relation to the zero plane. Use <a href="#">VX_SCALE_UNITY</a> in the numerator. |
| <a href="#">vx_uint32</a> | step_x        | Step of X dimension in pixels.                                                                                                                                                            |
| <a href="#">vx_uint32</a> | step_y        | Step of Y dimension in pixels.                                                                                                                                                            |

#### union vx\_pixel\_value\_t

Union that describes the value of a pixel for any image format. Use the field corresponding to the image format.

Definition at line 1684 of file [vx\\_types.h](#).

## Data Fields

|                           |              |                                                              |
|---------------------------|--------------|--------------------------------------------------------------|
| <a href="#">vx_uint8</a>  | RGB[3]       | <a href="#">VX_DF_IMAGE_RGB</a> format in the R,G,B order    |
| <a href="#">vx_uint8</a>  | RGBX[4]      | <a href="#">VX_DF_IMAGE_RGBX</a> format in the R,G,B,X order |
| <a href="#">vx_uint8</a>  | YUV[3]       | All YUV formats in the Y,U,V order.                          |
| <a href="#">vx_uint8</a>  | U8           | <a href="#">VX_DF_IMAGE_U8</a>                               |
| <a href="#">vx_uint16</a> | U16          | <a href="#">VX_DF_IMAGE_U16</a>                              |
| <a href="#">vx_int16</a>  | S16          | <a href="#">VX_DF_IMAGE_S16</a>                              |
| <a href="#">vx_uint32</a> | U32          | <a href="#">VX_DF_IMAGE_U32</a>                              |
| <a href="#">vx_int32</a>  | S32          | <a href="#">VX_DF_IMAGE_S32</a>                              |
| <a href="#">vx_uint8</a>  | reserved[16] |                                                              |

### 3.71.3 Typedef Documentation

**typedef struct \_vx\_image\* vx\_image**

An opaque reference to an image.

See also

[vxCreateImage](#)

Definition at line 179 of file [vx\\_types.h](#).

### 3.71.4 Enumeration Type Documentation

**enum vx\_image\_attribute\_e**

The image attributes list.

Enumerator

**VX\_IMAGE\_WIDTH** Queries an image for its width. Read-only. Use a [vx\\_uint32](#) parameter.

**VX\_IMAGE\_HEIGHT** Queries an image for its height. Read-only. Use a [vx\\_uint32](#) parameter.

**VX\_IMAGE\_FORMAT** Queries an image for its format. Read-only. Use a [vx\\_df\\_image](#) parameter.

**VX\_IMAGE\_PLANES** Queries an image for its number of planes. Read-only. Use a [vx\\_size](#) parameter.

**VX\_IMAGE\_SPACE** Queries an image for its color space (see [vx\\_color\\_space\\_e](#)). Read-write. Use a [vx\\_enum](#) parameter.

**VX\_IMAGE\_RANGE** Queries an image for its channel range (see [vx\\_channel\\_range\\_e](#)). Read-only. Use a [vx\\_enum](#) parameter.

**VX\_IMAGE\_MEMORY\_TYPE** Queries memory type if created using [vxCreateImageFromHandle](#). If [vx\\_image](#) was not created using [vxCreateImageFromHandle](#), [VX\\_MEMORY\\_TYPE\\_NONE](#) is returned. Use a [vx\\_memory\\_type\\_e](#) parameter.

**VX\_IMAGE\_IS\_UNIFORM** Queries if an image is uniform. Read-only. Use a [vx\\_bool](#) parameter.

**VX\_IMAGE\_UNIFORM\_VALUE** Queries the image uniform value if any. Read-only. Use a [vx\\_pixel\\_value\\_t](#) parameter.

Definition at line 946 of file [vx\\_types.h](#).

**enum vx\_color\_space\_e**

The image color space list used by the [VX\\_IMAGE\\_SPACE](#) attribute of a [vx\\_image](#).

Enumerator

**VX\_COLOR\_SPACE\_NONE** Use to indicate that no color space is used.



**VX\_COLOR\_SPACE\_BT601\_525** Use to indicate that the BT.601 coefficients and SMPTE C primaries are used for conversions.

**VX\_COLOR\_SPACE\_BT601\_625** Use to indicate that the BT.601 coefficients and BTU primaries are used for conversions.

**VX\_COLOR\_SPACE\_BT709** Use to indicate that the BT.709 coefficients are used for conversions.

**VX\_COLOR\_SPACE\_DEFAULT** All images in VX are by default BT.709.

Definition at line 1295 of file [vx\\_types.h](#).

#### enum vx\_channel\_range\_e

The image channel range list used by the [VX\\_IMAGE\\_RANGE](#) attribute of a [vx\\_image](#).

Enumerator

**VX\_CHANNEL\_RANGE\_FULL** Full range of the unit of the channel.

**VX\_CHANNEL\_RANGE\_RESTRICTED** Restricted range of the unit of the channel based on the space given.

Definition at line 1312 of file [vx\\_types.h](#).

#### enum vx\_map\_flag\_e

The Map/Unmap operation enumeration.

Enumerator

**VX\_NOGAP\_X** No Gap.

Definition at line 1845 of file [vx\\_types.h](#).

### 3.71.5 Function Documentation

**vx\_image VX\_API\_CALL vxCreateImage ( vx\_context context, vx\_uint32 width, vx\_uint32 height, vx\_df\_image color )**

Creates an opaque reference to an image buffer.

Not guaranteed to exist until the [vx\\_graph](#) containing it has been verified.

Parameters

|    |                |                                                                                                                                                                                                                                                           |
|----|----------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>context</i> | The reference to the implementation context.                                                                                                                                                                                                              |
| in | <i>width</i>   | The image width in pixels. The image in the formats of <a href="#">VX_DF_IMAGE_NV12</a> , <a href="#">VX_DF_IMAGE_NV21</a> , <a href="#">VX_DF_IMAGE_IYUV</a> , <a href="#">VX_DF_IMAGE_UYVY</a> , <a href="#">VX_DF_IMAGE_YUYV</a> must have even width. |
| in | <i>height</i>  | The image height in pixels. The image in the formats of <a href="#">VX_DF_IMAGE_NV12</a> , <a href="#">VX_DF_IMAGE_NV21</a> , <a href="#">VX_DF_IMAGE_IYUV</a> must have even height.                                                                     |
| in | <i>color</i>   | The VX_DF_IMAGE ( <a href="#">vx_df_image_e</a> ) code that represents the format of the image and the color space.                                                                                                                                       |

Returns

An image reference [vx\\_image](#). Any possible errors preventing a successful creation should be checked using [vxGetStatus](#).

See also

[vxMapImagePatch](#) to obtain direct memory access to the image data.

**vx\_image VX\_API\_CALL vxCreateImageFromROI ( vx\_image *img*, const vx\_rectangle\_t \* *rect* )**

Creates an image from another image given a rectangle. This second reference refers to the data in the original image. Updates to this image updates the parent image. The rectangle must be defined within the pixel space of the parent image.

#### Parameters

|    |             |                                                                                            |
|----|-------------|--------------------------------------------------------------------------------------------|
| in | <i>img</i>  | The reference to the parent image.                                                         |
| in | <i>rect</i> | The region of interest rectangle. Must contain points within the parent image pixel space. |

#### Returns

An image reference [vx\\_image](#) to the sub-image. Any possible errors preventing a successful creation should be checked using [vxGetStatus](#).

**vx\_image VX\_API\_CALL vxCreateUniformImage ( vx\_context *context*, vx\_uint32 *width*, vx\_uint32 *height*, vx\_df\_image *color*, const vx\_pixel\_value\_t \* *value* )**

Creates a reference to an image object that has a singular, uniform value in all pixels. The uniform image created is read-only.

#### Parameters

|    |                |                                                                                                                                                                                                                                                           |
|----|----------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>context</i> | The reference to the implementation context.                                                                                                                                                                                                              |
| in | <i>width</i>   | The image width in pixels. The image in the formats of <a href="#">VX_DF_IMAGE_NV12</a> , <a href="#">VX_DF_IMAGE_NV21</a> , <a href="#">VX_DF_IMAGE_IYUV</a> , <a href="#">VX_DF_IMAGE_UYVY</a> , <a href="#">VX_DF_IMAGE_YUYV</a> must have even width. |
| in | <i>height</i>  | The image height in pixels. The image in the formats of <a href="#">VX_DF_IMAGE_NV12</a> , <a href="#">VX_DF_IMAGE_NV21</a> , <a href="#">VX_DF_IMAGE_IYUV</a> must have even height.                                                                     |
| in | <i>color</i>   | The VX_DF_IMAGE ( <a href="#">vx_df_image_e</a> ) code that represents the format of the image and the color space.                                                                                                                                       |
| in | <i>value</i>   | The pointer to the pixel value to which to set all pixels. See <a href="#">vx_pixel_value_t</a> .                                                                                                                                                         |

#### Returns

An image reference [vx\\_image](#). Any possible errors preventing a successful creation should be checked using [vxGetStatus](#).

#### See also

[vxMapImagePatch](#) to obtain direct memory access to the image data.

#### Note

[vxMapImagePatch](#) and [vxUnmapImagePatch](#) may be called with a uniform image reference.

**vx\_image VX\_API\_CALL vxCreateVirtualImage ( vx\_graph *graph*, vx\_uint32 *width*, vx\_uint32 *height*, vx\_df\_image *color* )**

Creates an opaque reference to an image buffer with no direct user access. This function allows setting the image width, height, or format.

Virtual data objects allow users to connect various nodes within a graph via data references without access to that data, but they also permit the implementation to take maximum advantage of possible optimizations. Use this API to create a data reference to link two or more nodes together when the intermediate data are not required to be accessed by outside entities. This API in particular allows the user to define the image format of the data without requiring the exact dimensions. Virtual objects are scoped within the graph they are declared a part of, and can't be shared outside of this scope. All of the following constructions of virtual images are valid.

```

00001 vx_context context = vxCreateContext();
00002 vx_graph graph = vxCreateGraph(context);
00003 vx_image virt[] = {
00004 vxCreateVirtualImage(graph, 0, 0, VX_DF_IMAGE_U8), // no specified dimension
00005 vxCreateVirtualImage(graph, 320, 240, VX_DF_IMAGE_VIRT), // no specified format
00006 vxCreateVirtualImage(graph, 640, 480, VX_DF_IMAGE_U8), // no user access
00007 };

```

#### Parameters

|    |               |                                                                                                                                                                                                                                                                                                                                       |
|----|---------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>graph</i>  | The reference to the parent graph.                                                                                                                                                                                                                                                                                                    |
| in | <i>width</i>  | The width of the image in pixels. A value of zero informs the interface that the value is unspecified. The image in the formats of <a href="#">VX_DF_IMAGE_NV12</a> , <a href="#">VX_DF_IMAGE_NV21</a> , <a href="#">VX_DF_IMAGE_IYUV</a> , <a href="#">VX_DF_IMAGE_UYVY</a> , <a href="#">VX_DF_IMAGE_YUYV</a> must have even width. |
| in | <i>height</i> | The height of the image in pixels. A value of zero informs the interface that the value is unspecified. The image in the formats of <a href="#">VX_DF_IMAGE_NV12</a> , <a href="#">VX_DF_IMAGE_NV21</a> , <a href="#">VX_DF_IMAGE_IYUV</a> must have even height.                                                                     |
| in | <i>color</i>  | The <a href="#">VX_DF_IMAGE</a> ( <a href="#">vx_df_image_e</a> ) code that represents the format of the image and the color space. A value of <a href="#">VX_DF_IMAGE_VIRT</a> informs the interface that the format is unspecified.                                                                                                 |

#### Returns

An image reference [vx\\_image](#). Any possible errors preventing a successful creation should be checked using [vxGetStatus](#).

#### Note

Passing this reference to [vxMapImagePatch](#) will return an error.

**[vx\\_image](#) [VX\\_API\\_CALL](#) [vxCreateImageFromHandle](#) ( [vx\\_context](#) *context*, [vx\\_df\\_image](#) *color*, const [vx\\_imagepatch\\_addressing\\_t](#) *addrs*[], void \*const *ptrs*[], [vx\\_enum](#) *memory\_type* )**

Creates a reference to an image object that was externally allocated.

#### Parameters

|    |                    |                                                                                                                                                                          |
|----|--------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>context</i>     | The reference to the implementation context.                                                                                                                             |
| in | <i>color</i>       | See the <a href="#">vx_df_image_e</a> codes. This mandates the number of planes needed to be valid in the <i>addrs</i> and <i>ptrs</i> arrays based on the format given. |
| in | <i>addrs</i> []    | The array of image patch addressing structures that define the dimension and stride of the array of pointers. See note below.                                            |
| in | <i>ptrs</i> []     | The array of platform-defined references to each plane. See note below.                                                                                                  |
| in | <i>memory_type</i> | <a href="#">vx_memory_type_e</a> . When giving <a href="#">VX_MEMORY_TYPE_HOST</a> the <i>ptrs</i> array is assumed to be HOST accessible pointers to memory.            |

#### Returns

An image reference [vx\\_image](#). Any possible errors preventing a successful creation should be checked using [vxGetStatus](#).

#### Note

The user must call [vxMapImagePatch](#) prior to accessing the pixels of an image, even if the image was created via [vxCreateImageFromHandle](#). Reads or writes to memory referenced by *ptrs*[ ] after calling [vxCreateImageFromHandle](#) without first calling [vxMapImagePatch](#) will result in undefined behavior.

The property of `addr[]` and `ptrs[]` arrays is kept by the caller (It means that the implementation will make an internal copy of the provided information. `addr` and `ptrs` can then simply be application's local variables). Only `dim_x`, `dim_y`, `stride_x` and `stride_y` fields of the `vx_imagepatch_addressing_t` need to be provided by the application. Other fields (`step_x`, `step_y`, `scale_x` & `scale_y`) are ignored by this function. The layout of the imported memory must follow a row-major order. In other words, `stride_x` should be sufficiently large so that there is no overlap between data elements corresponding to different pixels, and `stride_y`  $\geq$  `stride_x` \* `dim_x`.

In order to release the image back to the application we should use `vxSwapImageHandle`.

Import type of the created image is available via the image attribute `vx_image_attribute_e` parameter.

**`vx_status VX_API_CALL vxSwapImageHandle ( vx_image image, void *const new_ptrs[], void *prev_ptrs[], vx_size num_planes )`**

Swaps the image handle of an image previously created from handle.

This function sets the new image handle (i.e. pointer to all image planes) and returns the previous one.

Once this function call has completed, the application gets back the ownership of the memory referenced by the previous handle. This memory contains up-to-date pixel data, and the application can safely reuse or release it.

The memory referenced by the new handle must have been allocated consistently with the image properties since the import type, memory layout and dimensions are unchanged (see `addr`s, `color`, and `memory_type` in `vxCreateImageFromHandle`).

All images created from ROI or channel with this image as parent or ancestor will automatically use the memory referenced by the new handle.

The behavior of `vxSwapImageHandle` when called from a user node is undefined.

#### Parameters

|     |                          |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
|-----|--------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <code>image</code>       | The reference to an image created from handle                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
| in  | <code>new_ptrs[]</code>  | <p>pointer to a caller owned array that contains the new image handle (image plane pointers)</p> <ul style="list-style-type: none"> <li><code>new_ptrs</code> is non NULL. <code>new_ptrs[i]</code> must be non NULL for each <code>i</code> such as <math>0 &lt; i &lt; \text{nbPlanes}</math>, otherwise, this is an error. The address of the storage memory for image plane <code>i</code> is set to <code>new_ptrs[i]</code></li> <li><code>new_ptrs</code> is NULL: the previous image storage memory is reclaimed by the caller, while no new handle is provided.</li> </ul> |
| out | <code>prev_ptrs[]</code> | <p>pointer to a caller owned array in which the application returns the previous image handle</p> <ul style="list-style-type: none"> <li><code>prev_ptrs</code> is non NULL. <code>prev_ptrs</code> must have at least as many elements as the number of image planes. For each <code>i</code> such as <math>0 &lt; i &lt; \text{nbPlanes}</math>, <code>prev_ptrs[i]</code> is set to the address of the previous storage memory for plane <code>i</code>.</li> <li><code>prev_ptrs</code> NULL: the previous handle is not returned.</li> </ul>                                   |
| in  | <code>num_planes</code>  | Number of planes in the image. This must be set equal to the number of planes of the input image. The number of elements in <code>new_ptrs</code> and <code>prev_ptrs</code> arrays must be equal to or greater than <code>num_planes</code> . If either array has more than <code>num_planes</code> elements, the extra elements are ignored. If either array is smaller than <code>num_planes</code> , the results are undefined.                                                                                                                                                 |

#### Returns

A `vx_status_e` enumeration.

#### Return values

|                         |            |
|-------------------------|------------|
| <code>VX_SUCCESS</code> | No errors. |
|-------------------------|------------|

## Return values

|                                          |                                                                                |
|------------------------------------------|--------------------------------------------------------------------------------|
| <code>VX_ERROR_INVALID_REFERENCE</code>  | image is not a valid <code>vx_image</code> reference. reference.               |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | The image was not created from handle or the content of new_ptrs is not valid. |
| <code>VX_FAILURE</code>                  | The image was already being accessed.                                          |

**vx\_status VX\_API\_CALL vxQueryImage ( vx\_image *image*, vx\_enum *attribute*, void \* *ptr*, vx\_size *size* )**

Retrieves various attributes of an image.

## Parameters

|     |                  |                                                                   |
|-----|------------------|-------------------------------------------------------------------|
| in  | <i>image</i>     | The reference to the image to query.                              |
| in  | <i>attribute</i> | The attribute to query. Use a <code>vx_image_attribute_e</code> . |
| out | <i>ptr</i>       | The location at which to store the resulting value.               |
| in  | <i>size</i>      | The size in bytes of the container to which <i>ptr</i> points.    |

## Returns

A `vx_status_e` enumeration.

## Return values

|                                          |                                                           |
|------------------------------------------|-----------------------------------------------------------|
| <code>VX_SUCCESS</code>                  | No errors; any other value indicates failure.             |
| <code>VX_ERROR_INVALID_REFERENCE</code>  | image is not a valid <code>vx_image</code> reference.     |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | If any of the other parameters are incorrect.             |
| <code>VX_ERROR_NOT_SUPPORTED</code>      | If the attribute is not supported on this implementation. |

**vx\_status VX\_API\_CALL vxSetImageAttribute ( vx\_image *image*, vx\_enum *attribute*, const void \* *ptr*, vx\_size *size* )**

Allows setting attributes on the image.

## Parameters

|    |                  |                                                                            |
|----|------------------|----------------------------------------------------------------------------|
| in | <i>image</i>     | The reference to the image on which to set the attribute.                  |
| in | <i>attribute</i> | The attribute to set. Use a <code>vx_image_attribute_e</code> enumeration. |
| in | <i>ptr</i>       | The pointer to the location from which to read the value.                  |
| in | <i>size</i>      | The size in bytes of the object pointed to by <i>ptr</i> .                 |

## Returns

A `vx_status_e` enumeration.

## Return values

|                                          |                                                       |
|------------------------------------------|-------------------------------------------------------|
| <code>VX_SUCCESS</code>                  | No errors; any other value indicates failure.         |
| <code>VX_ERROR_INVALID_REFERENCE</code>  | image is not a valid <code>vx_image</code> reference. |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | If any of the other parameters are incorrect.         |

**vx\_status VX\_API\_CALL vxSetImagePixelValues ( vx\_image *image*, const vx\_pixel\_value\_t \* *pixel\_value* )**

Initialize an image with the given pixel value.

#### Parameters

|    |                    |                                                                                                                |
|----|--------------------|----------------------------------------------------------------------------------------------------------------|
| in | <i>image</i>       | The reference to the image to initialize.                                                                      |
| in | <i>pixel_value</i> | The pointer to the constant pixel value to initialize all image pixels. See <a href="#">vx_pixel_value_t</a> . |

#### Returns

A [vx\\_status\\_e](#) enumeration.

#### Return values

|                                    |                                                                                       |
|------------------------------------|---------------------------------------------------------------------------------------|
| <i>VX_SUCCESS</i>                  | No errors.                                                                            |
| <i>VX_ERROR_INVALID_REFERENCE</i>  | If the image is a uniform image, a virtual image, or not a <a href="#">vx_image</a> . |
| <i>VX_ERROR_INVALID_PARAMETERS</i> | If any of the other parameters are incorrect.                                         |

#### Note

All pixels of the entire image are initialized to the indicated pixel value, independently from the valid region. The valid region of the image is unaffected by this function. The image remains mutable after the call to this function, so its pixels and mutable attributes may be changed by subsequent functions.

**vx\_status VX\_API\_CALL vxReleaseImage ( vx\_image \* *image* )**

Releases a reference to an image object. The object may not be garbage collected until its total reference count is zero.

An implementation may defer the actual object destruction after its total reference count is zero (potentially until context destruction). Thus, releasing an image created from handle (see [vxCreateImageFromHandle](#)) and all others objects that may reference it (nodes, ROI, or channel for instance) are not sufficient to get back the ownership of the memory referenced by the current image handle. The only way for this is to call [vxSwapImageHandle](#) before releasing the image.

#### Parameters

|    |              |                                      |
|----|--------------|--------------------------------------|
| in | <i>image</i> | The pointer to the image to release. |
|----|--------------|--------------------------------------|

#### Postcondition

After returning from this function the reference is zeroed.

#### Returns

A [vx\\_status\\_e](#) enumeration.

#### Return values

|                                   |                                                          |
|-----------------------------------|----------------------------------------------------------|
| <i>VX_SUCCESS</i>                 | No errors; any other value indicates failure.            |
| <i>VX_ERROR_INVALID_REFERENCE</i> | image is not a valid <a href="#">vx_image</a> reference. |

**void\* VX\_API\_CALL vxFormatImagePatchAddress1d ( void \* *ptr*, vx\_uint32 *index*, const vx\_imagepatch\_addressing\_t \* *addr* )**

Accesses a specific indexed pixel in an image patch.

#### Parameters

|    |              |                                                                                                                         |
|----|--------------|-------------------------------------------------------------------------------------------------------------------------|
| in | <i>ptr</i>   | The base pointer of the patch as returned from <a href="#">vxMapImagePatch</a> .                                        |
| in | <i>index</i> | The 0 based index of the pixel count in the patch. Indexes increase horizontally by 1 then wrap around to the next row. |
| in | <i>addr</i>  | The pointer to the addressing mode information returned from <a href="#">vxMapImagePatch</a> .                          |

#### Returns

void \* Returns the pointer to the specified pixel.

#### Precondition

[vxMapImagePatch](#)

**void\* VX\_API\_CALL vxFormatImagePatchAddress2d ( void \* *ptr*, vx\_uint32 *x*, vx\_uint32 *y*, const vx\_imagepatch\_addressing\_t \* *addr* )**

Accesses a specific pixel at a 2d coordinate in an image patch.

#### Parameters

|    |             |                                                                                                |
|----|-------------|------------------------------------------------------------------------------------------------|
| in | <i>ptr</i>  | The base pointer of the patch as returned from <a href="#">vxMapImagePatch</a> .               |
| in | <i>x</i>    | The x dimension within the patch.                                                              |
| in | <i>y</i>    | The y dimension within the patch.                                                              |
| in | <i>addr</i> | The pointer to the addressing mode information returned from <a href="#">vxMapImagePatch</a> . |

#### Returns

void \* Returns the pointer to the specified pixel.

#### Precondition

[vxMapImagePatch](#)

**vx\_status VX\_API\_CALL vxGetValidRegionImage ( vx\_image *image*, vx\_rectangle\_t \* *rect* )**

Retrieves the valid region of the image as a rectangle.

#### Parameters

|     |              |                                                    |
|-----|--------------|----------------------------------------------------|
| in  | <i>image</i> | The image from which to retrieve the valid region. |
| out | <i>rect</i>  | The destination rectangle.                         |

#### Returns

A [vx\\_status\\_e](#) enumeration.

## Return values

|                                    |                                                          |
|------------------------------------|----------------------------------------------------------|
| <i>VX_SUCCESS</i>                  | No errors; any other value indicates failure.            |
| <i>VX_ERROR_INVALID_REFERENCE</i>  | image is not a valid <a href="#">vx_image</a> reference. |
| <i>VX_ERROR_INVALID_PARAMETERS</i> | Invalid rect.                                            |

## Note

This rectangle can be passed directly to [vxMapImagePatch](#) to get the full valid region of the image.

**vx\_status VX\_API\_CALL vxCopyImagePatch ( vx\_image image, const vx\_rectangle\_t \* image\_rect, vx\_uint32 image\_plane\_index, const vx\_imagepatch\_addressing\_t \* user\_addr, void \* user\_ptr, vx\_enum usage, vx\_enum user\_mem\_type )**

Allows the application to copy a rectangular patch from/into an image object plane.

## Parameters

|    |                          |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
|----|--------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>image</i>             | The reference to the image object that is the source or the destination of the copy.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| in | <i>image_rect</i>        | The coordinates of the image patch. The patch must be within the bounds of the image. (start_x, start_y) gives the coordinates of the topleft pixel inside the patch, while (end_x, end_y) gives the coordinates of the bottomright element out of the patch. Must be 0 <= start < end <= number of pixels in the image dimension.                                                                                                                                                                                                                                                   |
| in | <i>image_plane_index</i> | The plane index of the image object that is the source or the destination of the patch copy.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
| in | <i>user_addr</i>         | The address of a structure describing the layout of the user memory location pointed by user_ptr. In the structure, only dim_x, dim_y, stride_x and stride_y fields must be provided, other fields are ignored by the function. The layout of the user memory must follow a row major order: stride_x >= pixel size in bytes, and stride_y >= stride_x * dim_x.                                                                                                                                                                                                                      |
| in | <i>user_ptr</i>          | The address of the memory location where to store the requested data if the copy was requested in read mode, or from where to get the data to store into the image object if the copy was requested in write mode. The accessible memory must be large enough to contain the specified patch with the specified layout: accessible memory in bytes >= (end_y - start_y) * stride_y.                                                                                                                                                                                                  |
| in | <i>usage</i>             | This declares the effect of the copy with regard to the image object using the <a href="#">vx_accessor_e</a> enumeration. For uniform images, only <a href="#">VX_READ_ONLY</a> is supported. For other images, Only <a href="#">VX_READ_ONLY</a> and <a href="#">VX_WRITE_ONLY</a> are supported: <ul style="list-style-type: none"> <li>• <a href="#">VX_READ_ONLY</a> means that data is copied from the image object into the application memory</li> <li>• <a href="#">VX_WRITE_ONLY</a> means that data is copied into the image object from the application memory</li> </ul> |
| in | <i>user_mem_type</i>     | A <a href="#">vx_memory_type_e</a> enumeration that specifies the memory type of the memory referenced by the user_addr.                                                                                                                                                                                                                                                                                                                                                                                                                                                             |

## Returns

A [vx\\_status\\_e](#) enumeration.

## Return values

|                   |                                               |
|-------------------|-----------------------------------------------|
| <i>VX_SUCCESS</i> | No errors; any other value indicates failure. |
|-------------------|-----------------------------------------------|



## Return values

|                                          |                                                                                    |
|------------------------------------------|------------------------------------------------------------------------------------|
| <code>VX_ERROR_OPTIMIZED_AWAY</code>     | This is a reference to a virtual image that cannot be accessed by the application. |
| <code>VX_ERROR_INVALID_REFERENCE</code>  | image is not a valid <a href="#">vx_image</a> reference.                           |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | An other parameter is incorrect.                                                   |

## Note

The application may ask for data outside the bounds of the valid region, but such data has an undefined value.

**vx\_status VX\_API\_CALL vxMapImagePatch ( vx\_image image, const vx\_rectangle\_t \* rect, vx\_uint32 plane\_index, vx\_map\_id \* map\_id, vx\_imagepatch\_addressing\_t \* addr, void \*\* ptr, vx\_enum usage, vx\_enum mem\_type, vx\_uint32 flags )**

Allows the application to get direct access to a rectangular patch of an image object plane.

## Parameters

|     |                    |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
|-----|--------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>image</i>       | The reference to the image object that contains the patch to map.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
| in  | <i>rect</i>        | The coordinates of image patch. The patch must be within the bounds of the image. (start_x, start_y) gives the coordinate of the topleft element inside the patch, while (end_x, end_y) give the coordinate of the bottomright element out of the patch. Must be 0 ≤ start < end.                                                                                                                                                                                                                                                                                                                                                                                                    |
| in  | <i>plane_index</i> | The plane index of the image object to be accessed.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
| out | <i>map_id</i>      | The address of a <a href="#">vx_map_id</a> variable where the function returns a map identifier. <ul style="list-style-type: none"> <li>(<i>*map_id</i>) must eventually be provided as the <i>map_id</i> parameter of a call to <a href="#">vxUnmapImagePatch</a>.</li> </ul>                                                                                                                                                                                                                                                                                                                                                                                                       |
| out | <i>addr</i>        | The address of a structure describing the memory layout of the image patch to access. The function fills the structure pointed by <i>addr</i> with the layout information that the application must consult to access the pixel data at address ( <i>*ptr</i> ). The layout of the mapped memory follows a row-major order: <i>stride_x</i> > 0, <i>stride_y</i> > 0 and <i>stride_y</i> ≥ <i>stride_x</i> * <i>dim_x</i> . If the image object being accessed was created via <a href="#">vxCreateImageFromHandle</a> , then the returned memory layout will be the identical to that of the addressing structure provided when <a href="#">vxCreateImageFromHandle</a> was called. |
| out | <i>ptr</i>         | The address of a pointer that the function sets to the address where the requested data can be accessed. This returned ( <i>*ptr</i> ) address is only valid between the call to this function and the corresponding call to <a href="#">vxUnmapImagePatch</a> . If image was created via <a href="#">vxCreateImageFromHandle</a> then the returned address ( <i>*ptr</i> ) will be the address of the patch in the original pixel buffer provided when image was created.                                                                                                                                                                                                           |

## Parameters

|    |                 |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
|----|-----------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>usage</i>    | <p>This declares the access mode for the image patch, using the <a href="#">vx_accessor_e</a> enumeration. For uniform images, only <code>VX_READ_ONLY</code> is supported.</p> <ul style="list-style-type: none"> <li>• <a href="#">VX_READ_ONLY</a>: after the function call, the content of the memory location pointed by (*ptr) contains the image patch data. Writing into this memory location is forbidden and its behavior is undefined.</li> <li>• <a href="#">VX_READ_AND_WRITE</a>: after the function call, the content of the memory location pointed by (*ptr) contains the image patch data; writing into this memory is allowed only for the location of pixels only and will result in a modification of the written pixels in the image object once the patch is unmapped. Writing into a gap between pixels (when <code>addr-&gt;stride_x &gt; pixel size in bytes</code> or <code>addr-&gt;stride_y &gt; addr-&gt;stride_x*addr-&gt;dim_x</code>) is forbidden and its behavior is undefined.</li> <li>• <a href="#">VX_WRITE_ONLY</a>: after the function call, the memory location pointed by (*ptr) contains undefined data; writing each pixel of the patch is required prior to unmapping. Pixels not written by the application before unmap will become undefined after unmap, even if they were well defined before map. Like for <code>VX_READ_AND_WRITE</code>, writing into a gap between pixels is forbidden and its behavior is undefined.</li> </ul> |
| in | <i>mem_type</i> | A <a href="#">vx_memory_type_e</a> enumeration that specifies the type of the memory where the image patch is requested to be mapped.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
| in | <i>flags</i>    | An integer that allows passing options to the map operation. Use the <a href="#">vx_map_flag_e</a> enumeration.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |

## Returns

A [vx\\_status\\_e](#) enumeration.

## Return values

|                                    |                                                                                    |
|------------------------------------|------------------------------------------------------------------------------------|
| <i>VX_SUCCESS</i>                  | No errors; any other value indicates failure.                                      |
| <i>VX_ERROR_OPTIMIZED_AWAY</i>     | This is a reference to a virtual image that cannot be accessed by the application. |
| <i>VX_ERROR_INVALID_REFERENCE</i>  | image is not a valid <a href="#">vx_image</a> reference. reference.                |
| <i>VX_ERROR_INVALID_PARAMETERS</i> | An other parameter is incorrect.                                                   |

## Note

The user may ask for data outside the bounds of the valid region, but such data has an undefined value.

## Postcondition

[vxUnmapImagePatch](#) with same (\*map\_id) value.

**vx\_status VX\_API\_CALL vxUnmapImagePatch ( vx\_image image, vx\_map\_id map\_id )**

Unmap and commit potential changes to a image object patch that were previously mapped. Unmapping an image patch invalidates the memory location from which the patch could be accessed by the application. Accessing this memory location after the unmap function completes has an undefined behavior.

## Parameters

|     |               |                                                                                  |
|-----|---------------|----------------------------------------------------------------------------------|
| in  | <i>image</i>  | The reference to the image object to unmap.                                      |
| out | <i>map_id</i> | The unique map identifier that was returned by <a href="#">vxMapImagePatch</a> . |

## Returns

A `vx_status_e` enumeration.

## Return values

|                                          |                                                       |
|------------------------------------------|-------------------------------------------------------|
| <code>VX_SUCCESS</code>                  | No errors; any other value indicates failure.         |
| <code>VX_ERROR_INVALID_REFERENCE</code>  | image is not a valid <code>vx_image</code> reference. |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | An other parameter is incorrect.                      |

## Precondition

`vxMapImagePatch` with same `map_id` value

**vx\_image VX\_API\_CALL vxCreateImageFromChannel ( vx\_image *img*, vx\_enum *channel* )**

Create a sub-image from a single plane channel of another image.

The sub-image refers to the data in the original image. Updates to this image update the parent image and reversely.

The function supports only channels that occupy an entire plane of a multi-planar images, as listed below. Other cases are not supported. `VX_CHANNEL_Y` from YUV4, IYUV, NV12, NV21 `VX_CHANNEL_U` from YUV4, IYUV `VX_CHANNEL_V` from YUV4, IYUV

## Parameters

|    |                |                                               |
|----|----------------|-----------------------------------------------|
| in | <i>img</i>     | The reference to the parent image.            |
| in | <i>channel</i> | The <code>vx_channel_e</code> channel to use. |

## Returns

An image reference `vx_image` to the sub-image. Any possible errors preventing a successful creation should be checked using `vxGetStatus`.

**vx\_status VX\_API\_CALL vxSetImageValidRectangle ( vx\_image *image*, const vx\_rectangle\_t \* *rect* )**

Sets the valid rectangle for an image according to a supplied rectangle.

## Note

Setting or changing the valid region from within a user node by means other than the call-back, for example by calling `vxSetImageValidRectangle`, might result in an incorrect valid region calculation by the framework.

## Parameters

|    |              |                                                                                                               |
|----|--------------|---------------------------------------------------------------------------------------------------------------|
| in | <i>image</i> | The reference to the image.                                                                                   |
| in | <i>rect</i>  | The value to be set to the image valid rectangle. A NULL indicates that the valid region is the entire image. |

## Returns

A `vx_status_e` enumeration.

## Return values

|                                    |                                                          |
|------------------------------------|----------------------------------------------------------|
| <i>VX_SUCCESS</i>                  | No errors; any other value indicates failure.            |
| <i>VX_ERROR_INVALID_REFERENCE</i>  | image is not a valid <a href="#">vx_image</a> reference. |
| <i>VX_ERROR_INVALID_PARAMETERS</i> | The rect does not define a proper valid rectangle.       |

## 3.72 Object: LUT

### 3.72.1 Detailed Description

Defines the Look-Up Table Interface.

A lookup table is an array that simplifies run-time computation by replacing computation with a simpler array indexing operation.

#### Typedefs

- typedef struct \_vx\_lut \* [vx\\_lut](#)  
The Look-Up Table (LUT) Object.

#### Enumerations

- enum [vx\\_lut\\_attribute\\_e](#) {  
[VX\\_LUT\\_TYPE](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_TYPE\\_LUT](#) << 8)) + 0x0,  
[VX\\_LUT\\_COUNT](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_TYPE\\_LUT](#) << 8)) + 0x1,  
[VX\\_LUT\\_SIZE](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_TYPE\\_LUT](#) << 8)) + 0x2,  
[VX\\_LUT\\_OFFSET](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_TYPE\\_LUT](#) << 8)) + 0x3 }  
The Look-Up Table (LUT) attribute list.

#### Functions

- [vx\\_status VX\\_API\\_CALL vxCopyLUT](#) ([vx\\_lut](#) lut, void \*user\_ptr, [vx\\_enum](#) usage, [vx\\_enum](#) user\_mem\_type)  
Allows the application to copy from/into a LUT object.
- [vx\\_lut VX\\_API\\_CALL vxCreateLUT](#) ([vx\\_context](#) context, [vx\\_enum](#) data\_type, [vx\\_size](#) count)  
Creates LUT object of a given type. The value of [VX\\_LUT\\_OFFSET](#) is equal to 0 for data\_type = [VX\\_TYPE\\_UINT8](#), and (vx\_uint32)(count/2) for [VX\\_TYPE\\_INT16](#).
- [vx\\_lut VX\\_API\\_CALL vxCreateVirtualLUT](#) ([vx\\_graph](#) graph, [vx\\_enum](#) data\_type, [vx\\_size](#) count)  
Creates an opaque reference to a LUT object with no direct user access.
- [vx\\_status VX\\_API\\_CALL vxMapLUT](#) ([vx\\_lut](#) lut, [vx\\_map\\_id](#) \*map\_id, void \*\*ptr, [vx\\_enum](#) usage, [vx\\_enum](#) mem\_type, [vx\\_bitfield](#) flags)  
Allows the application to get direct access to LUT object.
- [vx\\_status VX\\_API\\_CALL vxQueryLUT](#) ([vx\\_lut](#) lut, [vx\\_enum](#) attribute, void \*ptr, [vx\\_size](#) size)  
Queries attributes from a LUT.
- [vx\\_status VX\\_API\\_CALL vxReleaseLUT](#) ([vx\\_lut](#) \*lut)  
Releases a reference to a LUT object. The object may not be garbage collected until its total reference count is zero.
- [vx\\_status VX\\_API\\_CALL vxUnmapLUT](#) ([vx\\_lut](#) lut, [vx\\_map\\_id](#) map\_id)  
Unmap and commit potential changes to LUT object that was previously mapped. Unmapping a LUT invalidates the memory location from which the LUT data could be accessed by the application. Accessing this memory location after the unmap function completes has an undefined behavior.

### 3.72.2 Enumeration Type Documentation

#### enum [vx\\_lut\\_attribute\\_e](#)

The Look-Up Table (LUT) attribute list.

Enumerator

- [VX\\_LUT\\_TYPE](#) Indicates the value type of the LUT. Read-only. Use a [vx\\_enum](#).
- [VX\\_LUT\\_COUNT](#) Indicates the number of elements in the LUT. Read-only. Use a [vx\\_size](#).
- [VX\\_LUT\\_SIZE](#) Indicates the total size of the LUT in bytes. Read-only. Uses a [vx\\_size](#).
- [VX\\_LUT\\_OFFSET](#) Indicates the index of the input value = 0. Read-only. Uses a [vx\\_uint32](#).

Definition at line 1020 of file [vx\\_types.h](#).

### 3.72.3 Function Documentation

**vx\_lut VX\_API\_CALL vxCreateLUT ( vx\_context *context*, vx\_enum *data\_type*, vx\_size *count* )**

Creates LUT object of a given type. The value of `VX_LUT_OFFSET` is equal to 0 for `data_type = VX_TYPE_UINT8`, and `(vx_uint32)(count/2)` for `VX_TYPE_INT16`.

#### Parameters

|    |                  |                                     |
|----|------------------|-------------------------------------|
| in | <i>context</i>   | The reference to the context.       |
| in | <i>data_type</i> | The type of data stored in the LUT. |
| in | <i>count</i>     | The number of entries desired.      |

#### Note

`data_type` can only be `VX_TYPE_UINT8` or `VX_TYPE_INT16`. If `data_type` is `VX_TYPE_UINT8`, `count` should be not greater than 256. If `data_type` is `VX_TYPE_INT16`, `count` should not be greater than 65536.

#### Returns

An LUT reference `vx_lut`. Any possible errors preventing a successful creation should be checked using `vxGetStatus`.

**vx\_lut VX\_API\_CALL vxCreateVirtualLUT ( vx\_graph *graph*, vx\_enum *data\_type*, vx\_size *count* )**

Creates an opaque reference to a LUT object with no direct user access.

#### Parameters

|    |                  |                                     |
|----|------------------|-------------------------------------|
| in | <i>graph</i>     | The reference to the parent graph.  |
| in | <i>data_type</i> | The type of data stored in the LUT. |
| in | <i>count</i>     | The number of entries desired.      |

#### See also

`vxCreateLUT`

#### Note

`data_type` can only be `VX_TYPE_UINT8` or `VX_TYPE_INT16`. If `data_type` is `VX_TYPE_UINT8`, `count` should be not greater than 256. If `data_type` is `VX_TYPE_INT16`, `count` should not be greater than 65536.

#### Returns

An LUT reference `vx_lut`. Any possible errors preventing a successful creation should be checked using `vxGetStatus`.

**vx\_status VX\_API\_CALL vxReleaseLUT ( vx\_lut \* *lut* )**

Releases a reference to a LUT object. The object may not be garbage collected until its total reference count is zero.

#### Parameters

|    |            |                                    |
|----|------------|------------------------------------|
| in | <i>lut</i> | The pointer to the LUT to release. |
|----|------------|------------------------------------|

## Postcondition

After returning from this function the reference is zeroed.

## Returns

A `vx_status_e` enumeration.

## Return values

|                                         |                                                   |
|-----------------------------------------|---------------------------------------------------|
| <code>VX_SUCCESS</code>                 | No errors; any other value indicates failure.     |
| <code>VX_ERROR_INVALID_REFERENCE</code> | lut is not a valid <code>vx_lut</code> reference. |

**`vx_status VX_API_CALL vxQueryLUT ( vx_lut lut, vx_enum attribute, void * ptr, vx_size size )`**

Queries attributes from a LUT.

## Parameters

|     |                  |                                                                            |
|-----|------------------|----------------------------------------------------------------------------|
| in  | <i>lut</i>       | The LUT to query.                                                          |
| in  | <i>attribute</i> | The attribute to query. Use a <code>vx_lut_attribute_e</code> enumeration. |
| out | <i>ptr</i>       | The location at which to store the resulting value.                        |
| in  | <i>size</i>      | The size in bytes of the container to which <i>ptr</i> points.             |

## Returns

A `vx_status_e` enumeration.

## Return values

|                                         |                                                   |
|-----------------------------------------|---------------------------------------------------|
| <code>VX_SUCCESS</code>                 | No errors; any other value indicates failure.     |
| <code>VX_ERROR_INVALID_REFERENCE</code> | lut is not a valid <code>vx_lut</code> reference. |

**`vx_status VX_API_CALL vxCopyLUT ( vx_lut lut, void * user_ptr, vx_enum usage, vx_enum user_mem_type )`**

Allows the application to copy from/into a LUT object.

## Parameters

|    |                 |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
|----|-----------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>lut</i>      | The reference to the LUT object that is the source or the destination of the copy.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
| in | <i>user_ptr</i> | The address of the memory location where to store the requested data if the copy was requested in read mode, or from where to get the data to store into the LUT object if the copy was requested in write mode. In the user memory, the LUT is represented as a array with elements of the type corresponding to <code>VX_LUT_TYPE</code> , and with a number of elements equal to the value returned via <code>VX_LUT_COUNT</code> . The accessible memory must be large enough to contain this array: accessible memory in bytes $\geq \text{sizeof}(\text{data\_element}) * \text{count}$ . |

## Parameters

|    |                      |                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
|----|----------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>usage</i>         | This declares the effect of the copy with regard to the LUT object using the <code>vx_accessor_e</code> enumeration. Only <code>VX_READ_ONLY</code> and <code>VX_WRITE_ONLY</code> are supported: <ul style="list-style-type: none"> <li>• <code>VX_READ_ONLY</code> means that data are copied from the LUT object into the user memory.</li> <li>• <code>VX_WRITE_ONLY</code> means that data are copied into the LUT object from the user memory.</li> </ul> |
| in | <i>user_mem_type</i> | A <code>vx_memory_type_e</code> enumeration that specifies the memory type of the memory referenced by the <code>user_addr</code> .                                                                                                                                                                                                                                                                                                                             |

## Returns

A `vx_status_e` enumeration.

## Return values

|                                          |                                                   |
|------------------------------------------|---------------------------------------------------|
| <code>VX_SUCCESS</code>                  | No errors; any other value indicates failure.     |
| <code>VX_ERROR_INVALID_REFERENCE</code>  | lut is not a valid <code>vx_lut</code> reference. |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | An other parameter is incorrect.                  |

**vx\_status VX\_API\_CALL vxMapLUT ( vx\_lut lut, vx\_map\_id \* map\_id, void \*\* ptr, vx\_enum usage, vx\_enum mem\_type, vx\_bitfield flags )**

Allows the application to get direct access to LUT object.

## Parameters

|     |               |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
|-----|---------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>lut</i>    | The reference to the LUT object to map.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
| out | <i>map_id</i> | The address of a <code>vx_map_id</code> variable where the function returns a map identifier. <ul style="list-style-type: none"> <li>• (*map_id) must eventually be provided as the <code>map_id</code> parameter of a call to <code>vxUnmapLUT</code>.</li> </ul>                                                                                                                                                                                                                                                                                                         |
| out | <i>ptr</i>    | The address of a pointer that the function sets to the address where the requested data can be accessed. In the mapped memory area, the LUT data are structured as an array with elements of the type corresponding to <code>VX_LUT_TYPE</code> , with a number of elements equal to the value returned via <code>VX_LUT_COUNT</code> . Accessing the memory out of the bound of this array is forbidden and has an undefined behavior. The returned (*ptr) address is only valid between the call to the function and the corresponding call to <code>vxUnmapLUT</code> . |



## Parameters

|    |                 |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
|----|-----------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>usage</i>    | This declares the access mode for the LUT, using the <code>vx_accessor_e</code> enumeration. <ul style="list-style-type: none"> <li>• <code>VX_READ_ONLY</code>: after the function call, the content of the memory location pointed by (*ptr) contains the LUT data. Writing into this memory location is forbidden and its behavior is undefined.</li> <li>• <code>VX_READ_AND_WRITE</code>: after the function call, the content of the memory location pointed by (*ptr) contains the LUT data; writing into this memory is allowed only for the location of entries and will result in a modification of the affected entries in the LUT object once the LUT is unmapped.</li> <li>• <code>VX_WRITE_ONLY</code>: after the function call, the memory location pointed by(*ptr) contains undefined data; writing each entry of LUT is required prior to unmapping. Entries not written by the application before unmap will become undefined after unmap, even if they were well defined before map.</li> </ul> |
| in | <i>mem_type</i> | A <code>vx_memory_type_e</code> enumeration that specifies the type of the memory where the LUT is requested to be mapped.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
| in | <i>flags</i>    | An integer that allows passing options to the map operation. Use 0 for this option.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |

## Returns

A `vx_status_e` enumeration.

## Return values

|                                          |                                                   |
|------------------------------------------|---------------------------------------------------|
| <code>VX_SUCCESS</code>                  | No errors; any other value indicates failure.     |
| <code>VX_ERROR_INVALID_REFERENCE</code>  | lut is not a valid <code>vx_lut</code> reference. |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | An other parameter is incorrect.                  |

## Postcondition

`vxUnmapLUT` with same (\*map\_id) value.

**vx\_status VX\_API\_CALL vxUnmapLUT ( vx\_lut lut, vx\_map\_id map\_id )**

Unmap and commit potential changes to LUT object that was previously mapped. Unmapping a LUT invalidates the memory location from which the LUT data could be accessed by the application. Accessing this memory location after the unmap function completes has an undefined behavior.

## Parameters

|     |               |                                                                                  |
|-----|---------------|----------------------------------------------------------------------------------|
| in  | <i>lut</i>    | The reference to the LUT object to unmap.                                        |
| out | <i>map_id</i> | The unique map identifier that was returned when calling <code>vxMapLUT</code> . |

## Returns

A `vx_status_e` enumeration.

## Return values

|                                          |                                                   |
|------------------------------------------|---------------------------------------------------|
| <code>VX_SUCCESS</code>                  | No errors; any other value indicates failure.     |
| <code>VX_ERROR_INVALID_REFERENCE</code>  | lut is not a valid <code>vx_lut</code> reference. |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | An other parameter is incorrect.                  |

Precondition

`vxMapLUT` returning the same `map_id` value

## 3.73 Object: Matrix

### 3.73.1 Detailed Description

Defines the Matrix Object Interface.

#### Typedefs

- typedef struct \_vx\_matrix \* [vx\\_matrix](#)

*The Matrix Object. An MxN matrix of some unit type.*

#### Enumerations

- enum [vx\\_matrix\\_attribute\\_e](#) {  
[VX\\_MATRIX\\_TYPE](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_TYPE\\_MATRIX](#) << 8)) + 0x0,  
[VX\\_MATRIX\\_ROWS](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_TYPE\\_MATRIX](#) << 8)) + 0x1,  
[VX\\_MATRIX\\_COLUMNS](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_TYPE\\_MATRIX](#) << 8)) + 0x2,  
[VX\\_MATRIX\\_SIZE](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_TYPE\\_MATRIX](#) << 8)) + 0x3,  
[VX\\_MATRIX\\_ORIGIN](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_TYPE\\_MATRIX](#) << 8)) + 0x4,  
[VX\\_MATRIX\\_PATTERN](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_TYPE\\_MATRIX](#) << 8)) + 0x5 }

*The matrix attributes.*

#### Functions

- [vx\\_status VX\\_API\\_CALL vxCopyMatrix](#) ([vx\\_matrix](#) matrix, void \*user\_ptr, [vx\\_enum](#) usage, [vx\\_enum](#) user\_↵ mem\_type)  
*Allows the application to copy from/into a matrix object.*
- [vx\\_matrix VX\\_API\\_CALL vxCreateMatrix](#) ([vx\\_context](#) c, [vx\\_enum](#) data\_type, [vx\\_size](#) columns, [vx\\_size](#) rows)  
*Creates a reference to a matrix object.*
- [vx\\_matrix VX\\_API\\_CALL vxCreateMatrixFromPattern](#) ([vx\\_context](#) context, [vx\\_enum](#) pattern, [vx\\_size](#) columns, [vx\\_size](#) rows)  
*Creates a reference to a matrix object from a boolean pattern.*
- [vx\\_matrix VX\\_API\\_CALL vxCreateMatrixFromPatternAndOrigin](#) ([vx\\_context](#) context, [vx\\_enum](#) pattern, [vx\\_↵ size](#) columns, [vx\\_size](#) rows, [vx\\_size](#) origin\_col, [vx\\_size](#) origin\_row)  
*Creates a reference to a matrix object from a boolean pattern, with a user-specified origin.*
- [vx\\_matrix VX\\_API\\_CALL vxCreateVirtualMatrix](#) ([vx\\_graph](#) graph, [vx\\_enum](#) data\_type, [vx\\_size](#) columns, [vx\\_↵ \\_size](#) rows)  
*Creates an opaque reference to a matrix object without direct user access.*
- [vx\\_status VX\\_API\\_CALL vxQueryMatrix](#) ([vx\\_matrix](#) mat, [vx\\_enum](#) attribute, void \*ptr, [vx\\_size](#) size)  
*Queries an attribute on the matrix object.*
- [vx\\_status VX\\_API\\_CALL vxReleaseMatrix](#) ([vx\\_matrix](#) \*mat)  
*Releases a reference to a matrix object. The object may not be garbage collected until its total reference count is zero.*

### 3.73.2 Enumeration Type Documentation

#### enum [vx\\_matrix\\_attribute\\_e](#)

The matrix attributes.

Enumerator

**[VX\\_MATRIX\\_TYPE](#)** The value type of the matrix. Read-only. Use a [vx\\_enum](#) parameter.

**[VX\\_MATRIX\\_ROWS](#)** The M dimension of the matrix. Read-only. Use a [vx\\_size](#) parameter.

**[VX\\_MATRIX\\_COLUMNS](#)** The N dimension of the matrix. Read-only. Use a [vx\\_size](#) parameter.

**[VX\\_MATRIX\\_SIZE](#)** The total size of the matrix in bytes. Read-only. Use a [vx\\_size](#) parameter.

**VX\_MATRIX\_ORIGIN** The origin of the matrix with a default value of `[floor(VX_MATRIX_COLUMNS/2), floor(VX_MATRIX_ROWS/2)]`. Read-only. Use a `vx_coordinates2d_t` parameter.

**VX\_MATRIX\_PATTERN** The pattern of the matrix. See `vx_pattern_e`. Read-only. Use a `vx_enum` parameter. If the matrix was created via `vxCreateMatrixFromPattern` or `vxCreateMatrixFromPatternAndOrigin`, the attribute corresponds to the given pattern. Otherwise the attribute is `VX_PATTERN_OTHER`.

Definition at line 1075 of file `vx_types.h`.

### 3.73.3 Function Documentation

**vx\_matrix VX\_API\_CALL vxCreateMatrix ( vx\_context *c*, vx\_enum *data\_type*, vx\_size *columns*, vx\_size *rows* )**

Creates a reference to a matrix object.

#### Parameters

|    |                  |                                                                                                                           |
|----|------------------|---------------------------------------------------------------------------------------------------------------------------|
| in | <i>c</i>         | The reference to the overall context.                                                                                     |
| in | <i>data_type</i> | The unit format of the matrix. <code>VX_TYPE_UINT8</code> or <code>VX_TYPE_INT32</code> or <code>VX_TYPE_FLOAT32</code> . |
| in | <i>columns</i>   | The first dimensionality.                                                                                                 |
| in | <i>rows</i>      | The second dimensionality.                                                                                                |

#### Returns

An matrix reference `vx_matrix`. Any possible errors preventing a successful creation should be checked using `vxGetStatus`.

**vx\_matrix VX\_API\_CALL vxCreateVirtualMatrix ( vx\_graph *graph*, vx\_enum *data\_type*, vx\_size *columns*, vx\_size *rows* )**

Creates an opaque reference to a matrix object without direct user access.

#### Parameters

|    |                  |                                                                                                                           |
|----|------------------|---------------------------------------------------------------------------------------------------------------------------|
| in | <i>graph</i>     | The reference to the parent graph.                                                                                        |
| in | <i>data_type</i> | The unit format of the matrix. <code>VX_TYPE_UINT8</code> or <code>VX_TYPE_INT32</code> or <code>VX_TYPE_FLOAT32</code> . |
| in | <i>columns</i>   | The first dimensionality.                                                                                                 |
| in | <i>rows</i>      | The second dimensionality.                                                                                                |

#### See also

`vxCreateMatrix`

#### Returns

An matrix reference `vx_matrix`. Any possible errors preventing a successful creation should be checked using `vxGetStatus`.

**vx\_status VX\_API\_CALL vxReleaseMatrix ( vx\_matrix \* *mat* )**

Releases a reference to a matrix object. The object may not be garbage collected until its total reference count is zero.

**Parameters**

|    |            |                                  |
|----|------------|----------------------------------|
| in | <i>mat</i> | The matrix reference to release. |
|----|------------|----------------------------------|

**Postcondition**

After returning from this function the reference is zeroed.

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                                         |                                                             |
|-----------------------------------------|-------------------------------------------------------------|
| <code>VX_SUCCESS</code>                 | No errors; any other value indicates failure.               |
| <code>VX_ERROR_INVALID_REFERENCE</code> | <i>mat</i> is not a valid <code>vx_matrix</code> reference. |

**vx\_status VX\_API\_CALL vxQueryMatrix ( vx\_matrix *mat*, vx\_enum *attribute*, void \* *ptr*, vx\_size *size* )**

Queries an attribute on the matrix object.

**Parameters**

|     |                  |                                                                               |
|-----|------------------|-------------------------------------------------------------------------------|
| in  | <i>mat</i>       | The matrix object to set.                                                     |
| in  | <i>attribute</i> | The attribute to query. Use a <code>vx_matrix_attribute_e</code> enumeration. |
| out | <i>ptr</i>       | The location at which to store the resulting value.                           |
| in  | <i>size</i>      | The size in bytes of the container to which <i>ptr</i> points.                |

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                                         |                                                             |
|-----------------------------------------|-------------------------------------------------------------|
| <code>VX_SUCCESS</code>                 | No errors; any other value indicates failure.               |
| <code>VX_ERROR_INVALID_REFERENCE</code> | <i>mat</i> is not a valid <code>vx_matrix</code> reference. |

**vx\_status VX\_API\_CALL vxCopyMatrix ( vx\_matrix *matrix*, void \* *user\_ptr*, vx\_enum *usage*, vx\_enum *user\_mem\_type* )**

Allows the application to copy from/into a matrix object.

**Parameters**

|    |                 |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
|----|-----------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>matrix</i>   | The reference to the matrix object that is the source or the destination of the copy.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
| in | <i>user_ptr</i> | The address of the memory location where to store the requested data if the copy was requested in read mode, or from where to get the data to store into the matrix object if the copy was requested in write mode. In the user memory, the matrix is structured as a row-major 2D array with elements of the type corresponding to <code>VX_MATRIX_TYPE</code> , with a number of rows corresponding to <code>VX_MATRIX_ROWS</code> and a number of columns corresponding to <code>VX_MATRIX_COLUMNS</code> . The accessible memory must be large enough to contain this 2D array: accessible memory in bytes $\geq \text{sizeof}(\text{data\_element}) * \text{rows} * \text{columns}$ . |

**Parameters**

|    |                      |                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
|----|----------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>usage</i>         | This declares the effect of the copy with regard to the matrix object using the <code>vx_accessor_e</code> enumeration. Only <code>VX_READ_ONLY</code> and <code>VX_WRITE_ONLY</code> are supported: <ul style="list-style-type: none"> <li>• <code>VX_READ_ONLY</code> means that data are copied from the matrix object into the user memory.</li> <li>• <code>VX_WRITE_ONLY</code> means that data are copied into the matrix object from the user memory.</li> </ul> |
| in | <i>user_mem_type</i> | A <code>vx_memory_type_e</code> enumeration that specifies the memory type of the memory referenced by the <code>user_addr</code> .                                                                                                                                                                                                                                                                                                                                      |

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                                          |                                                         |
|------------------------------------------|---------------------------------------------------------|
| <code>VX_SUCCESS</code>                  | No errors; any other value indicates failure.           |
| <code>VX_ERROR_INVALID_REFERENCE</code>  | matrix is not a valid <code>vx_matrix</code> reference. |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | An other parameter is incorrect.                        |

**vx\_matrix VX\_API\_CALL vxCreateMatrixFromPattern ( vx\_context *context*, vx\_enum *pattern*, vx\_size *columns*, vx\_size *rows* )**

Creates a reference to a matrix object from a boolean pattern.

See also

`vxCreateMatrixFromPatternAndOrigin` for a description of the matrix patterns.

**Parameters**

|    |                |                                                                 |
|----|----------------|-----------------------------------------------------------------|
| in | <i>context</i> | The reference to the overall context.                           |
| in | <i>pattern</i> | The pattern of the matrix. See <code>VX_MATRIX_PATTERN</code> . |
| in | <i>columns</i> | The first dimensionality.                                       |
| in | <i>rows</i>    | The second dimensionality.                                      |

**Returns**

A matrix reference `vx_matrix` of type `VX_TYPE_UINT8`. Any possible errors preventing a successful creation should be checked using `vxGetStatus`.

**vx\_matrix VX\_API\_CALL vxCreateMatrixFromPatternAndOrigin ( vx\_context *context*, vx\_enum *pattern*, vx\_size *columns*, vx\_size *rows*, vx\_size *origin\_col*, vx\_size *origin\_row* )**

Creates a reference to a matrix object from a boolean pattern, with a user-specified origin.

The matrix created by this function is of type `VX_TYPE_UINT8`, with the value 0 representing False, and the value 255 representing True. It supports the patterns as described below:

- `VX_PATTERN_BOX` is a matrix with dimensions equal to the given number of rows and columns, and all cells equal to 255. Dimensions of 3x3 and 5x5 must be supported.

- `VX_PATTERN_CROSS` is a matrix with dimensions equal to the given number of rows and columns, which both must be odd numbers. All cells in the center row and center column are equal to 255, and the rest are equal to zero. Dimensions of 3x3 and 5x5 must be supported.
- `VX_PATTERN_DISK` is a matrix with dimensions equal to the given number of rows ( $R$ ) and columns ( $C$ ), where  $R$  and  $C$  are odd and cell  $(c, r)$  is 255 if:  
 $(r-R/2 + 0.5)^2 / (R/2)^2 + (c-C/2 + 0.5)^2 / (C/2)^2$  is less than or equal to 1,  
 and 0 otherwise.

A matrix created from pattern is read-only. The behavior when attempting to modify such a matrix is undefined.

#### Parameters

|    |                   |                                                                    |
|----|-------------------|--------------------------------------------------------------------|
| in | <i>context</i>    | The reference to the overall context.                              |
| in | <i>pattern</i>    | The pattern of the matrix. See <a href="#">VX_MATRIX_PATTERN</a> . |
| in | <i>columns</i>    | The first dimensionality.                                          |
| in | <i>rows</i>       | The second dimensionality.                                         |
| in | <i>origin_col</i> | The origin (first dimensionality).                                 |
| in | <i>origin_row</i> | The origin (second dimensionality).                                |

#### Returns

A matrix reference `vx_matrix` of type `VX_TYPE_UINT8`. Any possible errors preventing a successful creation should be checked using `vxGetStatus`.

## 3.74 Object: Pyramid

### 3.74.1 Detailed Description

Defines the Image Pyramid Object Interface.

A Pyramid object in OpenVX represents a collection of related images. Typically, these images are created by either downscaling or upscaling a *base image*, contained in level zero of the pyramid. Successive levels of the pyramid increase or decrease in size by a factor given by the `VX_PYRAMID_SCALE` attribute. For instance, in a pyramid with 3 levels and `VX_SCALE_PYRAMID_HALF`, the level one image is one-half the width and one-half the height of the level zero image, and the level two image is one-quarter the width and one quarter the height of the level zero image. When downscaling or upscaling results in a non-integral number of pixels at any level, fractional pixels always get rounded up to the nearest integer. (E.g., a 3-level image pyramid beginning with level zero having a width of 9 and a scaling of `VX_SCALE_PYRAMID_HALF` results in the level one image with a width of  $5 = \text{ceil}(9 * 0.5)$  and a level two image with a width of  $3 = \text{ceil}(5 * 0.5)$ ). Position  $(r_N, c_N)$  at level  $N$  corresponds to position  $(r_{N-1}/\text{scale}, c_{N-1}/\text{scale})$  at level  $N - 1$ .

### Macros

- `#define VX_SCALE_PYRAMID_HALF (0.5f)`  
*Use to indicate a half-scale pyramid.*
- `#define VX_SCALE_PYRAMID_ORB ((vx_float32)0.8408964f)`  
*Use to indicate a ORB scaled pyramid whose scaling factor is  $\frac{1}{\sqrt{2}}$ .*

### Typedefs

- `typedef struct _vx_pyramid * vx_pyramid`  
*The Image Pyramid object. A set of scaled images.*

### Enumerations

- `enum vx_pyramid_attribute_e {`  
`VX_PYRAMID_LEVELS = ((( VX_ID_KHRONOS ) << 20) | ( VX_TYPE_PYRAMID << 8)) + 0x0,`  
`VX_PYRAMID_SCALE = ((( VX_ID_KHRONOS ) << 20) | ( VX_TYPE_PYRAMID << 8)) + 0x1,`  
`VX_PYRAMID_WIDTH = ((( VX_ID_KHRONOS ) << 20) | ( VX_TYPE_PYRAMID << 8)) + 0x2,`  
`VX_PYRAMID_HEIGHT = ((( VX_ID_KHRONOS ) << 20) | ( VX_TYPE_PYRAMID << 8)) + 0x3,`  
`VX_PYRAMID_FORMAT = ((( VX_ID_KHRONOS ) << 20) | ( VX_TYPE_PYRAMID << 8)) + 0x4 }`  
*The pyramid object attributes.*

### Functions

- `vx_pyramid VX_API_CALL vxCreatePyramid (vx_context context, vx_size levels, vx_float32 scale, vx_uint32 width, vx_uint32 height, vx_df_image format)`  
*Creates a reference to a pyramid object of the supplied number of levels.*
- `vx_pyramid VX_API_CALL vxCreateVirtualPyramid (vx_graph graph, vx_size levels, vx_float32 scale, vx_uint32 width, vx_uint32 height, vx_df_image format)`  
*Creates a reference to a virtual pyramid object of the supplied number of levels.*
- `vx_image VX_API_CALL vxGetPyramidLevel (vx_pyramid pyr, vx_uint32 index)`  
*Retrieves a level of the pyramid as a `vx_image`, which can be used elsewhere in OpenVX. A call to `vxReleaseImage` is necessary to release an image for each call of `vxGetPyramidLevel`.*
- `vx_status VX_API_CALL vxQueryPyramid (vx_pyramid pyr, vx_enum attribute, void *ptr, vx_size size)`  
*Queries an attribute from an image pyramid.*
- `vx_status VX_API_CALL vxReleasePyramid (vx_pyramid *pyr)`  
*Releases a reference to a pyramid object. The object may not be garbage collected until its total reference count is zero.*



### 3.74.2 Enumeration Type Documentation

#### enum vx\_pyramid\_attribute\_e

The pyramid object attributes.

Enumerator

**VX\_PYRAMID\_LEVELS** The number of levels of the pyramid. Read-only. Use a [vx\\_size](#) parameter.

**VX\_PYRAMID\_SCALE** The scale factor between each level of the pyramid. Read-only. Use a [vx\\_float32](#) parameter.

**VX\_PYRAMID\_WIDTH** The width of the 0th image in pixels. Read-only. Use a [vx\\_uint32](#) parameter.

**VX\_PYRAMID\_HEIGHT** The height of the 0th image in pixels. Read-only. Use a [vx\\_uint32](#) parameter.

**VX\_PYRAMID\_FORMAT** The [vx\\_df\\_image\\_e](#) format of the image. Read-only. Use a [vx\\_df\\_image](#) parameter.

Definition at line 1115 of file [vx\\_types.h](#).

### 3.74.3 Function Documentation

**vx\_pyramid VX\_API\_CALL vxCreatePyramid ( vx\_context context, vx\_size levels, vx\_float32 scale, vx\_uint32 width, vx\_uint32 height, vx\_df\_image format )**

Creates a reference to a pyramid object of the supplied number of levels.

#### Parameters

|    |                |                                                                                                                                                                                                        |
|----|----------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>context</i> | The reference to the overall context.                                                                                                                                                                  |
| in | <i>levels</i>  | The number of levels desired. This is required to be a non-zero value.                                                                                                                                 |
| in | <i>scale</i>   | Used to indicate the scale between pyramid levels. This is required to be a non-zero positive value. <a href="#">VX_SCALE_PYRAMID_HALF</a> and <a href="#">VX_SCALE_PYRAMID_ORB</a> must be supported. |
| in | <i>width</i>   | The width of the 0th level image in pixels.                                                                                                                                                            |
| in | <i>height</i>  | The height of the 0th level image in pixels.                                                                                                                                                           |
| in | <i>format</i>  | The format of all images in the pyramid. NV12, NV21, IYUV, UYVY and YUYV formats are not supported.                                                                                                    |

#### Returns

A pyramid reference [vx\\_pyramid](#) containing the sub-images. Any possible errors preventing a successful creation should be checked using [vxGetStatus](#).

**vx\_pyramid VX\_API\_CALL vxCreateVirtualPyramid ( vx\_graph graph, vx\_size levels, vx\_float32 scale, vx\_uint32 width, vx\_uint32 height, vx\_df\_image format )**

Creates a reference to a virtual pyramid object of the supplied number of levels.

Virtual Pyramids can be used to connect Nodes together when the contents of the pyramids will not be accessed by the user of the API. All of the following constructions are valid:

```
00001 vx_context context = vxCreateContext();
00002 vx_graph graph = vxCreateGraph(context);
00003 vx_pyramid virt[] = {
00004 vxCreateVirtualPyramid(graph, 4, VX_SCALE_PYRAMID_HALF, 0, 0, VX_DF_IMAGE_VIRT), // no dimension
 and format specified for level 0
00005 vxCreateVirtualPyramid(graph, 4, VX_SCALE_PYRAMID_HALF, 640, 480, VX_DF_IMAGE_VIRT), // no format
 specified.
00006 vxCreateVirtualPyramid(graph, 4, VX_SCALE_PYRAMID_HALF, 640, 480, VX_DF_IMAGE_U8), // no access
00007 };
```

**Parameters**

|    |               |                                                                                                                                                                                                        |
|----|---------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>graph</i>  | The reference to the parent graph.                                                                                                                                                                     |
| in | <i>levels</i> | The number of levels desired. This is required to be a non-zero value.                                                                                                                                 |
| in | <i>scale</i>  | Used to indicate the scale between pyramid levels. This is required to be a non-zero positive value. <a href="#">VX_SCALE_PYRAMID_HALF</a> and <a href="#">VX_SCALE_PYRAMID_ORB</a> must be supported. |
| in | <i>width</i>  | The width of the 0th level image in pixels. This may be set to zero to indicate to the interface that the value is unspecified.                                                                        |
| in | <i>height</i> | The height of the 0th level image in pixels. This may be set to zero to indicate to the interface that the value is unspecified.                                                                       |
| in | <i>format</i> | The format of all images in the pyramid. This may be set to <a href="#">VX_DF_IMAGE_VIRT</a> to indicate that the format is unspecified.                                                               |

**Returns**

A pyramid reference [vx\\_pyramid](#). Any possible errors preventing a successful creation should be checked using [vxGetStatus](#).

**Note**

Images extracted with [vxGetPyramidLevel](#) behave as Virtual Images and cause [vxMapImagePatch](#) to return errors.

**vx\_status VX\_API\_CALL vxReleasePyramid ( vx\_pyramid \* pyr )**

Releases a reference to a pyramid object. The object may not be garbage collected until its total reference count is zero.

**Parameters**

|    |            |                                        |
|----|------------|----------------------------------------|
| in | <i>pyr</i> | The pointer to the pyramid to release. |
|----|------------|----------------------------------------|

**Returns**

A [vx\\_status\\_e](#) enumeration.

**Return values**

|                                            |                                                          |
|--------------------------------------------|----------------------------------------------------------|
| <a href="#">VX_SUCCESS</a>                 | No errors; any other value indicates failure.            |
| <a href="#">VX_ERROR_INVALID_REFERENCE</a> | pyr is not a valid <a href="#">vx_pyramid</a> reference. |

**Postcondition**

After returning from this function the reference is zeroed.

**vx\_status VX\_API\_CALL vxQueryPyramid ( vx\_pyramid pyr, vx\_enum attribute, void \* ptr, vx\_size size )**

Queries an attribute from an image pyramid.

**Parameters**

|     |                  |                                                                                             |
|-----|------------------|---------------------------------------------------------------------------------------------|
| in  | <i>pyr</i>       | The pyramid to query.                                                                       |
| in  | <i>attribute</i> | The attribute for which to query. Use a <a href="#">vx_pyramid_attribute_e</a> enumeration. |
| out | <i>ptr</i>       | The location at which to store the resulting value.                                         |
| in  | <i>size</i>      | The size in bytes of the container to which <i>ptr</i> points.                              |

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                                         |                                                                    |
|-----------------------------------------|--------------------------------------------------------------------|
| <code>VX_SUCCESS</code>                 | No errors; any other value indicates failure.                      |
| <code>VX_ERROR_INVALID_REFERENCE</code> | <code>pyr</code> is not a valid <code>vx_pyramid</code> reference. |

**`vx_image VX_API_CALL vxGetPyramidLevel ( vx_pyramid pyr, vx_uint32 index )`**

Retrieves a level of the pyramid as a `vx_image`, which can be used elsewhere in OpenVX. A call to `vxReleaseImage` is necessary to release an image for each call of `vxGetPyramidLevel`.

**Parameters**

|    |                    |                                                                                         |
|----|--------------------|-----------------------------------------------------------------------------------------|
| in | <code>pyr</code>   | The pyramid object.                                                                     |
| in | <code>index</code> | The index of the level, such that <code>index</code> is less than <code>levels</code> . |

**Returns**

A `vx_image` reference. Any possible errors preventing a successful function completion should be checked using `vxGetStatus`.

## 3.75 Object: Remap

### 3.75.1 Detailed Description

Defines the Remap Object Interface.

#### Typedefs

- typedef struct \_vx\_remap \* [vx\\_remap](#)

*The remap table Object. A remap table contains per-pixel mapping of output pixels to input pixels.*

#### Enumerations

- enum [vx\\_remap\\_attribute\\_e](#) {  
[VX\\_REMAP\\_SOURCE\\_WIDTH](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_TYPE\\_REMAP](#) << 8)) + 0x0,  
[VX\\_REMAP\\_SOURCE\\_HEIGHT](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_TYPE\\_REMAP](#) << 8)) + 0x1,  
[VX\\_REMAP\\_DESTINATION\\_WIDTH](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_TYPE\\_REMAP](#) << 8)) + 0x2,  
[VX\\_REMAP\\_DESTINATION\\_HEIGHT](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_TYPE\\_REMAP](#) << 8)) + 0x3 }

*The remap object attributes.*

#### Functions

- [vx\\_status VX\\_API\\_CALL vxCopyRemapPatch](#) ([vx\\_remap](#) remap, const [vx\\_rectangle\\_t](#) \*rect, [vx\\_size](#) user\_↔\_stride\_y, void \*user\_ptr, [vx\\_enum](#) user\_coordinate\_type, [vx\\_enum](#) usage, [vx\\_enum](#) user\_mem\_type)  
*Allows the application to copy a rectangular patch from/into a remap object.*
- [vx\\_remap VX\\_API\\_CALL vxCreateRemap](#) ([vx\\_context](#) context, [vx\\_uint32](#) src\_width, [vx\\_uint32](#) src\_height, [vx\\_uint32](#) dst\_width, [vx\\_uint32](#) dst\_height)  
*Creates a remap table object.*
- [vx\\_remap VX\\_API\\_CALL vxCreateVirtualRemap](#) ([vx\\_graph](#) graph, [vx\\_uint32](#) src\_width, [vx\\_uint32](#) src\_↔\_height, [vx\\_uint32](#) dst\_width, [vx\\_uint32](#) dst\_height)  
*Creates an opaque reference to a remap table object without direct user access.*
- [vx\\_status VX\\_API\\_CALL vxMapRemapPatch](#) ([vx\\_remap](#) remap, const [vx\\_rectangle\\_t](#) \*rect, [vx\\_map\\_↔\\_id](#) \*map\_id, [vx\\_size](#) \*stride\_y, void \*\*ptr, [vx\\_enum](#) coordinate\_type, [vx\\_enum](#) usage, [vx\\_enum](#) mem\_type)  
*Allows the application to get direct access to a rectangular patch of a remap object.*
- [vx\\_status VX\\_API\\_CALL vxQueryRemap](#) ([vx\\_remap](#) table, [vx\\_enum](#) attribute, void \*ptr, [vx\\_size](#) size)  
*Queries attributes from a Remap table.*
- [vx\\_status VX\\_API\\_CALL vxReleaseRemap](#) ([vx\\_remap](#) \*table)  
*Releases a reference to a remap table object. The object may not be garbage collected until its total reference count is zero.*
- [vx\\_status VX\\_API\\_CALL vxUnmapRemapPatch](#) ([vx\\_remap](#) remap, [vx\\_map\\_id](#) map\_id)  
*Unmap and commit potential changes to a remap object patch that was previously mapped.*

### 3.75.2 Enumeration Type Documentation

#### enum [vx\\_remap\\_attribute\\_e](#)

The remap object attributes.

Enumerator

**[VX\\_REMAP\\_SOURCE\\_WIDTH](#)** The source width. Read-only. Use a [vx\\_uint32](#) parameter.

**[VX\\_REMAP\\_SOURCE\\_HEIGHT](#)** The source height. Read-only. Use a [vx\\_uint32](#) parameter.

**[VX\\_REMAP\\_DESTINATION\\_WIDTH](#)** The destination width. Read-only. Use a [vx\\_uint32](#) parameter.

**[VX\\_REMAP\\_DESTINATION\\_HEIGHT](#)** The destination height. Read-only. Use a [vx\\_uint32](#) parameter.

Definition at line 1131 of file [vx\\_types.h](#).

### 3.75.3 Function Documentation

**vx\_remap VX\_API\_CALL vxCreateRemap ( vx\_context *context*, vx\_uint32 *src\_width*, vx\_uint32 *src\_height*, vx\_uint32 *dst\_width*, vx\_uint32 *dst\_height* )**

Creates a remap table object.

#### Parameters

|    |                   |                                            |
|----|-------------------|--------------------------------------------|
| in | <i>context</i>    | The reference to the overall context.      |
| in | <i>src_width</i>  | Width of the source image in pixel.        |
| in | <i>src_height</i> | Height of the source image in pixels.      |
| in | <i>dst_width</i>  | Width of the destination image in pixels.  |
| in | <i>dst_height</i> | Height of the destination image in pixels. |

#### Returns

A remap reference [vx\\_remap](#). Any possible errors preventing a successful creation should be checked using [vxGetStatus](#).

**vx\_remap VX\_API\_CALL vxCreateVirtualRemap ( vx\_graph *graph*, vx\_uint32 *src\_width*, vx\_uint32 *src\_height*, vx\_uint32 *dst\_width*, vx\_uint32 *dst\_height* )**

Creates an opaque reference to a remap table object without direct user access.

#### Parameters

|    |                   |                                            |
|----|-------------------|--------------------------------------------|
| in | <i>graph</i>      | The reference to the parent graph.         |
| in | <i>src_width</i>  | Width of the source image in pixel.        |
| in | <i>src_height</i> | Height of the source image in pixels.      |
| in | <i>dst_width</i>  | Width of the destination image in pixels.  |
| in | <i>dst_height</i> | Height of the destination image in pixels. |

#### See also

[vxCreateRemap](#)

#### Returns

A remap reference [vx\\_remap](#). Any possible errors preventing a successful creation should be checked using [vxGetStatus](#).

**vx\_status VX\_API\_CALL vxReleaseRemap ( vx\_remap \* *table* )**

Releases a reference to a remap table object. The object may not be garbage collected until its total reference count is zero.

#### Parameters

|    |              |                                            |
|----|--------------|--------------------------------------------|
| in | <i>table</i> | The pointer to the remap table to release. |
|----|--------------|--------------------------------------------|

#### Postcondition

After returning from this function the reference is zeroed.

## Returns

A `vx_status_e` enumeration.

## Return values

|                                         |                                                       |
|-----------------------------------------|-------------------------------------------------------|
| <code>VX_SUCCESS</code>                 | No errors; any other value indicates failure.         |
| <code>VX_ERROR_INVALID_REFERENCE</code> | table is not a valid <code>vx_remap</code> reference. |

**`vx_status VX_API_CALL vxMapRemapPatch ( vx_remap remap, const vx_rectangle_t * rect, vx_map_id * map_id, vx_size * stride_y, void ** ptr, vx_enum coordinate_type, vx_enum usage, vx_enum mem_type )`**

Allows the application to get direct access to a rectangular patch of a remap object.

The patch is specified within the destination dimensions and its data provide the corresponding coordinate within the source dimensions. The patch is mapped as a 2D array of elements of the type associated with the `coordinate_type` parameter (i.e., `vx_coordinates2df_t` for `VX_TYPE_COORDINATES2DF`). The memory layout of the mapped 2D array follows a row-major order where rows are compact (without any gap between elements), and where the potential padding after each lines is determined by (`* stride_y`).

## Parameters

|     |                        |                                                                                                                                                                                                                                                                                                                                                                                                                                             |
|-----|------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>remap</i>           | The reference to the remap object that contains the patch to map.                                                                                                                                                                                                                                                                                                                                                                           |
| in  | <i>rect</i>            | The coordinates of remap patch. The patch must be specified within the bounds of the remap destination dimensions ( <code>VX_REMAP_DESTINATION_WIDTH</code> x <code>VX_REMAP_DESTINATION_HEIGHT</code> ). ( <code>start_x</code> , <code>start_y</code> ) gives the coordinate of the topleft element inside the patch, while ( <code>end_x</code> , <code>end_y</code> ) gives the coordinate of the bottomright element out of the patch. |
| out | <i>map_id</i>          | The address of a <code>vx_map_id</code> variable where the function returns a map identifier. <ul style="list-style-type: none"> <li>(<code>*map_id</code>) must eventually be provided as the <code>map_id</code> parameter of a call to <code>vxUnmapRemapPatch</code>.</li> </ul>                                                                                                                                                        |
| out | <i>stride_y</i>        | The address of a <code>vx_size</code> variable where the function returns the difference between the address of the first element of two successive lines in the mapped remap patch. The stride value follows the following rule : ( <code>*stride_y</code> ) >= <code>sizeof(&lt;ELEMENT_TYPE&gt;) * (rect-&gt;end_x - rect-&gt;start_x)</code>                                                                                            |
| out | <i>ptr</i>             | The address of a pointer where the function returns where remap patch data can be accessed. ( <code>*ptr</code> ) is the address of the the top-left element of the remap patch. The returned ( <code>*ptr</code> ) address is only valid between the call to this function and the corresponding call to <code>vxUnmapRemapPatch</code> .                                                                                                  |
| in  | <i>coordinate_type</i> | This declares the type of the source coordinate data that the application wants to access in the remap patch. It must be <code>VX_TYPE_COORDINATES2DF</code> .                                                                                                                                                                                                                                                                              |

## Parameters

|    |                 |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
|----|-----------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>usage</i>    | <p>This declares the access mode for the remap patch, using the <code>vx_accessor_e</code> enumeration.</p> <ul style="list-style-type: none"> <li>• <code>VX_READ_ONLY</code>: after the function call, the content of the memory location pointed by (*ptr) contains the remap patch data. Writing into this memory location is forbidden and its behavior is undefined.</li> <li>• <code>VX_READ_AND_WRITE</code>: after the function call, the content of the memory location pointed by (*ptr) contains the remap patch data; writing into this memory is allowed for the location of elements only and will result in a modification of the written elements in the remap object once the patch is unmapped. Writing into a gap between element lines (when <math>(*stride\_y) &gt; \text{sizeof}(&lt;ELEMENT\_TYPE&gt;) * (\text{rect-&gt;end\_x} - \text{rect-&gt;start\_x})</math>) is forbidden and its behavior is undefined.</li> <li>• <code>VX_WRITE_ONLY</code>: after the function call, the memory location pointed by (*ptr) contains undefined data; writing each element of the patch is required prior to unmapping. Elements not written by the application before unmap will become undefined after unmap, even if they were well defined before map. Like for <code>VX_READ_AND_WRITE</code>, writing into a gap between element lines is forbidden and its behavior is undefined.</li> </ul> |
| in | <i>mem_type</i> | A <code>vx_memory_type_e</code> enumeration that specifies the type of the memory where the remap patch is requested to be mapped.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |

## Returns

A `vx_status_e` enumeration.

## Return values

|                                          |                                                       |
|------------------------------------------|-------------------------------------------------------|
| <code>VX_SUCCESS</code>                  | No errors; any other value indicates failure.         |
| <code>VX_ERROR_INVALID_REFERENCE</code>  | remap is not a valid <code>vx_remap</code> reference. |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | An other parameter is incorrect.                      |

## Postcondition

`vxUnmapRemapPatch` with same (\*map\_id) value.

**vx\_status VX\_API\_CALL vxUnmapRemapPatch ( vx\_remap remap, vx\_map\_id map\_id )**

Unmap and commit potential changes to a remap object patch that was previously mapped.

Unmapping a remap patch invalidates the memory location from which the patch could be accessed by the application. Accessing this memory location after the unmap function completes has an undefined behavior.

## Parameters

|     |               |                                                                               |
|-----|---------------|-------------------------------------------------------------------------------|
| in  | <i>remap</i>  | The reference to the remap object to unmap.                                   |
| out | <i>map_id</i> | The unique map identifier that was returned by <code>vxMapRemapPatch</code> . |

## Returns

A `vx_status_e` enumeration.

## Return values

|                                          |                                                       |
|------------------------------------------|-------------------------------------------------------|
| <code>VX_SUCCESS</code>                  | No errors; any other value indicates failure.         |
| <code>VX_ERROR_INVALID_REFERENCE</code>  | remap is not a valid <code>vx_remap</code> reference. |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | An other parameter is incorrect.                      |

## Precondition

`vxMapRemapPatch` with same `map_id` value

**`vx_status VX_API_CALL vxCopyRemapPatch ( vx_remap remap, const vx_rectangle_t * rect, vx_size user_stride_y, void * user_ptr, vx_enum user_coordinate_type, vx_enum usage, vx_enum user_mem_type )`**

Allows the application to copy a rectangular patch from/into a remap object.

The patch is specified within the destination dimensions and its data provide the corresponding coordinate within the source dimensions. The patch in user memory is a 2D array of elements of the type associated with the `coordinate_type` parameter (i.e., `vx_coordinates2df_t` for `VX_TYPE_COORDINATES2DF`). The memory layout of this array follows a row-major order where rows are compact (without any gap between elements), and where the potential padding after each line is determined by the `user_stride_y` parameter.

## Parameters

|    |                                   |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
|----|-----------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <code>remap</code>                | The reference to the remap object that is the source or the destination of the patch copy.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| in | <code>rect</code>                 | The coordinates of remap patch. The patch must be specified within the bounds of the remap destination dimensions ( <code>VX_REMAP_DESTINATION_WIDTH</code> x <code>VX_REMAP_DESTINATION_HEIGHT</code> ). ( <code>start_x</code> , <code>start_y</code> ) gives the coordinate of the topleft element inside the patch, while ( <code>end_x</code> , <code>end_y</code> ) gives the coordinate of the bottomright element out of the patch.                                                                                                                                |
| in | <code>user_stride_y</code>        | The difference between the address of the first element of two successive lines of the remap patch in user memory (pointed by <code>user_ptr</code> ). The layout of the user memory must follow a row major order and <code>user_stride_y</code> must follow the following rule : <code>user_stride_y &gt;= sizeof(&lt;ELEMENT_TYPE&gt;) * (rect-&gt;end_x - rect-&gt;start_x)</code> .                                                                                                                                                                                   |
| in | <code>user_ptr</code>             | The address of the user memory location where to store the requested remap data if the copy was requested in read mode, or from where to get the remap data to store into the remap object if the copy was requested in write mode. <code>user_ptr</code> is the address of the the top-left element of the remap patch. The accessible user memory must be large enough to contain the specified patch with the specified layout: accessible memory in bytes <code>&gt;= (rect-&gt;end_y - rect-&gt;start_y) * user_stride_y</code> .                                     |
| in | <code>user_coordinate_type</code> | This declares the type of the source coordinate remap data in the user memory. It must be <code>VX_TYPE_COORDINATES2DF</code> .                                                                                                                                                                                                                                                                                                                                                                                                                                            |
| in | <code>usage</code>                | This declares the effect of the copy with regard to the remap object using the <code>vx_accessor_e</code> enumeration. Only <code>VX_READ_ONLY</code> and <code>VX_WRITE_ONLY</code> are supported: <ul style="list-style-type: none"> <li><code>VX_READ_ONLY</code> means that data is copied from the remap object into the user memory pointer by <code>user_ptr</code>. The potential padding after each line in user memory will stay unchanged.</li> <li><code>VX_WRITE_ONLY</code> means that data is copied into the remap object from the user memory.</li> </ul> |
| in | <code>user_mem_type</code>        | A <code>vx_memory_type_e</code> enumeration that specifies the type of the memory pointer by <code>user_ptr</code> .                                                                                                                                                                                                                                                                                                                                                                                                                                                       |



## Returns

A `vx_status_e` enumeration.

## Return values

|                                          |                                                       |
|------------------------------------------|-------------------------------------------------------|
| <code>VX_SUCCESS</code>                  | No errors; any other value indicates failure.         |
| <code>VX_ERROR_INVALID_REFERENCE</code>  | remap is not a valid <code>vx_remap</code> reference. |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | An other parameter is incorrect.                      |

**`vx_status VX_API_CALL vxQueryRemap ( vx_remap table, vx_enum attribute, void * ptr, vx_size size )`**

Queries attributes from a Remap table.

## Parameters

|     |                  |                                                                              |
|-----|------------------|------------------------------------------------------------------------------|
| in  | <i>table</i>     | The remap to query.                                                          |
| in  | <i>attribute</i> | The attribute to query. Use a <code>vx_remap_attribute_e</code> enumeration. |
| out | <i>ptr</i>       | The location at which to store the resulting value.                          |
| in  | <i>size</i>      | The size in bytes of the container to which <i>ptr</i> points.               |

## Returns

A `vx_status_e` enumeration.

## Return values

|                                         |                                                       |
|-----------------------------------------|-------------------------------------------------------|
| <code>VX_SUCCESS</code>                 | No errors; any other value indicates failure.         |
| <code>VX_ERROR_INVALID_REFERENCE</code> | table is not a valid <code>vx_remap</code> reference. |

## 3.76 Object: Scalar

### 3.76.1 Detailed Description

Defines the Scalar Object interface.

#### Typedefs

- typedef struct \_vx\_scalar \* vx\_scalar  
*An opaque reference to a scalar.*

#### Enumerations

- enum vx\_scalar\_attribute\_e { VX\_SCALAR\_TYPE = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_TYPE\_SCALAR << 8)) + 0x0 }  
*The scalar attributes list.*
- enum vx\_scalar\_operation\_e {  
VX\_SCALAR\_OP\_AND = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_ENUM\_SCALAR\_OPERATION << 12)) + 0x0,  
VX\_SCALAR\_OP\_OR = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_ENUM\_SCALAR\_OPERATION << 12)) + 0x1,  
VX\_SCALAR\_OP\_XOR = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_ENUM\_SCALAR\_OPERATION << 12)) + 0x2,  
VX\_SCALAR\_OP\_NAND = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_ENUM\_SCALAR\_OPERATION << 12)) + 0x3,  
VX\_SCALAR\_OP\_EQUAL = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_ENUM\_SCALAR\_OPERATION << 12)) + 0x4,  
VX\_SCALAR\_OP\_NOTEQUAL = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_ENUM\_SCALAR\_OPERATION << 12)) + 0x5,  
VX\_SCALAR\_OP\_LESS = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_ENUM\_SCALAR\_OPERATION << 12)) + 0x6,  
VX\_SCALAR\_OP\_LESSEQ = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_ENUM\_SCALAR\_OPERATION << 12)) + 0x7,  
VX\_SCALAR\_OP\_GREATER = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_ENUM\_SCALAR\_OPERATION << 12)) + 0x8,  
VX\_SCALAR\_OP\_GREATEREQ = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_ENUM\_SCALAR\_OPERATION << 12)) + 0x9,  
VX\_SCALAR\_OP\_ADD = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_ENUM\_SCALAR\_OPERATION << 12)) + 0xA,  
VX\_SCALAR\_OP\_SUBTRACT = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_ENUM\_SCALAR\_OPERATION << 12)) + 0xB,  
VX\_SCALAR\_OP\_MULTIPLY = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_ENUM\_SCALAR\_OPERATION << 12)) + 0xC,  
VX\_SCALAR\_OP\_DIVIDE = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_ENUM\_SCALAR\_OPERATION << 12)) + 0xD,  
VX\_SCALAR\_OP\_MODULUS = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_ENUM\_SCALAR\_OPERATION << 12)) + 0xE,  
VX\_SCALAR\_OP\_MIN = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_ENUM\_SCALAR\_OPERATION << 12)) + 0xF,  
VX\_SCALAR\_OP\_MAX = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_ENUM\_SCALAR\_OPERATION << 12)) + 0x10 }  
*A type of operation in which both operands are scalars.*

#### Functions

- vx\_status VX\_API\_CALL vxCopyScalar (vx\_scalar scalar, void \*user\_ptr, vx\_enum usage, vx\_enum user\_mem\_type)  
*Allows the application to copy from/into a scalar object.*

- [vx\\_status VX\\_API\\_CALL vxCopyScalarWithSize](#) ([vx\\_scalar](#) scalar, [vx\\_size](#) size, void \*user\_ptr, [vx\\_enum](#) usage, [vx\\_enum](#) user\_mem\_type)  
*Allows the application to copy from/into a scalar object with size.*
- [vx\\_scalar VX\\_API\\_CALL vxCreateScalar](#) ([vx\\_context](#) context, [vx\\_enum](#) data\_type, const void \*ptr)  
*Creates a reference to a scalar object. Also see [Node Parameters](#).*
- [vx\\_scalar VX\\_API\\_CALL vxCreateScalarWithSize](#) ([vx\\_context](#) context, [vx\\_enum](#) data\_type, const void \*ptr, [vx\\_size](#) size)  
*Creates a reference to a scalar object. Also see [Node Parameters](#).*
- [vx\\_scalar VX\\_API\\_CALL vxCreateVirtualScalar](#) ([vx\\_graph](#) graph, [vx\\_enum](#) data\_type)  
*Creates an opaque reference to a scalar object with no direct user access.*
- [vx\\_status VX\\_API\\_CALL vxQueryScalar](#) ([vx\\_scalar](#) scalar, [vx\\_enum](#) attribute, void \*ptr, [vx\\_size](#) size)  
*Queries attributes from a scalar.*
- [vx\\_status VX\\_API\\_CALL vxReleaseScalar](#) ([vx\\_scalar](#) \*scalar)  
*Releases a reference to a scalar object. The object may not be garbage collected until its total reference count is zero.*

### 3.76.2 Typedef Documentation

**typedef struct \_vx\_scalar\* vx\_scalar**

An opaque reference to a scalar.

A scalar can be up to 64 bits wide.

See also

[vxCreateScalar](#)

Definition at line 172 of file [vx\\_types.h](#).

### 3.76.3 Enumeration Type Documentation

**enum vx\_scalar\_attribute\_e**

The scalar attributes list.

Enumerator

**VX\_SCALAR\_TYPE** Queries the type of atomic that is contained in the scalar. Read-only. Use a [vx\\_enum](#) parameter.

Definition at line 971 of file [vx\\_types.h](#).

**enum vx\_scalar\_operation\_e**

A type of operation in which both operands are scalars.

See also

[Object: Scalar](#)

Enumerator

**VX\_SCALAR\_OP\_AND** logical and.

**VX\_SCALAR\_OP\_OR** logical or.

**VX\_SCALAR\_OP\_XOR** logical exclusive or.

**VX\_SCALAR\_OP\_NAND** logical nand.

**VX\_SCALAR\_OP\_EQUAL** comparison (equal).

**VX\_SCALAR\_OP\_NOTEQUAL** comparison (not equal).

**VX\_SCALAR\_OP\_LESS** comparison (less than).

**VX\_SCALAR\_OP\_LESSEQ** comparison (less than or equal to).

**VX\_SCALAR\_OP\_GREATER** comparison (greater than).

**VX\_SCALAR\_OP\_GREATEREQ** comparison (greater than or equal to).

**VX\_SCALAR\_OP\_ADD** arithmetic addition.

**VX\_SCALAR\_OP\_SUBTRACT** arithmetic subtraction.

**VX\_SCALAR\_OP\_MULTIPLY** arithmetic multiplication.

**VX\_SCALAR\_OP\_DIVIDE** arithmetic division.

**VX\_SCALAR\_OP\_MODULUS** arithmetic (modulo operator).

**VX\_SCALAR\_OP\_MIN** minimum of two scalars.

**VX\_SCALAR\_OP\_MAX** maximum of two scalars.

Definition at line 980 of file [vx\\_types.h](#).

### 3.76.4 Function Documentation

**vx\_scalar VX\_API\_CALL vxCreateScalar ( vx\_context context, vx\_enum data\_type, const void \* ptr )**

Creates a reference to a scalar object. Also see [Node Parameters](#).

#### Parameters

|    |                  |                                                                                                                                                                                                                                                |
|----|------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>context</i>   | The reference to the system context.                                                                                                                                                                                                           |
| in | <i>data_type</i> | The type of data to hold. Must be greater than <a href="#">VX_TYPE_INVALID</a> and less than or equal to <a href="#">VX_TYPE_VENDOR_STRUCT_END</a> . Or must be a <a href="#">vx_enum</a> returned from <a href="#">vxRegisterUserStruct</a> . |
| in | <i>ptr</i>       | The pointer to the initial value of the scalar.                                                                                                                                                                                                |

#### Returns

A scalar reference [vx\\_scalar](#). Any possible errors preventing a successful creation should be checked using [vxGetStatus](#).

**vx\_scalar VX\_API\_CALL vxCreateScalarWithSize ( vx\_context context, vx\_enum data\_type, const void \* ptr, vx\_size size )**

Creates a reference to a scalar object. Also see [Node Parameters](#).

#### Parameters

|    |                  |                                                                                                                                                                                                                                                |
|----|------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>context</i>   | The reference to the system context.                                                                                                                                                                                                           |
| in | <i>data_type</i> | The type of data to hold. Must be greater than <a href="#">VX_TYPE_INVALID</a> and less than or equal to <a href="#">VX_TYPE_VENDOR_STRUCT_END</a> . Or must be a <a href="#">vx_enum</a> returned from <a href="#">vxRegisterUserStruct</a> . |
| in | <i>ptr</i>       | The pointer to the initial value of the scalar.                                                                                                                                                                                                |
| in | <i>size</i>      | Size of data at ptr in bytes.                                                                                                                                                                                                                  |

#### Returns

A scalar reference [vx\\_scalar](#). Any possible errors preventing a successful creation should be checked using [vxGetStatus](#).

**vx\_scalar VX\_API\_CALL vxCreateVirtualScalar ( vx\_graph graph, vx\_enum data\_type )**

Creates an opaque reference to a scalar object with no direct user access.

**Parameters**

|    |                  |                                                                                                                                                                                                                                    |
|----|------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>graph</i>     | The reference to the parent graph.                                                                                                                                                                                                 |
| in | <i>data_type</i> | The type of data to hold. Must be greater than <code>VX_TYPE_INVALID</code> and less than or equal to <code>VX_TYPE_VENDOR_STRUCT_END</code> . Or must be a <code>vx_enum</code> returned from <code>vxRegisterUserStruct</code> . |

**See also**

`vxCreateScalar`

**Returns**

A scalar reference `vx_scalar`. Any possible errors preventing a successful creation should be checked using `vxGetStatus`.

**vx\_status VX\_API\_CALL vxReleaseScalar ( vx\_scalar \* *scalar* )**

Releases a reference to a scalar object. The object may not be garbage collected until its total reference count is zero.

**Parameters**

|    |               |                                       |
|----|---------------|---------------------------------------|
| in | <i>scalar</i> | The pointer to the scalar to release. |
|----|---------------|---------------------------------------|

**Postcondition**

After returning from this function the reference is zeroed.

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                                         |                                                         |
|-----------------------------------------|---------------------------------------------------------|
| <code>VX_SUCCESS</code>                 | No errors; any other value indicates failure.           |
| <code>VX_ERROR_INVALID_REFERENCE</code> | scalar is not a valid <code>vx_scalar</code> reference. |

**vx\_status VX\_API\_CALL vxQueryScalar ( vx\_scalar *scalar*, vx\_enum *attribute*, void \* *ptr*, vx\_size *size* )**

Queries attributes from a scalar.

**Parameters**

|     |                  |                                                                                 |
|-----|------------------|---------------------------------------------------------------------------------|
| in  | <i>scalar</i>    | The scalar object.                                                              |
| in  | <i>attribute</i> | The enumeration to query. Use a <code>vx_scalar_attribute_e</code> enumeration. |
| out | <i>ptr</i>       | The location at which to store the resulting value.                             |
| in  | <i>size</i>      | The size of the container to which <i>ptr</i> points.                           |

**Returns**

A `vx_status_e` enumeration.

## Return values

|                                   |                                                   |
|-----------------------------------|---------------------------------------------------|
| <i>VX_SUCCESS</i>                 | No errors; any other value indicates failure.     |
| <i>VX_ERROR_INVALID_REFERENCE</i> | scalar is not a valid <i>vx_scalar</i> reference. |

**vx\_status VX\_API\_CALL vxCopyScalar ( vx\_scalar scalar, void \* user\_ptr, vx\_enum usage, vx\_enum user\_mem\_type )**

Allows the application to copy from/into a scalar object.

## Parameters

|    |                      |                                                                                                                                                                                                                                                                                                                                                                                                                                            |
|----|----------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>scalar</i>        | The reference to the scalar object that is the source or the destination of the copy.                                                                                                                                                                                                                                                                                                                                                      |
| in | <i>user_ptr</i>      | The address of the memory location where to store the requested data if the copy was requested in read mode, or from where to get the data to store into the scalar object if the copy was requested in write mode. In the user memory, the scalar is a variable of the type corresponding to <i>VX_SCALAR_TYPE</i> . The accessible memory must be large enough to contain this variable.                                                 |
| in | <i>usage</i>         | This declares the effect of the copy with regard to the scalar object using the <i>vx_accessor_e</i> enumeration. Only <i>VX_READ_ONLY</i> and <i>VX_WRITE_ONLY</i> are supported: <ul style="list-style-type: none"> <li>• <i>VX_READ_ONLY</i> means that data are copied from the scalar object into the user memory.</li> <li>• <i>VX_WRITE_ONLY</i> means that data are copied into the scalar object from the user memory.</li> </ul> |
| in | <i>user_mem_type</i> | A <i>vx_memory_type_e</i> enumeration that specifies the memory type of the memory referenced by the <i>user_ptr</i> .                                                                                                                                                                                                                                                                                                                     |

## Returns

A *vx\_status\_e* enumeration.

## Return values

|                                    |                                                   |
|------------------------------------|---------------------------------------------------|
| <i>VX_SUCCESS</i>                  | No errors; any other value indicates failure.     |
| <i>VX_ERROR_INVALID_REFERENCE</i>  | scalar is not a valid <i>vx_scalar</i> reference. |
| <i>VX_ERROR_INVALID_PARAMETERS</i> | An other parameter is incorrect.                  |

**vx\_status VX\_API\_CALL vxCopyScalarWithSize ( vx\_scalar scalar, vx\_size size, void \* user\_ptr, vx\_enum usage, vx\_enum user\_mem\_type )**

Allows the application to copy from/into a scalar object with size.

## Parameters

|    |                 |                                                                                                                                                                                                                                                                                                                                                                                            |
|----|-----------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>scalar</i>   | The reference to the scalar object that is the source or the destination of the copy.                                                                                                                                                                                                                                                                                                      |
| in | <i>size</i>     | The size in bytes of the container to which <i>user_ptr</i> points.                                                                                                                                                                                                                                                                                                                        |
| in | <i>user_ptr</i> | The address of the memory location where to store the requested data if the copy was requested in read mode, or from where to get the data to store into the scalar object if the copy was requested in write mode. In the user memory, the scalar is a variable of the type corresponding to <i>VX_SCALAR_TYPE</i> . The accessible memory must be large enough to contain this variable. |

**Parameters**

|    |                      |                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
|----|----------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>usage</i>         | <p>This declares the effect of the copy with regard to the scalar object using the <code>vx_accessor_e</code> enumeration. Only <code>VX_READ_ONLY</code> and <code>VX_WRITE_ONLY</code> are supported:</p> <ul style="list-style-type: none"><li>• <code>VX_READ_ONLY</code> means that data are copied from the scalar object into the user memory.</li><li>• <code>VX_WRITE_ONLY</code> means that data are copied into the scalar object from the user memory.</li></ul> |
| in | <i>user_mem_type</i> | <p>A <code>vx_memory_type_e</code> enumeration that specifies the memory type of the memory referenced by the <code>user_addr</code>.</p>                                                                                                                                                                                                                                                                                                                                    |

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                                          |                                                          |
|------------------------------------------|----------------------------------------------------------|
| <code>VX_ERROR_INVALID_REFERENCE</code>  | The scalar reference is not actually a scalar reference. |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | An other parameter is incorrect.                         |

## 3.77 Object: Threshold

### 3.77.1 Detailed Description

Defines the Threshold Object Interface.

#### Typedefs

- typedef struct \_vx\_threshold \* [vx\\_threshold](#)

*The Threshold Object. A thresholding object contains the types and limit values of the thresholding required.*

#### Enumerations

- enum [vx\\_threshold\\_attribute\\_e](#) {  
[VX\\_THRESHOLD\\_TYPE](#) = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_TYPE\_THRESHOLD << 8)) + 0x0,  
[VX\\_THRESHOLD\\_INPUT\\_FORMAT](#) = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_TYPE\_THRESHOLD << 8))  
+ 0x7,  
[VX\\_THRESHOLD\\_OUTPUT\\_FORMAT](#) = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_TYPE\_THRESHOLD << 8)) + 0x8 }

*The threshold attributes.*

- enum [vx\\_threshold\\_type\\_e](#) {  
[VX\\_THRESHOLD\\_TYPE\\_BINARY](#) = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_ENUM\_THRESHOLD\_TYPE << 12)) + 0x0,  
[VX\\_THRESHOLD\\_TYPE\\_RANGE](#) = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_ENUM\_THRESHOLD\_TYPE << 12)) + 0x1 }

*The Threshold types.*

#### Functions

- [vx\\_status VX\\_API\\_CALL vxCopyThresholdOutput](#) ([vx\\_threshold](#) thresh, [vx\\_pixel\\_value\\_t](#) \*true\_value\_ptr, [vx\\_pixel\\_value\\_t](#) \*false\_value\_ptr, [vx\\_enum](#) usage, [vx\\_enum](#) user\_mem\_type)  
*Allows the application to copy the true and false output values from/into a threshold object.*
- [vx\\_status VX\\_API\\_CALL vxCopyThresholdRange](#) ([vx\\_threshold](#) thresh, [vx\\_pixel\\_value\\_t](#) \*lower\_value\_ptr, [vx\\_pixel\\_value\\_t](#) \*upper\_value\_ptr, [vx\\_enum](#) usage, [vx\\_enum](#) user\_mem\_type)  
*Allows the application to copy thresholding values from/into a threshold object with type [VX\\_THRESHOLD\\_TYPE\\_RANGE](#).*
- [vx\\_status VX\\_API\\_CALL vxCopyThresholdValue](#) ([vx\\_threshold](#) thresh, [vx\\_pixel\\_value\\_t](#) \*value\_ptr, [vx\\_enum](#) usage, [vx\\_enum](#) user\_mem\_type)  
*Allows the application to copy the thresholding value from/into a threshold object with type [VX\\_THRESHOLD\\_TYPE\\_BINARY](#).*
- [vx\\_threshold VX\\_API\\_CALL vxCreateThresholdForImage](#) ([vx\\_context](#) context, [vx\\_enum](#) thresh\_type, [vx\\_df\\_image](#) input\_format, [vx\\_df\\_image](#) output\_format)  
*Creates a threshold object and returns a reference to it.*
- [vx\\_threshold VX\\_API\\_CALL vxCreateVirtualThresholdForImage](#) ([vx\\_graph](#) graph, [vx\\_enum](#) thresh\_type, [vx\\_df\\_image](#) input\_format, [vx\\_df\\_image](#) output\_format)  
*Creates an opaque reference to a threshold object without direct user access.*
- [vx\\_status VX\\_API\\_CALL vxQueryThreshold](#) ([vx\\_threshold](#) thresh, [vx\\_enum](#) attribute, void \*ptr, [vx\\_size](#) size)  
*Queries an attribute on the threshold object.*
- [vx\\_status VX\\_API\\_CALL vxReleaseThreshold](#) ([vx\\_threshold](#) \*thresh)  
*Releases a reference to a threshold object. The object may not be garbage collected until its total reference count is zero.*
- [vx\\_status VX\\_API\\_CALL vxSetThresholdAttribute](#) ([vx\\_threshold](#) thresh, [vx\\_enum](#) attribute, const void \*ptr, [vx\\_size](#) size)  
*Sets attributes on the threshold object.*



### 3.77.2 Enumeration Type Documentation

#### enum vx\_threshold\_type\_e

The Threshold types.

Enumerator

**VX\_THRESHOLD\_TYPE\_BINARY** A threshold with only 1 value.

**VX\_THRESHOLD\_TYPE\_RANGE** A threshold with 2 values (upper/lower). Use with Canny Edge Detection.

Definition at line 1053 of file [vx\\_types.h](#).

#### enum vx\_threshold\_attribute\_e

The threshold attributes.

Enumerator

**VX\_THRESHOLD\_TYPE** The value type of the threshold. Read-only. Use a [vx\\_enum](#) parameter. Will contain a [vx\\_threshold\\_type\\_e](#).

**VX\_THRESHOLD\_INPUT\_FORMAT** The input image format the threshold was created for. Read-only. Use a [vx\\_enum](#) parameter. Will contain a [vx\\_df\\_image\\_e](#).

**VX\_THRESHOLD\_OUTPUT\_FORMAT** The output image format the threshold was created for. Read-only. Use a [vx\\_enum](#) parameter. Will contain a [vx\\_df\\_image\\_e](#).

Definition at line 1063 of file [vx\\_types.h](#).

### 3.77.3 Function Documentation

**vx\_threshold VX\_API\_CALL vxCreateThresholdForImage ( vx\_context context, vx\_enum thresh\_type, vx\_df\_image input\_format, vx\_df\_image output\_format )**

Creates a threshold object and returns a reference to it.

The threshold object defines the parameters of a thresholding operation to an input image, that generates an output image that can have a different format. The thresholding 'false' or 'true' output values are specified per pixel channels of the output format and can be modified with [vxCopyThresholdOutput](#). The default 'false' output value of pixels channels should be 0, and the default 'true' value should be non-zero. For standard image formats, default output pixel values are defined as following:

- [VX\\_DF\\_IMAGE\\_RGB](#) : false={0, 0, 0}, true={255,255,255}
- [VX\\_DF\\_IMAGE\\_RGBX](#) : false={0, 0, 0, 0}, true={255,255,255,255}
- [VX\\_DF\\_IMAGE\\_NV12](#) : false={0, 0, 0}, true={255,255,255}
- [VX\\_DF\\_IMAGE\\_NV21](#) : false={0, 0, 0}, true={255,255,255}
- [VX\\_DF\\_IMAGE\\_UYVY](#) : false={0, 0, 0}, true={255,255,255}
- [VX\\_DF\\_IMAGE\\_YUYV](#) : false={0, 0, 0}, true={255,255,255}
- [VX\\_DF\\_IMAGE\\_IYUV](#) : false={0, 0, 0}, true={255,255,255}
- [VX\\_DF\\_IMAGE\\_YUV4](#) : false={0, 0, 0}, true={255,255,255}
- [VX\\_DF\\_IMAGE\\_U8](#) : false=0, true=0xFF
- [VX\\_DF\\_IMAGE\\_S16](#) : false=0, true=-1
- [VX\\_DF\\_IMAGE\\_U16](#) : false=0, true=0xFFFF
- [VX\\_DF\\_IMAGE\\_S32](#) : false=0, true=-1
- [VX\\_DF\\_IMAGE\\_U32](#) : false=0, true=0xFFFFFFFF

**Parameters**

|    |                      |                                                                                |
|----|----------------------|--------------------------------------------------------------------------------|
| in | <i>context</i>       | The reference to the context in which the object is created.                   |
| in | <i>thresh_type</i>   | The type of thresholding operation.                                            |
| in | <i>input_format</i>  | The format of images that will be used as input of the thresholding operation. |
| in | <i>output_format</i> | The format of images that will be generated by the thresholding operation.     |

**Returns**

A threshold reference [vx\\_threshold](#). Any possible errors preventing a successful creation should be checked using [vxGetStatus](#).

**vx\_status VX\_API\_CALL vxCreateVirtualThresholdForImage ( vx\_graph *graph*, vx\_enum *thresh\_type*, vx\_df\_image *input\_format*, vx\_df\_image *output\_format* )**

Creates an opaque reference to a threshold object without direct user access.

**Parameters**

|    |                      |                                                                                |
|----|----------------------|--------------------------------------------------------------------------------|
| in | <i>graph</i>         | The reference to the parent graph.                                             |
| in | <i>thresh_type</i>   | The type of thresholding operation.                                            |
| in | <i>input_format</i>  | The format of images that will be used as input of the thresholding operation. |
| in | <i>output_format</i> | The format of images that will be generated by the thresholding operation.     |

**See also**

[vxCreateThresholdForImage](#)

**Returns**

A threshold reference [vx\\_threshold](#). Any possible errors preventing a successful creation should be checked using [vxGetStatus](#).

**vx\_status VX\_API\_CALL vxCopyThresholdValue ( vx\_threshold *thresh*, vx\_pixel\_value\_t \* *value\_ptr*, vx\_enum *usage*, vx\_enum *user\_mem\_type* )**

Allows the application to copy the thresholding value from/into a threshold object with type [VX\\_THRESHOLD\\_TYPE\\_BINARY](#).

**Parameters**

|         |                  |                                                                                                                                                                                                                                          |
|---------|------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in      | <i>thresh</i>    | The reference to the threshold object that is the source or the destination of the copy.                                                                                                                                                 |
| in, out | <i>value_ptr</i> | The address of the memory location where to store the thresholding value if the copy was requested in read mode, or from where to get the thresholding value to store into the threshold object if the copy was requested in write mode. |

## Parameters

|    |                      |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
|----|----------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>usage</i>         | This declares the effect of the copy with regard to the threshold object using the <code>vx_accessor_e</code> enumeration. Only <code>VX_READ_ONLY</code> and <code>VX_WRITE_ONLY</code> are supported: <ul style="list-style-type: none"> <li><code>VX_READ_ONLY</code> means that the thresholding value is copied from the threshold object into the user memory. After the copy, only the field of the (<i>*value_ptr</i>) union that corresponds to the input image format of the threshold object is meaningful.</li> <li><code>VX_WRITE_ONLY</code> means the field of the (<i>*value_ptr</i>) union corresponding to the input format of the threshold object is copied into the threshold object.</li> </ul> |
| in | <i>user_mem_type</i> | A <code>vx_memory_type_e</code> enumeration that specifies the type of the memory referenced by <i>value_ptr</i> .                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |

## Returns

A `vx_status_e` enumeration.

## Return values

|                                          |                                                                              |
|------------------------------------------|------------------------------------------------------------------------------|
| <code>VX_ERROR_INVALID_REFERENCE</code>  | The threshold reference is not actually a threshold reference.               |
| <code>VX_ERROR_NOT_COMPATIBLE</code>     | The threshold object doesn't have type <code>VX_THRESHOLD_TYPE_BINARY</code> |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | An other parameter is incorrect.                                             |

**vx\_status VX\_API\_CALL vxCopyThresholdRange ( vx\_threshold *thresh*, vx\_pixel\_value\_t \* *lower\_value\_ptr*, vx\_pixel\_value\_t \* *upper\_value\_ptr*, vx\_enum *usage*, vx\_enum *user\_mem\_type* )**

Allows the application to copy thresholding values from/into a threshold object with type `VX_THRESHOLD_TYPE_RANGE`.

## Parameters

|         |                        |                                                                                                                                                                                                                                                      |
|---------|------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in      | <i>thresh</i>          | The reference to the threshold object that is the source or the destination of the copy.                                                                                                                                                             |
| in, out | <i>lower_value_ptr</i> | The address of the memory location where to store the lower thresholding value if the copy was requested in read mode, or from where to get the lower thresholding value to store into the threshold object if the copy was requested in write mode. |
| in, out | <i>upper_value_ptr</i> | The address of the memory location where to store the upper thresholding value if the copy was requested in read mode, or from where to get the upper thresholding value to store into the threshold object if the copy was requested in write mode. |

## Parameters

|    |                      |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
|----|----------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>usage</i>         | This declares the effect of the copy with regard to the threshold object using the <code>vx_accessor_e</code> enumeration. Only <code>VX_READ_ONLY</code> and <code>VX_WRITE_ONLY</code> are supported: <ul style="list-style-type: none"> <li><code>VX_READ_ONLY</code> means that thresholding values are copied from the threshold object into the user memory. After the copy, only the field of (<code>*lower_value_ptr</code>) and (<code>*upper_value_ptr</code>) unions that corresponds to the input image format of the threshold object is meaningful.</li> <li><code>VX_WRITE_ONLY</code> means the field of the (<code>*lower_value_ptr</code>) and (<code>*upper_value_ptr</code>) unions corresponding to the input format of the threshold object is copied into the threshold object.</li> </ul> |
| in | <i>user_mem_type</i> | A <code>vx_memory_type_e</code> enumeration that specifies the type of the memory referenced by <code>lower_value_ptr</code> and <code>upper_value_ptr</code> .                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |

## Returns

A `vx_status_e` enumeration.

## Return values

|                                          |                                                                             |
|------------------------------------------|-----------------------------------------------------------------------------|
| <code>VX_ERROR_INVALID_REFERENCE</code>  | The threshold reference is not actually a threshold reference.              |
| <code>VX_ERROR_NOT_COMPATIBLE</code>     | The threshold object doesn't have type <code>VX_THRESHOLD_TYPE_RANGE</code> |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | An other parameter is incorrect.                                            |

**`vx_status VX_API_CALL vxCopyThresholdOutput ( vx_threshold thresh, vx_pixel_value_t * true_value_ptr, vx_pixel_value_t * false_value_ptr, vx_enum usage, vx_enum user_mem_type )`**

Allows the application to copy the true and false output values from/into a threshold object.

## Parameters

|         |                        |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
|---------|------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in      | <i>thresh</i>          | The reference to the threshold object that is the source or the destination of the copy.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
| in, out | <i>true_value_ptr</i>  | The address of the memory location where to store the true output value if the copy was requested in read mode, or from where to get the true output value to store into the threshold object if the copy was requested in write mode.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| in, out | <i>false_value_ptr</i> | The address of the memory location where to store the false output value if the copy was requested in read mode, or from where to get the false output value to store into the threshold object if the copy was requested in write mode.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
| in      | <i>usage</i>           | This declares the effect of the copy with regard to the threshold object using the <code>vx_accessor_e</code> enumeration. Only <code>VX_READ_ONLY</code> and <code>VX_WRITE_ONLY</code> are supported: <ul style="list-style-type: none"> <li><code>VX_READ_ONLY</code> means that true and false output values are copied from the threshold object into the user memory. After the copy, only the field of (<code>*true_value_ptr</code>) and (<code>*false_value_ptr</code>) unions that corresponds to the output image format of the threshold object is meaningful.</li> <li><code>VX_WRITE_ONLY</code> means the field of the (<code>*true_value_ptr</code>) and (<code>*false_value_ptr</code>) unions corresponding to the output format of the threshold object is copied into the threshold object.</li> </ul> |

**Parameters**

|    |                      |                                                                                                                                                       |
|----|----------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>user_mem_type</i> | A <a href="#">vx_memory_type_e</a> enumeration that specifies the type of the memory referenced by <i>true_value_ptr</i> and <i>false_value_ptr</i> . |
|----|----------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------|

**Returns**

A [vx\\_status\\_e](#) enumeration.

**Return values**

|                                    |                                                                |
|------------------------------------|----------------------------------------------------------------|
| <i>VX_ERROR_INVALID_REFERENCE</i>  | The threshold reference is not actually a threshold reference. |
| <i>VX_ERROR_INVALID_PARAMETERS</i> | An other parameter is incorrect.                               |

**vx\_status VX\_API\_CALL vxReleaseThreshold ( vx\_threshold \* *thresh* )**

Releases a reference to a threshold object. The object may not be garbage collected until its total reference count is zero.

**Parameters**

|    |               |                                          |
|----|---------------|------------------------------------------|
| in | <i>thresh</i> | The pointer to the threshold to release. |
|----|---------------|------------------------------------------|

**Postcondition**

After returning from this function the reference is zeroed.

**Returns**

A [vx\\_status\\_e](#) enumeration.

**Return values**

|                                   |                                                                      |
|-----------------------------------|----------------------------------------------------------------------|
| <i>VX_SUCCESS</i>                 | No errors; any other value indicates failure.                        |
| <i>VX_ERROR_INVALID_REFERENCE</i> | <i>thresh</i> is not a valid <a href="#">vx_threshold</a> reference. |

**vx\_status VX\_API\_CALL vxSetThresholdAttribute ( vx\_threshold *thresh*, vx\_enum *attribute*, const void \* *ptr*, vx\_size *size* )**

Sets attributes on the threshold object.

**Parameters**

|    |                  |                                                                                      |
|----|------------------|--------------------------------------------------------------------------------------|
| in | <i>thresh</i>    | The threshold object to set.                                                         |
| in | <i>attribute</i> | The attribute to modify. Use a <a href="#">vx_threshold_attribute_e</a> enumeration. |
| in | <i>ptr</i>       | The pointer to the value to which to set the attribute.                              |
| in | <i>size</i>      | The size of the data pointed to by <i>ptr</i> .                                      |

**Returns**

A [vx\\_status\\_e](#) enumeration.

## Return values

|                                         |                                                            |
|-----------------------------------------|------------------------------------------------------------|
| <code>VX_SUCCESS</code>                 | No errors; any other value indicates failure.              |
| <code>VX_ERROR_INVALID_REFERENCE</code> | thresh is not a valid <code>vx_threshold</code> reference. |

**vx\_status VX\_API\_CALL vxQueryThreshold ( vx\_threshold *thresh*, vx\_enum *attribute*, void \* *ptr*, vx\_size *size* )**

Queries an attribute on the threshold object.

## Parameters

|     |                  |                                                                                  |
|-----|------------------|----------------------------------------------------------------------------------|
| in  | <i>thresh</i>    | The threshold object to set.                                                     |
| in  | <i>attribute</i> | The attribute to query. Use a <code>vx_threshold_attribute_e</code> enumeration. |
| out | <i>ptr</i>       | The location at which to store the resulting value.                              |
| in  | <i>size</i>      | The size of the container to which <i>ptr</i> points.                            |

## Returns

A `vx_status_e` enumeration.

## Return values

|                                         |                                                            |
|-----------------------------------------|------------------------------------------------------------|
| <code>VX_SUCCESS</code>                 | No errors; any other value indicates failure.              |
| <code>VX_ERROR_INVALID_REFERENCE</code> | thresh is not a valid <code>vx_threshold</code> reference. |

## 3.78 Object: ObjectArray

### 3.78.1 Detailed Description

An opaque array object that could be an array of any data-object (not data-type) of OpenVX except Delay and ObjectArray objects.

ObjectArray is a strongly-typed container of OpenVX data-objects. ObjectArray refers to the collection of similar data-objects as a single entity that can be created or assigned as inputs/outputs and as a single entity. In addition, a single object from the collection can be accessed individually by getting its reference. The single object remains as part of the ObjectArray through its entire life cycle.

### Typedefs

- typedef struct \_vx\_object\_array \* [vx\\_object\\_array](#)

*The ObjectArray Object. ObjectArray is a strongly-typed container of OpenVX data-objects.*

### Enumerations

- enum [vx\\_object\\_array\\_attribute\\_e](#) {  
[VX\\_OBJECT\\_ARRAY\\_ITEMTYPE](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_TYPE\\_OBJECT\\_ARRAY](#) << 8)) + 0x0,  
[VX\\_OBJECT\\_ARRAY\\_NUMITEMS](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_TYPE\\_OBJECT\\_ARRAY](#) << 8)) + 0x1 }

*The ObjectArray object attributes.*

### Functions

- [vx\\_object\\_array](#) [VX\\_API\\_CALL](#) [vxCreateObjectArray](#) ([vx\\_context](#) context, [vx\\_reference](#) exemplar, [vx\\_size](#) count)  
*Creates a reference to an ObjectArray of count objects.*
- [vx\\_object\\_array](#) [VX\\_API\\_CALL](#) [vxCreateVirtualObjectArray](#) ([vx\\_graph](#) graph, [vx\\_reference](#) exemplar, [vx\\_size](#) count)  
*Creates an opaque reference to a virtual ObjectArray with no direct user access.*
- [vx\\_reference](#) [VX\\_API\\_CALL](#) [vxGetObjectArrayItem](#) ([vx\\_object\\_array](#) arr, [vx\\_uint32](#) index)  
*Retrieves the reference to the OpenVX Object in location index of the ObjectArray.*
- [vx\\_status](#) [VX\\_API\\_CALL](#) [vxQueryObjectArray](#) ([vx\\_object\\_array](#) arr, [vx\\_enum](#) attribute, void \*ptr, [vx\\_size](#) size)  
*Queries an attribute from the ObjectArray.*
- [vx\\_status](#) [VX\\_API\\_CALL](#) [vxReleaseObjectArray](#) ([vx\\_object\\_array](#) \*arr)  
*Releases a reference of an ObjectArray object.*

### 3.78.2 Enumeration Type Documentation

#### enum [vx\\_object\\_array\\_attribute\\_e](#)

The ObjectArray object attributes.

Enumerator

**[VX\\_OBJECT\\_ARRAY\\_ITEMTYPE](#)** The type of the ObjectArray items. Read-only. Use a [vx\\_enum](#) parameter.

**[VX\\_OBJECT\\_ARRAY\\_NUMITEMS](#)** The number of items in the ObjectArray. Read-only. Use a [vx\\_size](#) parameter.

Definition at line 1159 of file [vx\\_types.h](#).

### 3.78.3 Function Documentation

**vx\_object\_array VX\_API\_CALL vxCreateObjectArray ( vx\_context *context*, vx\_reference *exemplar*, vx\_size *count* )**

Creates a reference to an ObjectArray of count objects.

It uses the metadata of the exemplar to determine the object attributes, ignoring the object data. It does not alter the exemplar or keep or release the reference to the exemplar. For the definition of supported attributes see [vxSetMetaFormatAttribute](#). In case the exemplar is a virtual object it must be of immutable metadata, thus it is not allowed to be dimensionless or formatless.

#### Parameters

|    |                 |                                                                                          |
|----|-----------------|------------------------------------------------------------------------------------------|
| in | <i>context</i>  | The reference to the overall Context.                                                    |
| in | <i>exemplar</i> | The exemplar object that defines the metadata of the created objects in the ObjectArray. |
| in | <i>count</i>    | Number of Objects to create in the ObjectArray. This value must be greater than zero.    |

#### Returns

An ObjectArray reference [vx\\_object\\_array](#). Any possible errors preventing a successful creation should be checked using [vxGetStatus](#). Data objects are not initialized by this function.

**vx\_object\_array VX\_API\_CALL vxCreateVirtualObjectArray ( vx\_graph *graph*, vx\_reference *exemplar*, vx\_size *count* )**

Creates an opaque reference to a virtual ObjectArray with no direct user access.

This function creates an ObjectArray of count objects with similar behavior as [vxCreateObjectArray](#). The only difference is that the objects that are created are virtual in the given graph.

#### Parameters

|    |                 |                                                                                                                                                                                               |
|----|-----------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>graph</i>    | Reference to the graph where to create the virtual ObjectArray.                                                                                                                               |
| in | <i>exemplar</i> | The exemplar object that defines the type of object in the ObjectArray. Only exemplar type of <a href="#">vx_image</a> , <a href="#">vx_array</a> and <a href="#">vx_pyramid</a> are allowed. |
| in | <i>count</i>    | Number of Objects to create in the ObjectArray.                                                                                                                                               |

#### Returns

A ObjectArray reference [vx\\_object\\_array](#). Any possible errors preventing a successful creation should be checked using [vxGetStatus](#).

**vx\_reference VX\_API\_CALL vxGetObjectArrayItem ( vx\_object\_array *arr*, vx\_uint32 *index* )**

Retrieves the reference to the OpenVX Object in location index of the ObjectArray.

This is a vx\_reference, which can be used elsewhere in OpenVX. A call to vxRelease<Object> or [vx↔ReleaseReference](#) is necessary to release the Object for each call to this function.

#### Parameters

|    |              |                                             |
|----|--------------|---------------------------------------------|
| in | <i>arr</i>   | The ObjectArray.                            |
| in | <i>index</i> | The index of the object in the ObjectArray. |

#### Returns

A reference to an OpenVX data object. Any possible errors preventing a successful completion of the function should be checked using [vxGetStatus](#).



**vx\_status VX\_API\_CALL vxReleaseObjectArray ( vx\_object\_array \* arr )**

Releases a reference of an ObjectArray object.

The object may not be garbage collected until its total reference and its contained objects count is zero. After returning from this function the reference is zeroed/cleared.

**Parameters**

|    |            |                                            |
|----|------------|--------------------------------------------|
| in | <i>arr</i> | The pointer to the ObjectArray to release. |
|----|------------|--------------------------------------------|

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                                         |                                                                   |
|-----------------------------------------|-------------------------------------------------------------------|
| <code>VX_SUCCESS</code>                 | No errors; any other value indicates failure.                     |
| <code>VX_ERROR_INVALID_REFERENCE</code> | <i>arr</i> is not a valid <code>vx_object_array</code> reference. |

**vx\_status VX\_API\_CALL vxQueryObjectArray ( vx\_object\_array arr, vx\_enum attribute, void \* ptr, vx\_size size )**

Queries an attribute from the ObjectArray.

**Parameters**

|     |                  |                                                                          |
|-----|------------------|--------------------------------------------------------------------------|
| in  | <i>arr</i>       | The reference to the ObjectArray.                                        |
| in  | <i>attribute</i> | The attribute to query. Use a <code>vx_object_array_attribute_e</code> . |
| out | <i>ptr</i>       | The location at which to store the resulting value.                      |
| in  | <i>size</i>      | The size in bytes of the container to which <i>ptr</i> points.           |

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                                          |                                                                          |
|------------------------------------------|--------------------------------------------------------------------------|
| <code>VX_SUCCESS</code>                  | No errors; any other value indicates failure.                            |
| <code>VX_ERROR_INVALID_REFERENCE</code>  | <i>arr</i> is not a valid <code>vx_object_array</code> reference.        |
| <code>VX_ERROR_NOT_SUPPORTED</code>      | If the <i>attribute</i> is not a value supported on this implementation. |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | If any of the other parameters are incorrect.                            |

## 3.79 Object: Tensor

### 3.79.1 Detailed Description

Defines The Tensor Object Interface.

The `vx_tensor` object represents an opaque multidimensional array. The object is said to be opaque because the programmer has no visibility into the internal implementation of the object, and can only manipulate them via the defined API. Implementations can apply many optimizations that are transparent to the user. OpenVX implementations must support `vx_tensor` objects of at least 4 dimensions, although a vendor can choose to support more dimensions in his implementation. The maximum number of dimensions supported by a given implementation can be queried via the context attribute `VX_CONTEXT_MAX_TENSOR_DIMS`. Implementations must support tensors from one dimension (i.e., vectors) through `VX_CONTEXT_MAX_TENSOR_DIMS`, inclusive. The individual elements of the tensor object may be any numerical data type. For each kernel in the specification, it is specified which data types a compliant implementations must support. Integer elements can represent fractional values by assigning a non-zero radix point. As an example: `VX_TYPE_INT16` element with radix point of 8, corresponds to Q7.8 signed fixed-point in “Q” notation. A vendor may choose to support whatever values for the radix point in his implementation. Since functions using tensors, need to understand the context of each dimension. We describe a layout of the dimensions in each function. That layout is not mandated. It is done specifically to explain the functions and not to mandate layout. Different implementation may have different layout. Therefore the layout description is logical and not physical. It refers to the order of dimensions given in `vxCreateTensor` and `vxCreateVirtualTensor`.

### Typedefs

- typedef struct `_vx_tensor_t` \* `vx_tensor`  
*The multidimensional data object (Tensor).*

### Enumerations

- enum `vx_tensor_attribute_e` {  
`VX_TENSOR_NUMBER_OF_DIMS` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_TYPE_TENSOR` << 8)) + 0x0,  
`VX_TENSOR_DIMS` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_TYPE_TENSOR` << 8)) + 0x1,  
`VX_TENSOR_DATA_TYPE` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_TYPE_TENSOR` << 8)) + 0x2,  
`VX_TENSOR_FIXED_POINT_POSITION` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_TYPE_TENSOR` << 8)) + 0x3 }  
*tensor Data attributes.*

### Functions

- `vx_status VX_API_CALL vxCopyTensorPatch` (`vx_tensor` tensor, `vx_size` number\_of\_dims, const `vx_size` \*view\_start, const `vx_size` \*view\_end, const `vx_size` \*user\_stride, void \*user\_ptr, `vx_enum` usage, `vx_enum` user\_memory\_type)  
*Allows the application to copy a view patch from/into an tensor object .*
- `vx_object_array VX_API_CALL vxCreateImageObjectArrayFromTensor` (`vx_tensor` tensor, const `vx_rectangle_t` \*rect, `vx_size` array\_size, `vx_size` jump, `vx_df_image` image\_format)  
*Creates an array of images into the multi-dimension data, this can be adjacent 2D images or not depending on the stride value. The stride value is representing bytes in the third dimension. The OpenVX image object that points to a three dimension data and access it as an array of images. This has to be portion of the third lowest dimension, and the stride correspond to that third dimension. The returned Object array is an array of images. Where the image data is pointing to a specific memory in the input tensor.*
- `vx_tensor VX_API_CALL vxCreateTensor` (`vx_context` context, `vx_size` number\_of\_dims, const `vx_size` \*dims, `vx_enum` data\_type, `vx_int8` fixed\_point\_position)  
*Creates an opaque reference to a tensor data buffer.*
- `vx_tensor VX_API_CALL vxCreateTensorFromView` (`vx_tensor` tensor, `vx_size` number\_of\_dims, const `vx_size` \*view\_start, const `vx_size` \*view\_end)  
*Creates a tensor data from another tensor data given a view. This second reference refers to the data in the original tensor data. Updates to this tensor data updates the parent tensor data. The view must be defined within the dimensions of the parent tensor data.*

- **vx\_tensor VX\_API\_CALL vxCreateVirtualTensor** (**vx\_graph** graph, **vx\_size** number\_of\_dims, const **vx\_size** \*dims, **vx\_enum** data\_type, **vx\_int8** fixed\_point\_position)  
*Creates an opaque reference to a tensor data buffer with no direct user access. This function allows setting the tensor data dimensions or data format.*
- **vx\_status VX\_API\_CALL vxQueryTensor** (**vx\_tensor** tensor, **vx\_enum** attribute, void \*ptr, **vx\_size** size)  
*Retrieves various attributes of a tensor data.*
- **vx\_status VX\_API\_CALL vxReleaseTensor** (**vx\_tensor** \*tensor)  
*Releases a reference to a tensor data object. The object may not be garbage collected until its total reference count is zero.*

### 3.79.2 Typedef Documentation

**typedef struct \_vx\_tensor\_t\* vx\_tensor**

The multidimensional data object (Tensor).

See also

[vxCreateTensor](#)

Definition at line 284 of file [vx\\_types.h](#).

### 3.79.3 Enumeration Type Documentation

**enum vx\_tensor\_attribute\_e**

tensor Data attributes.

Enumerator

**VX\_TENSOR\_NUMBER\_OF\_DIMS** Number of dimensions.

**VX\_TENSOR\_DIMS** Dimension sizes.

**VX\_TENSOR\_DATA\_TYPE** tensor Data element data type. [vx\\_type\\_e](#)

**VX\_TENSOR\_FIXED\_POINT\_POSITION** fixed point position when the input element type is integer.

Definition at line 1168 of file [vx\\_types.h](#).

### 3.79.4 Function Documentation

**vx\_tensor VX\_API\_CALL vxCreateTensor** ( **vx\_context** context, **vx\_size** number\_of\_dims, const **vx\_size** \*dims, **vx\_enum** data\_type, **vx\_int8** fixed\_point\_position )

Creates an opaque reference to a tensor data buffer.

Not guaranteed to exist until the [vx\\_graph](#) containing it has been verified. Since functions using tensors, need to understand the context of each dimension. We describe a layout of the dimensions in each function using tensors. That layout is not mandatory. It is done specifically to explain the functions and not to mandate layout. Different implementation may have different layout. Therefore the layout description is logical and not physical. It refers to the order of dimensions given in this function.

Parameters

|    |                             |                                                                                                                              |
|----|-----------------------------|------------------------------------------------------------------------------------------------------------------------------|
| in | <i>context</i>              | The reference to the implementation context.                                                                                 |
| in | <i>number_of_dims</i>       | The number of dimensions.                                                                                                    |
| in | <i>dims</i>                 | Dimensions sizes in elements.                                                                                                |
| in | <i>data_type</i>            | The <a href="#">vx_type_e</a> that represents the data type of the tensor data elements.                                     |
| in | <i>fixed_point_position</i> | Specifies the fixed point position when the input element type is integer. if 0, calculations are performed in integer math. |

## Returns

A tensor data reference. Any possible errors preventing a successful creation should be checked using `vx↵GetStatus`.

**vx\_object\_array VX\_API\_CALL vxCreateImageObjectArrayFromTensor ( vx\_tensor *tensor*, const vx\_rectangle\_t \* *rect*, vx\_size *array\_size*, vx\_size *jump*, vx\_df\_image *image\_format* )**

Creates an array of images into the multi-dimension data, this can be adjacent 2D images or not depending on the stride value. The stride value is representing bytes in the third dimension. The OpenVX image object that points to a three dimension data and access it as an array of images. This has to be portion of the third lowest dimension, and the stride correspond to that third dimension. The returned Object array is an array of images. Where the image data is pointing to a specific memory in the input tensor.

## Parameters

|    |                     |                                                                          |
|----|---------------------|--------------------------------------------------------------------------|
| in | <i>tensor</i>       | The tensor data from which to extract the images. Has to be a 3d tensor. |
| in | <i>rect</i>         | Image coordinates within tensor data.                                    |
| in | <i>array_size</i>   | Number of images to extract.                                             |
| in | <i>jump</i>         | Delta between two images in the array.                                   |
| in | <i>image_format</i> | The requested image format. Should match the tensor data's data type.    |

## Returns

An array of images pointing to the tensor data's data.

**vx\_tensor VX\_API\_CALL vxCreateTensorFromView ( vx\_tensor *tensor*, vx\_size *number\_of\_dims*, const vx\_size \* *view\_start*, const vx\_size \* *view\_end* )**

Creates a tensor data from another tensor data given a view. This second reference refers to the data in the original tensor data. Updates to this tensor data updates the parent tensor data. The view must be defined within the dimensions of the parent tensor data.

## Parameters

|    |                       |                                                                                                                                                                                 |
|----|-----------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>tensor</i>         | The reference to the parent tensor data.                                                                                                                                        |
| in | <i>number_of_dims</i> | Number of dimensions in the view. Error return if 0 or greater than number of tensor dimensions. If smaller than number of tensor dimensions, the lower dimensions are assumed. |
| in | <i>view_start</i>     | View start coordinates                                                                                                                                                          |
| in | <i>view_end</i>       | View end coordinates                                                                                                                                                            |

## Returns

The reference to the sub-tensor. Any possible errors preventing a successful creation should be checked using `vxGetStatus`.

**vx\_tensor VX\_API\_CALL vxCreateVirtualTensor ( vx\_graph *graph*, vx\_size *number\_of\_dims*, const vx\_size \* *dims*, vx\_enum *data\_type*, vx\_int8 *fixed\_point\_position* )**

Creates an opaque reference to a tensor data buffer with no direct user access. This function allows setting the tensor data dimensions or data format.

Virtual data objects allow users to connect various nodes within a graph via data references without access to that data, but they also permit the implementation to take maximum advantage of possible optimizations. Use this API to create a data reference to link two or more nodes together when the intermediate data are not required to be accessed by outside entities. This API in particular allows the user to define the tensor data format of the

data without requiring the exact dimensions. Virtual objects are scoped within the graph they are declared a part of, and can't be shared outside of this scope. Since functions using tensors, need to understand the context of each dimension. We describe a layout of the dimensions in each function. That layout is not mandated. It is done specifically to explain the functions and not to mandate layout. Different implementation may have different layout. Therefore the layout description is logical and not physical. It refers to the order of dimensions given in `vxCreateTensor` and `vxCreateVirtualTensor`.

#### Parameters

|    |                             |                                                                                                                              |
|----|-----------------------------|------------------------------------------------------------------------------------------------------------------------------|
| in | <i>graph</i>                | The reference to the parent graph.                                                                                           |
| in | <i>number_of_dims</i>       | The number of dimensions.                                                                                                    |
| in | <i>dims</i>                 | Dimensions sizes in elements.                                                                                                |
| in | <i>data_type</i>            | The <code>vx_type_e</code> that represents the data type of the tensor data elements.                                        |
| in | <i>fixed_point_position</i> | Specifies the fixed point position when the input element type is integer. If 0, calculations are performed in integer math. |

#### Returns

A tensor data reference. Any possible errors preventing a successful creation should be checked using `vx↵GetStatus`.

#### Note

Passing this reference to `vxCopyTensorPatch` will return an error.

**vx\_status VX\_API\_CALL vxCopyTensorPatch ( vx\_tensor tensor, vx\_size number\_of\_dims, const vx\_size \* view\_start, const vx\_size \* view\_end, const vx\_size \* user\_stride, void \* user\_ptr, vx\_enum usage, vx\_enum user\_memory\_type )**

Allows the application to copy a view patch from/into an tensor object .

#### Parameters

|    |                         |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
|----|-------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>tensor</i>           | The reference to the tensor object that is the source or the destination of the copy.                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
| in | <i>number_of_dims</i>   | Number of patch dimension. Error return if 0 or greater than number of tensor dimensions. If smaller than number of tensor dimensions, the lower dimensions are assumed.                                                                                                                                                                                                                                                                                                                                                                            |
| in | <i>view_start</i>       | Array of patch start points in each dimension                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
| in | <i>view_end</i>         | Array of patch end points in each dimension                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
| in | <i>user_stride</i>      | Array of user memory strides in each dimension                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
| in | <i>user_ptr</i>         | The address of the memory location where to store the requested data if the copy was requested in read mode, or from where to get the data to store into the tensor object if the copy was requested in write mode. The accessible memory must be large enough to contain the specified patch with the specified layout:<br>accessible memory in bytes $\geq (\text{end}[\text{last\_dimension}] - \text{start}[\text{last\_dimension}]) * \text{stride}[\text{last\_dimension}]$ .<br>The layout of the user memory must follow a row major order. |
| in | <i>usage</i>            | This declares the effect of the copy with regard to the tensor object using the <code>vx_accessor_e</code> enumeration. Only <code>VX_READ_ONLY</code> and <code>VX_WRITE_ONLY</code> are supported: <ul style="list-style-type: none"> <li><code>VX_READ_ONLY</code> means that data is copied from the tensor object into the application memory</li> <li><code>VX_WRITE_ONLY</code> means that data is copied into the tensor object from the application memory</li> </ul>                                                                      |
| in | <i>user_memory_type</i> | A <code>vx_memory_type_e</code> enumeration that specifies the memory type of the memory referenced by the <code>user_addr</code> .                                                                                                                                                                                                                                                                                                                                                                                                                 |

## Returns

A `vx_status_e` enumeration.

## Return values

|                                          |                                                                                     |
|------------------------------------------|-------------------------------------------------------------------------------------|
| <code>VX_ERROR_OPTIMIZED_AWAY</code>     | This is a reference to a virtual tensor that cannot be accessed by the application. |
| <code>VX_ERROR_INVALID_REFERENCE</code>  | The tensor reference is not actually an tensor reference.                           |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | An other parameter is incorrect.                                                    |

**`vx_status VX_API_CALL vxQueryTensor ( vx_tensor tensor, vx_enum attribute, void * ptr, vx_size size )`**

Retrieves various attributes of a tensor data.

## Parameters

|     |                  |                                                                    |
|-----|------------------|--------------------------------------------------------------------|
| in  | <i>tensor</i>    | The reference to the tensor data to query.                         |
| in  | <i>attribute</i> | The attribute to query. Use a <code>vx_tensor_attribute_e</code> . |
| out | <i>ptr</i>       | The location at which to store the resulting value.                |
| in  | <i>size</i>      | The size of the container to which <i>ptr</i> points.              |

## Returns

A `vx_status_e` enumeration.

## Return values

|                                          |                                               |
|------------------------------------------|-----------------------------------------------|
| <code>VX_SUCCESS</code>                  | No errors.                                    |
| <code>VX_ERROR_INVALID_REFERENCE</code>  | If data is not a <code>vx_tensor</code> .     |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | If any of the other parameters are incorrect. |

**`vx_status VX_API_CALL vxReleaseTensor ( vx_tensor * tensor )`**

Releases a reference to a tensor data object. The object may not be garbage collected until its total reference count is zero.

## Parameters

|    |               |                                            |
|----|---------------|--------------------------------------------|
| in | <i>tensor</i> | The pointer to the tensor data to release. |
|----|---------------|--------------------------------------------|

## Postcondition

After returning from this function the reference is zeroed.

## Returns

A `vx_status_e` enumeration.

## Return values

|                         |                                                   |
|-------------------------|---------------------------------------------------|
| <code>VX_SUCCESS</code> | No errors; all other values indicate failure      |
| *                       | An error occurred. See <code>vx_status_e</code> . |

## 3.80 Administrative Features

### 3.80.1 Detailed Description

Defines the Administrative Features of OpenVX.

These features are administrative in nature and require more understanding and are more complex to use.

#### Modules

- [Advanced Objects](#)

*Defines the Advanced Objects of OpenVX.*

- [Advanced Framework API](#)

*Describes components that are considered to be advanced.*

## 3.81 Advanced Objects

### 3.81.1 Detailed Description

Defines the Advanced Objects of OpenVX.

#### Modules

- [Object: Array \(Advanced\)](#)  
*Defines the advanced features of the Array Interface.*
- [Object: Node \(Advanced\)](#)  
*Defines the advanced features of the Node Interface.*
- [Object: Delay](#)  
*Defines the Delay Object interface.*
- [Object: Kernel](#)  
*Defines the Kernel Object and Interface.*
- [Object: Parameter](#)  
*Defines the Parameter Object interface.*



## 3.82 Object: Array (Advanced)

### 3.82.1 Detailed Description

Defines the advanced features of the Array Interface.

#### Functions

- `vx_enum VX_API_CALL vxRegisterUserStruct (vx_context context, vx_size size)`  
*Registers user-defined structures to the context.*

### 3.82.2 Function Documentation

`vx_enum VX_API_CALL vxRegisterUserStruct ( vx_context context, vx_size size )`

Registers user-defined structures to the context.

#### Parameters

|    |                |                                              |
|----|----------------|----------------------------------------------|
| in | <i>context</i> | The reference to the implementation context. |
| in | <i>size</i>    | The size of user struct in bytes.            |

#### Returns

A `vx_enum` value that is a type given to the User to refer to their custom structure when declaring a `vx_↵  
array` of that structure.

#### Return values

|                              |                                               |
|------------------------------|-----------------------------------------------|
| <code>VX_TYPE_INVALID</code> | If the namespace of types has been exhausted. |
|------------------------------|-----------------------------------------------|

#### Note

This call should only be used once within the lifetime of a context for a specific structure.

## 3.83 Object: Node (Advanced)

### 3.83.1 Detailed Description

Defines the advanced features of the Node Interface.

#### Modules

- [Node: Border Modes](#)

*Defines the border mode behaviors.*

#### Functions

- [vx\\_node VX\\_API\\_CALL vxCreateGenericNode](#) ([vx\\_graph](#) graph, [vx\\_kernel](#) kernel)

*Creates a reference to a node object for a given kernel.*

### 3.83.2 Function Documentation

**[vx\\_node VX\\_API\\_CALL vxCreateGenericNode](#) ( [vx\\_graph](#) *graph*, [vx\\_kernel](#) *kernel* )**

Creates a reference to a node object for a given kernel.

This node has no references assigned as parameters after completion. The client is then required to set these parameters manually by [vxSetParameterByIndex](#). When clients supply their own node creation functions (for use with User Kernels), this is the API to use along with the parameter setting API.

#### Parameters

|    |               |                                                       |
|----|---------------|-------------------------------------------------------|
| in | <i>graph</i>  | The reference to the graph in which this node exists. |
| in | <i>kernel</i> | The kernel reference to associate with this new node. |

#### Returns

A node reference [vx\\_node](#). Any possible errors preventing a successful creation should be checked using [vxGetStatus](#).

#### Note

A call to this API sets all parameters to NULL.

#### Postcondition

Call [vxSetParameterByIndex](#) for as many parameters as needed to be set.

## 3.84 Node: Border Modes

### 3.84.1 Detailed Description

Defines the border mode behaviors.

Border Mode behavior is set as an attribute of the node, not as a direct parameter to the kernel. This allows clients to *set-and-forget* the modes of any particular node that supports border modes. All nodes shall support [VX\\_BORDER\\_UNDEFINED](#).

### Data Structures

- struct [vx\\_border\\_t](#)

Use with the enumeration [VX\\_NODE\\_BORDER](#) to set the border mode behavior of a node that supports borders.  
*More...*

### Enumerations

- enum [vx\\_border\\_e](#) {  
[VX\\_BORDER\\_UNDEFINED](#) = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_ENUM\_BORDER << 12)) + 0x0,  
[VX\\_BORDER\\_CONSTANT](#) = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_ENUM\_BORDER << 12)) + 0x1,  
[VX\\_BORDER\\_REPLICATE](#) = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_ENUM\_BORDER << 12)) + 0x2 }

*The border mode list.*

- enum [vx\\_border\\_policy\\_e](#) {  
[VX\\_BORDER\\_POLICY\\_DEFAULT\\_TO\\_UNDEFINED](#) = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_ENUM\_BORDER\_POLICY << 12)) + 0x0,  
[VX\\_BORDER\\_POLICY\\_RETURN\\_ERROR](#) = ((( VX\_ID\_KHRONOS ) << 20) | ( VX\_ENUM\_BORDER\_POLICY << 12)) + 0x1 }

*The unsupported border mode policy list.*

### 3.84.2 Data Structure Documentation

#### struct [vx\\_border\\_t](#)

Use with the enumeration [VX\\_NODE\\_BORDER](#) to set the border mode behavior of a node that supports borders.

If the indicated border mode is not supported, an error [VX\\_ERROR\\_NOT\\_SUPPORTED](#) will be reported either at the time the [VX\\_NODE\\_BORDER](#) is set or at the time of graph verification.

Definition at line 1729 of file [vx\\_types.h](#).

#### Data Fields

|                                  |                |                                                                                                         |
|----------------------------------|----------------|---------------------------------------------------------------------------------------------------------|
| <a href="#">vx_enum</a>          | mode           | See <a href="#">vx_border_e</a> .                                                                       |
| <a href="#">vx_pixel_value_t</a> | constant_value | For the mode <a href="#">VX_BORDER_CONSTANT</a> , this union contains the value of out-of-bound pixels. |

### 3.84.3 Enumeration Type Documentation

#### enum [vx\\_border\\_e](#)

The border mode list.

Enumerator

**[VX\\_BORDER\\_UNDEFINED](#)** No defined border mode behavior is given.

**[VX\\_BORDER\\_CONSTANT](#)** For nodes that support this behavior, a constant value is *filled-in* when accessing out-of-bounds pixels.

**[VX\\_BORDER\\_REPLICATE](#)** For nodes that support this behavior, a replication of the nearest edge pixels value is given for out-of-bounds pixels.

Definition at line 1336 of file [vx\\_types.h](#).

**enum vx\_border\_policy\_e**

The unsupported border mode policy list.

Enumerator

**VX\_BORDER\_POLICY\_DEFAULT\_TO\_UNDEFINED** Use VX\_BORDER\_UNDEFINED instead of unsupported border modes.

**VX\_BORDER\_POLICY\_RETURN\_ERROR** Return VX\_ERROR\_NOT\_SUPPORTED for unsupported border modes.

Definition at line 1352 of file [vx\\_types.h](#).

## 3.85 Object: Delay

### 3.85.1 Detailed Description

Defines the Delay Object interface.

A Delay is an opaque object that contains a manually-controlled, temporally-delayed list of objects. A Delay cannot be an output of a kernel. Also, aging of a Delay (see [vxAgeDelay](#)) cannot be performed during graph execution. Supported delay object types include:

- [VX\\_TYPE\\_ARRAY](#),
- [VX\\_TYPE\\_IMAGE](#),
- [VX\\_TYPE\\_PYRAMID](#),
- [VX\\_TYPE\\_MATRIX](#),
- [VX\\_TYPE\\_CONVOLUTION](#),
- [VX\\_TYPE\\_DISTRIBUTION](#),
- [VX\\_TYPE\\_REMAP](#),
- [VX\\_TYPE\\_LUT](#),
- [VX\\_TYPE\\_THRESHOLD](#),
- [VX\\_TYPE\\_SCALAR](#)

### Typedefs

- typedef struct \_vx\_delay \* [vx\\_delay](#)

*The delay object. This is like a ring buffer of objects that is maintained by the OpenVX implementation.*

### Enumerations

- enum [vx\\_delay\\_attribute\\_e](#) {  
[VX\\_DELAY\\_TYPE](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_TYPE\\_DELAY](#) << 8)) + 0x0,  
[VX\\_DELAY\\_SLOTS](#) = ((( [VX\\_ID\\_KHRONOS](#) ) << 20) | ( [VX\\_TYPE\\_DELAY](#) << 8)) + 0x1 }

*The delay attribute list.*

### Functions

- [vx\\_status VX\\_API\\_CALL vxAgeDelay](#) ([vx\\_delay](#) delay)  
*Shifts the internal delay ring by one.*
- [vx\\_delay VX\\_API\\_CALL vxCreateDelay](#) ([vx\\_context](#) context, [vx\\_reference](#) exemplar, [vx\\_size](#) num\_slots)  
*Creates a Delay object.*
- [vx\\_reference VX\\_API\\_CALL vxGetReferenceFromDelay](#) ([vx\\_delay](#) delay, [vx\\_int32](#) index)  
*Retrieves a reference to a delay slot object.*
- [vx\\_status VX\\_API\\_CALL vxQueryDelay](#) ([vx\\_delay](#) delay, [vx\\_enum](#) attribute, void \*ptr, [vx\\_size](#) size)  
*Queries a [vx\\_delay](#) object attribute.*
- [vx\\_status VX\\_API\\_CALL vxReleaseDelay](#) ([vx\\_delay](#) \*delay)  
*Releases a reference to a delay object. The object may not be garbage collected until its total reference count is zero.*

### 3.85.2 Typedef Documentation

**typedef struct \_vx\_delay\* [vx\\_delay](#)**

The delay object. This is like a ring buffer of objects that is maintained by the OpenVX implementation.

See also

[vxCreateDelay](#)

Definition at line 223 of file [vx\\_types.h](#).

### 3.85.3 Enumeration Type Documentation

#### enum vx\_delay\_attribute\_e

The delay attribute list.

Enumerator

**VX\_DELAY\_TYPE** The type of objects in the delay. Read-only. Use a [vx\\_enum](#) parameter.

**VX\_DELAY\_SLOTS** The number of items in the delay. Read-only. Use a [vx\\_size](#) parameter.

Definition at line [1388](#) of file [vx\\_types.h](#).

### 3.85.4 Function Documentation

**vx\_status VX\_API\_CALL vxQueryDelay ( vx\_delay delay, vx\_enum attribute, void \* ptr, vx\_size size )**

Queries a [vx\\_delay](#) object attribute.

Parameters

|     |                  |                                                                                 |
|-----|------------------|---------------------------------------------------------------------------------|
| in  | <i>delay</i>     | The reference to a delay object.                                                |
| in  | <i>attribute</i> | The attribute to query. Use a <a href="#">vx_delay_attribute_e</a> enumeration. |
| out | <i>ptr</i>       | The location at which to store the resulting value.                             |
| in  | <i>size</i>      | The size of the container to which <i>ptr</i> points.                           |

Returns

A [vx\\_status\\_e](#) enumeration.

Return values

|                                   |                                                          |
|-----------------------------------|----------------------------------------------------------|
| <i>VX_SUCCESS</i>                 | No errors; any other value indicates failure.            |
| <i>VX_ERROR_INVALID_REFERENCE</i> | delay is not a valid <a href="#">vx_delay</a> reference. |

**vx\_status VX\_API\_CALL vxReleaseDelay ( vx\_delay \* delay )**

Releases a reference to a delay object. The object may not be garbage collected until its total reference count is zero.

Parameters

|    |              |                                                       |
|----|--------------|-------------------------------------------------------|
| in | <i>delay</i> | The pointer to the delay object reference to release. |
|----|--------------|-------------------------------------------------------|

Postcondition

After returning from this function the reference is zeroed.

Returns

A [vx\\_status\\_e](#) enumeration.

Return values

|                                   |                                                          |
|-----------------------------------|----------------------------------------------------------|
| <i>VX_SUCCESS</i>                 | No errors; any other value indicates failure.            |
| <i>VX_ERROR_INVALID_REFERENCE</i> | delay is not a valid <a href="#">vx_delay</a> reference. |

**vx\_delay VX\_API\_CALL vxCreateDelay ( vx\_context *context*, vx\_reference *exemplar*, vx\_size *num\_slots* )**

Creates a Delay object.

This function creates a delay object with `num_slots` slots. Each slot contains a clone of the exemplar. The clones only inherit the metadata of the exemplar. The data content of the exemplar is ignored and the clones have their data undefined at delay creation time. The function does not alter the exemplar. Also, it doesn't retain or release the reference to the exemplar.

Note

For the definition of metadata attributes see [vxSetMetaFormatAttribute](#).

#### Parameters

|    |                  |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
|----|------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>context</i>   | The reference to the context.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| in | <i>exemplar</i>  | The exemplar object. Supported exemplar object types are: <ul style="list-style-type: none"> <li>• <a href="#">VX_TYPE_ARRAY</a></li> <li>• <a href="#">VX_TYPE_CONVOLUTION</a></li> <li>• <a href="#">VX_TYPE_DISTRIBUTION</a></li> <li>• <a href="#">VX_TYPE_IMAGE</a></li> <li>• <a href="#">VX_TYPE_LUT</a></li> <li>• <a href="#">VX_TYPE_MATRIX</a></li> <li>• <a href="#">VX_TYPE_OBJECT_ARRAY</a></li> <li>• <a href="#">VX_TYPE_PYRAMID</a></li> <li>• <a href="#">VX_TYPE_REMAP</a></li> <li>• <a href="#">VX_TYPE_SCALAR</a></li> <li>• <a href="#">VX_TYPE_THRESHOLD</a></li> <li>• <a href="#">VX_TYPE_TENSOR</a></li> </ul> |
| in | <i>num_slots</i> | The number of objects in the delay. This value must be greater than zero.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |

#### Returns

A delay reference [vx\\_delay](#). Any possible errors preventing a successful creation should be checked using [vxGetStatus](#).

**vx\_reference VX\_API\_CALL vxGetReferenceFromDelay ( vx\_delay *delay*, vx\_int32 *index* )**

Retrieves a reference to a delay slot object.

#### Parameters

|    |              |                                                                         |
|----|--------------|-------------------------------------------------------------------------|
| in | <i>delay</i> | The reference to the delay object.                                      |
| in | <i>index</i> | The index of the delay slot from which to extract the object reference. |

#### Returns

[vx\\_reference](#). Any possible errors preventing a successful completion of the function should be checked using [vxGetStatus](#).

**Note**

The delay index is in the range  $[-count + 1, 0]$ . 0 is always the *current* object.

A reference retrieved with this function must not be given to its associated release API (e.g. [vxReleaseImage](#)) unless [vxRetainReference](#) is used.

**vx\_status VX\_API\_CALL vxAgeDelay ( vx\_delay delay )**

Shifts the internal delay ring by one.

This function performs a shift of the internal delay ring by one. This means that, the data originally at index 0 move to index -1 and so forth until index  $-count + 1$ . The data originally at index  $-count + 1$  move to index 0. Here *count* is the number of slots in delay ring. When a delay is aged, any graph making use of this delay (delay object itself or data objects in delay slots) gets its data automatically updated accordingly.

**Parameters**

|    |              |  |
|----|--------------|--|
| in | <i>delay</i> |  |
|----|--------------|--|

**Returns**

A [vx\\_status\\_e](#) enumeration.

**Return values**

|                                            |                                                          |
|--------------------------------------------|----------------------------------------------------------|
| <a href="#">VX_SUCCESS</a>                 | Delay was aged; any other value indicates failure.       |
| <a href="#">VX_ERROR_INVALID_REFERENCE</a> | delay is not a valid <a href="#">vx_delay</a> reference. |



## 3.86 Object: Kernel

### 3.86.1 Detailed Description

Defines the Kernel Object and Interface.

A Kernel in OpenVX is the abstract representation of an computer vision function, such as a “Sobel Gradient” or “Lucas Kanade Feature Tracking”. A vision function may implement many similar or identical features from other functions, but it is still considered a single unique kernel as long as it is named by the same string and enumeration and conforms to the results specified by OpenVX. Kernels are similar to function signatures in this regard.

In each of the cases, a client of OpenVX could request the kernels in nearly the same manner. There are two main approaches, which depend on the method a client calls to get the kernel reference. The first uses enumerations.

```
vx_kernel kernel = vxGetKernelByEnum(context,
VX_KERNEL_SOBEL_3x3);
vx_node node = vxCreateGenericNode(graph, kernel);
```

The second method depends on using strings to get the kernel reference.

```
vx_kernel kernel = vxGetKernelByName(context, "
org.khronos.openvx.sobel_3x3");
vx_node node = vxCreateGenericNode(graph, kernel);
```

### Data Structures

- struct `vx_kernel_info_t`

*The Kernel Information Structure. This is returned by the Context to indicate which kernels are available in the OpenVX implementation. [More...](#)*

### Macros

- #define `VX_MAX_KERNEL_NAME` (256)

*Defines the length of a kernel name string to be added to OpenVX, including the trailing zero.*

### Typedefs

- typedef struct `_vx_kernel` \* `vx_kernel`

*An opaque reference to the descriptor of a kernel.*

### Enumerations

- enum `vx_kernel_attribute_e` {  
`VX_KERNEL_PARAMETERS` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_TYPE_KERNEL` << 8)) + 0x0,  
`VX_KERNEL_NAME` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_TYPE_KERNEL` << 8)) + 0x1,  
`VX_KERNEL_ENUM` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_TYPE_KERNEL` << 8)) + 0x2,  
`VX_KERNEL_LOCAL_DATA_SIZE` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_TYPE_KERNEL` << 8)) + 0x3  
}

*The kernel attributes list.*

- enum `vx_kernel_e` {  
`VX_KERNEL_COLOR_CONVERT` = `VX_KERNEL_BASE`(`VX_ID_KHRONOS`, `VX_LIBRARY_KHR_BASE`) + 0x1,  
`VX_KERNEL_CHANNEL_EXTRACT` = `VX_KERNEL_BASE`(`VX_ID_KHRONOS`, `VX_LIBRARY_KHR_BASE`) + 0x2,  
`VX_KERNEL_CHANNEL_COMBINE` = `VX_KERNEL_BASE`(`VX_ID_KHRONOS`, `VX_LIBRARY_KHR_BASE`) + 0x3,  
`VX_KERNEL_SOBEL_3x3` = `VX_KERNEL_BASE`(`VX_ID_KHRONOS`, `VX_LIBRARY_KHR_BASE`) + 0x4,  
`VX_KERNEL_MAGNITUDE` = `VX_KERNEL_BASE`(`VX_ID_KHRONOS`, `VX_LIBRARY_KHR_BASE`) + 0x5,  
`VX_KERNEL_PHASE` = `VX_KERNEL_BASE`(`VX_ID_KHRONOS`, `VX_LIBRARY_KHR_BASE`) + 0x6,  
`VX_KERNEL_SCALE_IMAGE` = `VX_KERNEL_BASE`(`VX_ID_KHRONOS`, `VX_LIBRARY_KHR_BASE`) + 0x7,  
`VX_KERNEL_TABLE_LOOKUP` = `VX_KERNEL_BASE`(`VX_ID_KHRONOS`, `VX_LIBRARY_KHR_BASE`) +

```

0x8,
VX_KERNEL_HISTOGRAM = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE) + 0x9,
VX_KERNEL_EQUALIZE_HISTOGRAM = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_↵
_BASE) + 0xA,
VX_KERNEL_ABSDIFF = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE) + 0xB,
VX_KERNEL_MEAN_STDDEV = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE) +
0xC,
VX_KERNEL_THRESHOLD = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE) + 0xD,
VX_KERNEL_INTEGRAL_IMAGE = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE)
+ 0xE,
VX_KERNEL_DILATE_3x3 = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE) + 0xF,
VX_KERNEL_ERODE_3x3 = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE) + 0x10,
VX_KERNEL_MEDIAN_3x3 = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE) + 0x11,
VX_KERNEL_BOX_3x3 = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE) + 0x12,
VX_KERNEL_GAUSSIAN_3x3 = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE) +
0x13,
VX_KERNEL_CUSTOM_CONVOLUTION = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KH_↵
R_BASE) + 0x14,
VX_KERNEL_GAUSSIAN_PYRAMID = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_B_↵
ASE) + 0x15,
VX_KERNEL_ACCUMULATE = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE) +
0x16,
VX_KERNEL_ACCUMULATE_WEIGHTED = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_K_↵
HR_BASE) + 0x17,
VX_KERNEL_ACCUMULATE_SQUARE = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_↵
_BASE) + 0x18,
VX_KERNEL_MINMAXLOC = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE) + 0x19,
VX_KERNEL_CONVERTDEPTH = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE) +
0x1A,
VX_KERNEL_CANNY_EDGE_DETECTOR = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_K_↵
HR_BASE) + 0x1B,
VX_KERNEL_AND = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE) + 0x1C,
VX_KERNEL_OR = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE) + 0x1D,
VX_KERNEL_XOR = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE) + 0x1E,
VX_KERNEL_NOT = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE) + 0x1F,
VX_KERNEL_MULTIPLY = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE) + 0x20,
VX_KERNEL_ADD = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE) + 0x21,
VX_KERNEL_SUBTRACT = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE) + 0x22,
VX_KERNEL_WARP_AFFINE = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE) +
0x23,
VX_KERNEL_WARP_PERSPECTIVE = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_B_↵
ASE) + 0x24,
VX_KERNEL_HARRIS_CORNERS = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE)
+ 0x25,
VX_KERNEL_FAST_CORNERS = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE) +
0x26,
VX_KERNEL_OPTICAL_FLOW_PYR_LK = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KH_↵
R_BASE) + 0x27,
VX_KERNEL_REMAP = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE) + 0x28,
VX_KERNEL_HALFSCALE_GAUSSIAN = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_↵
_BASE) + 0x29,
VX_KERNEL_MAX_1_0,
VX_KERNEL_LAPLACIAN_PYRAMID = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_B_↵
ASE) + 0x2A,
VX_KERNEL_LAPLACIAN_RECONSTRUCT = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_↵
KHR_BASE) + 0x2B,
VX_KERNEL_NON_LINEAR_FILTER = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_B_↵

```

```

ASE) + 0x2C,
VX_KERNEL_MAX_1_1,
VX_KERNEL_MATCH_TEMPLATE = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE)
+ 0x2D,
VX_KERNEL_LBP = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE) + 0x2E,
VX_KERNEL_HOUGH_LINES_P = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE) +
0x2F,
VX_KERNEL_TENSOR_MULTIPLY = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE)
+ 0x30,
VX_KERNEL_TENSOR_ADD = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE) +
0x31,
VX_KERNEL_TENSOR_SUBTRACT = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BA↵
SE) + 0x32,
VX_KERNEL_TENSOR_TABLE_LOOKUP = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KH↵
R_BASE) + 0x33,
VX_KERNEL_TENSOR_TRANSPOSE = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_↵
BASE) + 0x34,
VX_KERNEL_TENSOR_CONVERT_DEPTH = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_↵
KHR_BASE) + 0x35,
VX_KERNEL_TENSOR_MATRIX_MULTIPLY = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_↵
KHR_BASE) + 0x36,
VX_KERNEL_COPY = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE) + 0x37,
VX_KERNEL_NON_MAX_SUPPRESSION = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KH↵
R_BASE) + 0x38,
VX_KERNEL_SCALAR_OPERATION = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_B↵
ASE) + 0x39,
VX_KERNEL_HOG_FEATURES = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE) +
0x3A,
VX_KERNEL_HOG_CELLS = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE) +
0x3B,
VX_KERNEL_BILATERAL_FILTER = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE)
+ 0x3C,
VX_KERNEL_SELECT = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE) + 0x3D,
VX_KERNEL_MAX_1_2,
VX_KERNEL_MAX = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE) + 0x3E,
VX_KERNEL_MIN = VX_KERNEL_BASE(VX_ID_KHRONOS, VX_LIBRARY_KHR_BASE) + 0x3F }

```

*The standard list of available vision kernels.*

- enum `vx_library_e` { `VX_LIBRARY_KHR_BASE` = 0x0 }

*The standard list of available libraries.*

## Functions

- `vx_kernel VX_API_CALL vxGetKernelByEnum (vx_context context, vx_enum kernel)`  
*Obtains a reference to the kernel using the `vx_kernel_e` enumeration.*
- `vx_kernel VX_API_CALL vxGetKernelByName (vx_context context, const vx_char *name)`  
*Obtains a reference to a kernel using a string to specify the name.*
- `vx_status VX_API_CALL vxQueryKernel (vx_kernel kernel, vx_enum attribute, void *ptr, vx_size size)`  
*This allows the client to query the kernel to get information about the number of parameters, enum values, etc.*
- `vx_status VX_API_CALL vxReleaseKernel (vx_kernel *kernel)`  
*Release the reference to the kernel. The object may not be garbage collected until its total reference count is zero.*

### 3.86.2 Data Structure Documentation

#### struct `vx_kernel_info_t`

The Kernel Information Structure. This is returned by the Context to indicate which kernels are available in the OpenVX implementation.

Definition at line 1608 of file [vx\\_types.h](#).

## Data Fields

|                         |                          |                                                                                                                                                   |
|-------------------------|--------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------|
| <a href="#">vx_enum</a> | enumeration              | The kernel enumeration value from <a href="#">vx_kernel_e</a> (or an extension thereof).<br><br>See also<br><br><a href="#">vxGetKernelByEnum</a> |
| <a href="#">vx_char</a> | name[VX_MAX_KERNEL_NAME] | The kernel name in dotted hierarchical format. e.g. "org.khronos.openvx.sobel_3x3".<br><br>See also<br><br><a href="#">vxGetKernelByName</a>      |

### 3.86.3 Typedef Documentation

**typedef struct \_vx\_kernel\* vx\_kernel**

An opaque reference to the descriptor of a kernel.

See also

[vxGetKernelByName](#)  
[vxGetKernelByEnum](#)

Definition at line 187 of file [vx\\_types.h](#).

### 3.86.4 Enumeration Type Documentation

**enum vx\_library\_e**

The standard list of available libraries.

Enumerator

**VX\_LIBRARY\_KHR\_BASE** The base set of kernels as defined by Khronos.Definition at line 34 of file [vx\\_kernels.h](#).**enum vx\_kernel\_e**

The standard list of available vision kernels.

Each kernel listed here can be used with the [vxGetKernelByEnum](#) call. When programming the parameters, use

- [VX\\_INPUT](#) for [in]
- [VX\\_OUTPUT](#) for [out]
- [VX\\_BIDIRECTIONAL](#) for [in,out]

When programming the parameters, use

- [VX\\_TYPE\\_IMAGE](#) for a [vx\\_image](#) in the size field of [vxGetParameterByIndex](#) or [vxSetParameterByIndex](#) \*
- [VX\\_TYPE\\_ARRAY](#) for a [vx\\_array](#) in the size field of [vxGetParameterByIndex](#) or [vxSetParameterByIndex](#) \*
- or other appropriate types in [vx\\_type\\_e](#).

Enumerator

**VX\_KERNEL\_COLOR\_CONVERT** The Color Space conversion kernel. The conversions are based on the [vx\\_df\\_image\\_e](#) code in the images.

See also

[Color Convert](#)

**VX\_KERNEL\_CHANNEL\_EXTRACT** The Generic Channel Extraction Kernel. This kernel can remove individual color channels from an interleaved or semi-planar, planar, sub-sampled planar image. A client could extract a red channel from an interleaved RGB image or do a Luma extract from a YUV format.

See also

[Channel Extract](#)

**VX\_KERNEL\_CHANNEL\_COMBINE** The Generic Channel Combine Kernel. This kernel combine multiple individual planes into a single multiplanar image of the type specified in the output image.

See also

[Channel Combine](#)

**VX\_KERNEL\_SOBEL\_3x3** The Sobel 3x3 Filter Kernel.

See also

[Sobel 3x3](#)

**VX\_KERNEL\_MAGNITUDE** The Magnitude Kernel. This kernel produces a magnitude plane from two input gradients.

See also

[Magnitude](#)

**VX\_KERNEL\_PHASE** The Phase Kernel. This kernel produces a phase plane from two input gradients.

See also

[Phase](#)

**VX\_KERNEL\_SCALE\_IMAGE** The Scale Image Kernel. This kernel provides resizing of an input image to an output image. The scaling factor is determined but the relative sizes of the input and output.

See also

[Scale Image](#)

**VX\_KERNEL\_TABLE\_LOOKUP** The Table Lookup kernel.

See also

[TableLookup](#)

**VX\_KERNEL\_HISTOGRAM** The Histogram Kernel.

See also

[Histogram](#)

**VX\_KERNEL\_EQUALIZE\_HISTOGRAM** The Histogram Equalization Kernel.

See also

[Equalize Histogram](#)

**VX\_KERNEL\_ABSDIFF** The Absolute Difference Kernel.

See also

[Absolute Difference](#)

**VX\_KERNEL\_MEAN\_STDDEV** The Mean and Standard Deviation Kernel.

See also

[Mean and Standard Deviation](#)

**VX\_KERNEL\_THRESHOLD** The Threshold Kernel.

See also

[Thresholding](#)

**VX\_KERNEL\_INTEGRAL\_IMAGE** The Integral Image Kernel.

See also

[Integral Image](#)

**VX\_KERNEL\_DILATE\_3x3** The dilate kernel.

See also

[Dilate Image](#)

**VX\_KERNEL\_ERODE\_3x3** The erode kernel.

See also

[Erode Image](#)

**VX\_KERNEL\_MEDIAN\_3x3** The median image filter.

See also

[Median Filter](#)

**VX\_KERNEL\_BOX\_3x3** The box filter kernel.

See also

[Box Filter](#)

**VX\_KERNEL\_GAUSSIAN\_3x3** The gaussian filter kernel.

See also

[Gaussian Filter](#)

**VX\_KERNEL\_CUSTOM\_CONVOLUTION** The custom convolution kernel.

See also

[Custom Convolution](#)

**VX\_KERNEL\_GAUSSIAN\_PYRAMID** The gaussian image pyramid kernel.

See also

[Gaussian Image Pyramid](#)

**VX\_KERNEL\_ACCUMULATE** The accumulation kernel.

See also

[Accumulate](#)

**VX\_KERNEL\_ACCUMULATE\_WEIGHTED** The weighed accumulation kernel.

See also

[Accumulate Weighted](#)

**VX\_KERNEL\_ACCUMULATE\_SQUARE** The squared accumulation kernel.

See also

[Accumulate Squared](#)

**VX\_KERNEL\_MINMAXLOC** The min and max location kernel.

See also

[Min, Max Location](#)

**VX\_KERNEL\_CONVERTDEPTH** The bit-depth conversion kernel.

See also

[Convert Bit depth](#)

**VX\_KERNEL\_CANNY\_EDGE\_DETECTOR** The Canny Edge Detector.

See also

[Canny Edge Detector](#)

**VX\_KERNEL\_AND** The Bitwise And Kernel.

See also

[Bitwise AND](#)

**VX\_KERNEL\_OR** The Bitwise Inclusive Or Kernel.

See also

[Bitwise INCLUSIVE OR](#)

**VX\_KERNEL\_XOR** The Bitwise Exclusive Or Kernel.

See also

[Bitwise EXCLUSIVE OR](#)

**VX\_KERNEL\_NOT** The Bitwise Not Kernel.

See also

[Bitwise NOT](#)

**VX\_KERNEL\_MULTIPLY** The Pixelwise Multiplication Kernel.

See also

[Pixel-wise Multiplication](#)

**VX\_KERNEL\_ADD** The Addition Kernel.

See also

[Arithmetic Addition](#)

**VX\_KERNEL\_SUBTRACT** The Subtraction Kernel.

See also

[Arithmetic Subtraction](#)

**VX\_KERNEL\_WARP\_AFFINE** The Warp Affine Kernel.

See also

[Warp Affine](#)

**VX\_KERNEL\_WARP\_PERSPECTIVE** The Warp Perspective Kernel.

See also

[Warp Perspective](#)

**VX\_KERNEL\_HARRIS\_CORNERS** The Harris Corners Kernel.

See also

[Harris Corners](#)

**VX\_KERNEL\_FAST\_CORNERS** The FAST Corners Kernel.

See also

[Fast Corners](#)

**VX\_KERNEL\_OPTICAL\_FLOW\_PYR\_LK** The Optical Flow Pyramid (LK) Kernel.

See also

[Optical Flow Pyramid \(LK\)](#)

**VX\_KERNEL\_REMAP** The Remap Kernel.

See also

[Remap](#)

**VX\_KERNEL\_HALFSCALE\_GAUSSIAN** The Half Scale Gaussian Kernel.

See also

[Scale Image](#)

**VX\_KERNEL\_LAPLACIAN\_PYRAMID** The Laplacian Image Pyramid Kernel.



See also

[Laplacian Image Pyramid](#)

**VX\_KERNEL\_LAPLACIAN\_RECONSTRUCT** The Laplacian Pyramid Reconstruct Kernel.

See also

[Laplacian Image Pyramid](#)

**VX\_KERNEL\_NON\_LINEAR\_FILTER** The Non Linear Filter Kernel.

See also

[Non Linear Filter](#)

**VX\_KERNEL\_MATCH\_TEMPLATE** The Match Template Kernel.

See also

[group\\_vision\\_match\\_template](#)

**VX\_KERNEL\_LBP** The LBP Kernel.

See also

[group\\_lbp](#)

**VX\_KERNEL\_HOUGH\_LINES\_P** The hough lines probability Kernel.

See also

[group\\_vision\\_hough\\_lines\\_p](#)

**VX\_KERNEL\_TENSOR\_MULTIPLY** The tensor multiply Kernel.

See also

[Tensor Multiply](#)

**VX\_KERNEL\_TENSOR\_ADD** The tensor add Kernel.

See also

[Tensor Add](#)

**VX\_KERNEL\_TENSOR\_SUBTRACT** The tensor subtract Kernel.

See also

[Tensor Subtract](#)

**VX\_KERNEL\_TENSOR\_TABLE\_LOOKUP** The tensor table look up Kernel.

See also

[Tensor TableLookUp](#)

**VX\_KERNEL\_TENSOR\_TRANSPOSE** The tensor transpose Kernel.

See also

[Tensor Transpose](#)

**VX\_KERNEL\_TENSOR\_CONVERT\_DEPTH** The tensor convert depth Kernel.

See also

[Tensor Convert Bit-Depth](#)

**VX\_KERNEL\_TENSOR\_MATRIX\_MULTIPLY** The tensor matrix multiply Kernel.

See also

[Tensor Matrix Multiply](#)

**VX\_KERNEL\_COPY** The data object copy kernel.

See also

[Data Object Copy](#)

**VX\_KERNEL\_NON\_MAX\_SUPPRESSION** The non-max suppression kernel.

See also

[Non-Maxima Suppression](#)

**VX\_KERNEL\_SCALAR\_OPERATION** The scalar operation kernel.

See also

[Control Flow](#)

**VX\_KERNEL\_HOG\_FEATURES** The HOG features kernel.

See also

[HOG](#)

**VX\_KERNEL\_HOG\_CELLS** The HOG Cells kernel.

See also

[HOG](#)

**VX\_KERNEL\_BILATERAL\_FILTER** The bilateral filter kernel.

See also

[Bilateral Filter](#)

**VX\_KERNEL\_SELECT** The select kernel.

See also

[Control Flow](#)

**VX\_KERNEL\_MAX** The max kernel.

See also

[Max](#)

**VX\_KERNEL\_MIN** The min kernel.

See also

[Min](#)

Definition at line 52 of file [vx\\_kernels.h](#).

## enum vx\_kernel\_attribute\_e

The kernel attributes list.

Enumerator

**VX\_KERNEL\_PARAMETERS** Queries a kernel for the number of parameters the kernel supports. Read-only. Use a [vx\\_uint32](#) parameter.

**VX\_KERNEL\_NAME** Queries the name of the kernel. Not settable. Read-only. Use a [vx\\_char\[VX\\_MAX\\_KERNEL\\_NAME\]](#) array (not a [vx\\_array](#)).

**VX\_KERNEL\_ENUM** Queries the enum of the kernel. Not settable. Read-only. Use a [vx\\_enum](#) parameter.

**VX\_KERNEL\_LOCAL\_DATA\_SIZE** The local data area allocated with each kernel when it becomes a node. Read-write. Can be written only before user-kernel finalization. Use a [vx\\_size](#) parameter.

Note

If not set it will default to zero.

Definition at line 862 of file [vx\\_types.h](#).

### 3.86.5 Function Documentation

**vx\_kernel VX\_API\_CALL vxGetKernelByName ( vx\_context *context*, const vx\_char \* *name* )**

Obtains a reference to a kernel using a string to specify the name.

User Kernels follow a "dotted" heirarchical syntax. For example: "com.company.example.xyz". The following are strings specifying the kernel names:

```
org.khronos.openvx.color_convert
org.khronos.openvx.channel_extract
org.khronos.openvx.channel_combine
org.khronos.openvx.sobel_3x3
org.khronos.openvx.magnitude
org.khronos.openvx.phase
org.khronos.openvx.scale_image
org.khronos.openvx.table_lookup
org.khronos.openvx.histogram
org.khronos.openvx.equalize_histogram
org.khronos.openvx.absdiff
org.khronos.openvx.mean_stddev
org.khronos.openvx.threshold
org.khronos.openvx.integral_image
org.khronos.openvx.dilate_3x3
org.khronos.openvx.erode_3x3
org.khronos.openvx.median_3x3
org.khronos.openvx.box_3x3
org.khronos.openvx.gaussian_3x3
org.khronos.openvx.custom_convolution
org.khronos.openvx.gaussian_pyramid
org.khronos.openvx.accumulate
org.khronos.openvx.accumulate_weighted
org.khronos.openvx.accumulate_square
org.khronos.openvx.minmaxloc
org.khronos.openvx.convertdepth
org.khronos.openvx.canny_edge_detector
org.khronos.openvx.and
org.khronos.openvx.or
org.khronos.openvx.xor
org.khronos.openvx.not
org.khronos.openvx.multiply
org.khronos.openvx.add
org.khronos.openvx.subtract
org.khronos.openvx.warp_affine
org.khronos.openvx.warp_perspective
org.khronos.openvx.harris_corners
org.khronos.openvx.fast_corners
org.khronos.openvx.optical_flow_pyr_lk
org.khronos.openvx.remap
org.khronos.openvx.halfscale_gaussian
org.khronos.openvx.laplacian_pyramid
org.khronos.openvx.laplacian_reconstruct
org.khronos.openvx.non_linear_filter
org.khronos.openvx.match_template
org.khronos.openvx.lbp
org.khronos.openvx.hough_lines_p
org.khronos.openvx.tensor_multiply
org.khronos.openvx.tensor_add
org.khronos.openvx.tensor_subtract
org.khronos.openvx.tensor_table_lookup
org.khronos.openvx.tensor_transpose
```

org.khronos.openvx.tensor\_convert\_depth  
 org.khronos.openvx.tensor\_matrix\_multiply  
 org.khronos.openvx.copy  
 org.khronos.openvx.non\_max\_suppression  
 org.khronos.openvx.scalar\_operation  
 org.khronos.openvx.hog\_features  
 org.khronos.openvx.hog\_cells  
 org.khronos.openvx.bilateral\_filter  
 org.khronos.openvx.select  
 org.khronos.openvx.min  
 org.khronos.openvx.max

#### Parameters

|    |                |                                              |
|----|----------------|----------------------------------------------|
| in | <i>context</i> | The reference to the implementation context. |
| in | <i>name</i>    | The string of the name of the kernel to get. |

#### Returns

A kernel reference. Any possible errors preventing a successful completion of the function should be checked using [vxGetStatus](#).

#### Precondition

[vxLoadKernels](#) if the kernel is not provided by the OpenVX implementation.

#### Note

User Kernels should follow a "dotted" hierarchical syntax. For example: "com.company.example.xyz".

### **vx\_kernel VX\_API\_CALL vxGetKernelByEnum ( vx\_context *context*, vx\_enum *kernel* )**

Obtains a reference to the kernel using the [vx\\_kernel\\_e](#) enumeration.

Enum values above the standard set are assumed to apply to loaded libraries.

#### Parameters

|    |                |                                                                               |
|----|----------------|-------------------------------------------------------------------------------|
| in | <i>context</i> | The reference to the implementation context.                                  |
| in | <i>kernel</i>  | A value from <a href="#">vx_kernel_e</a> or a vendor or client-defined value. |

#### Returns

A [vx\\_kernel](#) reference. Any possible errors preventing a successful completion of the function should be checked using [vxGetStatus](#).

#### Precondition

[vxLoadKernels](#) if the kernel is not provided by the OpenVX implementation.

### **vx\_status VX\_API\_CALL vxQueryKernel ( vx\_kernel *kernel*, vx\_enum *attribute*, void \* *ptr*, vx\_size *size* )**

This allows the client to query the kernel to get information about the number of parameters, enum values, etc.

#### Parameters

|    |               |                                |
|----|---------------|--------------------------------|
| in | <i>kernel</i> | The kernel reference to query. |
|----|---------------|--------------------------------|

**Parameters**

|     |                  |                                                                       |
|-----|------------------|-----------------------------------------------------------------------|
| in  | <i>attribute</i> | The attribute to query. Use a <a href="#">vx_kernel_attribute_e</a> . |
| out | <i>ptr</i>       | The pointer to the location at which to store the resulting value.    |
| in  | <i>size</i>      | The size of the container to which <i>ptr</i> points.                 |

**Returns**

A [vx\\_status\\_e](#) enumeration.

**Return values**

|                                    |                                                                 |
|------------------------------------|-----------------------------------------------------------------|
| <i>VX_SUCCESS</i>                  | No errors; any other value indicates failure.                   |
| <i>VX_ERROR_INVALID_REFERENCE</i>  | kernel is not a valid <a href="#">vx_kernel</a> reference.      |
| <i>VX_ERROR_INVALID_PARAMETERS</i> | If any of the other parameters are incorrect.                   |
| <i>VX_ERROR_NOT_SUPPORTED</i>      | If the attribute value is not supported in this implementation. |

**vx\_status VX\_API\_CALL vxReleaseKernel ( vx\_kernel \* *kernel* )**

Release the reference to the kernel. The object may not be garbage collected until its total reference count is zero.

**Parameters**

|    |               |                                                 |
|----|---------------|-------------------------------------------------|
| in | <i>kernel</i> | The pointer to the kernel reference to release. |
|----|---------------|-------------------------------------------------|

**Postcondition**

After returning from this function the reference is zeroed.

**Returns**

A [vx\\_status\\_e](#) enumeration.

**Return values**

|                                   |                                                            |
|-----------------------------------|------------------------------------------------------------|
| <i>VX_SUCCESS</i>                 | No errors; any other value indicates failure.              |
| <i>VX_ERROR_INVALID_REFERENCE</i> | kernel is not a valid <a href="#">vx_kernel</a> reference. |

## 3.87 Object: Parameter

### 3.87.1 Detailed Description

Defines the Parameter Object interface.

An abstract input, output, or bidirectional data object passed to a computer vision function. This object contains the signature of that parameter's usage from the kernel description. This information includes:

- *Signature Index* - The numbered index of the parameter in the signature.
- *Object Type* - e.g., `VX_TYPE_IMAGE` or `VX_TYPE_ARRAY` or some other object type from `vx_type_e`.
- *Usage Model* - e.g., `VX_INPUT`, `VX_OUTPUT`, or `VX_BIDIRECTIONAL`.
- *Presence State* - e.g., `VX_PARAMETER_STATE_REQUIRED` or `VX_PARAMETER_STATE_OPTIONAL`.

### Typedefs

- typedef struct \_vx\_parameter \* `vx_parameter`

*An opaque reference to a single parameter.*

### Enumerations

- enum `vx_direction_e` {  
`VX_INPUT` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_DIRECTION` << 12)) + 0x0,  
`VX_OUTPUT` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_DIRECTION` << 12)) + 0x1,  
`VX_BIDIRECTIONAL` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_DIRECTION` << 12)) + 0x2 }  
*An indication of how a kernel will treat the given parameter.*
- enum `vx_parameter_attribute_e` {  
`VX_PARAMETER_INDEX` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_TYPE_PARAMETER` << 8)) + 0x0,  
`VX_PARAMETER_DIRECTION` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_TYPE_PARAMETER` << 8)) + 0x1,  
`VX_PARAMETER_TYPE` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_TYPE_PARAMETER` << 8)) + 0x2,  
`VX_PARAMETER_STATE` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_TYPE_PARAMETER` << 8)) + 0x3,  
`VX_PARAMETER_REF` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_TYPE_PARAMETER` << 8)) + 0x4 }  
*The parameter attributes list.*
- enum `vx_parameter_state_e` {  
`VX_PARAMETER_STATE_REQUIRED` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_PARAMETER_STATE` << 12)) + 0x0,  
`VX_PARAMETER_STATE_OPTIONAL` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_PARAMETER_STATE` << 12)) + 0x1 }  
*The parameter state type.*

### Functions

- `vx_parameter VX_API_CALL vxGetKernelParameterByIndex (vx_kernel kernel, vx_uint32 index)`  
*Retrieves a `vx_parameter` from a `vx_kernel`.*
- `vx_parameter VX_API_CALL vxGetParameterByIndex (vx_node node, vx_uint32 index)`  
*Retrieves a `vx_parameter` from a `vx_node`.*
- `vx_status VX_API_CALL vxQueryParameter (vx_parameter parameter, vx_enum attribute, void *ptr, vx_size size)`  
*Allows the client to query a parameter to determine its meta-information.*
- `vx_status VX_API_CALL vxReleaseParameter (vx_parameter *param)`  
*Releases a reference to a parameter object. The object may not be garbage collected until its total reference count is zero.*
- `vx_status VX_API_CALL vxSetParameterByIndex (vx_node node, vx_uint32 index, vx_reference value)`  
*Sets the specified parameter data for a kernel on the node.*
- `vx_status VX_API_CALL vxSetParameterByReference (vx_parameter parameter, vx_reference value)`  
*Associates a parameter reference and a data reference with a kernel on a node.*

### 3.87.2 Typedef Documentation

**typedef struct \_vx\_parameter\* vx\_parameter**

An opaque reference to a single parameter.

See also

[vxGetParameterByIndex](#)

Definition at line 194 of file [vx\\_types.h](#).

### 3.87.3 Enumeration Type Documentation

**enum vx\_direction\_e**

An indication of how a kernel will treat the given parameter.

Enumerator

**VX\_INPUT** The parameter is an input only.

**VX\_OUTPUT** The parameter is an output only.

**VX\_BIDIRECTIONAL** The parameter is both an input and output.

Definition at line 611 of file [vx\\_types.h](#).

**enum vx\_parameter\_attribute\_e**

The parameter attributes list.

Enumerator

**VX\_PARAMETER\_INDEX** Queries a parameter for its index value on the kernel with which it is associated. Read-only. Use a [vx\\_uint32](#) parameter.

**VX\_PARAMETER\_DIRECTION** Queries a parameter for its direction value on the kernel with which it is associated. Read-only. Use a [vx\\_enum](#) parameter.

**VX\_PARAMETER\_TYPE** Queries a parameter for its type, [vx\\_type\\_e](#) is returned. Read-only. The size of the parameter is implied for plain data objects. For opaque data objects like images and arrays a query to their attributes has to be called to determine the size.

**VX\_PARAMETER\_STATE** Queries a parameter for its state. A value in [vx\\_parameter\\_state\\_e](#) is returned. Read-only. Use a [vx\\_enum](#) parameter.

**VX\_PARAMETER\_REF** Use to extract the reference contained in the parameter. Read-only. Use a [vx\\_reference](#) parameter.

Definition at line 930 of file [vx\\_types.h](#).

**enum vx\_parameter\_state\_e**

The parameter state type.

Enumerator

**VX\_PARAMETER\_STATE\_REQUIRED** Default. The parameter must be supplied. If not set, during Verify, an error is returned.

**VX\_PARAMETER\_STATE\_OPTIONAL** The parameter may be unspecified. The kernel takes care not to deference optional parameters until it is certain they are valid.

Definition at line 1322 of file [vx\\_types.h](#).

### 3.87.4 Function Documentation

**vx\_parameter VX\_API\_CALL vxGetKernelParameterByIndex ( vx\_kernel kernel, vx\_uint32 index )**

Retrieves a [vx\\_parameter](#) from a [vx\\_kernel](#).

**Parameters**

|    |               |                              |
|----|---------------|------------------------------|
| in | <i>kernel</i> | The reference to the kernel. |
| in | <i>index</i>  | The index of the parameter.  |

**Returns**

A `vx_parameter` reference. Any possible errors preventing a successful completion of the function should be checked using `vxGetStatus`.

**vx\_parameter VX\_API\_CALL vxGetParameterByIndex ( vx\_node *node*, vx\_uint32 *index* )**

Retrieves a `vx_parameter` from a `vx_node`.

**Parameters**

|    |              |                                                         |
|----|--------------|---------------------------------------------------------|
| in | <i>node</i>  | The node from which to extract the parameter.           |
| in | <i>index</i> | The index of the parameter to which to get a reference. |

**Returns**

A parameter reference `vx_parameter`. Any possible errors preventing a successful completion of the function should be checked using `vxGetStatus`.

**vx\_status VX\_API\_CALL vxReleaseParameter ( vx\_parameter \* *param* )**

Releases a reference to a parameter object. The object may not be garbage collected until its total reference count is zero.

**Parameters**

|    |              |                                          |
|----|--------------|------------------------------------------|
| in | <i>param</i> | The pointer to the parameter to release. |
|----|--------------|------------------------------------------|

**Postcondition**

After returning from this function the reference is zeroed.

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                                         |                                                                  |
|-----------------------------------------|------------------------------------------------------------------|
| <code>VX_SUCCESS</code>                 | No errors; any other value indicates failure.                    |
| <code>VX_ERROR_INVALID_REFERENCE</code> | <i>param</i> is not a valid <code>vx_parameter</code> reference. |

**vx\_status VX\_API\_CALL vxSetParameterByIndex ( vx\_node *node*, vx\_uint32 *index*, vx\_reference *value* )**

Sets the specified parameter data for a kernel on the node.

**Parameters**

|    |              |                                     |
|----|--------------|-------------------------------------|
| in | <i>node</i>  | The node that contains the kernel.  |
| in | <i>index</i> | The index of the parameter desired. |



**Parameters**

|    |              |                                     |
|----|--------------|-------------------------------------|
| in | <i>value</i> | The desired value of the parameter. |
|----|--------------|-------------------------------------|

**Note**

A user may not provide a NULL value for a mandatory parameter of this API.

**Returns**

A [vx\\_status\\_e](#) enumeration.

**Return values**

|                                   |                                                                                                                        |
|-----------------------------------|------------------------------------------------------------------------------------------------------------------------|
| <i>VX_SUCCESS</i>                 | No errors; any other value indicates failure.                                                                          |
| <i>VX_ERROR_INVALID_REFERENCE</i> | node is not a valid <a href="#">vx_node</a> reference, or value is not a valid <a href="#">vx_reference</a> reference. |

**See also**

[vxSetParameterByReference](#)

**vx\_status VX\_API\_CALL vxSetParameterByReference ( vx\_parameter *parameter*, vx\_reference *value* )**

Associates a parameter reference and a data reference with a kernel on a node.

**Parameters**

|    |                  |                                                   |
|----|------------------|---------------------------------------------------|
| in | <i>parameter</i> | The reference to the kernel parameter.            |
| in | <i>value</i>     | The value to associate with the kernel parameter. |

**Note**

A user may not provide a NULL value for a mandatory parameter of this API.

**Returns**

A [vx\\_status\\_e](#) enumeration.

**Return values**

|                                   |                                                                                                                                   |
|-----------------------------------|-----------------------------------------------------------------------------------------------------------------------------------|
| <i>VX_SUCCESS</i>                 | No errors; any other value indicates failure.                                                                                     |
| <i>VX_ERROR_INVALID_REFERENCE</i> | parameter is not a valid <a href="#">vx_parameter</a> reference, or value is not a valid <a href="#">vx_reference</a> reference.. |

**See also**

[vxGetParameterByIndex](#)

**vx\_status VX\_API\_CALL vxQueryParameter ( vx\_parameter *parameter*, vx\_enum *attribute*, void \* *ptr*, vx\_size *size* )**

Allows the client to query a parameter to determine its meta-information.

**Parameters**

|     |                  |                                                                          |
|-----|------------------|--------------------------------------------------------------------------|
| in  | <i>parameter</i> | The reference to the parameter.                                          |
| in  | <i>attribute</i> | The attribute to query. Use a <a href="#">vx_parameter_attribute_e</a> . |
| out | <i>ptr</i>       | The location at which to store the resulting value.                      |
| in  | <i>size</i>      | The size in bytes of the container to which <i>ptr</i> points.           |

**Returns**

A [vx\\_status\\_e](#) enumeration.

**Return values**

|                                   |                                                                  |
|-----------------------------------|------------------------------------------------------------------|
| <i>VX_SUCCESS</i>                 | No errors; any other value indicates failure.                    |
| <i>VX_ERROR_INVALID_REFERENCE</i> | parameter is not a valid <a href="#">vx_parameter</a> reference. |

## 3.88 Advanced Framework API

### 3.88.1 Detailed Description

Describes components that are considered to be advanced.

Advanced topics include: extensions through User Kernels; Reflection and Introspection; Performance Tweaking through Hinting and Directives; and Debugging Callbacks.

#### Modules

- [Framework: Node Callbacks](#)  
*Allows Clients to receive a callback after a specific node has completed execution.*
- [Framework: Performance Measurement](#)  
*Defines Performance measurement and reporting interfaces.*
- [Framework: Log](#)  
*Defines the debug logging interface.*
- [Framework: Hints](#)  
*Defines the Hints Interface.*
- [Framework: Directives](#)  
*Defines the Directives Interface.*
- [Framework: User Kernels](#)  
*Defines the User Kernels, which are a method to extend OpenVX with new vision functions.*
- [Framework: Graph Parameters](#)  
*Defines the Graph Parameter API.*

## 3.89 Framework: Node Callbacks

### 3.89.1 Detailed Description

Allows Clients to receive a callback after a specific node has completed execution.

Callbacks are not guaranteed to be called *immediately* after the Node completes. Callbacks are intended to be used to create simple *early exit* conditions for Vision graphs using `vx_action_e` return values. An example of setting up a callback can be seen below:

```
vx_graph graph = vxCreateGraph(context);
status = vxGetStatus((vx_reference)graph);
if (status == VX_SUCCESS) {
 vx_uint8 lmin = 0, lmax = 0;
 vx_uint32 minCount = 0, maxCount = 0;
 vx_scalar scalars[] = {
 vxCreateScalar(context, VX_TYPE_UINT8, &lmin),
 vxCreateScalar(context, VX_TYPE_UINT8, &lmax),
 vxCreateScalar(context, VX_TYPE_UINT32, &minCount),
 vxCreateScalar(context, VX_TYPE_UINT32, &maxCount),
 };
 vx_array arrays[] = {
 vxCreateArray(context, VX_TYPE_COORDINATES2D, 1),
 vxCreateArray(context, VX_TYPE_COORDINATES2D, 1)
 };
 vx_node nodes[] = {
 vxMinMaxLocNode(graph, input, scalars[0], scalars[1], arrays[0], arrays[1],
 scalars[2], scalars[3]),
 };
 status = vxAssignNodeCallback(nodes[0], &analyze_brightness);
 // do other
}
```

Once the graph has been initialized and the callback has been installed then the callback itself will be called during graph execution.

```
#define MY_DESIRED_THRESHOLD (10)
vx_action VX_CALLBACK analyze_brightness(vx_node node) {
 // extract the max value
 vx_action action = VX_ACTION_ABANDON;
 vx_parameter pmax = vxGetParameterByIndex(node, 2); // Max Value
 if (pmax) {
 vx_scalar smax = 0;
 vxQueryParameter(pmax, VX_PARAMETER_REF, &smax, sizeof(smax));
 if (smax) {
 vx_uint8 value = 0u;
 vxCopyScalar(smax, &value, VX_READ_ONLY,
 VX_MEMORY_TYPE_HOST);
 if (value >= MY_DESIRED_THRESHOLD) {
 action = VX_ACTION_CONTINUE;
 }
 vxReleaseScalar(&smax);
 }
 vxReleaseParameter(&pmax);
 }
 return action;
}
```

#### Warning

This should be used with **extreme** caution as it can *ruin* optimizations in the power/performance efficiency of a graph.

The callback must return a `vx_action` code indicating how the graph processing should proceed.

- If `VX_ACTION_CONTINUE` is returned, the graph will continue execution with no changes.
- If `VX_ACTION_ABANDON` is returned, execution is unspecified for all nodes for which this node is a dominator. Nodes that are dominators of this node will have executed. Execution of any other node is unspecified.




Figure 3.2: Node Callback Sequence

## Typedefs

- typedef `vx_enum vx_action`  
The formal typedef of the response from the callback.
- typedef `vx_action(* vx_nodecomplete_f) (vx_node node)`  
A callback to the client after a particular node has completed.

## Enumerations

- enum `vx_action_e` {  
`VX_ACTION_CONTINUE` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_ACTION` << 12)) + 0x0,  
`VX_ACTION_ABANDON` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_ACTION` << 12)) + 0x1 }  
 A return code enumeration from a `vx_nodecomplete_f` during execution.

## Functions

- `vx_status VX_API_CALL vxAssignNodeCallback (vx_node node, vx_nodecomplete_f callback)`  
Assigns a callback to a node. If a callback already exists in this node, this function must return an error and the user may clear the callback by passing a NULL pointer as the callback.
- `vx_nodecomplete_f VX_API_CALL vxRetrieveNodeCallback (vx_node node)`  
Retrieves the current node callback function pointer set on the node.

### 3.89.2 Typedef Documentation

#### **typedef vx\_enum vx\_action**

The formal typedef of the response from the callback.

See also

[vx\\_action\\_e](#)

Definition at line 451 of file [vx\\_types.h](#).

#### **typedef vx\_action( \* vx\_nodecomplete\_f ) ( vx\_node node )**

A callback to the client after a particular node has completed.

See also

[vx\\_action](#)

[vxAssignNodeCallback](#)

#### Parameters

|    |             |                                              |
|----|-------------|----------------------------------------------|
| in | <i>node</i> | The node to which the callback was attached. |
|----|-------------|----------------------------------------------|

#### Returns

An action code from [vx\\_action\\_e](#).

Definition at line 460 of file [vx\\_types.h](#).

### 3.89.3 Enumeration Type Documentation

#### **enum vx\_action\_e**

A return code enumeration from a [vx\\_nodecomplete\\_f](#) during execution.

See also

[vxAssignNodeCallback](#)

#### Enumerator

**VX\_ACTION\_CONTINUE** Continue executing the graph with no changes.

**VX\_ACTION\_ABANDON** Stop executing the graph.

Definition at line 601 of file [vx\\_types.h](#).

### 3.89.4 Function Documentation

#### **vx\_status VX\_API\_CALL vxAssignNodeCallback ( vx\_node node, vx\_nodecomplete\_f callback )**

Assigns a callback to a node. If a callback already exists in this node, this function must return an error and the user may clear the callback by passing a NULL pointer as the callback.

#### Parameters

|    |                 |                                                                  |
|----|-----------------|------------------------------------------------------------------|
| in | <i>node</i>     | The reference to the node.                                       |
| in | <i>callback</i> | The callback to associate with completion of this specific node. |

### Warning

This must be used with **extreme** caution as it can *ruin* optimizations in the power/performance efficiency of a graph.

### Returns

A `vx_status_e` enumeration.

### Return values

|                                         |                                                       |
|-----------------------------------------|-------------------------------------------------------|
| <code>VX_SUCCESS</code>                 | Callback assigned; any other value indicates failure. |
| <code>VX_ERROR_INVALID_REFERENCE</code> | node is not a valid <code>vx_node</code> reference.   |

### `vx_nodecomplete_f VX_API_CALL vxRetrieveNodeCallback ( vx_node node )`

Retrieves the current node callback function pointer set on the node.

### Parameters

|    |                   |                                                   |
|----|-------------------|---------------------------------------------------|
| in | <code>node</code> | The reference to the <code>vx_node</code> object. |
|----|-------------------|---------------------------------------------------|

### Returns

`vx_nodecomplete_f` The pointer to the callback function.

### Return values

|                   |                             |
|-------------------|-----------------------------|
| <code>NULL</code> | No callback is set.         |
| *                 | The node callback function. |

## 3.90 Framework: Performance Measurement

### 3.90.1 Detailed Description

Defines Performance measurement and reporting interfaces.

In OpenVX, both `vx_graph` objects and `vx_node` objects track performance information. A client can query either object type using their respective `vxQuery<Object>` function with their attribute enumeration `VX_<Object>_PERFORMANCE` along with a `vx_perf_t` structure to obtain the performance information.

```
vx_perf_t perf;
vxQueryNode(node, VX_NODE_PERFORMANCE, &perf, sizeof(perf));
```

### Data Structures

- struct `vx_perf_t`

*The performance measurement structure. The time or durations are in units of nano seconds. [More...](#)*

### 3.90.2 Data Structure Documentation

#### struct `vx_perf_t`

The performance measurement structure. The time or durations are in units of nano seconds.

Definition at line 1538 of file `vx_types.h`.

#### Data Fields

|                        |     |                                       |
|------------------------|-----|---------------------------------------|
| <code>vx_uint64</code> | tmp | Holds the last measurement.           |
| <code>vx_uint64</code> | beg | Holds the first measurement in a set. |
| <code>vx_uint64</code> | end | Holds the last measurement in a set.  |
| <code>vx_uint64</code> | sum | Holds the summation of durations.     |
| <code>vx_uint64</code> | avg | Holds the average of the durations.   |
| <code>vx_uint64</code> | min | Holds the minimum of the durations.   |
| <code>vx_uint64</code> | num | Holds the number of measurements.     |
| <code>vx_uint64</code> | max | Holds the maximum of the durations.   |



## 3.91 Framework: Log

### 3.91.1 Detailed Description

Defines the debug logging interface.

The functions of the debugging interface allow clients to receive important debugging information about OpenVX.

See also

[vx\\_status\\_e](#) for the list of possible errors.




Figure 3.3: Log messages only can be received after the callback is installed.

### Typedefs

- typedef void(\* [vx\\_log\\_callback\\_f](#)) ([vx\\_context](#) context, [vx\\_reference](#) ref, [vx\\_status](#) status, const [vx\\_char](#) string[])

*The log callback function.*

### Functions

- void [VX\\_API\\_CALL vxAddLogEntry](#) ([vx\\_reference](#) ref, [vx\\_status](#) status, const char \*message,...)  
*Adds a line to the log.*
- void [VX\\_API\\_CALL vxRegisterLogCallback](#) ([vx\\_context](#) context, [vx\\_log\\_callback\\_f](#) callback, [vx\\_bool](#) reentrant)

*Registers a callback facility to the OpenVX implementation to receive error logs.*

### 3.91.2 Function Documentation

**void [VX\\_API\\_CALL vxAddLogEntry](#) ( [vx\\_reference](#) ref, [vx\\_status](#) status, const char \* message, ... )**

Adds a line to the log.

#### Parameters

|    |                |                                                                                       |
|----|----------------|---------------------------------------------------------------------------------------|
| in | <i>ref</i>     | The reference to add the log entry against. Some valid value must be provided.        |
| in | <i>status</i>  | The status code. <a href="#">VX_SUCCESS</a> status entries are ignored and not added. |
| in | <i>message</i> | The human readable message to add to the log.                                         |
| in | <i>...</i>     | a list of variable arguments to the message.                                          |

**Note**

Messages may not exceed `VX_MAX_LOG_MESSAGE_LEN` bytes and will be truncated in the log if they exceed this limit.

**void VX\_API\_CALL vxRegisterLogCallback ( vx\_context *context*, vx\_log\_callback\_f *callback*, vx\_bool *reentrant* )**

Registers a callback facility to the OpenVX implementation to receive error logs.

**Parameters**

|    |                  |                                                                                                                                                             |
|----|------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>context</i>   | The overall context to OpenVX.                                                                                                                              |
| in | <i>callback</i>  | The callback function. If NULL, the previous callback is removed.                                                                                           |
| in | <i>reentrant</i> | If reentrancy flag is <code>vx_true_e</code> , then the callback may be entered from multiple simultaneous tasks or threads (if the host OS supports this). |

## 3.92 Framework: Hints

### 3.92.1 Detailed Description

Defines the Hints Interface.

*Hints* are messages given to the OpenVX implementation that it may support. (These are optional.)

#### Enumerations

- enum `vx_hint_e` {  
`VX_HINT_PERFORMANCE_DEFAULT` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_HINT` << 12)) + 0x1,  
`VX_HINT_PERFORMANCE_LOW_POWER` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_HINT` << 12)) + 0x2,  
`VX_HINT_PERFORMANCE_HIGH_SPEED` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_HINT` << 12)) + 0x3 }

*These enumerations are given to the `vxHint` API to enable/disable platform optimizations and/or features. Hints are optional and usually are vendor-specific.*

#### Functions

- `vx_status VX_API_CALL vxHint (vx_reference reference, vx_enum hint, const void *data, vx_size data_size)`

*Provides a generic API to give platform-specific hints to the implementation.*

### 3.92.2 Enumeration Type Documentation

#### enum `vx_hint_e`

These enumerations are given to the `vxHint` API to enable/disable platform optimizations and/or features. Hints are optional and usually are vendor-specific.

See also

`vxHint`

Enumerator

**`VX_HINT_PERFORMANCE_DEFAULT`** Indicates to the implementation that user do not apply any specific requirements for performance.

**`VX_HINT_PERFORMANCE_LOW_POWER`** Indicates the user preference is low power consumption versus highest performance.

**`VX_HINT_PERFORMANCE_HIGH_SPEED`** Indicates the user preference for highest performance over low power consumption.

Definition at line 625 of file `vx_types.h`.

### 3.92.3 Function Documentation

**`vx_status VX_API_CALL vxHint ( vx_reference reference, vx_enum hint, const void * data, vx_size data_size )`**

Provides a generic API to give platform-specific hints to the implementation.

Parameters

|    |                  |                                                                                                                                                                                                        |
|----|------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>reference</i> | The reference to the object to hint at. This could be <code>vx_context</code> , <code>vx_graph</code> , <code>vx_node</code> , <code>vx_image</code> , <code>vx_array</code> , or any other reference. |
| in | <i>hint</i>      | A <code>vx_hint_e</code> hint to give to a <code>vx_context</code> . This is a platform-specific optimization or implementation mechanism.                                                             |
| in | <i>data</i>      | Optional vendor specific data.                                                                                                                                                                         |
| in | <i>data_size</i> | Size of the data structure <i>data</i> .                                                                                                                                                               |

## Returns

A `vx_status_e` enumeration.

## Return values

|                                         |                                                               |
|-----------------------------------------|---------------------------------------------------------------|
| <code>VX_SUCCESS</code>                 | No errors; any other value indicates failure.                 |
| <code>VX_ERROR_INVALID_REFERENCE</code> | reference is not a valid <code>vx_reference</code> reference. |
| <code>VX_ERROR_NOT_SUPPORTED</code>     | If the hint is not supported.                                 |

## 3.93 Framework: Directives

### 3.93.1 Detailed Description

Defines the Directives Interface.

*Directives* are messages given the OpenVX implementation that it must support. (These are required, i.e., non-optional.)

#### Enumerations

- enum `vx_directive_e` {  
`VX_DIRECTIVE_DISABLE_LOGGING` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_DIRECTIVE` << 12)) + 0x0,  
`VX_DIRECTIVE_ENABLE_LOGGING` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_DIRECTIVE` << 12)) + 0x1,  
`VX_DIRECTIVE_DISABLE_PERFORMANCE` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_DIRECTIVE` << 12)) + 0x2,  
`VX_DIRECTIVE_ENABLE_PERFORMANCE` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_ENUM_DIRECTIVE` << 12)) + 0x3 }

*These enumerations are given to the `vxDirective` API to enable/disable platform optimizations and/or features. Directives are not optional and usually are vendor-specific, by defining a vendor range of directives and starting their enumeration from there.*

#### Functions

- `vx_status VX_API_CALL vxDirective (vx_reference reference, vx_enum directive)`

*Provides a generic API to give platform-specific directives to the implementations.*

### 3.93.2 Enumeration Type Documentation

#### enum `vx_directive_e`

These enumerations are given to the `vxDirective` API to enable/disable platform optimizations and/or features. Directives are not optional and usually are vendor-specific, by defining a vendor range of directives and starting their enumeration from there.

See also

`vxDirective`

Enumerator

**`VX_DIRECTIVE_DISABLE_LOGGING`** Disables recording information for graph debugging.

**`VX_DIRECTIVE_ENABLE_LOGGING`** Enables recording information for graph debugging.

**`VX_DIRECTIVE_DISABLE_PERFORMANCE`** Disables performance counters for the context. By default performance counters are disabled.

**`VX_DIRECTIVE_ENABLE_PERFORMANCE`** Enables performance counters for the context.

Definition at line 647 of file `vx_types.h`.

### 3.93.3 Function Documentation

`vx_status VX_API_CALL vxDirective ( vx_reference reference, vx_enum directive )`

Provides a generic API to give platform-specific directives to the implementations.

Parameters

|    |                  |                                                                                                                                                                                                                     |
|----|------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>reference</i> | The reference to the object to set the directive on. This could be <code>vx_context</code> , <code>vx_graph</code> , <code>vx_node</code> , <code>vx_image</code> , <code>vx_array</code> , or any other reference. |
| in | <i>directive</i> | The directive to set. See <code>vx_directive_e</code> .                                                                                                                                                             |

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                                         |                                                               |
|-----------------------------------------|---------------------------------------------------------------|
| <code>VX_SUCCESS</code>                 | No errors; any other value indicates failure.                 |
| <code>VX_ERROR_INVALID_REFERENCE</code> | reference is not a valid <code>vx_reference</code> reference. |
| <code>VX_ERROR_NOT_SUPPORTED</code>     | If the directive is not supported.                            |

**Note**

The performance counter directives are only available for the reference `vx_context`. Error `VX_ERROR_NOT_SUPPORTED` is returned when used with any other reference.

## 3.94 Framework: User Kernels

### 3.94.1 Detailed Description

Defines the User Kernels, which are a method to extend OpenVX with new vision functions.

User Kernels can be loaded by OpenVX and included as nodes in the graph or as immediate functions (if the Client supplies the interface). User Kernels will typically be loaded and executed on High Level Operating System/CPU compatible targets, not on remote processors or other accelerators. This specification does not mandate what constitutes compatible platforms.




Figure 3.4: Call sequence of User Kernels Installation




Figure 3.5: Call sequence of a Graph Verify and Release with User Kernels.




Figure 3.6: Call sequence of a Graph Execution with User Kernels

During the first graph verification, the implementation will perform the following action sequence:

1. Initialize local data node attributes

- If `VX_KERNEL_LOCAL_DATA_SIZE == 0`, then set `VX_NODE_LOCAL_DATA_SIZE` to 0 and set `VX_NODE_LOCAL_DATA_PTR` to NULL.



- If `VX_KERNEL_LOCAL_DATA_SIZE` != 0, set `VX_NODE_LOCAL_DATA_SIZE` to `VX_KERNEL_LOCAL_DATA_SIZE` and set `VX_NODE_LOCAL_DATA_PTR` to the address of a buffer of `VX_KERNEL_LOCAL_DATA_SIZE` bytes.
2. Call the `vx_kernel_validate_f` callback.
  3. Call the `vx_kernel_initialize_f` callback (if not NULL):
    - If `VX_KERNEL_LOCAL_DATA_SIZE` == 0, the callback is allowed to set `VX_NODE_LOCAL_DATA_SIZE` and `VX_NODE_LOCAL_DATA_PTR`.
    - If `VX_KERNEL_LOCAL_DATA_SIZE` != 0, then any attempt by the callback to set `VX_NODE_LOCAL_DATA_SIZE` or `VX_NODE_LOCAL_DATA_PTR` attributes will generate an error.
  4. Provide the buffer optionally requested by the application
    - If `VX_KERNEL_LOCAL_DATA_SIZE` == 0 and `VX_NODE_LOCAL_DATA_SIZE` != 0, and `VX_NODE_LOCAL_DATA_PTR` == NULL, then the implementation will set `VX_NODE_LOCAL_DATA_PTR` to the address of a buffer of `VX_NODE_LOCAL_DATA_SIZE` bytes.

At node destruction time, the implementation will perform the following action sequence:

1. Call `vx_kernel_deinitialize_f` callback (if not NULL): If the `VX_NODE_LOCAL_DATA_PTR` was set earlier by the implementation, then any attempt by the callback to set the `VX_NODE_LOCAL_DATA_PTR` attributes will generate an error.
2. If the `VX_NODE_LOCAL_DATA_PTR` was set earlier by the implementation, then the pointed memory must not be used anymore by the application after the `vx_kernel_deinitialize_f` callback completes.

A user node requires re-verification, if any changes below occurred after the last node verification:

1. The `VX_NODE_BORDER` node attribute was modified.
2. At least one of the node parameters was replaced by a data object with different meta-data, or was replaced by the 0 reference for optional parameters, or was set to a data object if previously not set because optional.

The node re-verification can be triggered explicitly by the application by calling `vxVerifyGraph` that will perform a complete graph verification. Otherwise, it will be triggered automatically at the next graph execution.

During user node re-verification, the following action sequence will occur:

1. Call the `vx_kernel_deinitialize_f` callback (if not NULL): If the `VX_NODE_LOCAL_DATA_PTR` was set earlier by the OpenVX implementation, then any attempt by the callback to set the `VX_NODE_LOCAL_DATA_PTR` attributes will generate an error.
2. Reinitialize local data node attributes if needed If `VX_KERNEL_LOCAL_DATA_SIZE` == 0:
  - set `VX_NODE_LOCAL_DATA_PTR` to NULL.
  - set `VX_NODE_LOCAL_DATA_SIZE` to 0.
3. Call the `vx_kernel_validate_f` callback.
4. Call the `vx_kernel_initialize_f` callback (if not NULL):
  - If `VX_KERNEL_LOCAL_DATA_SIZE` == 0, the callback is allowed to set `VX_NODE_LOCAL_DATA_SIZE` and `VX_NODE_LOCAL_DATA_PTR`.
  - If `VX_KERNEL_LOCAL_DATA_SIZE` is != 0, then any attempt by the callback to set `VX_NODE_LOCAL_DATA_SIZE` or `VX_NODE_LOCAL_DATA_PTR` attributes will generate an error.
5. Provide the buffer optionally requested by the application
  - If `VX_KERNEL_LOCAL_DATA_SIZE` == 0 and `VX_NODE_LOCAL_DATA_SIZE` != 0, and `VX_NODE_LOCAL_DATA_PTR` == NULL, then the OpenVX implementation will set `VX_NODE_LOCAL_DATA_PTR` to the address of a buffer of `VX_NODE_LOCAL_DATA_SIZE` bytes.

When an OpenVX implementation sets the `VX_NODE_LOCAL_DATA_PTR`, the data inside the buffer will not be persistent between kernel executions.

## Typedefs

- typedef `vx_status(* vx_kernel_deinitialize_f)` (`vx_node` node, const `vx_reference` \*parameters, `vx_uint32` num)  
*The pointer to the kernel deinitializer. If the host code requires a call to deinitialize data during a node garbage collection, this function is called if not NULL.*
- typedef `vx_status(* vx_kernel_f)` (`vx_node` node, const `vx_reference` \*parameters, `vx_uint32` num)  
*The pointer to the Host side kernel.*
- typedef `vx_status(* vx_kernel_image_valid_rectangle_f)` (`vx_node` node, `vx_uint32` index, const `vx_rectangle_t` \*const input\_valid[], `vx_rectangle_t` \*const output\_valid[])  
*A user-defined callback function to set the valid rectangle of an output image.*
- typedef `vx_status(* vx_kernel_initialize_f)` (`vx_node` node, const `vx_reference` \*parameters, `vx_uint32` num)  
*The pointer to the kernel initializer. If the host code requires a call to initialize data once all the parameters have been validated, this function is called if not NULL.*
- typedef `vx_status(* vx_kernel_validate_f)` (`vx_node` node, const `vx_reference` parameters[], `vx_uint32` num, `vx_meta_format` metas[])  
*The user-defined kernel node parameters validation function. The function only needs to fill in the meta data structure(s).*
- typedef struct `_vx_meta_format` \* `vx_meta_format`  
*This object is used by output validation functions to specify the meta data of the expected output data object.*
- typedef `vx_status(* vx_publish_kernels_f)` (`vx_context` context)  
*The type of the `vxPublishKernels` entry function of modules loaded by `vxLoadKernels` and unloaded by `vxUnloadKernels`.*
- typedef `vx_status(* vx_unpublish_kernels_f)` (`vx_context` context)  
*The type of the `vxUnpublishKernels` entry function of modules loaded by `vxLoadKernels` and unloaded by `vxUnloadKernels`.*

## Enumerations

- enum `vx_meta_valid_rect_attribute_e` { `VX_VALID_RECT_CALLBACK` = ((( `VX_ID_KHRONOS` ) << 20) | ( `VX_TYPE_META_FORMAT` << 8)) + 0x1 }
- The meta valid rectangle attributes.*

## Functions

- `vx_status VX_API_CALL vxAddParameterToKernel` (`vx_kernel` kernel, `vx_uint32` index, `vx_enum` dir, `vx_enum` data\_type, `vx_enum` state)  
*Allows users to set the signatures of the custom kernel.*
- `vx_kernel VX_API_CALL vxAddUserKernel` (`vx_context` context, const `vx_char` name[`VX_MAX_KERNEL_NAME`], `vx_enum` enumeration, `vx_kernel_f` func\_ptr, `vx_uint32` numParams, `vx_kernel_validate_f` validate, `vx_kernel_initialize_f` init, `vx_kernel_deinitialize_f` deinit)  
*Allows users to add custom kernels to a context at run-time.*
- `vx_status VX_API_CALL vxAllocateUserKernelId` (`vx_context` context, `vx_enum` \*pKernelEnumId)  
*Allocates and registers user-defined kernel enumeration to a context. The allocated enumeration is from available pool of 4096 enumerations reserved for dynamic allocation from `VX_KERNEL_BASE(VX_ID_USER,0)`.*
- `vx_status VX_API_CALL vxAllocateUserKernelLibraryId` (`vx_context` context, `vx_enum` \*pLibraryId)  
*Allocates and registers user-defined kernel library ID to a context.*
- `vx_status VX_API_CALL vxFinalizeKernel` (`vx_kernel` kernel)  
*This API is called after all parameters have been added to the kernel and the kernel is ready to be used. Notice that the reference to the kernel created by `vxAddUserKernel` is still valid after the call to `vxFinalizeKernel`. If an error occurs, the kernel is not available for usage by the clients of OpenVX. Typically this is due to a mismatch between the number of parameters requested and given.*
- `vx_status VX_API_CALL vxLoadKernels` (`vx_context` context, const `vx_char` \*module)  
*Loads a library of kernels, called module, into a context.*
- `vx_status VX_API_CALL vxRemoveKernel` (`vx_kernel` kernel)

*Removes a custom kernel from its context and releases it.*

- **vx\_status VX\_API\_CALL vxSetKernelAttribute** (**vx\_kernel** kernel, **vx\_enum** attribute, const void \*ptr, **vx\_size** size)

*Sets kernel attributes.*

- **vx\_status VX\_API\_CALL vxSetMetaFormatAttribute** (**vx\_meta\_format** meta, **vx\_enum** attribute, const void \*ptr, **vx\_size** size)

*This function allows a user to set the attributes of a **vx\_meta\_format** object in a kernel output validator.*

- **vx\_status VX\_API\_CALL vxSetMetaFormatFromReference** (**vx\_meta\_format** meta, **vx\_reference** exemplar)

*Set a meta format object from an exemplar data object reference.*

- **vx\_status VX\_API\_CALL vxUnloadKernels** (**vx\_context** context, const **vx\_char** \*module)

*Unloads all kernels from the OpenVX context that had been loaded from the module using the **vxLoadKernels** function.*

### 3.94.2 Typedef Documentation

#### **typedef struct \_vx\_meta\_format\* vx\_meta\_format**

This object is used by output validation functions to specify the meta data of the expected output data object.

#### Note

When the actual output object of the user node is virtual, the information given through the **vx\_meta\_format** object allows the OpenVX framework to automatically create the data object when meta data were not specified by the application at object creation time.

Definition at line 320 of file **vx\_types.h**.

#### **typedef vx\_status( \* vx\_publish\_kernels\_f) (vx\_context context)**

The type of the **vxPublishKernels** entry function of modules loaded by **vxLoadKernels** and unloaded by **vxUnloadKernels**.

#### Parameters

|    |                |                                                        |
|----|----------------|--------------------------------------------------------|
| in | <i>context</i> | The reference to the context kernels must be added to. |
|----|----------------|--------------------------------------------------------|

Definition at line 1744 of file **vx\_types.h**.

#### **typedef vx\_status( \* vx\_unpublish\_kernels\_f) (vx\_context context)**

The type of the **vxUnpublishKernels** entry function of modules loaded by **vxLoadKernels** and unloaded by **vxUnloadKernels**.

#### Parameters

|    |                |                                                          |
|----|----------------|----------------------------------------------------------|
| in | <i>context</i> | The reference to the context kernels have been added to. |
|----|----------------|----------------------------------------------------------|

Definition at line 1752 of file **vx\_types.h**.

#### **typedef vx\_status( \* vx\_kernel\_f) (vx\_node node, const vx\_reference \*parameters, vx\_uint32 num)**

The pointer to the Host side kernel.

#### Parameters

|    |                   |                                                   |
|----|-------------------|---------------------------------------------------|
| in | <i>node</i>       | The handle to the node that contains this kernel. |
| in | <i>parameters</i> | The array of parameter references.                |
| in | <i>num</i>        | The number of parameters.                         |

Definition at line 1761 of file [vx\\_types.h](#).

**typedef vx\_status( \* vx\_kernel\_initialize\_f) (vx\_node node, const vx\_reference \*parameters, vx\_uint32 num)**

The pointer to the kernel initializer. If the host code requires a call to initialize data once all the parameters have been validated, this function is called if not NULL.

#### Parameters

|    |                   |                                                   |
|----|-------------------|---------------------------------------------------|
| in | <i>node</i>       | The handle to the node that contains this kernel. |
| in | <i>parameters</i> | The array of parameter references.                |
| in | <i>num</i>        | The number of parameters.                         |

Definition at line 1772 of file [vx\\_types.h](#).

**typedef vx\_status( \* vx\_kernel\_deinitialize\_f) (vx\_node node, const vx\_reference \*parameters, vx\_uint32 num)**

The pointer to the kernel deinitializer. If the host code requires a call to deinitialize data during a node garbage collection, this function is called if not NULL.

#### Parameters

|    |                   |                                                   |
|----|-------------------|---------------------------------------------------|
| in | <i>node</i>       | The handle to the node that contains this kernel. |
| in | <i>parameters</i> | The array of parameter references.                |
| in | <i>num</i>        | The number of parameters.                         |

Definition at line 1783 of file [vx\\_types.h](#).

**typedef vx\_status( \* vx\_kernel\_validate\_f) (vx\_node node, const vx\_reference parameters[], vx\_uint32 num, vx\_meta\_format metas[])**

The user-defined kernel node parameters validation function. The function only needs to fill in the meta data structure(s).

#### Note

This function is called once for whole set of parameters.

#### Parameters

|    |                   |                                                                                                                                                                                                                                                                                                                                                                                                |
|----|-------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>node</i>       | The handle to the node that is being validated.                                                                                                                                                                                                                                                                                                                                                |
| in | <i>parameters</i> | The array of parameters to be validated.                                                                                                                                                                                                                                                                                                                                                       |
| in | <i>num</i>        | Number of parameters to be validated.                                                                                                                                                                                                                                                                                                                                                          |
| in | <i>metas</i>      | A pointer to a pre-allocated array of structure references that the system holds. The system pre-allocates a number of vx_meta_format structures for the output parameters only, indexed by the same indices as parameters[]. The validation function fills in the correct type, format, and dimensionality for the system to use either to create memory or to check against existing memory. |

#### Returns

An error code describing the validation status on parameters.

Definition at line 1799 of file [vx\\_types.h](#).

```
typedef vx_status(* vx_kernel_image_valid_rectangle_f) (vx_node node, vx_uint32 index, const
vx_rectangle_t *const input_valid[], vx_rectangle_t *const output_valid[])
```

A user-defined callback function to set the valid rectangle of an output image.

The `VX_VALID_RECT_CALLBACK` attribute in the `vx_meta_format` object should be set to the desired callback during user node's output validator. The callback must not call `vxGetValidRegionImage` or `vxSetImageValidRectangle`. Instead, an array of the valid rectangles of all the input images is supplied to the callback to calculate the output valid rectangle. The output of the user node may be a pyramid, or just an image. If it is just an image, the 'Out' array associated with that output only has one element. If the output is a pyramid, the array size is equal to the number of pyramid levels. Notice that the array memory allocation passed to the callback is managed by the framework, the application must not allocate or deallocate those pointers.

The behavior of the callback function `vx_kernel_image_valid_rectangle_f` is undefined if one of the following is true:

- One of the input arguments of a user node is a pyramid or an array of images.
- Either input or output argument of a user node is an array of pyramids.

#### Parameters

|         |                     |                                                                                                                                                                                                                                                                                                                                                                                                                           |
|---------|---------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in, out | <i>node</i>         | The handle to the node that is being validated.                                                                                                                                                                                                                                                                                                                                                                           |
| in      | <i>index</i>        | The index of the output parameter for which a valid region should be set.                                                                                                                                                                                                                                                                                                                                                 |
| in      | <i>input_valid</i>  | A pointer to an array of valid regions of input images or images contained in image container (e.g. pyramids). They are provided in same order as the parameter list of the kernel's declaration.                                                                                                                                                                                                                         |
| out     | <i>output_valid</i> | An array of valid regions that should be set for the output images or image containers (e.g. pyramid) after graph processing. The length of the array should be equal to the size of the image container (e.g. number of levels in the pyramid). For a simple output image the array size is always one. Each rectangle supplies the valid region for one image. The array memory allocation is managed by the framework. |

#### Returns

An error code describing the validation status on parameters.

Definition at line 1832 of file `vx_types.h`.

### 3.94.3 Enumeration Type Documentation

#### **enum vx\_meta\_valid\_rect\_attribute\_e**

The meta valid rectangle attributes.

#### Enumerator

**VX\_VALID\_RECT\_CALLBACK** Valid rectangle callback during output parameter validation. Write-only.

Definition at line 1183 of file `vx_types.h`.

### 3.94.4 Function Documentation

#### **vx\_status VX\_API\_CALL vxAllocateUserKernelId ( vx\_context context, vx\_enum \* pKernelEnumId )**

Allocates and registers user-defined kernel enumeration to a context. The allocated enumeration is from available pool of 4096 enumerations reserved for dynamic allocation from `VX_KERNEL_BASE(VX_ID_USER,0)`.

#### Parameters

|     |                      |                                                                 |
|-----|----------------------|-----------------------------------------------------------------|
| in  | <i>context</i>       | The reference to the implementation context.                    |
| out | <i>pKernelEnumId</i> | pointer to return <code>vx_enum</code> for user-defined kernel. |

## Return values

|                                         |                                                                  |
|-----------------------------------------|------------------------------------------------------------------|
| <code>VX_SUCCESS</code>                 | No errors; any other value indicates failure.                    |
| <code>VX_ERROR_INVALID_REFERENCE</code> | If the context is not a valid <code>vx_context</code> reference. |
| <code>VX_ERROR_NO_RESOURCES</code>      | The enumerations has been exhausted.                             |

**vx\_status VX\_API\_CALL vxAllocateUserKernelLibraryId ( vx\_context context, vx\_enum \* pLibraryId )**

Allocates and registers user-defined kernel library ID to a context.

The allocated library ID is from available pool of library IDs (1..255) reserved for dynamic allocation. The returned libraryId can be used by user-kernel library developer to specify individual kernel enum IDs in a header file, shown below:

```
00001 #define MY_KERNEL_ID1(libraryId) (VX_KERNEL_BASE(VX_ID_USER, libraryId) + 0);
00002 #define MY_KERNEL_ID2(libraryId) (VX_KERNEL_BASE(VX_ID_USER, libraryId) + 1);
00003 #define MY_KERNEL_ID3(libraryId) (VX_KERNEL_BASE(VX_ID_USER, libraryId) + 2);
```

## Parameters

|     |                   |                                                            |
|-----|-------------------|------------------------------------------------------------|
| in  | <i>context</i>    | The reference to the implementation context.               |
| out | <i>pLibraryId</i> | pointer to <code>vx_enum</code> for user-kernel libraryId. |

## Return values

|                                    |                                               |
|------------------------------------|-----------------------------------------------|
| <code>VX_SUCCESS</code>            | No errors; any other value indicates failure. |
| <code>VX_ERROR_NO_RESOURCES</code> | The enumerations has been exhausted.          |

**vx\_status VX\_API\_CALL vxLoadKernels ( vx\_context context, const vx\_char \* module )**

Loads a library of kernels, called module, into a context.

The module must be a dynamic library with by convention, two exported functions named `vxPublishKernels` and `vxUnpublishKernels`.

`vxPublishKernels` must have type `vx_publish_kernels_f`, and must add kernels to the context by calling `vxAddUserKernel` for each new kernel. `vxPublishKernels` is called by `vxLoadKernels`.

`vxUnpublishKernels` must have type `vx_unpublish_kernels_f`, and must remove kernels from the context by calling `vxRemoveKernel` for each kernel the `vxPublishKernels` has added. `vxUnpublishKernels` is called by `vxUnloadKernels`.

## Note

When all references to loaded kernels are released, the module may be automatically unloaded.

## Parameters

|    |                |                                                                                                                                                                                                                                                                                                                           |
|----|----------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>context</i> | The reference to the context the kernels must be added to.                                                                                                                                                                                                                                                                |
| in | <i>module</i>  | The short name of the module to load. On systems where there are specific naming conventions for modules, the name passed should ignore such conventions. For example: <code>libxyz.so</code> should be passed as just <code>xyz</code> and the implementation will <i>do the right thing</i> that the platform requires. |

**Note**

This API uses the system pre-defined paths for modules.

**Returns**

A [vx\\_status\\_e](#) enumeration.

**Return values**

|                                          |                                                              |
|------------------------------------------|--------------------------------------------------------------|
| <code>VX_SUCCESS</code>                  | No errors; any other value indicates failure.                |
| <code>VX_ERROR_INVALID_REFERENCE</code>  | context is not a valid <a href="#">vx_context</a> reference. |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | If any of the other parameters are incorrect.                |

**See also**

[vxGetKernelByName](#)

**vx\_status VX\_API\_CALL vxUnloadKernels ( vx\_context context, const vx\_char \* module )**

Unloads all kernels from the OpenVX context that had been loaded from the module using the [vxLoadKernels](#) function.

The kernel unloading is performed by calling the `vxUnpublishKernels` exported function of the module.

**Note**

`vxUnpublishKernels` is defined in the description of [vxLoadKernels](#).

**Parameters**

|    |                |                                                                                                                                                                                                                                                                                                                             |
|----|----------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>context</i> | The reference to the context the kernels must be removed from.                                                                                                                                                                                                                                                              |
| in | <i>module</i>  | The short name of the module to unload. On systems where there are specific naming conventions for modules, the name passed should ignore such conventions. For example: <code>libxyz.so</code> should be passed as just <code>xyz</code> and the implementation will <i>do the right thing</i> that the platform requires. |

**Note**

This API uses the system pre-defined paths for modules.

**Returns**

A [vx\\_status\\_e](#) enumeration.

**Return values**

|                                          |                                                              |
|------------------------------------------|--------------------------------------------------------------|
| <code>VX_SUCCESS</code>                  | No errors; any other value indicates failure.                |
| <code>VX_ERROR_INVALID_REFERENCE</code>  | context is not a valid <a href="#">vx_context</a> reference. |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | If any of the other parameters are incorrect.                |

See also

[vxLoadKernels](#)

**vx\_kernel VX\_API\_CALL vxAddUserKernel ( vx\_context *context*, const vx\_char *name*[VX\_MAX\_KERNEL\_NAME], vx\_enum *enumeration*, vx\_kernel\_f *func\_ptr*, vx\_uint32 *numParams*, vx\_kernel\_validate\_f *validate*, vx\_kernel\_initialize\_f *init*, vx\_kernel\_deinitialize\_f *deinit* )**

Allows users to add custom kernels to a context at run-time.

#### Parameters

|    |                    |                                                                                                  |
|----|--------------------|--------------------------------------------------------------------------------------------------|
| in | <i>context</i>     | The reference to the context the kernel must be added to.                                        |
| in | <i>name</i>        | The string to use to match the kernel.                                                           |
| in | <i>enumeration</i> | The enumerated value of the kernel to be used by clients.                                        |
| in | <i>func_ptr</i>    | The process-local function pointer to be invoked.                                                |
| in | <i>numParams</i>   | The number of parameters for this kernel.                                                        |
| in | <i>validate</i>    | The pointer to <a href="#">vx_kernel_validate_f</a> , which validates parameters to this kernel. |
| in | <i>init</i>        | The kernel initialization function.                                                              |
| in | <i>deinit</i>      | The kernel de-initialization function.                                                           |

#### Returns

A [vx\\_kernel](#) reference. Any possible errors preventing a successful creation should be checked using [vxGetStatus](#).

**vx\_status VX\_API\_CALL vxFinalizeKernel ( vx\_kernel *kernel* )**

This API is called after all parameters have been added to the kernel and the kernel is *ready* to be used. Notice that the reference to the kernel created by [vxAddUserKernel](#) is still valid after the call to [vxFinalizeKernel](#). If an error occurs, the kernel is not available for usage by the clients of OpenVX. Typically this is due to a mismatch between the number of parameters requested and given.

#### Parameters

|    |               |                                                                           |
|----|---------------|---------------------------------------------------------------------------|
| in | <i>kernel</i> | The reference to the loaded kernel from <a href="#">vxAddUserKernel</a> . |
|----|---------------|---------------------------------------------------------------------------|

#### Returns

A [vx\\_status\\_e](#) enumeration.

#### Return values

|                                   |                                                            |
|-----------------------------------|------------------------------------------------------------|
| <i>VX_SUCCESS</i>                 | No errors; any other value indicates failure.              |
| <i>VX_ERROR_INVALID_REFERENCE</i> | kernel is not a valid <a href="#">vx_kernel</a> reference. |

#### Precondition

[vxAddUserKernel](#) and [vxAddParameterToKernel](#)

**vx\_status VX\_API\_CALL vxAddParameterToKernel ( vx\_kernel *kernel*, vx\_uint32 *index*, vx\_enum *dir*, vx\_enum *data\_type*, vx\_enum *state* )**

Allows users to set the signatures of the custom kernel.



**Parameters**

|    |                  |                                                                                                                                                                                  |
|----|------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>kernel</i>    | The reference to the kernel added with <a href="#">vxAddUserKernel</a> .                                                                                                         |
| in | <i>index</i>     | The index of the parameter to add.                                                                                                                                               |
| in | <i>dir</i>       | The direction of the parameter. This must be either <a href="#">VX_INPUT</a> or <a href="#">VX_OUTPUT</a> . <a href="#">VX_BIDIRECTIONAL</a> is not supported for this function. |
| in | <i>data_type</i> | The type of parameter. This must be a value from <a href="#">vx_type_e</a> .                                                                                                     |
| in | <i>state</i>     | The state of the parameter (required or not). This must be a value from <a href="#">vx_parameter_state_e</a> .                                                                   |

**Returns**

A [vx\\_status\\_e](#) enumerated value.

**Return values**

|                                             |                                                                             |
|---------------------------------------------|-----------------------------------------------------------------------------|
| <a href="#">VX_SUCCESS</a>                  | Parameter is successfully set on kernel; any other value indicates failure. |
| <a href="#">VX_ERROR_INVALID_REFERENCE</a>  | kernel is not a valid <a href="#">vx_kernel</a> reference.                  |
| <a href="#">VX_ERROR_INVALID_PARAMETERS</a> | If the parameter is not valid for any reason.                               |

**Precondition**

[vxAddUserKernel](#)

**vx\_status VX\_API\_CALL vxRemoveKernel ( vx\_kernel *kernel* )**

Removes a custom kernel from its context and releases it.

**Parameters**

|    |               |                                                                                        |
|----|---------------|----------------------------------------------------------------------------------------|
| in | <i>kernel</i> | The reference to the kernel to remove. Returned from <a href="#">vxAddUserKernel</a> . |
|----|---------------|----------------------------------------------------------------------------------------|

**Note**

Any kernel enumerated in the base standard cannot be removed; only kernels added through [vxAddUserKernel](#) can be removed.

**Returns**

A [vx\\_status\\_e](#) enumeration. The function returns to the application full control over the memory resources provided at the kernel creation time.

**Return values**

|                                             |                                                                                                                                                                                                                                                                               |
|---------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <a href="#">VX_SUCCESS</a>                  | No errors; any other value indicates failure.                                                                                                                                                                                                                                 |
| <a href="#">VX_ERROR_INVALID_REFERENCE</a>  | kernel is not a valid <a href="#">vx_kernel</a> reference.                                                                                                                                                                                                                    |
| <a href="#">VX_ERROR_INVALID_PARAMETERS</a> | If a base kernel is passed in.                                                                                                                                                                                                                                                |
| <a href="#">VX_FAILURE</a>                  | If the application has not released all references to the kernel object OR if the application has not released all references to a node that is using this kernel OR if the application has not released all references to a graph which has nodes that is using this kernel. |

**vx\_status VX\_API\_CALL vxSetKernelAttribute ( vx\_kernel *kernel*, vx\_enum *attribute*, const void \* *ptr*, vx\_size *size* )**

Sets kernel attributes.

#### Parameters

|    |                  |                                                                                |
|----|------------------|--------------------------------------------------------------------------------|
| in | <i>kernel</i>    | The reference to the kernel.                                                   |
| in | <i>attribute</i> | The enumeration of the attributes. See <a href="#">vx_kernel_attribute_e</a> . |
| in | <i>ptr</i>       | The pointer to the location from which to read the attribute.                  |
| in | <i>size</i>      | The size in bytes of the data area indicated by <i>ptr</i> in bytes.           |

#### Note

After a kernel has been passed to [vxFinalizeKernel](#), no attributes can be altered.

#### Returns

A [vx\\_status\\_e](#) enumeration.

#### Return values

|                                            |                                                            |
|--------------------------------------------|------------------------------------------------------------|
| <a href="#">VX_SUCCESS</a>                 | No errors; any other value indicates failure.              |
| <a href="#">VX_ERROR_INVALID_REFERENCE</a> | kernel is not a valid <a href="#">vx_kernel</a> reference. |

**vx\_status VX\_API\_CALL vxSetMetaFormatAttribute ( vx\_meta\_format *meta*, vx\_enum *attribute*, const void \* *ptr*, vx\_size *size* )**

This function allows a user to set the attributes of a [vx\\_meta\\_format](#) object in a kernel output validator.

The [vx\\_meta\\_format](#) object contains two types of information: data object meta data and some specific information that defines how the valid region of an image changes

The meta data attributes that can be set are identified by this list:

- [vx\\_image](#) : [VX\\_IMAGE\\_FORMAT](#), [VX\\_IMAGE\\_HEIGHT](#), [VX\\_IMAGE\\_WIDTH](#)
- [vx\\_array](#) : [VX\\_ARRAY\\_CAPACITY](#), [VX\\_ARRAY\\_ITEMTYPE](#)
- [vx\\_pyramid](#) : [VX\\_PYRAMID\\_FORMAT](#), [VX\\_PYRAMID\\_HEIGHT](#), [VX\\_PYRAMID\\_WIDTH](#), [VX\\_PYRAMID\\_LEVELS](#), [VX\\_PYRAMID\\_SCALE](#)
- [vx\\_scalar](#) : [VX\\_SCALAR\\_TYPE](#)
- [vx\\_matrix](#) : [VX\\_MATRIX\\_TYPE](#), [VX\\_MATRIX\\_ROWS](#), [VX\\_MATRIX\\_COLUMNS](#)
- [vx\\_distribution](#) : [VX\\_DISTRIBUTION\\_BINS](#), [VX\\_DISTRIBUTION\\_OFFSET](#), [VX\\_DISTRIBUTION\\_RANGE](#)
- [vx\\_remap](#) : [VX\\_REMAP\\_SOURCE\\_WIDTH](#), [VX\\_REMAP\\_SOURCE\\_HEIGHT](#), [VX\\_REMAP\\_DESTINATION\\_WIDTH](#), [VX\\_REMAP\\_DESTINATION\\_HEIGHT](#)
- [vx\\_lut](#) : [VX\\_LUT\\_TYPE](#), [VX\\_LUT\\_COUNT](#)
- [vx\\_threshold](#) : [VX\\_THRESHOLD\\_TYPE](#), [VX\\_THRESHOLD\\_INPUT\\_FORMAT](#), [VX\\_THRESHOLD\\_INPUT\\_FORMAT](#)
- [vx\\_object\\_array](#) : [VX\\_OBJECT\\_ARRAY\\_NUMITEMS](#), [VX\\_OBJECT\\_ARRAY\\_ITEMTYPE](#)
- [vx\\_tensor](#) : [VX\\_TENSOR\\_NUMBER\\_OF\\_DIMS](#), [VX\\_TENSOR\\_DIMS](#), [VX\\_TENSOR\\_DATA\\_TYPE](#), [VX\\_TENSOR\\_FIXED\\_POINT\\_POSITION](#)
- [VX\\_VALID\\_RECT\\_CALLBACK](#)

**Note**

For `vx_image`, a specific attribute can be used to specify the valid region evolution. This information is not a meta data.

**Parameters**

|    |                  |                                                                                                                                    |
|----|------------------|------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>meta</i>      | The reference to the <code>vx_meta_format</code> struct to set                                                                     |
| in | <i>attribute</i> | Use the subset of data object attributes that define the meta data of this object or attributes from <code>vx_meta_format</code> . |
| in | <i>ptr</i>       | The input pointer of the value to set on the meta format object.                                                                   |
| in | <i>size</i>      | The size in bytes of the object to which <i>ptr</i> points.                                                                        |

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                                          |                                                                   |
|------------------------------------------|-------------------------------------------------------------------|
| <code>VX_SUCCESS</code>                  | The attribute was set; any other value indicates failure.         |
| <code>VX_ERROR_INVALID_REFERENCE</code>  | meta is not a valid <code>vx_meta_format</code> reference.        |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | size was not correct for the type needed.                         |
| <code>VX_ERROR_NOT_SUPPORTED</code>      | the object attribute was not supported on the meta format object. |
| <code>VX_ERROR_INVALID_TYPE</code>       | attribute type did not match known meta format type.              |

**`vx_status VX_API_CALL vxSetMetaFormatFromReference ( vx_meta_format meta, vx_reference exemplar )`**

Set a meta format object from an exemplar data object reference.

This function sets a `vx_meta_format` object from the meta data of the exemplar

**Parameters**

|    |                 |                               |
|----|-----------------|-------------------------------|
| in | <i>meta</i>     | The meta format object to set |
| in | <i>exemplar</i> | The exemplar data object.     |

**Returns**

A `vx_status_e` enumeration.

**Return values**

|                                         |                                                                                                                            |
|-----------------------------------------|----------------------------------------------------------------------------------------------------------------------------|
| <code>VX_SUCCESS</code>                 | The meta format was correctly set; any other value indicates failure.                                                      |
| <code>VX_ERROR_INVALID_REFERENCE</code> | meta is not a valid <code>vx_meta_format</code> reference, or exemplar is not a valid <code>vx_reference</code> reference. |

## 3.95 Framework: Graph Parameters

### 3.95.1 Detailed Description

Defines the Graph Parameter API.

Graph parameters allow Clients to create graphs with Client settable parameters. Clients can then create Graph creation methods (a.k.a. *Graph Factories*). When creating these factories, the client will typically not be able to use the standard Node creator functions such as `vxSobel13x3Node` but instead will use the *manual* method via `vxCreateGenericNode`.

```
vx_graph vxCornersGraphFactory(vx_context context)
{
 vx_status status = VX_SUCCESS;
 vx_uint32 i;
 vx_float32 strength_thresh = 10000.0f;
 vx_float32 r = 1.5f;
 vx_float32 sensitivity = 0.14f;
 vx_int32 window_size = 3;
 vx_int32 block_size = 3;
 vx_enum channel = VX_CHANNEL_Y;
 vx_graph graph = vxCreateGraph(context);
 if (vxGetStatus((vx_reference)graph) == VX_SUCCESS)
 {
 vx_image virts[] = {
 vxCreateVirtualImage(graph, 0, 0,
 VX_DF_IMAGE_VIRT),
 vxCreateVirtualImage(graph, 0, 0,
 VX_DF_IMAGE_VIRT),
 };
 vx_kernel kernels[] = {
 vxGetKernelByEnum(context,
 VX_KERNEL_CHANNEL_EXTRACT),
 vxGetKernelByEnum(context, VX_KERNEL_MEDIAN_3x3),
 vxGetKernelByEnum(context, VX_KERNEL_HARRIS_CORNERS),
 };
 vx_node nodes[dimof(kernels)] = {
 vxCreateGenericNode(graph, kernels[0]),
 vxCreateGenericNode(graph, kernels[1]),
 vxCreateGenericNode(graph, kernels[2]),
 };
 vx_scalar scalars[] = {
 vxCreateScalar(context, VX_TYPE_ENUM, &channel),
 vxCreateScalar(context, VX_TYPE_FLOAT32, &strength_thresh),
 vxCreateScalar(context, VX_TYPE_FLOAT32, &r),
 vxCreateScalar(context, VX_TYPE_FLOAT32, &sensitivity),
 vxCreateScalar(context, VX_TYPE_INT32, &window_size),
 vxCreateScalar(context, VX_TYPE_INT32, &block_size),
 };
 vx_parameter parameters[] = {
 vxGetParameterByIndex(nodes[0], 0),
 vxGetParameterByIndex(nodes[2], 6)
 };
 // Channel Extract
 status |= vxAddParameterToGraph(graph, parameters[0]);
 status |= vxSetParameterByIndex(nodes[0], 1, (
 vx_reference)scalars[0]);
 status |= vxSetParameterByIndex(nodes[0], 2, (
 vx_reference)virts[0]);
 // Median Filter
 status |= vxSetParameterByIndex(nodes[1], 0, (
 vx_reference)virts[0]);
 status |= vxSetParameterByIndex(nodes[1], 1, (
 vx_reference)virts[1]);
 // Harris Corners
 status |= vxSetParameterByIndex(nodes[2], 0, (
 vx_reference)virts[1]);
 status |= vxSetParameterByIndex(nodes[2], 1, (
 vx_reference)scalars[1]);
 status |= vxSetParameterByIndex(nodes[2], 2, (
 vx_reference)scalars[2]);
 status |= vxSetParameterByIndex(nodes[2], 3, (
 vx_reference)scalars[3]);
 status |= vxSetParameterByIndex(nodes[2], 4, (
 vx_reference)scalars[4]);
 status |= vxSetParameterByIndex(nodes[2], 5, (
 vx_reference)scalars[5]);
 status |= vxAddParameterToGraph(graph, parameters[1]);

 for (i = 0; i < dimof(scalars); i++)
 {
 vxReleaseScalar(&scalars[i]);
 }
 for (i = 0; i < dimof(virts); i++)
```

```

 {
 vxReleaseImage(&virt[s[i]]);
 }
 for (i = 0; i < dimof(kernels); i++)
 {
 vxReleaseKernel(&kernels[i]);
 }
 for (i = 0; i < dimof(nodes); i++)
 {
 vxReleaseNode(&nodes[i]);
 }
 for (i = 0; i < dimof(parameters); i++)
 {
 vxReleaseParameter(¶meters[i]);
 }
}
return graph;
}

```

Some data are contained in these Graphs and do not become exposed to Clients of the factory. This allows ISVs or Vendors to create custom IP or IP-sensitive factories that Clients can use but may not be able to determine what is inside the factory. As the graph contains internal references to the data, the objects will not be freed until the graph itself is released.

## Functions

- **vx\_status VX\_API\_CALL vxAddParameterToGraph** (**vx\_graph** graph, **vx\_parameter** parameter)  
*Adds the given parameter extracted from a vx\_node to the graph.*
- **vx\_parameter VX\_API\_CALL vxGetGraphParameterByIndex** (**vx\_graph** graph, **vx\_uint32** index)  
*Retrieves a vx\_parameter from a vx\_graph.*
- **vx\_status VX\_API\_CALL vxSetGraphParameterByIndex** (**vx\_graph** graph, **vx\_uint32** index, **vx\_reference** value)  
*Sets a reference to the parameter on the graph. The implementation must set this parameter on the originating node as well.*

### 3.95.2 Function Documentation

**vx\_status VX\_API\_CALL vxAddParameterToGraph** ( **vx\_graph** graph, **vx\_parameter** parameter )

Adds the given parameter extracted from a vx\_node to the graph.

#### Parameters

|    |           |                                                            |
|----|-----------|------------------------------------------------------------|
| in | graph     | The graph reference that contains the node.                |
| in | parameter | The parameter reference to add to the graph from the node. |

#### Returns

A vx\_status\_e enumeration.

#### Return values

|                             |                                                                                             |
|-----------------------------|---------------------------------------------------------------------------------------------|
| VX_SUCCESS                  | Parameter added to Graph; any other value indicates failure.                                |
| VX_ERROR_INVALID_REFERENCE  | graph is not a valid vx_graph reference or parameter is not a valid vx_parameter reference. |
| VX_ERROR_INVALID_PARAMETERS | The parameter is of a node not in this graph.                                               |

**vx\_status VX\_API\_CALL vxSetGraphParameterByIndex ( vx\_graph *graph*, vx\_uint32 *index*, vx\_reference *value* )**

Sets a reference to the parameter on the graph. The implementation must set this parameter on the originating node as well.

#### Parameters

|    |              |                                        |
|----|--------------|----------------------------------------|
| in | <i>graph</i> | The graph reference.                   |
| in | <i>index</i> | The parameter index.                   |
| in | <i>value</i> | The reference to set to the parameter. |

#### Returns

A `vx_status_e` enumeration.

#### Return values

|                                          |                                                                                                          |
|------------------------------------------|----------------------------------------------------------------------------------------------------------|
| <code>VX_SUCCESS</code>                  | Parameter set to Graph; any other value indicates failure.                                               |
| <code>VX_ERROR_INVALID_REFERENCE</code>  | graph is not a valid <code>vx_graph</code> reference or value is not a valid <code>vx_reference</code> . |
| <code>VX_ERROR_INVALID_PARAMETERS</code> | The parameter index is out of bounds or the dir parameter is incorrect.                                  |

**vx\_parameter VX\_API\_CALL vxGetGraphParameterByIndex ( vx\_graph *graph*, vx\_uint32 *index* )**

Retrieves a `vx_parameter` from a `vx_graph`.

#### Parameters

|    |              |                             |
|----|--------------|-----------------------------|
| in | <i>graph</i> | The graph.                  |
| in | <i>index</i> | The index of the parameter. |

#### Returns

`vx_parameter` reference. Any possible errors preventing a successful function completion should be checked using `vxGetStatus`.

# Bibliography

# Index

- Absolute Difference, [35](#)
  - [vxAbsDiffNode](#), [35](#)
  - [vxuAbsDiff](#), [35](#)
- Accumulate, [37](#)
  - [vxAccumulateImageNode](#), [37](#)
  - [vxuAccumulateImage](#), [37](#)
- Accumulate Squared, [39](#)
  - [vxAccumulateSquareImageNode](#), [39](#)
  - [vxuAccumulateSquareImage](#), [39](#)
- Accumulate Weighted, [43](#)
  - [vxAccumulateWeightedImageNode](#), [43](#)
  - [vxuAccumulateWeightedImage](#), [43](#)
- Administrative Features, [286](#)
- Advanced Framework API, [314](#)
- Advanced Objects, [287](#)
- Arithmetic Addition, [48](#)
  - [vxAddNode](#), [48](#)
  - [vxuAdd](#), [48](#)
- Arithmetic Subtraction, [50](#)
  - [vxSubtractNode](#), [50](#)
  - [vxuSubtract](#), [50](#)
- Basic Features, [169](#)
  - [VX\\_CHANNEL\\_0](#), [183](#)
  - [VX\\_CHANNEL\\_1](#), [183](#)
  - [VX\\_CHANNEL\\_2](#), [183](#)
  - [VX\\_CHANNEL\\_3](#), [183](#)
  - [VX\\_CHANNEL\\_A](#), [183](#)
  - [VX\\_CHANNEL\\_B](#), [183](#)
  - [VX\\_CHANNEL\\_G](#), [183](#)
  - [VX\\_CHANNEL\\_R](#), [183](#)
  - [VX\\_CHANNEL\\_U](#), [183](#)
  - [VX\\_CHANNEL\\_V](#), [183](#)
  - [VX\\_CHANNEL\\_Y](#), [183](#)
  - [VX\\_CONVERT\\_POLICY\\_SATURATE](#), [182](#)
  - [VX\\_CONVERT\\_POLICY\\_WRAP](#), [182](#)
  - [VX\\_DF\\_IMAGE\\_IYUV](#), [182](#)
  - [VX\\_DF\\_IMAGE\\_NV12](#), [182](#)
  - [VX\\_DF\\_IMAGE\\_NV21](#), [182](#)
  - [VX\\_DF\\_IMAGE\\_RGBX](#), [182](#)
  - [VX\\_DF\\_IMAGE\\_RGB](#), [182](#)
  - [VX\\_DF\\_IMAGE\\_S16](#), [182](#)
  - [VX\\_DF\\_IMAGE\\_S32](#), [182](#)
  - [VX\\_DF\\_IMAGE\\_U16](#), [182](#)
  - [VX\\_DF\\_IMAGE\\_U32](#), [182](#)
  - [VX\\_DF\\_IMAGE\\_U8](#), [182](#)
  - [VX\\_DF\\_IMAGE\\_UYVY](#), [182](#)
  - [VX\\_DF\\_IMAGE\\_VIRT](#), [182](#)
  - [VX\\_DF\\_IMAGE\\_YUV4](#), [182](#)
  - [VX\\_DF\\_IMAGE\\_YUYV](#), [182](#)
  - [VX\\_DF\\_IMAGE](#), [177](#)
  - [VX\\_ENUM\\_ACCESSOR](#), [181](#)
  - [VX\\_ENUM\\_ACTION](#), [181](#)
  - [VX\\_ENUM\\_BASE](#), [177](#)
  - [VX\\_ENUM\\_BORDER\\_POLICY](#), [181](#)
  - [VX\\_ENUM\\_BORDER](#), [181](#)
  - [VX\\_ENUM\\_CHANNEL](#), [181](#)
  - [VX\\_ENUM\\_COLOR\\_RANGE](#), [181](#)
  - [VX\\_ENUM\\_COLOR\\_SPACE](#), [181](#)
  - [VX\\_ENUM\\_COMP\\_METRIC](#), [181](#)
  - [VX\\_ENUM\\_COMPARISON](#), [181](#)
  - [VX\\_ENUM\\_CONVERT\\_POLICY](#), [181](#)
  - [VX\\_ENUM\\_DIRECTION](#), [181](#)
  - [VX\\_ENUM\\_DIRECTIVE](#), [181](#)
  - [VX\\_ENUM\\_GRAPH\\_STATE](#), [181](#)
  - [VX\\_ENUM\\_HINT](#), [181](#)
  - [VX\\_ENUM\\_INTERPOLATION](#), [181](#)
  - [VX\\_ENUM\\_LBP\\_FORMAT](#), [181](#)
  - [VX\\_ENUM\\_MEMORY\\_TYPE](#), [181](#)
  - [VX\\_ENUM\\_NONLINEAR](#), [181](#)
  - [VX\\_ENUM\\_NORM\\_TYPE](#), [181](#)
  - [VX\\_ENUM\\_OVERFLOW](#), [181](#)
  - [VX\\_ENUM\\_PARAMETER\\_STATE](#), [181](#)
  - [VX\\_ENUM\\_PATTERN](#), [181](#)
  - [VX\\_ENUM\\_ROUND\\_POLICY](#), [181](#)
  - [VX\\_ENUM\\_SCALAR\\_OPERATION](#), [181](#)
  - [VX\\_ENUM\\_TARGET](#), [181](#)
  - [VX\\_ENUM\\_TERM\\_CRITERIA](#), [181](#)
  - [VX\\_ENUM\\_THRESHOLD\\_TYPE](#), [181](#)
  - [VX\\_ERROR\\_GRAPH\\_ABANDONED](#), [180](#)
  - [VX\\_ERROR\\_GRAPH\\_SCHEDULED](#), [180](#)
  - [VX\\_ERROR\\_INVALID\\_DIMENSION](#), [180](#)
  - [VX\\_ERROR\\_INVALID\\_FORMAT](#), [180](#)
  - [VX\\_ERROR\\_INVALID\\_GRAPH](#), [180](#)
  - [VX\\_ERROR\\_INVALID\\_LINK](#), [180](#)
  - [VX\\_ERROR\\_INVALID\\_MODULE](#), [180](#)
  - [VX\\_ERROR\\_INVALID\\_NODE](#), [180](#)
  - [VX\\_ERROR\\_INVALID\\_PARAMETERS](#), [180](#)
  - [VX\\_ERROR\\_INVALID\\_REFERENCE](#), [180](#)
  - [VX\\_ERROR\\_INVALID\\_SCOPE](#), [180](#)
  - [VX\\_ERROR\\_INVALID\\_TYPE](#), [180](#)
  - [VX\\_ERROR\\_INVALID\\_VALUE](#), [180](#)
  - [VX\\_ERROR\\_MULTIPLE\\_WRITERS](#), [180](#)
  - [VX\\_ERROR\\_NO\\_MEMORY](#), [180](#)
  - [VX\\_ERROR\\_NO\\_RESOURCES](#), [180](#)
  - [VX\\_ERROR\\_NOT\\_ALLOCATED](#), [180](#)
  - [VX\\_ERROR\\_NOT\\_COMPATIBLE](#), [180](#)
  - [VX\\_ERROR\\_NOT\\_IMPLEMENTED](#), [181](#)
  - [VX\\_ERROR\\_NOT\\_SUFFICIENT](#), [180](#)



- VX\_ERROR\_NOT\_SUPPORTED, 181
- VX\_ERROR\_OPTIMIZED\_AWAY, 180
- VX\_ERROR\_REFERENCE\_NONZERO, 180
- VX\_FAILURE, 181
- VX\_ID\_AMD, 184
- VX\_ID\_ARM, 184
- VX\_ID\_AXIS, 184
- VX\_ID\_BDTI, 184
- VX\_ID\_BROADCOM, 184
- VX\_ID\_CADENCE, 185
- VX\_ID\_CEVA, 185
- VX\_ID\_DEFAULT, 185
- VX\_ID\_FREESCALE, 184
- VX\_ID\_HUAWEI, 185
- VX\_ID\_IMAGINATION, 185
- VX\_ID\_INTEL, 184
- VX\_ID\_ITSEEZ, 185
- VX\_ID\_KHRONOS, 184
- VX\_ID\_MARVELL, 184
- VX\_ID\_MEDIATEK, 185
- VX\_ID\_MOVIDIUS, 184
- VX\_ID\_NVIDIA, 184
- VX\_ID\_NXP, 185
- VX\_ID\_QUALCOMM, 184
- VX\_ID\_RENESAS, 184
- VX\_ID\_SAMSUNG, 184
- VX\_ID\_SOCIONEXT, 185
- VX\_ID\_SYNOPTICS, 185
- VX\_ID\_ST, 185
- VX\_ID\_TI, 184
- VX\_ID\_USER, 185
- VX\_ID\_VIDEANTIS, 185
- VX\_ID\_VIVANTE, 184
- VX\_ID\_XILINX, 184
- VX\_INTERPOLATION\_AREA, 184
- VX\_INTERPOLATION\_BILINEAR, 183
- VX\_INTERPOLATION\_NEAREST\_NEIGHBOR, 183
- VX\_NONLINEAR\_FILTER\_MAX, 184
- VX\_NONLINEAR\_FILTER\_MEDIAN, 184
- VX\_NONLINEAR\_FILTER\_MIN, 184
- VX\_PATTERN\_BOX, 184
- VX\_PATTERN\_CROSS, 184
- VX\_PATTERN\_DISK, 184
- VX\_PATTERN\_OTHER, 184
- VX\_STATUS\_MIN, 180
- VX\_SUCCESS, 181
- VX\_TARGET\_ANY, 182
- VX\_TARGET\_STRING, 182
- VX\_TARGET\_VENDOR\_BEGIN, 183
- VX\_TYPE\_ARRAY, 179
- VX\_TYPE\_BOOL, 178
- VX\_TYPE\_CHAR, 178
- VX\_TYPE\_CONTEXT, 179
- VX\_TYPE\_CONVOLUTION, 179
- VX\_TYPE\_COORDINATES2DF, 179
- VX\_TYPE\_COORDINATES2D, 178
- VX\_TYPE\_COORDINATES3D, 178
- VX\_TYPE\_DELAY, 179
- VX\_TYPE\_DF\_IMAGE, 178
- VX\_TYPE\_DISTRIBUTION, 179
- VX\_TYPE\_ENUM, 178
- VX\_TYPE\_ERROR, 179
- VX\_TYPE\_FLOAT32, 178
- VX\_TYPE\_FLOAT64, 178
- VX\_TYPE\_GRAPH, 179
- VX\_TYPE\_HOG\_PARAMS, 179
- VX\_TYPE\_HOUGH\_LINES\_PARAMS, 179
- VX\_TYPE\_IMAGE, 179
- VX\_TYPE\_INT16, 178
- VX\_TYPE\_INT32, 178
- VX\_TYPE\_INT64, 178
- VX\_TYPE\_INT8, 178
- VX\_TYPE\_INVALID, 178
- VX\_TYPE\_KERNEL, 179
- VX\_TYPE\_KEYPOINT, 178
- VX\_TYPE\_KHRONOS\_OBJECT\_END, 179
- VX\_TYPE\_KHRONOS\_OBJECT\_START, 179
- VX\_TYPE\_KHRONOS\_STRUCT\_MAX, 179
- VX\_TYPE\_LINE\_2D, 179
- VX\_TYPE\_LUT, 179
- VX\_TYPE\_MASK, 177
- VX\_TYPE\_MATRIX, 179
- VX\_TYPE\_META\_FORMAT, 179
- VX\_TYPE\_NODE, 179
- VX\_TYPE\_OBJECT\_ARRAY, 179
- VX\_TYPE\_PARAMETER, 179
- VX\_TYPE\_PYRAMID, 179
- VX\_TYPE\_RECTANGLE, 178
- VX\_TYPE\_REFERENCE, 179
- VX\_TYPE\_REMAP, 179
- VX\_TYPE\_SCALAR, 179
- VX\_TYPE\_SIZE, 178
- VX\_TYPE\_TENSOR\_MATRIX\_MULTIPLY\_PARAMS, 179
- VX\_TYPE\_TENSOR, 179
- VX\_TYPE\_THRESHOLD, 179
- VX\_TYPE\_UINT16, 178
- VX\_TYPE\_UINT32, 178
- VX\_TYPE\_UINT64, 178
- VX\_TYPE\_UINT8, 178
- VX\_TYPE\_USER\_STRUCT\_END, 179
- VX\_TYPE\_USER\_STRUCT\_START, 179
- VX\_TYPE\_VENDOR\_OBJECT\_END, 179
- VX\_TYPE\_VENDOR\_OBJECT\_START, 179
- VX\_TYPE\_VENDOR\_STRUCT\_END, 179
- VX\_TYPE\_VENDOR\_STRUCT\_START, 179
- vx\_bool, 177
- vx\_bool\_e, 178
- vx\_channel\_e, 183
- vx\_convert\_policy\_e, 181
- vx\_df\_image\_e, 182
- vx\_enum, 177
- vx\_enum\_e, 181
- vx\_false\_e, 178
- vx\_interpolation\_type\_e, 183

- [vx\\_non\\_linear\\_filter\\_e](#), 184
  - [vx\\_pattern\\_e](#), 184
  - [vx\\_status](#), 177
  - [vx\\_status\\_e](#), 179
  - [vx\\_target\\_e](#), 182
  - [vx\\_true\\_e](#), 178
  - [vx\\_type\\_e](#), 178
  - [vx\\_vendor\\_id\\_e](#), 184
  - [vxGetStatus](#), 185
- Bilateral Filter, 139
  - [vxBilateralFilterNode](#), 139
  - [vxuBilateralFilter](#), 140
- Bitwise AND, 52
  - [vxAndNode](#), 52
  - [vxuAnd](#), 52
- Bitwise EXCLUSIVE OR, 54
  - [vxXorNode](#), 54
  - [vxuXor](#), 54
- Bitwise INCLUSIVE OR, 56
  - [vxOrNode](#), 56
  - [vxuOr](#), 56
- Bitwise NOT, 58
  - [vxNotNode](#), 58
  - [vxuNot](#), 58
- Box Filter, 60
  - [vxBox3x3Node](#), 60
  - [vxuBox3x3](#), 60
- Canny Edge Detector, 64
  - [VX\\_NORM\\_L1](#), 65
  - [VX\\_NORM\\_L2](#), 65
  - [vx\\_norm\\_type\\_e](#), 65
  - [vxCannyEdgeDetectorNode](#), 65
  - [vxuCannyEdgeDetector](#), 66
- Channel Combine, 67
  - [vxChannelCombineNode](#), 67
  - [vxuChannelCombine](#), 67
- Channel Extract, 69
  - [vxChannelExtractNode](#), 69
  - [vxuChannelExtract](#), 69
- Color Convert, 71
  - [vxColorConvertNode](#), 73
  - [vxuColorConvert](#), 73
- Control Flow, 45
  - [vxScalarOperationNode](#), 46
  - [vxSelectNode](#), 46
- Convert Bit depth, 75
  - [vxConvertDepthNode](#), 75
  - [vxuConvertDepth](#), 76
- Custom Convolution, 77
  - [vxConvolveNode](#), 77
  - [vxuConvolve](#), 78
- Data Object Copy, 41
  - [vxCopyNode](#), 41
  - [vxuCopy](#), 41
- Dilate Image, 79
  - [vxDilate3x3Node](#), 79
  - [vxuDilate3x3](#), 79
- Equalize Histogram, 81
  - [vxEqualizeHistNode](#), 81
  - [vxuEqualizeHist](#), 81
- Erode Image, 82
  - [vxErode3x3Node](#), 82
  - [vxuErode3x3](#), 82
- Fast Corners, 84
  - [vxFastCornersNode](#), 85
  - [vxuFastCorners](#), 85
- Framework: Directives, 324
  - [VX\\_DIRECTIVE\\_DISABLE\\_LOGGING](#), 324
  - [VX\\_DIRECTIVE\\_DISABLE\\_PERFORMANCE](#), 324
  - [VX\\_DIRECTIVE\\_ENABLE\\_LOGGING](#), 324
  - [VX\\_DIRECTIVE\\_ENABLE\\_PERFORMANCE](#), 324
  - [vx\\_directive\\_e](#), 324
  - [vxDirective](#), 324
- Framework: Graph Parameters, 339
  - [vxAddParameterToGraph](#), 340
  - [vxGetGraphParameterByIndex](#), 341
  - [vxSetGraphParameterByIndex](#), 340
- Framework: Hints, 322
  - [VX\\_HINT\\_PERFORMANCE\\_DEFAULT](#), 322
  - [VX\\_HINT\\_PERFORMANCE\\_HIGH\\_SPEED](#), 322
  - [VX\\_HINT\\_PERFORMANCE\\_LOW\\_POWER](#), 322
  - [vx\\_hint\\_e](#), 322
  - [vxHint](#), 322
- Framework: Log, 320
  - [vxAddLogEntry](#), 320
  - [vxRegisterLogCallback](#), 321
- Framework: Node Callbacks, 315
  - [VX\\_ACTION\\_ABANDON](#), 317
  - [VX\\_ACTION\\_CONTINUE](#), 317
  - [vx\\_action](#), 317
  - [vx\\_action\\_e](#), 317
  - [vx\\_nodecomplete\\_f](#), 317
  - [vxAssignNodeCallback](#), 317
  - [vxRetrieveNodeCallback](#), 318
- Framework: Performance Measurement, 319
- Framework: User Kernels, 326
  - [VX\\_VALID\\_RECT\\_CALLBACK](#), 332
  - [vx\\_kernel\\_deinitialize\\_f](#), 331
  - [vx\\_kernel\\_f](#), 330
  - [vx\\_kernel\\_image\\_valid\\_rectangle\\_f](#), 331
  - [vx\\_kernel\\_initialize\\_f](#), 331
  - [vx\\_kernel\\_validate\\_f](#), 331
  - [vx\\_meta\\_format](#), 330
  - [vx\\_meta\\_valid\\_rect\\_attribute\\_e](#), 332
  - [vx\\_publish\\_kernels\\_f](#), 330
  - [vx\\_unpublish\\_kernels\\_f](#), 330
  - [vxAddParameterToKernel](#), 335
  - [vxAddUserKernel](#), 335
  - [vxAllocateUserKernelId](#), 332
  - [vxAllocateUserKernelLibraryId](#), 333
  - [vxFinalizeKernel](#), 335
  - [vxLoadKernels](#), 333
  - [vxRemoveKernel](#), 336
  - [vxSetKernelAttribute](#), 336
  - [vxSetMetaFormatAttribute](#), 337

- vxSetMetaFormatFromReference, 338
  - vxUnloadKernels, 334
- Gaussian Filter, 87
  - vxGaussian3x3Node, 87
  - vxuGaussian3x3, 87
- Gaussian Image Pyramid, 96
  - vxGaussianPyramidNode, 96
  - vxuGaussianPyramid, 96
- HOG, 146
  - vxHOGCellsNode, 147
  - vxHOGFeaturesNode, 148
  - vxuHOGCells, 149
  - vxuHOGFeatures, 150
- Harris Corners, 91
  - vxHarrisCornersNode, 92
  - vxuHarrisCorners, 93
- Histogram, 94
  - vxHistogramNode, 94
  - vxuHistogram, 94
- HoughLinesP, 152
  - vxHoughLinesPNode, 153
  - vxuHoughLinesP, 153
- Integral Image, 102
  - vxIntegralImageNode, 102
  - vxuIntegralImage, 102
- LBP, 143
  - VX\_LBP, 144
  - VX\_MLBP, 144
  - VX\_ULBP, 144
  - vx\_lbp\_format\_e, 144
  - vxLBPNode, 145
  - vxuLBP, 145
- Laplacian Image Pyramid, 98
  - vxLaplacianPyramidNode, 98
  - vxuLaplacianPyramid, 99
- Magnitude, 104
  - vxMagnitudeNode, 104
  - vxuMagnitude, 104
- MatchTemplate, 141
  - VX\_COMPARE\_CCORR\_NORM, 141
  - VX\_COMPARE\_CCORR, 141
  - VX\_COMPARE\_HAMMING, 141
  - VX\_COMPARE\_L1, 141
  - VX\_COMPARE\_L2, 141
  - VX\_COMPARE\_L2\_NORM, 141
  - vx\_comp\_metric\_e, 141
  - vxMatchTemplateNode, 142
  - vxuMatchTemplate, 142
- Max, 114
  - vxMaxNode, 114
  - vxuMax, 114
- Mean and Standard Deviation, 106
  - vxMeanStdDevNode, 106
  - vxuMeanStdDev, 106
- Median Filter, 108
  - vxMedian3x3Node, 108
  - vxuMedian3x3, 108
- Min, 112
  - vxMinNode, 112
  - vxuMin, 112
- Min, Max Location, 110
  - vxMinMaxLocNode, 110
  - vxuMinMaxLoc, 110
- Node: Border Modes, 290
  - VX\_BORDER\_CONSTANT, 290
  - VX\_BORDER\_POLICY\_DEFAULT\_TO\_UNDEFINED, 291
  - VX\_BORDER\_POLICY\_RETURN\_ERROR, 291
  - VX\_BORDER\_REPLICATE, 290
  - VX\_BORDER\_UNDEFINED, 290
  - vx\_border\_e, 290
  - vx\_border\_policy\_e, 290
- Non Linear Filter, 89
  - vxNonLinearFilterNode, 89
  - vxuNonLinearFilter, 89
- Non-Maxima Suppression, 62
  - vxNonMaxSuppressionNode, 62
  - vxuNonMaxSuppression, 62
- Object: Array, 210
  - VX\_ARRAY\_CAPACITY, 211
  - VX\_ARRAY\_ITEMSIZE, 211
  - VX\_ARRAY\_ITEMTYPE, 211
  - VX\_ARRAY\_NUMITEMS, 211
  - vx\_array\_attribute\_e, 211
  - vxAddArrayItems, 213
  - vxArrayItem, 211
  - vxCopyArrayRange, 214
  - vxCreateArray, 211
  - vxCreateVirtualArray, 212
  - vxFormatArrayPointer, 211
  - vxMapArrayRange, 215
  - vxQueryArray, 213
  - vxReleaseArray, 212
  - vxTruncateArray, 214
  - vxUnmapArrayRange, 216
- Object: Array (Advanced), 288
  - vxRegisterUserStruct, 288
- Object: Context, 191
  - VX\_CONTEXT\_CONVOLUTION\_MAX\_DIMENSION, 193
  - VX\_CONTEXT\_EXTENSIONS\_SIZE, 193
  - VX\_CONTEXT\_EXTENSIONS, 193
  - VX\_CONTEXT\_IMMEDIATE\_BORDER\_POLICY, 193
  - VX\_CONTEXT\_IMMEDIATE\_BORDER, 193
  - VX\_CONTEXT\_IMPLEMENTATION, 193
  - VX\_CONTEXT\_MAX\_TENSOR\_DIMS, 193
  - VX\_CONTEXT\_MODULES, 193
  - VX\_CONTEXT\_NONLINEAR\_MAX\_DIMENSION, 193

- VX\_CONTEXT\_OPTICAL\_FLOW\_MAX\_WINDOW\_DIMENSION, 193
- VX\_CONTEXT\_REFERENCES, 193
- VX\_CONTEXT\_UNIQUE\_KERNEL\_TABLE, 193
- VX\_CONTEXT\_UNIQUE\_KERNELS, 193
- VX\_CONTEXT\_VENDOR\_ID, 193
- VX\_CONTEXT\_VERSION, 193
- VX\_MEMORY\_TYPE\_HOST, 194
- VX\_MEMORY\_TYPE\_NONE, 194
- VX\_READ\_AND\_WRITE, 194
- VX\_READ\_ONLY, 194
- VX\_ROUND\_POLICY\_TO\_NEAREST\_EVEN, 194
- VX\_ROUND\_POLICY\_TO\_ZERO, 194
- VX\_TERM\_CRITERIA\_BOTH, 194
- VX\_TERM\_CRITERIA\_EPSILON, 194
- VX\_TERM\_CRITERIA\_ITERATIONS, 194
- VX\_WRITE\_ONLY, 194
- vx\_accessor\_e, 194
- vx\_context, 192
- vx\_context\_attribute\_e, 192
- vx\_memory\_type\_e, 193
- vx\_round\_policy\_e, 194
- vx\_termination\_criteria\_e, 194
- vxCreateContext, 195
- vxGetContext, 195
- vxQueryContext, 196
- vxReleaseContext, 195
- vxSetContextAttribute, 196
- vxSetImmediateModeTarget, 196
- Object: Convolution, 218
  - VX\_CONVOLUTION\_COLUMNS, 218
  - VX\_CONVOLUTION\_ROWS, 218
  - VX\_CONVOLUTION\_SCALE, 218
  - VX\_CONVOLUTION\_SIZE, 219
  - vx\_convolution\_attribute\_e, 218
  - vxCopyConvolutionCoefficients, 221
  - vxCreateConvolution, 219
  - vxCreateVirtualConvolution, 219
  - vxQueryConvolution, 220
  - vxReleaseConvolution, 219
  - vxSetConvolutionAttribute, 220
- Object: Delay, 292
  - VX\_DELAY\_SLOTS, 293
  - VX\_DELAY\_TYPE, 293
  - vx\_delay, 292
  - vx\_delay\_attribute\_e, 293
  - vxAgeDelay, 295
  - vxCreateDelay, 294
  - vxGetReferenceFromDelay, 294
  - vxQueryDelay, 293
  - vxReleaseDelay, 293
- Object: Distribution, 222
  - VX\_DISTRIBUTION\_BINS, 223
  - VX\_DISTRIBUTION\_DIMENSIONS, 223
  - VX\_DISTRIBUTION\_OFFSET, 223
  - VX\_DISTRIBUTION\_RANGE, 223
  - VX\_DISTRIBUTION\_SIZE, 223
  - VX\_DISTRIBUTION\_WINDOW, 223
  - vx\_distribution\_attribute\_e, 222
  - vxCopyDistribution, 224
  - vxCreateDistribution, 223
  - vxCreateVirtualDistribution, 223
  - vxMapDistribution, 225
  - vxQueryDistribution, 224
  - vxReleaseDistribution, 223
  - vxUnmapDistribution, 226
- Object: Graph, 198
  - VX\_GRAPH\_NUMNODES, 200
  - VX\_GRAPH\_NUMPARAMETERS, 200
  - VX\_GRAPH\_PERFORMANCE, 200
  - VX\_GRAPH\_STATE\_ABANDONED, 200
  - VX\_GRAPH\_STATE\_COMPLETED, 200
  - VX\_GRAPH\_STATE\_RUNNING, 199
  - VX\_GRAPH\_STATE\_UNVERIFIED, 199
  - VX\_GRAPH\_STATE\_VERIFIED, 199
  - VX\_GRAPH\_STATE, 200
  - vx\_graph, 199
  - vx\_graph\_attribute\_e, 200
  - vx\_graph\_state\_e, 199
  - vxCreateGraph, 200
  - vxIsGraphVerified, 204
  - vxProcessGraph, 201
  - vxQueryGraph, 203
  - vxRegisterAutoAging, 204
  - vxReleaseGraph, 200
  - vxScheduleGraph, 202
  - vxSetGraphAttribute, 203
  - vxVerifyGraph, 201
  - vxWaitGraph, 202
- Object: Image, 228
  - VX\_CHANNEL\_RANGE\_FULL, 232
  - VX\_CHANNEL\_RANGE\_RESTRICTED, 232
  - VX\_COLOR\_SPACE\_BT601\_525, 231
  - VX\_COLOR\_SPACE\_BT601\_625, 232
  - VX\_COLOR\_SPACE\_BT709, 232
  - VX\_COLOR\_SPACE\_DEFAULT, 232
  - VX\_COLOR\_SPACE\_NONE, 231
  - VX\_IMAGE\_FORMAT, 231
  - VX\_IMAGE\_HEIGHT, 231
  - VX\_IMAGE\_IS\_UNIFORM, 231
  - VX\_IMAGE\_MEMORY\_TYPE, 231
  - VX\_IMAGE\_PLANES, 231
  - VX\_IMAGE\_RANGE, 231
  - VX\_IMAGE\_SPACE, 231
  - VX\_IMAGE\_UNIFORM\_VALUE, 231
  - VX\_IMAGE\_WIDTH, 231
  - VX\_NOGAP\_X, 232
  - vx\_channel\_range\_e, 232
  - vx\_color\_space\_e, 231
  - vx\_image, 231
  - vx\_image\_attribute\_e, 231
  - vx\_map\_flag\_e, 232
  - vxCopyImagePatch, 239
  - vxCreateImage, 232
  - vxCreateImageFromChannel, 242
  - vxCreateImageFromHandle, 234

- vxCreateImageFromROI, [232](#)
- vxCreateUniformImage, [233](#)
- vxCreateVirtualImage, [233](#)
- vxFormatImagePatchAddress1d, [237](#)
- vxFormatImagePatchAddress2d, [238](#)
- vxGetValidRegionImage, [238](#)
- vxMapImagePatch, [240](#)
- vxQueryImage, [236](#)
- vxReleaseImage, [237](#)
- vxSetImageAttribute, [236](#)
- vxSetImagePixelValues, [236](#)
- vxSetImageValidRectangle, [242](#)
- vxSwapImageHandle, [235](#)
- vxUnmapImagePatch, [241](#)
- Object: Kernel, [296](#)
  - VX\_KERNEL\_ABSDIFF, [301](#)
  - VX\_KERNEL\_ACCUMULATE\_SQUARE, [302](#)
  - VX\_KERNEL\_ACCUMULATE\_WEIGHTED, [302](#)
  - VX\_KERNEL\_ACCUMULATE, [302](#)
  - VX\_KERNEL\_ADD, [303](#)
  - VX\_KERNEL\_AND, [302](#)
  - VX\_KERNEL\_BILATERAL\_FILTER, [305](#)
  - VX\_KERNEL\_BOX\_3x3, [302](#)
  - VX\_KERNEL\_CANNY\_EDGE\_DETECTOR, [302](#)
  - VX\_KERNEL\_CHANNEL\_COMBINE, [301](#)
  - VX\_KERNEL\_CHANNEL\_EXTRACT, [301](#)
  - VX\_KERNEL\_COLOR\_CONVERT, [300](#)
  - VX\_KERNEL\_CONVERTDEPTH, [302](#)
  - VX\_KERNEL\_COPY, [304](#)
  - VX\_KERNEL\_CUSTOM\_CONVOLUTION, [302](#)
  - VX\_KERNEL\_DILATE\_3x3, [302](#)
  - VX\_KERNEL\_ENUM, [305](#)
  - VX\_KERNEL\_EQUALIZE\_HISTOGRAM, [301](#)
  - VX\_KERNEL\_ERODE\_3x3, [302](#)
  - VX\_KERNEL\_FAST\_CORNERS, [303](#)
  - VX\_KERNEL\_GAUSSIAN\_3x3, [302](#)
  - VX\_KERNEL\_GAUSSIAN\_PYRAMID, [302](#)
  - VX\_KERNEL\_HALFSCALE\_GAUSSIAN, [303](#)
  - VX\_KERNEL\_HARRIS\_CORNERS, [303](#)
  - VX\_KERNEL\_HISTOGRAM, [301](#)
  - VX\_KERNEL\_HOG\_CELLS, [305](#)
  - VX\_KERNEL\_HOG\_FEATURES, [305](#)
  - VX\_KERNEL\_HOUGH\_LINES\_P, [304](#)
  - VX\_KERNEL\_INTEGRAL\_IMAGE, [301](#)
  - VX\_KERNEL\_LAPLACIAN\_PYRAMID, [303](#)
  - VX\_KERNEL\_LAPLACIAN\_RECONSTRUCT, [304](#)
  - VX\_KERNEL\_LBP, [304](#)
  - VX\_KERNEL\_LOCAL\_DATA\_SIZE, [305](#)
  - VX\_KERNEL\_MAGNITUDE, [301](#)
  - VX\_KERNEL\_MATCH\_TEMPLATE, [304](#)
  - VX\_KERNEL\_MAX, [305](#)
  - VX\_KERNEL\_MEAN\_STDDEV, [301](#)
  - VX\_KERNEL\_MEDIAN\_3x3, [302](#)
  - VX\_KERNEL\_MINMAXLOC, [302](#)
  - VX\_KERNEL\_MIN, [305](#)
  - VX\_KERNEL\_MULTIPLY, [303](#)
  - VX\_KERNEL\_NAME, [305](#)
  - VX\_KERNEL\_NON\_LINEAR\_FILTER, [304](#)
  - VX\_KERNEL\_NON\_MAX\_SUPPRESSION, [304](#)
  - VX\_KERNEL\_NOT, [303](#)
  - VX\_KERNEL\_OPTICAL\_FLOW\_PYR\_LK, [303](#)
  - VX\_KERNEL\_OR, [303](#)
  - VX\_KERNEL\_PARAMETERS, [305](#)
  - VX\_KERNEL\_PHASE, [301](#)
  - VX\_KERNEL\_REMAP, [303](#)
  - VX\_KERNEL\_SCALAR\_OPERATION, [305](#)
  - VX\_KERNEL\_SCALE\_IMAGE, [301](#)
  - VX\_KERNEL\_SELECT, [305](#)
  - VX\_KERNEL\_SOBEL\_3x3, [301](#)
  - VX\_KERNEL\_SUBTRACT, [303](#)
  - VX\_KERNEL\_TABLE\_LOOKUP, [301](#)
  - VX\_KERNEL\_TENSOR\_ADD, [304](#)
  - VX\_KERNEL\_TENSOR\_CONVERT\_DEPTH, [304](#)
  - VX\_KERNEL\_TENSOR\_MATRIX\_MULTIPLY, [304](#)
  - VX\_KERNEL\_TENSOR\_MULTIPLY, [304](#)
  - VX\_KERNEL\_TENSOR\_SUBTRACT, [304](#)
  - VX\_KERNEL\_TENSOR\_TABLE\_LOOKUP, [304](#)
  - VX\_KERNEL\_TENSOR\_TRANSPOSE, [304](#)
  - VX\_KERNEL\_THRESHOLD, [301](#)
  - VX\_KERNEL\_WARP\_AFFINE, [303](#)
  - VX\_KERNEL\_WARP\_PERSPECTIVE, [303](#)
  - VX\_KERNEL\_XOR, [303](#)
  - VX\_LIBRARY\_KHR\_BASE, [300](#)
  - vx\_kernel, [300](#)
  - vx\_kernel\_attribute\_e, [305](#)
  - vx\_kernel\_e, [300](#)
  - vx\_library\_e, [300](#)
  - vxGetKernelByEnum, [307](#)
  - vxGetKernelByName, [306](#)
  - vxQueryKernel, [307](#)
  - vxReleaseKernel, [308](#)
- Object: LUT, [244](#)
  - VX\_LUT\_COUNT, [244](#)
  - VX\_LUT\_OFFSET, [244](#)
  - VX\_LUT\_SIZE, [244](#)
  - VX\_LUT\_TYPE, [244](#)
  - vx\_lut\_attribute\_e, [244](#)
  - vxCopyLUT, [246](#)
  - vxCreateLUT, [245](#)
  - vxCreateVirtualLUT, [245](#)
  - vxMapLUT, [247](#)
  - vxQueryLUT, [246](#)
  - vxReleaseLUT, [245](#)
  - vxUnmapLUT, [248](#)
- Object: Matrix, [250](#)
  - VX\_MATRIX\_COLUMNS, [250](#)
  - VX\_MATRIX\_ORIGIN, [250](#)
  - VX\_MATRIX\_PATTERN, [251](#)
  - VX\_MATRIX\_ROWS, [250](#)
  - VX\_MATRIX\_SIZE, [250](#)
  - VX\_MATRIX\_TYPE, [250](#)
  - vx\_matrix\_attribute\_e, [250](#)
  - vxCopyMatrix, [252](#)
  - vxCreateMatrix, [251](#)
  - vxCreateMatrixFromPattern, [253](#)
  - vxCreateMatrixFromPatternAndOrigin, [253](#)

- vxCreateVirtualMatrix, 251
- vxQueryMatrix, 252
- vxReleaseMatrix, 251
- Object: Node, 205
  - VX\_NODE\_BORDER, 206
  - VX\_NODE\_IS\_REPLICATED, 206
  - VX\_NODE\_LOCAL\_DATA\_PTR, 206
  - VX\_NODE\_LOCAL\_DATA\_SIZE, 206
  - VX\_NODE\_PARAMETERS, 206
  - VX\_NODE\_PERFORMANCE, 206
  - VX\_NODE\_REPLICATE\_FLAGS, 206
  - VX\_NODE\_STATUS, 206
  - VX\_NODE\_VALID\_RECT\_RESET, 206
  - vx\_node, 206
  - vx\_node\_attribute\_e, 206
  - vxQueryNode, 206
  - vxReleaseNode, 207
  - vxRemoveNode, 208
  - vxReplicateNode, 208
  - vxSetNodeAttribute, 207
  - vxSetNodeTarget, 208
- Object: Node (Advanced), 289
  - vxCreateGenericNode, 289
- Object: ObjectArray, 278
  - VX\_OBJECT\_ARRAY\_ITEMTYPE, 278
  - VX\_OBJECT\_ARRAY\_NUMITEMS, 278
  - vx\_object\_array\_attribute\_e, 278
  - vxCreateObjectArray, 279
  - vxCreateVirtualObjectArray, 279
  - vxGetObjectArrayItem, 279
  - vxQueryObjectArray, 280
  - vxReleaseObjectArray, 279
- Object: Parameter, 309
  - VX\_BIDIRECTIONAL, 310
  - VX\_INPUT, 310
  - VX\_OUTPUT, 310
  - VX\_PARAMETER\_DIRECTION, 310
  - VX\_PARAMETER\_INDEX, 310
  - VX\_PARAMETER\_REF, 310
  - VX\_PARAMETER\_STATE\_OPTIONAL, 310
  - VX\_PARAMETER\_STATE\_REQUIRED, 310
  - VX\_PARAMETER\_STATE, 310
  - VX\_PARAMETER\_TYPE, 310
  - vx\_direction\_e, 310
  - vx\_parameter, 310
  - vx\_parameter\_attribute\_e, 310
  - vx\_parameter\_state\_e, 310
  - vxGetKernelParameterByIndex, 310
  - vxGetParameterByIndex, 311
  - vxQueryParameter, 312
  - vxReleaseParameter, 311
  - vxSetParameterByIndex, 311
  - vxSetParameterByReference, 312
- Object: Pyramid, 255
  - VX\_PYRAMID\_FORMAT, 256
  - VX\_PYRAMID\_HEIGHT, 256
  - VX\_PYRAMID\_LEVELS, 256
  - VX\_PYRAMID\_SCALE, 256
  - VX\_PYRAMID\_WIDTH, 256
  - vx\_pyramid\_attribute\_e, 256
  - vxCreatePyramid, 256
  - vxCreateVirtualPyramid, 256
  - vxGetPyramidLevel, 258
  - vxQueryPyramid, 257
  - vxReleasePyramid, 257
- Object: Reference, 187
  - VX\_MAX\_REFERENCE\_NAME, 187
  - VX\_REFERENCE\_COUNT, 188
  - VX\_REFERENCE\_NAME, 188
  - VX\_REFERENCE\_TYPE, 188
  - vx\_reference, 188
  - vx\_reference\_attribute\_e, 188
  - vxQueryReference, 188
  - vxReleaseReference, 188
  - vxRetainReference, 189
  - vxSetReferenceName, 189
- Object: Remap, 259
  - VX\_REMAP\_DESTINATION\_HEIGHT, 259
  - VX\_REMAP\_DESTINATION\_WIDTH, 259
  - VX\_REMAP\_SOURCE\_HEIGHT, 259
  - VX\_REMAP\_SOURCE\_WIDTH, 259
  - vx\_remap\_attribute\_e, 259
  - vxCopyRemapPatch, 263
  - vxCreateRemap, 260
  - vxCreateVirtualRemap, 260
  - vxMapRemapPatch, 261
  - vxQueryRemap, 264
  - vxReleaseRemap, 260
  - vxUnmapRemapPatch, 262
- Object: Scalar, 265
  - VX\_SCALAR\_OP\_ADD, 267
  - VX\_SCALAR\_OP\_AND, 266
  - VX\_SCALAR\_OP\_DIVIDE, 267
  - VX\_SCALAR\_OP\_EQUAL, 266
  - VX\_SCALAR\_OP\_GREATEREQ, 267
  - VX\_SCALAR\_OP\_GREATER, 266
  - VX\_SCALAR\_OP\_LESSEQ, 266
  - VX\_SCALAR\_OP\_LESS, 266
  - VX\_SCALAR\_OP\_MAX, 267
  - VX\_SCALAR\_OP\_MIN, 267
  - VX\_SCALAR\_OP\_MODULUS, 267
  - VX\_SCALAR\_OP\_MULTIPLY, 267
  - VX\_SCALAR\_OP\_NAND, 266
  - VX\_SCALAR\_OP\_NOTEQUAL, 266
  - VX\_SCALAR\_OP\_OR, 266
  - VX\_SCALAR\_OP\_SUBTRACT, 267
  - VX\_SCALAR\_OP\_XOR, 266
  - VX\_SCALAR\_TYPE, 266
  - vx\_scalar, 266
  - vx\_scalar\_attribute\_e, 266
  - vx\_scalar\_operation\_e, 266
  - vxCopyScalar, 269
  - vxCopyScalarWithSize, 269
  - vxCreateScalar, 267
  - vxCreateScalarWithSize, 267
  - vxCreateVirtualScalar, 267



- vxQueryScalar, 268
- vxReleaseScalar, 268
- Object: Tensor, 281
  - VX\_TENSOR\_DATA\_TYPE, 282
  - VX\_TENSOR\_DIMS, 282
  - VX\_TENSOR\_FIXED\_POINT\_POSITION, 282
  - VX\_TENSOR\_NUMBER\_OF\_DIMS, 282
  - vx\_tensor, 282
  - vx\_tensor\_attribute\_e, 282
  - vxCopyTensorPatch, 284
  - vxCreateImageObjectArrayFromTensor, 283
  - vxCreateTensor, 282
  - vxCreateTensorFromView, 283
  - vxCreateVirtualTensor, 283
  - vxQueryTensor, 285
  - vxReleaseTensor, 285
- Object: Threshold, 271
  - VX\_THRESHOLD\_INPUT\_FORMAT, 272
  - VX\_THRESHOLD\_OUTPUT\_FORMAT, 272
  - VX\_THRESHOLD\_TYPE\_BINARY, 272
  - VX\_THRESHOLD\_TYPE\_RANGE, 272
  - VX\_THRESHOLD\_TYPE, 272
  - vx\_threshold\_attribute\_e, 272
  - vx\_threshold\_type\_e, 272
  - vxCopyThresholdOutput, 275
  - vxCopyThresholdRange, 274
  - vxCopyThresholdValue, 273
  - vxCreateThresholdForImage, 272
  - vxCreateVirtualThresholdForImage, 273
  - vxQueryThreshold, 277
  - vxReleaseThreshold, 276
  - vxSetThresholdAttribute, 276
- Objects, 186
- Optical Flow Pyramid (LK), 116
  - vxOpticalFlowPyrLKNode, 117
  - vxuOpticalFlowPyrLK, 117
- Phase, 119
  - vxPhaseNode, 119
  - vxuPhase, 119
- Pixel-wise Multiplication, 121
  - vxMultiplyNode, 121
  - vxuMultiply, 122
- Reconstruction from a Laplacian Image Pyramid, 100
  - vxLaplacianReconstructNode, 100
  - vxuLaplacianReconstruct, 100
- Remap, 123
  - vxRemapNode, 123
  - vxuRemap, 123
- Scale Image, 125
  - vxHalfScaleGaussianNode, 127
  - vxScaleImageNode, 127
  - vxuHalfScaleGaussian, 128
  - vxuScaleImage, 128
- Sobel 3x3, 129
  - vxSobel3x3Node, 129
  - vxuSobel3x3, 129
- TableLookup, 131
  - vxTableLookupNode, 131
  - vxuTableLookup, 131
- Tensor Add, 157
  - vxTensorAddNode, 157
  - vxuTensorAdd, 157
- Tensor Convert Bit-Depth, 165
  - vxTensorConvertDepthNode, 165
  - vxuTensorConvertDepth, 165
- Tensor Matrix Multiply, 167
  - vxTensorMatrixMultiplyNode, 168
  - vxuTensorMatrixMultiply, 168
- Tensor Multiply, 155
  - vxTensorMultiplyNode, 155
  - vxuTensorMultiply, 155
- Tensor Subtract, 159
  - vxTensorSubtractNode, 159
  - vxuTensorSubtract, 159
- Tensor TableLookUp, 161
  - vxTensorTableLookupNode, 161
  - vxuTensorTableLookup, 161
- Tensor Transpose, 163
  - vxTensorTransposeNode, 163
  - vxuTensorTranspose, 163
- Thresholding, 133
  - vxThresholdNode, 133
  - vxuThreshold, 134
- VX\_ACTION\_ABANDON
  - Framework: Node Callbacks, 317
- VX\_ACTION\_CONTINUE
  - Framework: Node Callbacks, 317
- VX\_ARRAY\_CAPACITY
  - Object: Array, 211
- VX\_ARRAY\_ITEMSIZE
  - Object: Array, 211
- VX\_ARRAY\_ITEMTYPE
  - Object: Array, 211
- VX\_ARRAY\_NUMITEMS
  - Object: Array, 211
- VX\_BIDIRECTIONAL
  - Object: Parameter, 310
- VX\_BORDER\_CONSTANT
  - Node: Border Modes, 290
- VX\_BORDER\_POLICY\_DEFAULT\_TO\_UNDEFINED
  - Node: Border Modes, 291
- VX\_BORDER\_POLICY\_RETURN\_ERROR
  - Node: Border Modes, 291
- VX\_BORDER\_REPLICATE
  - Node: Border Modes, 290
- VX\_BORDER\_UNDEFINED
  - Node: Border Modes, 290
- VX\_CHANNEL\_0
  - Basic Features, 183
- VX\_CHANNEL\_1
  - Basic Features, 183
- VX\_CHANNEL\_2
  - Basic Features, 183
- VX\_CHANNEL\_3

- Basic Features, [183](#)
- VX\_CHANNEL\_RANGE\_FULL
  - Object: Image, [232](#)
- VX\_CHANNEL\_RANGE\_RESTRICTED
  - Object: Image, [232](#)
- VX\_CHANNEL\_A
  - Basic Features, [183](#)
- VX\_CHANNEL\_B
  - Basic Features, [183](#)
- VX\_CHANNEL\_G
  - Basic Features, [183](#)
- VX\_CHANNEL\_R
  - Basic Features, [183](#)
- VX\_CHANNEL\_U
  - Basic Features, [183](#)
- VX\_CHANNEL\_V
  - Basic Features, [183](#)
- VX\_CHANNEL\_Y
  - Basic Features, [183](#)
- VX\_COLOR\_SPACE\_BT601\_525
  - Object: Image, [231](#)
- VX\_COLOR\_SPACE\_BT601\_625
  - Object: Image, [232](#)
- VX\_COLOR\_SPACE\_BT709
  - Object: Image, [232](#)
- VX\_COLOR\_SPACE\_DEFAULT
  - Object: Image, [232](#)
- VX\_COLOR\_SPACE\_NONE
  - Object: Image, [231](#)
- VX\_COMPARE\_CCORR\_NORM
  - MatchTemplate, [141](#)
- VX\_COMPARE\_CCORR
  - MatchTemplate, [141](#)
- VX\_COMPARE\_HAMMING
  - MatchTemplate, [141](#)
- VX\_COMPARE\_L1
  - MatchTemplate, [141](#)
- VX\_COMPARE\_L2
  - MatchTemplate, [141](#)
- VX\_COMPARE\_L2\_NORM
  - MatchTemplate, [141](#)
- VX\_CONTEXT\_CONVOLUTION\_MAX\_DIMENSION
  - Object: Context, [193](#)
- VX\_CONTEXT\_EXTENSIONS\_SIZE
  - Object: Context, [193](#)
- VX\_CONTEXT\_EXTENSIONS
  - Object: Context, [193](#)
- VX\_CONTEXT\_IMMEDIATE\_BORDER\_POLICY
  - Object: Context, [193](#)
- VX\_CONTEXT\_IMMEDIATE\_BORDER
  - Object: Context, [193](#)
- VX\_CONTEXT\_IMPLEMENTATION
  - Object: Context, [193](#)
- VX\_CONTEXT\_MAX\_TENSOR\_DIMS
  - Object: Context, [193](#)
- VX\_CONTEXT\_MODULES
  - Object: Context, [193](#)
- VX\_CONTEXT\_NONLINEAR\_MAX\_DIMENSION
  - Object: Context, [193](#)
- VX\_CONTEXT\_OPTICAL\_FLOW\_MAX\_WINDOW\_DIMENSION
  - Object: Context, [193](#)
- VX\_CONTEXT\_REFERENCES
  - Object: Context, [193](#)
- VX\_CONTEXT\_UNIQUE\_KERNEL\_TABLE
  - Object: Context, [193](#)
- VX\_CONTEXT\_UNIQUE\_KERNELS
  - Object: Context, [193](#)
- VX\_CONTEXT\_VENDOR\_ID
  - Object: Context, [193](#)
- VX\_CONTEXT\_VERSION
  - Object: Context, [193](#)
- VX\_CONVERT\_POLICY\_SATURATE
  - Basic Features, [182](#)
- VX\_CONVERT\_POLICY\_WRAP
  - Basic Features, [182](#)
- VX\_CONVOLUTION\_COLUMNS
  - Object: Convolution, [218](#)
- VX\_CONVOLUTION\_ROWS
  - Object: Convolution, [218](#)
- VX\_CONVOLUTION\_SCALE
  - Object: Convolution, [218](#)
- VX\_CONVOLUTION\_SIZE
  - Object: Convolution, [219](#)
- VX\_DELAY\_SLOTS
  - Object: Delay, [293](#)
- VX\_DELAY\_TYPE
  - Object: Delay, [293](#)
- VX\_DF\_IMAGE\_IYUV
  - Basic Features, [182](#)
- VX\_DF\_IMAGE\_NV12
  - Basic Features, [182](#)
- VX\_DF\_IMAGE\_NV21
  - Basic Features, [182](#)
- VX\_DF\_IMAGE\_RGBX
  - Basic Features, [182](#)
- VX\_DF\_IMAGE\_RGB
  - Basic Features, [182](#)
- VX\_DF\_IMAGE\_S16
  - Basic Features, [182](#)
- VX\_DF\_IMAGE\_S32
  - Basic Features, [182](#)
- VX\_DF\_IMAGE\_U16
  - Basic Features, [182](#)
- VX\_DF\_IMAGE\_U32
  - Basic Features, [182](#)
- VX\_DF\_IMAGE\_U8
  - Basic Features, [182](#)
- VX\_DF\_IMAGE\_UYVY
  - Basic Features, [182](#)
- VX\_DF\_IMAGE\_VIRT
  - Basic Features, [182](#)
- VX\_DF\_IMAGE\_YUV4
  - Basic Features, [182](#)
- VX\_DF\_IMAGE\_YUYV
  - Basic Features, [182](#)



- VX\_DF\_IMAGE
  - Basic Features, [177](#)
- VX\_DIRECTIVE\_DISABLE\_LOGGING
  - Framework: Directives, [324](#)
- VX\_DIRECTIVE\_DISABLE\_PERFORMANCE
  - Framework: Directives, [324](#)
- VX\_DIRECTIVE\_ENABLE\_LOGGING
  - Framework: Directives, [324](#)
- VX\_DIRECTIVE\_ENABLE\_PERFORMANCE
  - Framework: Directives, [324](#)
- VX\_DISTRIBUTION\_BINS
  - Object: Distribution, [223](#)
- VX\_DISTRIBUTION\_DIMENSIONS
  - Object: Distribution, [223](#)
- VX\_DISTRIBUTION\_OFFSET
  - Object: Distribution, [223](#)
- VX\_DISTRIBUTION\_RANGE
  - Object: Distribution, [223](#)
- VX\_DISTRIBUTION\_SIZE
  - Object: Distribution, [223](#)
- VX\_DISTRIBUTION\_WINDOW
  - Object: Distribution, [223](#)
- VX\_ENUM\_ACCESSOR
  - Basic Features, [181](#)
- VX\_ENUM\_ACTION
  - Basic Features, [181](#)
- VX\_ENUM\_BASE
  - Basic Features, [177](#)
- VX\_ENUM\_BORDER\_POLICY
  - Basic Features, [181](#)
- VX\_ENUM\_BORDER
  - Basic Features, [181](#)
- VX\_ENUM\_CHANNEL
  - Basic Features, [181](#)
- VX\_ENUM\_COLOR\_RANGE
  - Basic Features, [181](#)
- VX\_ENUM\_COLOR\_SPACE
  - Basic Features, [181](#)
- VX\_ENUM\_COMP\_METRIC
  - Basic Features, [181](#)
- VX\_ENUM\_COMPARISON
  - Basic Features, [181](#)
- VX\_ENUM\_CONVERT\_POLICY
  - Basic Features, [181](#)
- VX\_ENUM\_DIRECTION
  - Basic Features, [181](#)
- VX\_ENUM\_DIRECTIVE
  - Basic Features, [181](#)
- VX\_ENUM\_GRAPH\_STATE
  - Basic Features, [181](#)
- VX\_ENUM\_HINT
  - Basic Features, [181](#)
- VX\_ENUM\_INTERPOLATION
  - Basic Features, [181](#)
- VX\_ENUM\_LBP\_FORMAT
  - Basic Features, [181](#)
- VX\_ENUM\_MEMORY\_TYPE
  - Basic Features, [181](#)
- VX\_ENUM\_NONLINEAR
  - Basic Features, [181](#)
- VX\_ENUM\_NORM\_TYPE
  - Basic Features, [181](#)
- VX\_ENUM\_OVERFLOW
  - Basic Features, [181](#)
- VX\_ENUM\_PARAMETER\_STATE
  - Basic Features, [181](#)
- VX\_ENUM\_PATTERN
  - Basic Features, [181](#)
- VX\_ENUM\_ROUND\_POLICY
  - Basic Features, [181](#)
- VX\_ENUM\_SCALAR\_OPERATION
  - Basic Features, [181](#)
- VX\_ENUM\_TARGET
  - Basic Features, [181](#)
- VX\_ENUM\_TERM\_CRITERIA
  - Basic Features, [181](#)
- VX\_ENUM\_THRESHOLD\_TYPE
  - Basic Features, [181](#)
- VX\_ERROR\_GRAPH\_ABANDONED
  - Basic Features, [180](#)
- VX\_ERROR\_GRAPH\_SCHEDULED
  - Basic Features, [180](#)
- VX\_ERROR\_INVALID\_DIMENSION
  - Basic Features, [180](#)
- VX\_ERROR\_INVALID\_FORMAT
  - Basic Features, [180](#)
- VX\_ERROR\_INVALID\_GRAPH
  - Basic Features, [180](#)
- VX\_ERROR\_INVALID\_LINK
  - Basic Features, [180](#)
- VX\_ERROR\_INVALID\_MODULE
  - Basic Features, [180](#)
- VX\_ERROR\_INVALID\_NODE
  - Basic Features, [180](#)
- VX\_ERROR\_INVALID\_PARAMETERS
  - Basic Features, [180](#)
- VX\_ERROR\_INVALID\_REFERENCE
  - Basic Features, [180](#)
- VX\_ERROR\_INVALID\_SCOPE
  - Basic Features, [180](#)
- VX\_ERROR\_INVALID\_TYPE
  - Basic Features, [180](#)
- VX\_ERROR\_INVALID\_VALUE
  - Basic Features, [180](#)
- VX\_ERROR\_MULTIPLE\_WRITERS
  - Basic Features, [180](#)
- VX\_ERROR\_NO\_MEMORY
  - Basic Features, [180](#)
- VX\_ERROR\_NO\_RESOURCES
  - Basic Features, [180](#)
- VX\_ERROR\_NOT\_ALLOCATED
  - Basic Features, [180](#)
- VX\_ERROR\_NOT\_COMPATIBLE
  - Basic Features, [180](#)
- VX\_ERROR\_NOT\_IMPLEMENTED
  - Basic Features, [181](#)

- VX\_ERROR\_NOT\_SUFFICIENT
  - Basic Features, [180](#)
- VX\_ERROR\_NOT\_SUPPORTED
  - Basic Features, [181](#)
- VX\_ERROR\_OPTIMIZED\_AWAY
  - Basic Features, [180](#)
- VX\_ERROR\_REFERENCE\_NONZERO
  - Basic Features, [180](#)
- VX\_FAILURE
  - Basic Features, [181](#)
- VX\_GRAPH\_NUMNODES
  - Object: Graph, [200](#)
- VX\_GRAPH\_NUMPARAMETERS
  - Object: Graph, [200](#)
- VX\_GRAPH\_PERFORMANCE
  - Object: Graph, [200](#)
- VX\_GRAPH\_STATE\_ABANDONED
  - Object: Graph, [200](#)
- VX\_GRAPH\_STATE\_COMPLETED
  - Object: Graph, [200](#)
- VX\_GRAPH\_STATE\_RUNNING
  - Object: Graph, [199](#)
- VX\_GRAPH\_STATE\_UNVERIFIED
  - Object: Graph, [199](#)
- VX\_GRAPH\_STATE\_VERIFIED
  - Object: Graph, [199](#)
- VX\_GRAPH\_STATE
  - Object: Graph, [200](#)
- VX\_HINT\_PERFORMANCE\_DEFAULT
  - Framework: Hints, [322](#)
- VX\_HINT\_PERFORMANCE\_HIGH\_SPEED
  - Framework: Hints, [322](#)
- VX\_HINT\_PERFORMANCE\_LOW\_POWER
  - Framework: Hints, [322](#)
- VX\_ID\_AMD
  - Basic Features, [184](#)
- VX\_ID\_ARM
  - Basic Features, [184](#)
- VX\_ID\_AXIS
  - Basic Features, [184](#)
- VX\_ID\_BDTI
  - Basic Features, [184](#)
- VX\_ID\_BROADCOM
  - Basic Features, [184](#)
- VX\_ID\_CADENCE
  - Basic Features, [185](#)
- VX\_ID\_CEVA
  - Basic Features, [185](#)
- VX\_ID\_DEFAULT
  - Basic Features, [185](#)
- VX\_ID\_FREESCALE
  - Basic Features, [184](#)
- VX\_ID\_HUAWEI
  - Basic Features, [185](#)
- VX\_ID\_IMAGINATION
  - Basic Features, [185](#)
- VX\_ID\_INTEL
  - Basic Features, [184](#)
- VX\_ID\_ITSEEZ
  - Basic Features, [185](#)
- VX\_ID\_KHRONOS
  - Basic Features, [184](#)
- VX\_ID\_MARVELL
  - Basic Features, [184](#)
- VX\_ID\_MEDIATEK
  - Basic Features, [185](#)
- VX\_ID\_MOVIDIUS
  - Basic Features, [184](#)
- VX\_ID\_NVIDIA
  - Basic Features, [184](#)
- VX\_ID\_NXP
  - Basic Features, [185](#)
- VX\_ID\_QUALCOMM
  - Basic Features, [184](#)
- VX\_ID\_RENESAS
  - Basic Features, [184](#)
- VX\_ID\_SAMSUNG
  - Basic Features, [184](#)
- VX\_ID\_SOCIONEXT
  - Basic Features, [185](#)
- VX\_ID\_SYNOPSYS
  - Basic Features, [185](#)
- VX\_ID\_ST
  - Basic Features, [185](#)
- VX\_ID\_TI
  - Basic Features, [184](#)
- VX\_ID\_USER
  - Basic Features, [185](#)
- VX\_ID\_VIDEANTIS
  - Basic Features, [185](#)
- VX\_ID\_VIVANTE
  - Basic Features, [184](#)
- VX\_ID\_XILINX
  - Basic Features, [184](#)
- VX\_IMAGE\_FORMAT
  - Object: Image, [231](#)
- VX\_IMAGE\_HEIGHT
  - Object: Image, [231](#)
- VX\_IMAGE\_IS\_UNIFORM
  - Object: Image, [231](#)
- VX\_IMAGE\_MEMORY\_TYPE
  - Object: Image, [231](#)
- VX\_IMAGE\_PLANES
  - Object: Image, [231](#)
- VX\_IMAGE\_RANGE
  - Object: Image, [231](#)
- VX\_IMAGE\_SPACE
  - Object: Image, [231](#)
- VX\_IMAGE\_UNIFORM\_VALUE
  - Object: Image, [231](#)
- VX\_IMAGE\_WIDTH
  - Object: Image, [231](#)
- VX\_INPUT
  - Object: Parameter, [310](#)
- VX\_INTERPOLATION\_AREA
  - Basic Features, [184](#)

- VX\_INTERPOLATION\_BILINEAR
  - Basic Features, [183](#)
- VX\_INTERPOLATION\_NEAREST\_NEIGHBOR
  - Basic Features, [183](#)
- VX\_KERNEL\_ABSDIFF
  - Object: Kernel, [301](#)
- VX\_KERNEL\_ACCUMULATE\_SQUARE
  - Object: Kernel, [302](#)
- VX\_KERNEL\_ACCUMULATE\_WEIGHTED
  - Object: Kernel, [302](#)
- VX\_KERNEL\_ACCUMULATE
  - Object: Kernel, [302](#)
- VX\_KERNEL\_ADD
  - Object: Kernel, [303](#)
- VX\_KERNEL\_AND
  - Object: Kernel, [302](#)
- VX\_KERNEL\_BILATERAL\_FILTER
  - Object: Kernel, [305](#)
- VX\_KERNEL\_BOX\_3x3
  - Object: Kernel, [302](#)
- VX\_KERNEL\_CANNY\_EDGE\_DETECTOR
  - Object: Kernel, [302](#)
- VX\_KERNEL\_CHANNEL\_COMBINE
  - Object: Kernel, [301](#)
- VX\_KERNEL\_CHANNEL\_EXTRACT
  - Object: Kernel, [301](#)
- VX\_KERNEL\_COLOR\_CONVERT
  - Object: Kernel, [300](#)
- VX\_KERNEL\_CONVERTDEPTH
  - Object: Kernel, [302](#)
- VX\_KERNEL\_COPY
  - Object: Kernel, [304](#)
- VX\_KERNEL\_CUSTOM\_CONVOLUTION
  - Object: Kernel, [302](#)
- VX\_KERNEL\_DILATE\_3x3
  - Object: Kernel, [302](#)
- VX\_KERNEL\_ENUM
  - Object: Kernel, [305](#)
- VX\_KERNEL\_EQUALIZE\_HISTOGRAM
  - Object: Kernel, [301](#)
- VX\_KERNEL\_ERODE\_3x3
  - Object: Kernel, [302](#)
- VX\_KERNEL\_FAST\_CORNERS
  - Object: Kernel, [303](#)
- VX\_KERNEL\_GAUSSIAN\_3x3
  - Object: Kernel, [302](#)
- VX\_KERNEL\_GAUSSIAN\_PYRAMID
  - Object: Kernel, [302](#)
- VX\_KERNEL\_HALFSCALE\_GAUSSIAN
  - Object: Kernel, [303](#)
- VX\_KERNEL\_HARRIS\_CORNERS
  - Object: Kernel, [303](#)
- VX\_KERNEL\_HISTOGRAM
  - Object: Kernel, [301](#)
- VX\_KERNEL\_HOG\_CELLS
  - Object: Kernel, [305](#)
- VX\_KERNEL\_HOG\_FEATURES
  - Object: Kernel, [305](#)
- VX\_KERNEL\_HOUGH\_LINES\_P
  - Object: Kernel, [304](#)
- VX\_KERNEL\_INTEGRAL\_IMAGE
  - Object: Kernel, [301](#)
- VX\_KERNEL\_LAPLACIAN\_PYRAMID
  - Object: Kernel, [303](#)
- VX\_KERNEL\_LAPLACIAN\_RECONSTRUCT
  - Object: Kernel, [304](#)
- VX\_KERNEL\_LBP
  - Object: Kernel, [304](#)
- VX\_KERNEL\_LOCAL\_DATA\_SIZE
  - Object: Kernel, [305](#)
- VX\_KERNEL\_MAGNITUDE
  - Object: Kernel, [301](#)
- VX\_KERNEL\_MATCH\_TEMPLATE
  - Object: Kernel, [304](#)
- VX\_KERNEL\_MAX
  - Object: Kernel, [305](#)
- VX\_KERNEL\_MEAN\_STDDEV
  - Object: Kernel, [301](#)
- VX\_KERNEL\_MEDIAN\_3x3
  - Object: Kernel, [302](#)
- VX\_KERNEL\_MINMAXLOC
  - Object: Kernel, [302](#)
- VX\_KERNEL\_MIN
  - Object: Kernel, [305](#)
- VX\_KERNEL\_MULTIPLY
  - Object: Kernel, [303](#)
- VX\_KERNEL\_NAME
  - Object: Kernel, [305](#)
- VX\_KERNEL\_NON\_LINEAR\_FILTER
  - Object: Kernel, [304](#)
- VX\_KERNEL\_NON\_MAX\_SUPPRESSION
  - Object: Kernel, [304](#)
- VX\_KERNEL\_NOT
  - Object: Kernel, [303](#)
- VX\_KERNEL\_OPTICAL\_FLOW\_PYR\_LK
  - Object: Kernel, [303](#)
- VX\_KERNEL\_OR
  - Object: Kernel, [303](#)
- VX\_KERNEL\_PARAMETERS
  - Object: Kernel, [305](#)
- VX\_KERNEL\_PHASE
  - Object: Kernel, [301](#)
- VX\_KERNEL\_REMAP
  - Object: Kernel, [303](#)
- VX\_KERNEL\_SCALAR\_OPERATION
  - Object: Kernel, [305](#)
- VX\_KERNEL\_SCALE\_IMAGE
  - Object: Kernel, [301](#)
- VX\_KERNEL\_SELECT
  - Object: Kernel, [305](#)
- VX\_KERNEL\_SOBEL\_3x3
  - Object: Kernel, [301](#)
- VX\_KERNEL\_SUBTRACT
  - Object: Kernel, [303](#)
- VX\_KERNEL\_TABLE\_LOOKUP
  - Object: Kernel, [301](#)

- VX\_KERNEL\_TENSOR\_ADD
  - Object: Kernel, [304](#)
- VX\_KERNEL\_TENSOR\_CONVERT\_DEPTH
  - Object: Kernel, [304](#)
- VX\_KERNEL\_TENSOR\_MATRIX\_MULTIPLY
  - Object: Kernel, [304](#)
- VX\_KERNEL\_TENSOR\_MULTIPLY
  - Object: Kernel, [304](#)
- VX\_KERNEL\_TENSOR\_SUBTRACT
  - Object: Kernel, [304](#)
- VX\_KERNEL\_TENSOR\_TABLE\_LOOKUP
  - Object: Kernel, [304](#)
- VX\_KERNEL\_TENSOR\_TRANSPOSE
  - Object: Kernel, [304](#)
- VX\_KERNEL\_THRESHOLD
  - Object: Kernel, [301](#)
- VX\_KERNEL\_WARP\_AFFINE
  - Object: Kernel, [303](#)
- VX\_KERNEL\_WARP\_PERSPECTIVE
  - Object: Kernel, [303](#)
- VX\_KERNEL\_XOR
  - Object: Kernel, [303](#)
- VX\_LBP
  - LBP, [144](#)
- VX\_LIBRARY\_KHR\_BASE
  - Object: Kernel, [300](#)
- VX\_LUT\_COUNT
  - Object: LUT, [244](#)
- VX\_LUT\_OFFSET
  - Object: LUT, [244](#)
- VX\_LUT\_SIZE
  - Object: LUT, [244](#)
- VX\_LUT\_TYPE
  - Object: LUT, [244](#)
- VX\_MATRIX\_COLUMNS
  - Object: Matrix, [250](#)
- VX\_MATRIX\_ORIGIN
  - Object: Matrix, [250](#)
- VX\_MATRIX\_PATTERN
  - Object: Matrix, [251](#)
- VX\_MATRIX\_ROWS
  - Object: Matrix, [250](#)
- VX\_MATRIX\_SIZE
  - Object: Matrix, [250](#)
- VX\_MATRIX\_TYPE
  - Object: Matrix, [250](#)
- VX\_MAX\_REFERENCE\_NAME
  - Object: Reference, [187](#)
- VX\_MEMORY\_TYPE\_HOST
  - Object: Context, [194](#)
- VX\_MEMORY\_TYPE\_NONE
  - Object: Context, [194](#)
- VX\_MLBP
  - LBP, [144](#)
- VX\_NODE\_BORDER
  - Object: Node, [206](#)
- VX\_NODE\_IS\_REPLICATED
  - Object: Node, [206](#)
- VX\_NODE\_LOCAL\_DATA\_PTR
  - Object: Node, [206](#)
- VX\_NODE\_LOCAL\_DATA\_SIZE
  - Object: Node, [206](#)
- VX\_NODE\_PARAMETERS
  - Object: Node, [206](#)
- VX\_NODE\_PERFORMANCE
  - Object: Node, [206](#)
- VX\_NODE\_REPLICATE\_FLAGS
  - Object: Node, [206](#)
- VX\_NODE\_STATUS
  - Object: Node, [206](#)
- VX\_NODE\_VALID\_RECT\_RESET
  - Object: Node, [206](#)
- VX\_NOGAP\_X
  - Object: Image, [232](#)
- VX\_NONLINEAR\_FILTER\_MAX
  - Basic Features, [184](#)
- VX\_NONLINEAR\_FILTER\_MEDIAN
  - Basic Features, [184](#)
- VX\_NONLINEAR\_FILTER\_MIN
  - Basic Features, [184](#)
- VX\_NORM\_L1
  - Canny Edge Detector, [65](#)
- VX\_NORM\_L2
  - Canny Edge Detector, [65](#)
- VX\_OBJECT\_ARRAY\_ITEMTYPE
  - Object: ObjectArray, [278](#)
- VX\_OBJECT\_ARRAY\_NUMITEMS
  - Object: ObjectArray, [278](#)
- VX\_OUTPUT
  - Object: Parameter, [310](#)
- VX\_PARAMETER\_DIRECTION
  - Object: Parameter, [310](#)
- VX\_PARAMETER\_INDEX
  - Object: Parameter, [310](#)
- VX\_PARAMETER\_REF
  - Object: Parameter, [310](#)
- VX\_PARAMETER\_STATE\_OPTIONAL
  - Object: Parameter, [310](#)
- VX\_PARAMETER\_STATE\_REQUIRED
  - Object: Parameter, [310](#)
- VX\_PARAMETER\_STATE
  - Object: Parameter, [310](#)
- VX\_PARAMETER\_TYPE
  - Object: Parameter, [310](#)
- VX\_PATTERN\_BOX
  - Basic Features, [184](#)
- VX\_PATTERN\_CROSS
  - Basic Features, [184](#)
- VX\_PATTERN\_DISK
  - Basic Features, [184](#)
- VX\_PATTERN\_OTHER
  - Basic Features, [184](#)
- VX\_PYRAMID\_FORMAT
  - Object: Pyramid, [256](#)
- VX\_PYRAMID\_HEIGHT
  - Object: Pyramid, [256](#)

- VX\_PYRAMID\_LEVELS
  - Object: Pyramid, [256](#)
- VX\_PYRAMID\_SCALE
  - Object: Pyramid, [256](#)
- VX\_PYRAMID\_WIDTH
  - Object: Pyramid, [256](#)
- VX\_READ\_AND\_WRITE
  - Object: Context, [194](#)
- VX\_READ\_ONLY
  - Object: Context, [194](#)
- VX\_REFERENCE\_COUNT
  - Object: Reference, [188](#)
- VX\_REFERENCE\_NAME
  - Object: Reference, [188](#)
- VX\_REFERENCE\_TYPE
  - Object: Reference, [188](#)
- VX\_REMAP\_DESTINATION\_HEIGHT
  - Object: Remap, [259](#)
- VX\_REMAP\_DESTINATION\_WIDTH
  - Object: Remap, [259](#)
- VX\_REMAP\_SOURCE\_HEIGHT
  - Object: Remap, [259](#)
- VX\_REMAP\_SOURCE\_WIDTH
  - Object: Remap, [259](#)
- VX\_ROUND\_POLICY\_TO\_NEAREST\_EVEN
  - Object: Context, [194](#)
- VX\_ROUND\_POLICY\_TO\_ZERO
  - Object: Context, [194](#)
- VX\_SCALAR\_OP\_ADD
  - Object: Scalar, [267](#)
- VX\_SCALAR\_OP\_AND
  - Object: Scalar, [266](#)
- VX\_SCALAR\_OP\_DIVIDE
  - Object: Scalar, [267](#)
- VX\_SCALAR\_OP\_EQUAL
  - Object: Scalar, [266](#)
- VX\_SCALAR\_OP\_GREATEREQ
  - Object: Scalar, [267](#)
- VX\_SCALAR\_OP\_GREATER
  - Object: Scalar, [266](#)
- VX\_SCALAR\_OP\_LESSEQ
  - Object: Scalar, [266](#)
- VX\_SCALAR\_OP\_LESS
  - Object: Scalar, [266](#)
- VX\_SCALAR\_OP\_MAX
  - Object: Scalar, [267](#)
- VX\_SCALAR\_OP\_MIN
  - Object: Scalar, [267](#)
- VX\_SCALAR\_OP\_MODULUS
  - Object: Scalar, [267](#)
- VX\_SCALAR\_OP\_MULTIPLY
  - Object: Scalar, [267](#)
- VX\_SCALAR\_OP\_NAND
  - Object: Scalar, [266](#)
- VX\_SCALAR\_OP\_NOTEQUAL
  - Object: Scalar, [266](#)
- VX\_SCALAR\_OP\_OR
  - Object: Scalar, [266](#)
- VX\_SCALAR\_OP\_SUBTRACT
  - Object: Scalar, [267](#)
- VX\_SCALAR\_OP\_XOR
  - Object: Scalar, [266](#)
- VX\_SCALAR\_TYPE
  - Object: Scalar, [266](#)
- VX\_STATUS\_MIN
  - Basic Features, [180](#)
- VX\_SUCCESS
  - Basic Features, [181](#)
- VX\_TARGET\_ANY
  - Basic Features, [182](#)
- VX\_TARGET\_STRING
  - Basic Features, [182](#)
- VX\_TARGET\_VENDOR\_BEGIN
  - Basic Features, [183](#)
- VX\_TENSOR\_DATA\_TYPE
  - Object: Tensor, [282](#)
- VX\_TENSOR\_DIMS
  - Object: Tensor, [282](#)
- VX\_TENSOR\_FIXED\_POINT\_POSITION
  - Object: Tensor, [282](#)
- VX\_TENSOR\_NUMBER\_OF\_DIMS
  - Object: Tensor, [282](#)
- VX\_TERM\_CRITERIA\_BOTH
  - Object: Context, [194](#)
- VX\_TERM\_CRITERIA\_EPSILON
  - Object: Context, [194](#)
- VX\_TERM\_CRITERIA\_ITERATIONS
  - Object: Context, [194](#)
- VX\_THRESHOLD\_INPUT\_FORMAT
  - Object: Threshold, [272](#)
- VX\_THRESHOLD\_OUTPUT\_FORMAT
  - Object: Threshold, [272](#)
- VX\_THRESHOLD\_TYPE\_BINARY
  - Object: Threshold, [272](#)
- VX\_THRESHOLD\_TYPE\_RANGE
  - Object: Threshold, [272](#)
- VX\_THRESHOLD\_TYPE
  - Object: Threshold, [272](#)
- VX\_TYPE\_ARRAY
  - Basic Features, [179](#)
- VX\_TYPE\_BOOL
  - Basic Features, [178](#)
- VX\_TYPE\_CHAR
  - Basic Features, [178](#)
- VX\_TYPE\_CONTEXT
  - Basic Features, [179](#)
- VX\_TYPE\_CONVOLUTION
  - Basic Features, [179](#)
- VX\_TYPE\_COORDINATES2DF
  - Basic Features, [179](#)
- VX\_TYPE\_COORDINATES2D
  - Basic Features, [178](#)
- VX\_TYPE\_COORDINATES3D
  - Basic Features, [178](#)
- VX\_TYPE\_DELAY
  - Basic Features, [179](#)

- VX\_TYPE\_DF\_IMAGE
  - Basic Features, [178](#)
- VX\_TYPE\_DISTRIBUTION
  - Basic Features, [179](#)
- VX\_TYPE\_ENUM
  - Basic Features, [178](#)
- VX\_TYPE\_ERROR
  - Basic Features, [179](#)
- VX\_TYPE\_FLOAT32
  - Basic Features, [178](#)
- VX\_TYPE\_FLOAT64
  - Basic Features, [178](#)
- VX\_TYPE\_GRAPH
  - Basic Features, [179](#)
- VX\_TYPE\_HOG\_PARAMS
  - Basic Features, [179](#)
- VX\_TYPE\_HOUGH\_LINES\_PARAMS
  - Basic Features, [179](#)
- VX\_TYPE\_IMAGE
  - Basic Features, [179](#)
- VX\_TYPE\_INT16
  - Basic Features, [178](#)
- VX\_TYPE\_INT32
  - Basic Features, [178](#)
- VX\_TYPE\_INT64
  - Basic Features, [178](#)
- VX\_TYPE\_INT8
  - Basic Features, [178](#)
- VX\_TYPE\_INVALID
  - Basic Features, [178](#)
- VX\_TYPE\_KERNEL
  - Basic Features, [179](#)
- VX\_TYPE\_KEYPOINT
  - Basic Features, [178](#)
- VX\_TYPE\_KHRONOS\_OBJECT\_END
  - Basic Features, [179](#)
- VX\_TYPE\_KHRONOS\_OBJECT\_START
  - Basic Features, [179](#)
- VX\_TYPE\_KHRONOS\_STRUCT\_MAX
  - Basic Features, [179](#)
- VX\_TYPE\_LINE\_2D
  - Basic Features, [179](#)
- VX\_TYPE\_LUT
  - Basic Features, [179](#)
- VX\_TYPE\_MASK
  - Basic Features, [177](#)
- VX\_TYPE\_MATRIX
  - Basic Features, [179](#)
- VX\_TYPE\_META\_FORMAT
  - Basic Features, [179](#)
- VX\_TYPE\_NODE
  - Basic Features, [179](#)
- VX\_TYPE\_OBJECT\_ARRAY
  - Basic Features, [179](#)
- VX\_TYPE\_PARAMETER
  - Basic Features, [179](#)
- VX\_TYPE\_PYRAMID
  - Basic Features, [179](#)
- VX\_TYPE\_RECTANGLE
  - Basic Features, [178](#)
- VX\_TYPE\_REFERENCE
  - Basic Features, [179](#)
- VX\_TYPE\_REMAP
  - Basic Features, [179](#)
- VX\_TYPE\_SCALAR
  - Basic Features, [179](#)
- VX\_TYPE\_SIZE
  - Basic Features, [178](#)
- VX\_TYPE\_TENSOR\_MATRIX\_MULTIPLY\_PARAMS
  - Basic Features, [179](#)
- VX\_TYPE\_TENSOR
  - Basic Features, [179](#)
- VX\_TYPE\_THRESHOLD
  - Basic Features, [179](#)
- VX\_TYPE\_UINT16
  - Basic Features, [178](#)
- VX\_TYPE\_UINT32
  - Basic Features, [178](#)
- VX\_TYPE\_UINT64
  - Basic Features, [178](#)
- VX\_TYPE\_UINT8
  - Basic Features, [178](#)
- VX\_TYPE\_USER\_STRUCT\_END
  - Basic Features, [179](#)
- VX\_TYPE\_USER\_STRUCT\_START
  - Basic Features, [179](#)
- VX\_TYPE\_VENDOR\_OBJECT\_END
  - Basic Features, [179](#)
- VX\_TYPE\_VENDOR\_OBJECT\_START
  - Basic Features, [179](#)
- VX\_TYPE\_VENDOR\_STRUCT\_END
  - Basic Features, [179](#)
- VX\_TYPE\_VENDOR\_STRUCT\_START
  - Basic Features, [179](#)
- VX\_ULBP
  - LBP, [144](#)
- VX\_VALID\_RECT\_CALLBACK
  - Framework: User Kernels, [332](#)
- VX\_WRITE\_ONLY
  - Object: Context, [194](#)
- Vision Functions, [31](#)
- vx\_accessor\_e
  - Object: Context, [194](#)
- vx\_action
  - Framework: Node Callbacks, [317](#)
- vx\_action\_e
  - Framework: Node Callbacks, [317](#)
- vx\_array\_attribute\_e
  - Object: Array, [211](#)
- vx\_bool
  - Basic Features, [177](#)
- vx\_bool\_e
  - Basic Features, [178](#)
- vx\_border\_e
  - Node: Border Modes, [290](#)
- vx\_border\_policy\_e

- Node: Border Modes, 290
- vx\_border\_t, 290
- vx\_channel\_e
  - Basic Features, 183
- vx\_channel\_range\_e
  - Object: Image, 232
- vx\_color\_space\_e
  - Object: Image, 231
- vx\_comp\_metric\_e
  - MatchTemplate, 141
- vx\_context
  - Object: Context, 192
- vx\_context\_attribute\_e
  - Object: Context, 192
- vx\_convert\_policy\_e
  - Basic Features, 181
- vx\_convolution\_attribute\_e
  - Object: Convolution, 218
- vx\_coordinates2d\_t, 175
- vx\_coordinates2df\_t, 175
- vx\_coordinates3d\_t, 176
- vx\_delay
  - Object: Delay, 292
- vx\_delay\_attribute\_e
  - Object: Delay, 293
- vx\_df\_image\_e
  - Basic Features, 182
- vx\_direction\_e
  - Object: Parameter, 310
- vx\_directive\_e
  - Framework: Directives, 324
- vx\_distribution\_attribute\_e
  - Object: Distribution, 222
- vx\_enum
  - Basic Features, 177
- vx\_enum\_e
  - Basic Features, 181
- vx\_false\_e
  - Basic Features, 178
- vx\_graph
  - Object: Graph, 199
- vx\_graph\_attribute\_e
  - Object: Graph, 200
- vx\_graph\_state\_e
  - Object: Graph, 199
- vx\_hint\_e
  - Framework: Hints, 322
- vx\_hog\_t, 146
- vx\_hough\_lines\_p\_t, 152
- vx\_image
  - Object: Image, 231
- vx\_image\_attribute\_e
  - Object: Image, 231
- vx\_imagepatch\_addressing\_t, 230
- vx\_interpolation\_type\_e
  - Basic Features, 183
- vx\_kernel
  - Object: Kernel, 300
- vx\_kernel\_attribute\_e
  - Object: Kernel, 305
- vx\_kernel\_deinitialize\_f
  - Framework: User Kernels, 331
- vx\_kernel\_e
  - Object: Kernel, 300
- vx\_kernel\_f
  - Framework: User Kernels, 330
- vx\_kernel\_image\_valid\_rectangle\_f
  - Framework: User Kernels, 331
- vx\_kernel\_info\_t, 298
- vx\_kernel\_initialize\_f
  - Framework: User Kernels, 331
- vx\_kernel\_validate\_f
  - Framework: User Kernels, 331
- vx\_keypoint\_t, 176
- vx\_lbp\_format\_e
  - LBP, 144
- vx\_library\_e
  - Object: Kernel, 300
- vx\_line2d\_t, 176
- vx\_lut\_attribute\_e
  - Object: LUT, 244
- vx\_map\_flag\_e
  - Object: Image, 232
- vx\_matrix\_attribute\_e
  - Object: Matrix, 250
- vx\_memory\_type\_e
  - Object: Context, 193
- vx\_meta\_format
  - Framework: User Kernels, 330
- vx\_meta\_valid\_rect\_attribute\_e
  - Framework: User Kernels, 332
- vx\_node
  - Object: Node, 206
- vx\_node\_attribute\_e
  - Object: Node, 206
- vx\_nodecomplete\_f
  - Framework: Node Callbacks, 317
- vx\_non\_linear\_filter\_e
  - Basic Features, 184
- vx\_norm\_type\_e
  - Canny Edge Detector, 65
- vx\_object\_array\_attribute\_e
  - Object: ObjectArray, 278
- vx\_parameter
  - Object: Parameter, 310
- vx\_parameter\_attribute\_e
  - Object: Parameter, 310
- vx\_parameter\_state\_e
  - Object: Parameter, 310
- vx\_pattern\_e
  - Basic Features, 184
- vx\_perf\_t, 319
- vx\_pixel\_value\_t, 230
- vx\_publish\_kernels\_f
  - Framework: User Kernels, 330
- vx\_pyramid\_attribute\_e



- Object: Pyramid, 256
- vx\_rectangle\_t, 176
- vx\_reference
  - Object: Reference, 188
- vx\_reference\_attribute\_e
  - Object: Reference, 188
- vx\_remap\_attribute\_e
  - Object: Remap, 259
- vx\_round\_policy\_e
  - Object: Context, 194
- vx\_scalar
  - Object: Scalar, 266
- vx\_scalar\_attribute\_e
  - Object: Scalar, 266
- vx\_scalar\_operation\_e
  - Object: Scalar, 266
- vx\_status
  - Basic Features, 177
- vx\_status\_e
  - Basic Features, 179
- vx\_target\_e
  - Basic Features, 182
- vx\_tensor
  - Object: Tensor, 282
- vx\_tensor\_attribute\_e
  - Object: Tensor, 282
- vx\_tensor\_matrix\_multiply\_params\_t, 167
- vx\_termination\_criteria\_e
  - Object: Context, 194
- vx\_threshold\_attribute\_e
  - Object: Threshold, 272
- vx\_threshold\_type\_e
  - Object: Threshold, 272
- vx\_true\_e
  - Basic Features, 178
- vx\_type\_e
  - Basic Features, 178
- vx\_unpublish\_kernels\_f
  - Framework: User Kernels, 330
- vx\_vendor\_id\_e
  - Basic Features, 184
- vxAbsDiffNode
  - Absolute Difference, 35
- vxAccumulateImageNode
  - Accumulate, 37
- vxAccumulateSquareImageNode
  - Accumulate Squared, 39
- vxAccumulateWeightedImageNode
  - Accumulate Weighted, 43
- vxAddArrayItems
  - Object: Array, 213
- vxAddLogEntry
  - Framework: Log, 320
- vxAddNode
  - Arithmetic Addition, 48
- vxAddParameterToGraph
  - Framework: Graph Parameters, 340
- vxAddParameterToKernel
  - Framework: User Kernels, 335
- vxAddUserKernel
  - Framework: User Kernels, 335
- vxAgeDelay
  - Object: Delay, 295
- vxAllocateUserKernelId
  - Framework: User Kernels, 332
- vxAllocateUserKernelLibraryId
  - Framework: User Kernels, 333
- vxAndNode
  - Bitwise AND, 52
- vxArrayItem
  - Object: Array, 211
- vxAssignNodeCallback
  - Framework: Node Callbacks, 317
- vxBilateralFilterNode
  - Bilateral Filter, 139
- vxBox3x3Node
  - Box Filter, 60
- vxCannyEdgeDetectorNode
  - Canny Edge Detector, 65
- vxChannelCombineNode
  - Channel Combine, 67
- vxChannelExtractNode
  - Channel Extract, 69
- vxColorConvertNode
  - Color Convert, 73
- vxConvertDepthNode
  - Convert Bit depth, 75
- vxConvolveNode
  - Custom Convolution, 77
- vxCopyArrayRange
  - Object: Array, 214
- vxCopyConvolutionCoefficients
  - Object: Convolution, 221
- vxCopyDistribution
  - Object: Distribution, 224
- vxCopyImagePatch
  - Object: Image, 239
- vxCopyLUT
  - Object: LUT, 246
- vxCopyMatrix
  - Object: Matrix, 252
- vxCopyNode
  - Data Object Copy, 41
- vxCopyRemapPatch
  - Object: Remap, 263
- vxCopyScalar
  - Object: Scalar, 269
- vxCopyScalarWithSize
  - Object: Scalar, 269
- vxCopyTensorPatch
  - Object: Tensor, 284
- vxCopyThresholdOutput
  - Object: Threshold, 275
- vxCopyThresholdRange
  - Object: Threshold, 274
- vxCopyThresholdValue



- Object: Threshold, 273
- vxCreateArray
  - Object: Array, 211
- vxCreateContext
  - Object: Context, 195
- vxCreateConvolution
  - Object: Convolution, 219
- vxCreateDelay
  - Object: Delay, 294
- vxCreateDistribution
  - Object: Distribution, 223
- vxCreateGenericNode
  - Object: Node (Advanced), 289
- vxCreateGraph
  - Object: Graph, 200
- vxCreateImage
  - Object: Image, 232
- vxCreateImageFromChannel
  - Object: Image, 242
- vxCreateImageFromHandle
  - Object: Image, 234
- vxCreateImageFromROI
  - Object: Image, 232
- vxCreateImageObjectArrayFromTensor
  - Object: Tensor, 283
- vxCreateLUT
  - Object: LUT, 245
- vxCreateMatrix
  - Object: Matrix, 251
- vxCreateMatrixFromPattern
  - Object: Matrix, 253
- vxCreateMatrixFromPatternAndOrigin
  - Object: Matrix, 253
- vxCreateObjectArray
  - Object: ObjectArray, 279
- vxCreatePyramid
  - Object: Pyramid, 256
- vxCreateRemap
  - Object: Remap, 260
- vxCreateScalar
  - Object: Scalar, 267
- vxCreateScalarWithSize
  - Object: Scalar, 267
- vxCreateTensor
  - Object: Tensor, 282
- vxCreateTensorFromView
  - Object: Tensor, 283
- vxCreateThresholdForImage
  - Object: Threshold, 272
- vxCreateUniformImage
  - Object: Image, 233
- vxCreateVirtualArray
  - Object: Array, 212
- vxCreateVirtualConvolution
  - Object: Convolution, 219
- vxCreateVirtualDistribution
  - Object: Distribution, 223
- vxCreateVirtualImage
  - Object: Image, 233
- vxCreateVirtualLUT
  - Object: LUT, 245
- vxCreateVirtualMatrix
  - Object: Matrix, 251
- vxCreateVirtualObjectArray
  - Object: ObjectArray, 279
- vxCreateVirtualPyramid
  - Object: Pyramid, 256
- vxCreateVirtualRemap
  - Object: Remap, 260
- vxCreateVirtualScalar
  - Object: Scalar, 267
- vxCreateVirtualTensor
  - Object: Tensor, 283
- vxCreateVirtualThresholdForImage
  - Object: Threshold, 273
- vxDilate3x3Node
  - Dilate Image, 79
- vxDirective
  - Framework: Directives, 324
- vxEqualizeHistNode
  - Equalize Histogram, 81
- vxErode3x3Node
  - Erode Image, 82
- vxFastCornersNode
  - Fast Corners, 85
- vxFinalizeKernel
  - Framework: User Kernels, 335
- vxFormatArrayPointer
  - Object: Array, 211
- vxFormatImagePatchAddress1d
  - Object: Image, 237
- vxFormatImagePatchAddress2d
  - Object: Image, 238
- vxGaussian3x3Node
  - Gaussian Filter, 87
- vxGaussianPyramidNode
  - Gaussian Image Pyramid, 96
- vxGetContext
  - Object: Context, 195
- vxGetGraphParameterByIndex
  - Framework: Graph Parameters, 341
- vxGetKernelByEnum
  - Object: Kernel, 307
- vxGetKernelByName
  - Object: Kernel, 306
- vxGetKernelParameterByIndex
  - Object: Parameter, 310
- vxGetObjectArrayItem
  - Object: ObjectArray, 279
- vxGetParameterByIndex
  - Object: Parameter, 311
- vxGetPyramidLevel
  - Object: Pyramid, 258
- vxGetReferenceFromDelay
  - Object: Delay, 294
- vxGetStatus

- Basic Features, 185
- vxGetValidRegionImage
  - Object: Image, 238
- vxHOGCellsNode
  - HOG, 147
- vxHOGFeaturesNode
  - HOG, 148
- vxHalfScaleGaussianNode
  - Scale Image, 127
- vxHarrisCornersNode
  - Harris Corners, 92
- vxHint
  - Framework: Hints, 322
- vxHistogramNode
  - Histogram, 94
- vxHoughLinesPNode
  - HoughLinesP, 153
- vxIntegrallImageNode
  - Integral Image, 102
- vxIsGraphVerified
  - Object: Graph, 204
- vxLBPNNode
  - LBP, 145
- vxLaplacianPyramidNode
  - Laplacian Image Pyramid, 98
- vxLaplacianReconstructNode
  - Reconstruction from a Laplacian Image Pyramid, 100
- vxLoadKernels
  - Framework: User Kernels, 333
- vxMagnitudeNode
  - Magnitude, 104
- vxMapArrayRange
  - Object: Array, 215
- vxMapDistribution
  - Object: Distribution, 225
- vxMapImagePatch
  - Object: Image, 240
- vxMapLUT
  - Object: LUT, 247
- vxMapRemapPatch
  - Object: Remap, 261
- vxMatchTemplateNode
  - MatchTemplate, 142
- vxMaxNode
  - Max, 114
- vxMeanStdDevNode
  - Mean and Standard Deviation, 106
- vxMedian3x3Node
  - Median Filter, 108
- vxMinMaxLocNode
  - Min, Max Location, 110
- vxMinNode
  - Min, 112
- vxMultiplyNode
  - Pixel-wise Multiplication, 121
- vxNonLinearFilterNode
  - Non Linear Filter, 89
- vxNonMaxSuppressionNode
  - Non-Maxima Suppression, 62
- vxNotNode
  - Bitwise NOT, 58
- vxOpticalFlowPyrLKNNode
  - Optical Flow Pyramid (LK), 117
- vxOrNode
  - Bitwise INCLUSIVE OR, 56
- vxPhaseNode
  - Phase, 119
- vxProcessGraph
  - Object: Graph, 201
- vxQueryArray
  - Object: Array, 213
- vxQueryContext
  - Object: Context, 196
- vxQueryConvolution
  - Object: Convolution, 220
- vxQueryDelay
  - Object: Delay, 293
- vxQueryDistribution
  - Object: Distribution, 224
- vxQueryGraph
  - Object: Graph, 203
- vxQueryImage
  - Object: Image, 236
- vxQueryKernel
  - Object: Kernel, 307
- vxQueryLUT
  - Object: LUT, 246
- vxQueryMatrix
  - Object: Matrix, 252
- vxQueryNode
  - Object: Node, 206
- vxQueryObjectArray
  - Object: ObjectArray, 280
- vxQueryParameter
  - Object: Parameter, 312
- vxQueryPyramid
  - Object: Pyramid, 257
- vxQueryReference
  - Object: Reference, 188
- vxQueryRemap
  - Object: Remap, 264
- vxQueryScalar
  - Object: Scalar, 268
- vxQueryTensor
  - Object: Tensor, 285
- vxQueryThreshold
  - Object: Threshold, 277
- vxRegisterAutoAging
  - Object: Graph, 204
- vxRegisterLogCallback
  - Framework: Log, 321
- vxRegisterUserStruct
  - Object: Array (Advanced), 288
- vxReleaseArray
  - Object: Array, 212

- vxReleaseContext
  - Object: Context, [195](#)
- vxReleaseConvolution
  - Object: Convolution, [219](#)
- vxReleaseDelay
  - Object: Delay, [293](#)
- vxReleaseDistribution
  - Object: Distribution, [223](#)
- vxReleaseGraph
  - Object: Graph, [200](#)
- vxReleaseImage
  - Object: Image, [237](#)
- vxReleaseKernel
  - Object: Kernel, [308](#)
- vxReleaseLUT
  - Object: LUT, [245](#)
- vxReleaseMatrix
  - Object: Matrix, [251](#)
- vxReleaseNode
  - Object: Node, [207](#)
- vxReleaseObjectArray
  - Object: ObjectArray, [279](#)
- vxReleaseParameter
  - Object: Parameter, [311](#)
- vxReleasePyramid
  - Object: Pyramid, [257](#)
- vxReleaseReference
  - Object: Reference, [188](#)
- vxReleaseRemap
  - Object: Remap, [260](#)
- vxReleaseScalar
  - Object: Scalar, [268](#)
- vxReleaseTensor
  - Object: Tensor, [285](#)
- vxReleaseThreshold
  - Object: Threshold, [276](#)
- vxRemapNode
  - Remap, [123](#)
- vxRemoveKernel
  - Framework: User Kernels, [336](#)
- vxRemoveNode
  - Object: Node, [208](#)
- vxReplicateNode
  - Object: Node, [208](#)
- vxRetainReference
  - Object: Reference, [189](#)
- vxRetrieveNodeCallback
  - Framework: Node Callbacks, [318](#)
- vxScalarOperationNode
  - Control Flow, [46](#)
- vxScaleImageNode
  - Scale Image, [127](#)
- vxScheduleGraph
  - Object: Graph, [202](#)
- vxSelectNode
  - Control Flow, [46](#)
- vxSetContextAttribute
  - Object: Context, [196](#)
- vxSetConvolutionAttribute
  - Object: Convolution, [220](#)
- vxSetGraphAttribute
  - Object: Graph, [203](#)
- vxSetGraphParameterByIndex
  - Framework: Graph Parameters, [340](#)
- vxSetImageAttribute
  - Object: Image, [236](#)
- vxSetImagePixelValues
  - Object: Image, [236](#)
- vxSetImageValidRectangle
  - Object: Image, [242](#)
- vxSetImmediateModeTarget
  - Object: Context, [196](#)
- vxSetKernelAttribute
  - Framework: User Kernels, [336](#)
- vxSetMetaFormatAttribute
  - Framework: User Kernels, [337](#)
- vxSetMetaFormatFromReference
  - Framework: User Kernels, [338](#)
- vxSetNodeAttribute
  - Object: Node, [207](#)
- vxSetNodeTarget
  - Object: Node, [208](#)
- vxSetParameterByIndex
  - Object: Parameter, [311](#)
- vxSetParameterByReference
  - Object: Parameter, [312](#)
- vxSetReferenceName
  - Object: Reference, [189](#)
- vxSetThresholdAttribute
  - Object: Threshold, [276](#)
- vxSobel3x3Node
  - Sobel 3x3, [129](#)
- vxSubtractNode
  - Arithmetic Subtraction, [50](#)
- vxSwapImageHandle
  - Object: Image, [235](#)
- vxTableLookupNode
  - TableLookup, [131](#)
- vxTensorAddNode
  - Tensor Add, [157](#)
- vxTensorConvertDepthNode
  - Tensor Convert Bit-Depth, [165](#)
- vxTensorMatrixMultiplyNode
  - Tensor Matrix Multiply, [168](#)
- vxTensorMultiplyNode
  - Tensor Multiply, [155](#)
- vxTensorSubtractNode
  - Tensor Subtract, [159](#)
- vxTensorTableLookupNode
  - Tensor TableLookUp, [161](#)
- vxTensorTransposeNode
  - Tensor Transpose, [163](#)
- vxThresholdNode
  - Thresholding, [133](#)
- vxTruncateArray
  - Object: Array, [214](#)

- vxUnloadKernels
  - Framework: User Kernels, 334
- vxUnmapArrayRange
  - Object: Array, 216
- vxUnmapDistribution
  - Object: Distribution, 226
- vxUnmapImagePatch
  - Object: Image, 241
- vxUnmapLUT
  - Object: LUT, 248
- vxUnmapRemapPatch
  - Object: Remap, 262
- vxVerifyGraph
  - Object: Graph, 201
- vxWaitGraph
  - Object: Graph, 202
- vxWarpAffineNode
  - Warp Affine, 135
- vxWarpPerspectiveNode
  - Warp Perspective, 137
- vxXorNode
  - Bitwise EXCLUSIVE OR, 54
- vxuAbsDiff
  - Absolute Difference, 35
- vxuAccumulateImage
  - Accumulate, 37
- vxuAccumulateSquareImage
  - Accumulate Squared, 39
- vxuAccumulateWeightedImage
  - Accumulate Weighted, 43
- vxuAdd
  - Arithmetic Addition, 48
- vxuAnd
  - Bitwise AND, 52
- vxuBilateralFilter
  - Bilateral Filter, 140
- vxuBox3x3
  - Box Filter, 60
- vxuCannyEdgeDetector
  - Canny Edge Detector, 66
- vxuChannelCombine
  - Channel Combine, 67
- vxuChannelExtract
  - Channel Extract, 69
- vxuColorConvert
  - Color Convert, 73
- vxuConvertDepth
  - Convert Bit depth, 76
- vxuConvolve
  - Custom Convolution, 78
- vxuCopy
  - Data Object Copy, 41
- vxuDilate3x3
  - Dilate Image, 79
- vxuEqualizeHist
  - Equalize Histogram, 81
- vxuErode3x3
  - Erode Image, 82
- vxuFastCorners
  - Fast Corners, 85
- vxuGaussian3x3
  - Gaussian Filter, 87
- vxuGaussianPyramid
  - Gaussian Image Pyramid, 96
- vxuHOGCells
  - HOG, 149
- vxuHOGFeatures
  - HOG, 150
- vxuHalfScaleGaussian
  - Scale Image, 128
- vxuHarrisCorners
  - Harris Corners, 93
- vxuHistogram
  - Histogram, 94
- vxuHoughLinesP
  - HoughLinesP, 153
- vxuIntegrallImage
  - Integral Image, 102
- vxuLBP
  - LBP, 145
- vxuLaplacianPyramid
  - Laplacian Image Pyramid, 99
- vxuLaplacianReconstruct
  - Reconstruction from a Laplacian Image Pyramid, 100
- vxuMagnitude
  - Magnitude, 104
- vxuMatchTemplate
  - MatchTemplate, 142
- vxuMax
  - Max, 114
- vxuMeanStdDev
  - Mean and Standard Deviation, 106
- vxuMedian3x3
  - Median Filter, 108
- vxuMin
  - Min, 112
- vxuMinMaxLoc
  - Min, Max Location, 110
- vxuMultiply
  - Pixel-wise Multiplication, 122
- vxuNonLinearFilter
  - Non Linear Filter, 89
- vxuNonMaxSuppression
  - Non-Maxima Suppression, 62
- vxuNot
  - Bitwise NOT, 58
- vxuOpticalFlowPyrLK
  - Optical Flow Pyramid (LK), 117
- vxuOr
  - Bitwise INCLUSIVE OR, 56
- vxuPhase
  - Phase, 119
- vxuRemap
  - Remap, 123
- vxuScaleImage

- Scale Image, [128](#)
- vxuSobel3x3
  - Sobel 3x3, [129](#)
- vxuSubtract
  - Arithmetic Subtraction, [50](#)
- vxuTableLookup
  - TableLookup, [131](#)
- vxuTensorAdd
  - Tensor Add, [157](#)
- vxuTensorConvertDepth
  - Tensor Convert Bit-Depth, [165](#)
- vxuTensorMatrixMultiply
  - Tensor Matrix Multiply, [168](#)
- vxuTensorMultiply
  - Tensor Multiply, [155](#)
- vxuTensorSubtract
  - Tensor Subtract, [159](#)
- vxuTensorTableLookup
  - Tensor TableLookUp, [161](#)
- vxuTensorTranspose
  - Tensor Transpose, [163](#)
- vxuThreshold
  - Thresholding, [134](#)
- vxuWarpAffine
  - Warp Affine, [136](#)
- vxuWarpPerspective
  - Warp Perspective, [138](#)
- vxuXor
  - Bitwise EXCLUSIVE OR, [54](#)
- Warp Affine, [135](#)
  - vxWarpAffineNode, [135](#)
  - vxuWarpAffine, [136](#)
- Warp Perspective, [137](#)
  - vxWarpPerspectiveNode, [137](#)
  - vxuWarpPerspective, [138](#)