

# remote

## XML section name

```
<remote>
</remote>
```

Configuration of manager to listen for events from the agents.

## Options

- [connection](#)
- [port](#)
- [protocol](#)
- [allowed-ips](#)
- [deny-ips](#)
- [local\\_ip](#)
- [ipv6](#)

### connection

Specifies a type of incoming connection to accept: secure or syslog.

Default value	secure
Allowed values	secure, syslog

### port


Specifies the port to use to listen for events.

Default value	1514 if secure, 514 if syslog
Allowed values	Any port number from 1 to 65535

### protocol

Specifies the protocol to use. It is available for secure connections and syslog events.

Default value	udp
Allowed values	udp, tcp


 Note

It is not possible to use both protocols simultaneously.

### allowed-ips

List of IP addresses that are allowed to send syslog messages to the server (one per line).

Default value	n/a
Allowed values	Any IP address or network

 Note

It is necessary to list at least one IP address when using the syslog connection type.

## deny-ips

List of IP addresses that are not allowed to send syslog messages to the server (one per line).

Default value	n/a
Allowed values	Any IP address or network

## local\_ip

Local ip address to use to listen for connections.

Default value	All interfaces
Allowed values	Any internal ip address

## ipv6

Local ipv6 address to listen for connections.

Default value	n/a
Allowed values	Any IPv6 address

## Example of configuration

```
<remote>
  <connection>syslog</connection>
  <port>514</port>
  <protocol>udp</protocol>
  <allowed_ips>192.168.1.0/24</allowed_ips>
  <local_ip>192.168.1.5</local_ip>
</remote>

<remote>
  <connection>secure</connection>
  <port>1514</port>
  <protocol>udp</protocol>
</remote>
```