

Install Kinect Sensor, OpenNI, PrimeSense Ubuntu 12.04

This tutorial is modified from the [post by Michael](#).

Step 1. install dependencies

```
$ sudo apt-get install git-core cmake freeglut3-dev pkg-config build-essential libxmu-dev libxi-dev libusb-1.0-0-dev doxygen graphviz mono-complete
```

Step 2. Make a directory for installation (you should install the git if you don't have it)

```
$ mkdir ~/kinect && cd ~/kinect
```

```
$ git clone https://github.com/OpenNI/OpenNI.git
```

Step 3. install OpenNI

```
# install Java sdk
```

```
$ sudo apt-get install openjdk-7-jdk
```

```
$ cd OpenNI/Platform/Linux/CreateRedist/
```

```
$ chmod +x RedistMaker
```

```
$ ./RedistMaker
```

```
$ cd ../Redist/OpenNI-Bin-Dev-Linux-x64-v1.5.2.23/
```

```
$ sudo ./install.sh
```

Step 4. Install KinectSensor

```
# download the package from here, extract and install.
```

For my case, I download this one [SensorKinect093-Bin-Linux-x64-v5.1.2.1.tar.bz2](#) — SensorKinect-0.93 (5.1.2.1) for Ubuntu 12.04 64-bit (x64)

```
$ tar xvjf SensorKinect093-Bin-Linux-x64-v5.1.2.1.tar.bz2
```

```
$ cd Sensor-Bin-Linux-x64-v5.1.2.1/
```

```
$ sudo ./install.sh
```

Step 5. download [Primesense NITE](#)

```
$ tar xvjf NITE-Bin-Linux64-v1.4.0.5.tar.bz2
```

```
$ cd ~/kinect/NITE/Data
```

```
# Change License for Sample-Scene.xml, Sample-Tracking.xml, and Sample-User.xml.
```

```
# <License vendor="PrimeSense" key="0KOIk2JeIBYClPWVnMoRKn5cdY4="/>
```

```
$ sudo nano Sample-Scene.xml
```

```
# then change the license for all the .xml files.
```

Step 6. Test Kinect Installation

```
# Plug in your Kinect, go to folder
```

```
$ ~/kinect/OpenNI/Platform/Linux/Bin/x64-Release
```

or

```
$ cd ~/kinect/NITE/Samples/Bin/Release
```

```
$ ./Sample-PointViewer
```

