

# FreeTAK Server User Manual



FTS V. 1.9.8  
Dec 2021  
Release

# 1. Introduction

Welcome to the user manual for the FreeTAKServer (FTS) Web User interface (webUI)!

FreeTAKServer, as of Release 1.9, provides Situational Awareness and other capabilities such as:

- Web administration
- Federation Service (Connecting two or more FTS instances)
- Data Package upload and retrieval
- Private data package (user to user)
- Image transfer and storage
- COT recording in a database
- Execution of common task list (using the ExCheck plugin for WinTAK; ATAK plugin only available to users with takmaps.com access)
- SSL Encryption
- User Management
- Command Line Interface for start and stop services
- REST API for creation of information such as emergency, Enemy units and so on

## About the Web UI


FTS webUI allows administrators to easily manage the server.

This video, based on a pre-production version, provides an overview of most features described in the manual

[https://www.youtube.com/watch?v=q4BpolzIDLw&ab\\_channel=%2aDA-B6%2a](https://www.youtube.com/watch?v=q4BpolzIDLw&ab_channel=%2aDA-B6%2a)

WebUI is a completely separate application connecting to the FTS backend.

It uses an API to seamless query server functions. Depending on his deployment, may or may not be seen from remote machines.



FTS also offers a separate Command Line Interface (CLI). Follow this link for its documentation <https://freetakteam.github.io/FreeTAKServer-User-Docs/CLI/>.

## Installation and configuration

This section provides an overview of the installation process. Refer to the online documentation for details.

To install FTS and the UI type in a console

```
sudo python3 -m pip install FreeTAKServer[ui]
```

### Setup your Configuration

your administrator will need to configure the following files

- Config.py for the UI
- MainConfig.py for FTS

### Start FTS

```
nohup sudo python3 -m FreeTAKServer.controllers.services.FTS
```

### Start the WebUI


```
nohup sudo python3  
/usr/local/lib/python3.8/dist-packages/FreeTAKServer-UI/run.py
```

## Basics

### Login

Open a browser and navigate to [webUIIP]:[PORT]

*For example 127.0.0.1:5000*



Insert the user and password created with the function “System User” (see 4.1).  
Click login

The function “Don't have an account? **Create**” could be useful to provide anyone with the link to the UI with the ability to create a System user. For security purposes it's disabled in the standard configuration and his activation should be avoided


First login can be done using:

- Username: admin (all non capital)
- Password: password (all non capital)

**It's strongly suggested to immediately create a new user and delete the generated one.**

# 1.0 Navigation


To the Left of the main screen, there is a menu with 6 sub menus. These are: Home, Mission, User, Connect, Configure and About.



Each of these is linked to a different screen with specific information to be seen and edited. The current section is highlighted with a blue dot

- **Home:** System status
- **WebMap:** a web client displaying all is sent to your FTS server
- **Mission:** Data Packages and other files
- **User:** UI users and groups configuration
- **Connect:** send CoTs and system messages
- **Configure:** Services and federated servers
- **About:** FTS and web UI version and special thanks

## 1.1 Top Navigation Bar



The Events button is currently inactive. It provides a list of the last 5 events. The user button allow to log out or to edit the current user Profile

## 1.2 Profile Screen

The screenshot shows the 'EDIT PROFILE' screen. It contains the following fields and controls:

- [EDIT PROFILE]**: A blue link at the top left.
- Name (disabled)**: A text input field containing 'Eliopoli HQ'.
- Group**: A text input field containing 'Pirates'.
- Token**: A text input field containing '...'.
- Password**: A text input field containing '...'.
- Certs**: A text input field containing 'Eliopoli HQ.zip'.
- Save**: A blue button at the bottom left.

Use this screen to change the current login user password, token and group

## 2.0 Home


Here the main information about the FTS can be visualized. This information is periodically updated from the server. You can change this period in the UI configuration

([UIInstallation]/UI/app/\_\_init\_\_.py

. Default, expressed in milliseconds are

- USER INTERVAL= '180000'
- SERVER HEALTH INTERVAL = '180000'
- SYS STATUS INTERVAL = '600000'


## 2.1 System Status



The status of FTS services is visualized as a series (6) of rotating concentric circles. The information is color coded:

- **Blue:** Service is running and activated
- **Red:** Service is activated but not running (screenshot)
- **Gray:** Service is turned off (See 5.1 System Configuration)

## 2.2 Run Time & connected clients



This section shows the start and current run time of the FTS, as well as the number of connected clients. The start time is provided by the server, so if you are in a different time zone you may see negative up times.

## 2.3 System Health



In this section the % resources required by the server are displayed as its consumption of CPU, RAM, and Disk. The gauge shows both numerical (RAM: 32) as well as visual (circle  $\sim\frac{1}{3}$  full) values.

## 2.4 Logs

The image shows a 'Logs' table with a dark background. In the top right corner, the word '[LOGS]' is displayed in blue. The table has four columns: 'TIME', 'TYPE', 'FILE', and 'MESSAGE'. A single log entry is shown with the following data:


TIME	TYPE	FILE	MESSAGE
20:01	WARNING	FederationClientService.py:151	exception thrown creating new federation [Erno III] Connection refused

Last Errors and other log messages will appear here



## 3.0 WebMap

Since FTS 1.8, the UI has a Tab to a webMap. The webmap is a separate component, part of the FreeTAKHub concept (see <https://github.com/FreeTAKTeam/FreeTAKHub> for more details)




The webmap is a partial TAK client only. It displays all the connected clients and the COT sent from the moment in which it connects. Clicking on another tab closes the webmap, no memory of past events is kept.

### 3.1 Webmap Special functions


Following functions are also available:

- Zoom in and out


- Measure distances and bearing



- Import KML
  - Drag and drop a valid KML into the map to display it (server only, not shared with clients)




- Add markers to the map (right click) and send to all the connected clients




A screenshot of a web application showing a map with a grid. A white dialog box is open over the map, containing the following fields: 'Attitude' with a dropdown menu set to 'Friend', 'Type' with a dropdown menu set to 'Rifleman', 'Timeout' with a text input set to '600' and a unit selector set to 'S', and 'Name' with an empty text input. A 'Send' button is at the bottom of the dialog box. The dialog box has a close button (X) in the top right corner.

- *Attitude: the attitude of the target toward the users, reflected in the color*
- *Type: Basic infantry types are supported*
- *Timeout: time before the markers disappears in seconds*
- *Name: unique name of the marker, if the same name is re-used, it will move an existing marker*


- Delete an existing Marker



- Search COT by name




- Search geo location



- Select different map styles



- Filter COTs by type (each COT type is placed in a layer)



## 4.0 Mission

A multipurpose section with a broad role in managing data and files

## 4.1 Data Packages

Name	Author	Index	Is Private	Size (KB)	Submitted
NOAA_RNC.xml	KabulAfghanistan	214	<input type="checkbox"/>	0.999	Tue, 12 Jan 2021 15:08:39 GMT
MOBAC-Maps-master.zip		215	<input checked="" type="checkbox"/>	4.279	Tue, 12 Jan 2021 15:08:39 GMT
DAB6.zip	server	216	<input checked="" type="checkbox"/>	7.462	Tue, 12 Jan 2021 15:08:39 GMT
ESRI Clarity.xml	KabulAfghanistan	219	<input type="checkbox"/>	0.881	Tue, 12 Jan 2021 15:08:39 GMT
Google_Mapsources.zip	314C	220	<input checked="" type="checkbox"/>	1.452	Tue, 12 Jan 2021 15:08:39 GMT
ESRI Clarity.xml	KabulAfghanistan	221	<input type="checkbox"/>	0.882	Tue, 12 Jan 2021 15:08:39 GMT
MOBAC-Maps-master.zip	server	222	<input type="checkbox"/>	4.44	Tue, 12 Jan 2021 15:08:39 GMT

DELETE ADD

From here one can see, add, download, delete and hide available data packages.

- **Add:** By pressing on the three dots in the bottom right of the menu, a dialogue will appear with your file explorer. Select the Zip file meant for upload and click on “open”. The dialogue will close. Now click on “add” (next to “delete” at the bottom left) and the file will be uploaded as a data package.  
The maximum size for a Data Package is 15 MB. You can change this size in the UI configuration ([UIInstallation]/UI/app/\_\_init\_\_.py
- **Download to local drive:** Simply click on the data package name in blue. The file will be downloaded to your “downloads” folder
- **Delete:** This can be done by selecting the undesired data packages (click anywhere except the blue name), the delete button will change to indicate the # of selected rows. Click “delete” (bottom left)
- **Index:** the unique index number of the Data Package in the DB
- **Hide:** The fourth information column from the right is labeled as “is private”. This function allows you to hide data packages from ATAK / WinTAK users simply by checking the box in this column. All private data packages, exchanged between clients, are listed as private

## 4.2 Mission

Name	Description	Keywords	Creator	Groups	Created
No Records Found					


DELETE ADD

For future development, currently non functional. Will allow users to share data packages, CoTs and ExCheck lists with others, organized in “missions”. Still under development as of this version of FTS (V 1.5).

## 4.3 ExCheck

ExCheck allows users to collaborate on the execution and monitoring of tasks based on templates. To use ExCheck, you need to have a server that supports it. FTS supports the plugin since version 1.3. See this article for an example of how to use it:

[https://www.reddit.com/r/ATAK/comments/jzltvt/use\\_freetakserver\\_and\\_excheck\\_plugin\\_to/](https://www.reddit.com/r/ATAK/comments/jzltvt/use_freetakserver_and_excheck_plugin_to/)



The screenshot shows a web interface for ExCheck. At the top right, there is a tab labeled "[EXCHECK]". Below it is a table with the following columns: Name, Submitter, Type, Size, and Submitted. The table contains two entries:

Name	Submitter	Type	Size	Submitted
test from atak		cdd39d06-b43e-42f4-839d-32362febe9a1.xml	1735	moment(2021-01-11T09:29:03.583715Z).format("DD-MM-YYYY")
KillChain		b7c4d94c-5714-4a8a-a11f-92396ea2c723.xml	5638	moment(2021-01-11T14:54:42.916052Z).format("DD-MM-YYYY")

Below the table, there are two buttons: "DELETE" and "ADD". To the right of the "ADD" button is a three-dot menu icon.

Allows you to see, add and delete ExCheck templates.

- **Add:** Add: By pressing on the three dots in the bottom right of the menu, a dialogue of your file explorer will appear. Select the file meant for upload and click on “open”. The dialogue will close. Now click on “add” (next to “delete” at the bottom left) and the file will be uploaded as a data package.  
The uploaded template must be valid in a XML format.
- **Delete:** This can be done by selecting the undesired data packages, and then clicking on “delete” (bottom left)

## 4.4 Federation

The federation function allows FTS to connect to another server of the TAK family and exchange information such as COT and chats. The current implementation (1.9) does not allow sending Data packages and Missions yet.

### 4.4.1 Federating to a legacy TAK server

To set up a federated connection with another server you need to upload the certificate authority to the target server.

Under the certs directory there's a file called `pubserver.pem` containing your server public certificate.

Download this file, rename it to something easy to remember like `FTS204.134.0.60.pem` and upload it to the Legacy TAK server you want to federate to.



## 4.4.2 Federating to a FTS server

- **On the federated server:** activate the Federation service under Configure/system configuration
- **On the federated client:** Simply create the connection to the federated server

[OUTGOING FEDERATIONS]					
Name	Address	Port	Fallback	Status	Rec. Interval
lantern	3.96.240.142	9000	None	Enabled	32
<div> <div>DELETE</div> <div>ADD</div> </div>					

Here one can see the status of federated servers the current instance connects to, as well as deleting, editing and adding news ones.

- **Add:** Pressing the “Add” button will open an extension of the window. In the correct slots, fill out the pertinent information (Name, IP Address, and Port). Additionally, you can add a fallback (backup) server, by enabling or disabling the option. In the current version (1.5 this is not yet active) Press submit once finished.

**In the event the status remains disabled it is likely there was an error in the creation of your federation, the associated error message can be found in the farthest right most column of your federation (you may need to scroll to the right to see it).**

[OUTGOING FEDERATIONS]					
Name	Address	Port	Fallback	Status	Rec. Interval
lantern	3.96.240.142	9000	None	Enabled	32
<div> <div>DELETE</div> <div>ADD</div> </div> <div> <div>Name</div> <div>IP Address</div> <div>Port</div> <div>Fallback Server</div> <div>lantern</div> <div>Status</div> <div>Enabled</div> <div>Max Retries</div> <div>Rec Interval</div> </div> <div>Submit</div>					

- **Editing:** When selecting the desired server, a new button labeled “editing” will appear next to “delete” (bottom right of panel). Pressing this will enter the information of the selected server in the otherwise blank fields. Information can now be edited to desired values.
- **Delete:** This can be done by selecting the undesired federation and then clicking on “delete” (bottom right)

## 5.0 User

Allows the user to add or delete System Users and edit user group permissions.

### 5.1 System users

This panel shows all of the registered users of the UI and allows the user to add and delete users. A System User, other than an anonymous one is associated with a group, a Token for API, a password that can be used to login into the ui and finally certificates allowing to securely connect to FTS

[SYSTEM USERS]				
Name	Group	Token	Password	Certs
Ralph	Blue	*****	*****	Ralph.zip
FEATHER	cyan	*****	*****	FEATHER.zip
NOVA	Cyan	*****	*****	NOVA.zip
LowSpeed	white	*****	*****	LowSpeed.zip
C0rv0	Yellow	*****	*****	C0rv0.zip
CorvoMobile	Yellow	*****	*****	CorvoMobile.zip
JAVA	Yellow	*****	*****	JAVA.zip
DAB6	Red	*****	*****	DAB6.zip
Peregrin	Yellow	*****	*****	
				<input type="button" value="DELETE"/> <input type="button" value="ADD"/>

- **Add:** This can be done by clicking on the “add” button (bottom right of panel). An extension will appear, with empty fields for the new user’s name, group, token and password.
  - **Name:** name of the created user. For the certs deployment to work must be the same as a connected user (see below)
  - **Group:** group of individuals this user belong to (team a, team b, team c)
  - **Token:** gives an unique combination that this user can leverage for the FTS REST API
  - **Password:** unique password that can be used for interact with the FTS
  - **Certs:** true/false. If true certs will be generated (see below)

Once the fields have been filled, simply press submit to add a new user.

[SYSTEM USERS]

Name	Group	Token	Password	Certs
Ralph	Blue	*****	*****	Ralph.zip
FEATHER	cyan	*****	*****	FEATHER.zip
NOVA	Cyan	*****	*****	NOVA.zip
LowSpeed	white	*****	*****	LowSpeed.zip
C0rv0	Yellow	*****	*****	C0rv0.zip
CorvoMobile	Yellow	*****	*****	CorvoMobile.zip
JAVA	Yellow	*****	*****	JAVA.zip
DAB6	Red	*****	*****	DAB6.zip
Peregrin	Yellow	*****	*****	

DELETE ADD

Name

Group

Token

Password

Certs

True ▼

Submit

- **Delete:** This can be done by selecting the undesired user and then clicking on “delete” (bottom right). You can only delete one user each time. **Since version 1.9 when you delete an user that has a certificate, the certificate will be invalid.**

### 5.1.1 Automate certificates creation and deployment

TAK clients can connect to a server using TCP or secure connection (SSL), this requires the creation of valid certification on the server that needs to be deployed to each client.

FTS supports an advanced system to generate and distribute valid certification.

When creating a system user, by leaving “certs” on “true”, the user will automatically be notified of his new connection, but **only if he is connected to the same server at that moment.**

FTS will:

- Create a system User (e.g. Joe)
- Generate valid Certifications
- Package the certs into a zip file with the same name of the user (e.g. Joe.zip)
- Create a private Data Package. This can be seen in the Mission section, with the other Data Packages
- Send the private DP automatically to a ATAK/Wintak (or compatible client)
- To the user with the same name (Joe)  
The user will receive a notification of the reception
- Under “manage server connection” a new entry with the name `FreeTAKServer_[SERVERIP]` will appear.
- The user needs to activate the connection (in WinTAK he may need to restart the software)

### 5.1.2 Alternate certificates distribution


If the user is not online at the moment of the certs creations, it’s possible to deploy the certifications by:

- Download the data package and use another type of secure transportation
- As soon the user is online, set the certification Data Package to be public, allowing the user to download it and then changing it back to private

### 5.1.3 Deactivate Certification

Since FTS 1.9 it's possible to deactivate a certification by deleting the user associated with it. The next time the user tries to connect to the server, will get an `IO error`.

## 5.2 Group Permissions



Future functionality, not currently active.

Allows to create and assign permission to groups. When activated, will filter what an user can receive from FTS.

## 6.0 Connect

A menu that can be used to create Center Of Target (CoTs) using a “Human API” and send system messages to FTS users. This is a User interface to some of the FTS Public UI (see [https://freetakteam.github.io/FreeTAKServer-User-Docs/API/REST\\_APIDoc.html](https://freetakteam.github.io/FreeTAKServer-User-Docs/API/REST_APIDoc.html) for complete description of the API)

### 6.1 Send CoT

Can be used to create a CoT (also called a geoObject)

[SEND COT]

Name

Attitude

Longitude

GeoObject

Latitude

Timeout

Send

fill out the fields with the desired values.

- **Name:** geoObject name that will display on map
- **Longitude/Latitude:** Determines where the object will appear
- **Attitude:** Sets the colour and external shape (and thus faction) of the geoObject based on MILSTD 2525D
- **GeoObject:** Changes the shape and type of the object (ex: sniper, grenadier)
- **Timeout:** The length of time the object appears, measured in seconds

## 6.2 Emergency

Allows to see, delete and create new emergencies on the server

[EMERGENCY]

Name	Latitude	Longitude	Type	UID
No Records.				

DELETE ADD

- **Delete:** This can be done by selecting the undesired data packages and then clicking on “delete” (bottom right)
- **Add:** Start by clicking the “add” button at bottom right. An extension of the panel will appear. Simply fill out the pertinent information (name, location in longitude/latitude, type of emergency). Press “send” once finished

[EMERGENCY]

Name	Latitude	Longitude	Type	UID
No Records.				


DELETE ADD

Name  Latitude  Longitude  In Contact

Send

## 6.3 Manage Presence

Using this the user can create a custom team member (friendly Dot) on the ATAK map, who will however appear like a real TAK user.




The screenshot shows a dark-themed panel titled "[MANAGE PRESENCE]" in the top right corner. It contains three input fields on the left: "Name", "Longitude", and "Latitude". On the right, there are two dropdown menus: "Role" (set to "Team Member") and "Team" (set to "Blue"). A "Send" button is located in the bottom right corner of the panel.

To create a new member simply fill out the fields with the proper information. Once finished, press “send” (bottom right of panel).

## 6.4 Message

This function allows users to send system messages to all connected TAK clients.



The screenshot shows a dark-themed panel titled "[MESSAGE]" in the top right corner. It features a large text input field at the top with placeholder text "ex.The server will shutdown in 5 minutes...". Below this is a "Sender" label followed by an input field. A "Send" button is positioned in the bottom right corner.

To send a message it suffices to enter the message in the top field, and then specify the sender name in the field marked “sender”. Once finished, press “Send”.

## 7.0 Configure

Used to configure services and federated servers.

### 7.1 System Configuration

Here the services can be turned on and off and a port can be assigned to the service.

The Data Package IP is initially determined by the starting parameter of FTS.

```
sudo python3 -m FreeTAKServer.controllers.services.FTS -DataPackageIP
204.48.30.216 -AutoStart True
```

FTS supports following services:

- **TCP COT:** used when a client connects with regular TCP
- **SSL COT:** used when a client connects with an encrypted channel
- **HTTP DP:** Data package function over HTTP
- **SSL DP:** Data package function over an encrypted channel
- **API:** the Public REST API. Allows to send data over REST for integration with other systems. If deactivated some function of the WebUI will not work
- **FED:** Federation function, allow to create outgoing connections to other TAK servers

Service	Status	Port
TCP COT	On	8087
HTTP DP	On	8080
API	On	19023
SSL COT	On	8089
SSL DP	On	8443
FED	On	9000

To turn a service on and off:

- click on the slider of the desired service
- Click 'apply'

To change a service port:

- Move the slider to stop the service
- Click 'apply'
- Change value of the port
- Click 'apply'
- Reactivate the service by moving the slider
- Click 'apply'

## 7.2 Outgoing Federations

See 4.4 Federations.

## FTS 1.5 - User Manual

Name

Reconnect

30

Max Retries

3

Enabled

▼

[OUTGOING FEDERATION]

IP / Domain

Port

Fallback

lantern


▼

Apply



## 8.0 About

FTS and UI version notes and special thanks



### 7.1 About FTS

A description of the software

### 7.2 FTS and UI version

Current running version and IP, important when reporting bugs

### 7.3 Credits

A list of individuals and organization that have contributed to FTS

### 7.4 Open Source Note

A list of libraries and other projects being used

