



Auto Scaling (Version 2011-01-01)

Quick Reference Card, Page 1

Auto Scaling Groups		Launch Configurations
as-create-auto-scaling-group Creates a new Auto Scaling group with specified name and other attributes. as-create-auto-scaling-group <i>AutoScalingGroupName</i> --availability-zones <i>value</i> [, <i>value...</i>] --launch-configuration <i>value</i> --max-size <i>value</i> --min-size <i>value</i> [--default-cooldown <i>value</i>] [--desired-capacity <i>value</i>] [--grace-period <i>value</i>] [--health-check-type <i>value</i>] [--load-balancers <i>value</i> [, <i>value...</i>]] [--placement-group <i>value</i>] [--vpc-zone-identifier <i>subnetId</i> [, <i>subnetId...</i>]]	as-update-auto-scaling-group Updates specified Auto Scaling groups with attributes. as-update-auto-scaling-group <i>AutoScalingGroupName</i> [--availability-zones <i>value</i> [, <i>value...</i>]] [--default-cooldown <i>value</i>] [--desired-capacity <i>value</i>] [--grace-period <i>value</i>] [--health-check-type <i>value</i>] [--launch-configuration <i>value</i>] [--max-size <i>value</i>] [--min-size <i>value</i>] [--placement-group <i>value</i>] [--vpc-zone-identifier <i>value</i>]	as-create-launch-config Creates a new launch configuration with specified attributes. as-create-launch-config <i>LaunchConfigurationName</i> --image-id <i>value</i> --instance-type <i>value</i> [--iam-instance-profile <i>value</i>] [--spot-price <i>value</i>] [--block-device-mapping "key1=value1, key2=value2..."] [--monitoring-enabled/monitoring-disabled] [--kernel <i>value</i>] [--key <i>value</i>] [--ramdisk <i>value</i>] [--group <i>value</i> [, <i>value...</i>]] [--user-data <i>value</i>] [--user-data-file <i>value</i>]
as-delete-auto-scaling-group Deletes the specified Auto Scaling group if the group has no instances and no scaling activities in progress. as-delete-auto-scaling-group <i>AutoScalingGroupName</i> [--force-delete] [--force]	as-set-desired-capacity Sets the desired capacity of the specified Auto Scaling group (within the range of the group's minimum and maximum size). as-set-desired-capacity <i>AutoScalingGroupName</i> --desired-capacity <i>value</i> [--honor-cooldown/no-honor-cooldown]	as-delete-launch-config Deletes the specified launch configuration. as-delete-launch-config <i>LaunchConfigurationName</i> [--force]
as-describe-auto-scaling-groups Returns a full description of the specified Auto Scaling group(s). as-describe-auto-scaling-groups [<i>AutoScalingGroupName</i> [<i>AutoScalingGroupName...</i>]] [--max-records <i>value</i>]		as-describe-launch-configs Describes the specified launch configurations. as-describe-launch-configs [<i>LaunchConfigurationName</i> [<i>LaunchConfigurationName...</i>]] [--max-records <i>value</i>]
Instances		Processes
as-describe-auto-scaling-instances Returns a description of the Amazon EC2 instance(s) if the instance(s) exists in the Auto Scaling group. as-describe-auto-scaling-instances [<i>InstanceIds</i> [<i>InstanceIds</i> ...]] [--max-records <i>value</i>]	as-set-instance-health Sets the health of the instance. as-set-instance-health <i>InstanceId</i> --status <i>value</i> [--respect-grace-period/no-respect-grace-period]	as-suspend-processes Suspends all scaling processes for an Auto Scaling group. as-suspend-processes <i>AutoScalingGroupName</i>
as-terminate-instance-in-auto-scaling-group Terminates a given instance with/without reducing the group's capacity. as-terminate-instance-in-auto-scaling-group <i>InstanceId</i> --decrement-desired-capacity/no-decrement-desired-capacity [--force]		as-resume-processes Resumes all suspended scaling processes for a given Auto Scaling group. as-resume-processes <i>AutoScalingGroupName</i>
		as-describe-process-types Returns descriptions of suspendable scaling processes. If arguments are passed, returns matching process types. as-describe-process-types [<i>ProcessName</i> ...]



Auto Scaling (Version 2011-01-01)

Quick Reference Card, Page 2

Policies	Scheduled Actions	Notification Configuration
as-put-scaling-policy Creates or updates a scaling policy with specified attributes. <code>as-put-scaling-policy PolicyName --type value --auto-scaling-group value --adjustment value [--cooldown value] [--min-adjustment-step value]</code>	as-describe-scheduled-actions Describes the specified scheduled action(s) if the scheduled action(s) exists. <code>as-describe-scheduled-actions [ScheduledActionNames [ScheduledActionNames ...]] [--auto-scaling-group value] [--start-time value] [--end-time value] [--max-records value]</code>	as-put-notification-configuration Configures an Auto Scaling group to send notifications when specified events take place. <code>as-put-notification-configuration AutoScalingGroupName --notification-types value --topic-arn topic-ARN</code>
as-delete-policy Deletes the specified policy. <code>as-delete-policy PolicyName [--auto-scaling-group value] [--force]</code>	as-delete-scheduled-action Deletes the specified scheduled action. <code>as-delete-scheduled-action ScheduledActionName --auto-scaling-group value [--force]</code>	as-describe-notification-configurations Returns a list of notification actions associated with Auto Scaling groups for specified events. <code>as-describe-notification-configurations [--auto-scaling-groups value [, value ...]] [--maxrecords value]</code>
as-describe-adjustment-types Describes valid adjustment types for calls to as-put-scaling-policy . If arguments are passed, describes only adjustment types with names that match the arguments. <code>as-describe-adjustment-types [AdjustmentTypes [AdjustmentTypes ...]]</code>	as-put-scheduled-update-group-action Creates or updates a specified scheduled update group action with attributes. <code>as-put-scheduled-update-group-action ScheduledActionName --auto-scaling-group value --time value [--desired-capacity value] [--max-size value] [--min-size value] [--recurrence value]</code>	as-delete-notification-configuration Deletes notifications created by as-put-notification-configuration . <code>as-delete-notification-configuration AutoScalingGroupName --topic-arn topic-ARN</code>
as-describe-policies Describes the specified policy/policies if specified policy/policies exist. <code>as-describe-policies [PolicyNames [PolicyNames ...]] [--auto-scaling-group value] [--max-records value]</code>	Metrics Collection	
as-execute-policy Executes the specified policy. <code>as-execute-policy PolicyName [--auto-scaling-group value] [--honor-cooldown/no-honor-cooldown]</code>	as-enable-metrics-collection Enables collection of Auto Scaling group metrics. <code>as-enable-metrics-collection AutoScalingGroupName --granularity value [--metrics value [, value ...]]</code>	as-describe-auto-scaling-notification-types Returns a list of all notification types that are supported by Auto Scaling. <code>as-describe-auto-scaling-notification-types</code>
Scaling Activities	as-disable-metrics-collection Disables collection of Auto Scaling group metrics. <code>as-disable-metrics-collection AutoScalingGroupName [--metrics value [, value ...]]</code>	as-describe-metric-collection-types Describes all metric collection types and metric granularity types. <code>as-describe-metric-collection-types</code>
as-describe-scaling-activities Describes a set of activities or all activities belonging to a group. <code>as-describe-scaling-activities [ActivityIds [ActivityIds ...]] [--auto-scaling-group value] [--max-records value]</code>		