

Dell™ NetVault™ Backup 10.0.5

CLI Reference Guide



© 2015 Dell Inc.
ALL RIGHTS RESERVED.

This guide contains proprietary information protected by copyright. The software described in this guide is furnished under a software license or nondisclosure agreement. This software may be used or copied only in accordance with the terms of the applicable agreement. No part of this guide may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopying and recording for any purpose other than the purchaser's personal use without the written permission of Dell Inc.

The information in this document is provided in connection with Dell products. No license, express or implied, by estoppel or otherwise, to any intellectual property right is granted by this document or in connection with the sale of Dell products. EXCEPT AS SET FORTH IN THE TERMS AND CONDITIONS AS SPECIFIED IN THE LICENSE AGREEMENT FOR THIS PRODUCT, DELL ASSUMES NO LIABILITY WHATSOEVER AND DISCLAIMS ANY EXPRESS, IMPLIED OR STATUTORY WARRANTY RELATING TO ITS PRODUCTS INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NON-INFRINGEMENT. IN NO EVENT SHALL DELL BE LIABLE FOR ANY DIRECT, INDIRECT, CONSEQUENTIAL, PUNITIVE, SPECIAL OR INCIDENTAL DAMAGES (INCLUDING, WITHOUT LIMITATION, DAMAGES FOR LOSS OF PROFITS, BUSINESS INTERRUPTION OR LOSS OF INFORMATION) ARISING OUT OF THE USE OR INABILITY TO USE THIS DOCUMENT, EVEN IF DELL HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. Dell makes no representations or warranties with respect to the accuracy or completeness of the contents of this document and reserves the right to make changes to specifications and product descriptions at any time without notice. Dell does not make any commitment to update the information contained in this document.

If you have any questions regarding your potential use of this material, contact:

Dell Inc.
Attn: LEGAL Dept
5 Polaris Way
Aliso Viejo, CA 92656

Refer to our web site (software.dell.com) for regional and international office information.

Patents

This product is protected by U.S. Patents # 7,814,260; 7,913,043; 7,979,650; 8,086,782; 8,145,864; 8,171,247; 8,255,654; 8,271,755; 8,311,985; and 8,452,731. Protected by Japanese, E.U., French, and UK patents 1615131 and 05250687.0, and German patent DE602004002858. Additional patents pending. For more information, go to <http://software.dell.com/legal/patents.aspx>.

Trademarks

Dell, the Dell logo, and NetVault are trademarks of Dell Inc. IBM, AIX, DB2, and Domino are registered trademarks of International Business Machines Corporation. EMC, Data Domain, and DD Boost are registered trademarks or trademarks of EMC Corporation in the United States and other countries. FreeBSD is a registered trademark of The FreeBSD Foundation. Linux is a registered trademark of Linus Torvalds in the United States, other countries, or both. Mac and OS X are trademarks of Apple Inc., registered in the U.S. and other countries. MySQL is a registered trademark of MySQL AB in the United States, the European Union and other countries. NetApp, SnapMirror, Snapshot, and SnapVault are trademarks of NetApp, Inc., registered in the U.S. and/or other countries. SAP is the registered trademark of SAP AG in Germany and in several other countries. Sun, Oracle, and Oracle Solaris are trademarks or registered trademarks of Oracle and/or its affiliates in the United States and other countries. SPARC is a registered trademark of SPARC International, Inc. in the United States and other countries. Products bearing the SPARC trademarks are based on an architecture developed by Oracle Corporation. SLES and SUSE are registered trademarks of SUSE LLC in the United States and other countries. Sybase is a trademark of Sybase, Inc. Windows, Hyper-V, SQL Server, and SharePoint are either registered trademarks or trademarks of Microsoft Corporation in the United States and/or other countries. UNIX is a registered trademark of The Open Group in the United States and other countries. VMware is registered trademark of VMware, Inc. in the United States and other jurisdictions. Other trademarks and trade names may be used in this document to refer to either the entities claiming the marks and names or their products. Dell disclaims any proprietary interest in the marks and names of others.

Legend



CAUTION: A CAUTION icon indicates potential damage to hardware or loss of data if instructions are not followed.



WARNING: A WARNING icon indicates a potential for property damage, personal injury, or death.



IMPORTANT NOTE, NOTE, TIP, MOBILE, or VIDEO: An information icon indicates supporting information.

Contents

Introduction	6
About Dell™ NetVault™ Backup	6
Key benefits	6
Feature summary	7
About this document	7
Target audience	8
Recommended additional reading	8
Getting started	9
About NetVault Backup Command Line Interface	9
Working with command-line utilities	9
Prerequisites	9
Command syntax	10
CLI help	10
Command exit status	11
Environment variables	11
Starting and stopping the NetVault Backup Service	12
Using the command-line utilities	13
Client-specific utilities	13
nvclient	13
nvclientaccess	14
nvclientadd	15
nvclientlist	16
nvclientname	16
nvclientremove	17
Device-specific utilities	17
asf_load_media	17
asf_release_drive	18
nvacslsmedia	18
nvaddfiler	19
nvcheckdrive	20
nvcleandrive	21
nvclosedoor	22
nvcloseeeport	22
nvcloseeeportcleaning	23
nvдав	23
nvdelldrda	24
nvddbboost	26
nvdevice	27
nvdeviceeject	28
nvlibrarymodify	28
nvopendoor	31
nvopeneeport	31

nvremovefiler	32
nvresetdrivstats	32
nvscandrives	33
nvsetcleaninglives	34
nvsetdrivecleaning	35
nvsmartdisk	36
nvsvtlgrow	37
Media-specific utilities	38
nvblankmedia	38
nvbulkblankmedia	39
nvexportmedia	41
nvlabelmedia	41
nvlistblankmedia	42
nvlistmedia	43
nvloadmedia	44
nvmakemedia	44
nvmediadetails	46
nvremovemedia	47
nvreusemedia	47
nvscanmedia	48
nvsynchronizesilomedia	49
nvupdateserialnumber	49
Job-specific utilities	50
nvexpiresaveset	50
nvjobabort	52
nvjobcreate	52
nvjobdelete	54
nvjobhold	56
nvjoblist	57
nvjobmodify	57
nvjobresume	59
nvjobstart	60
nvpolicy	61
nvrestore	63
Notes	65
nvsetcreate	66
nvsetdelete	76
nvsetexport	76
nvsetimport	77
nvsetmodify	78
nvtrigger	82
Log-specific utilities	83
nvlogdump	83
nvlogpurge	84
nvreadlog	84
Other utilities	85
bonedate	85
getmachineid	86

installplugin86
licenseinstall86
nvlicenseinfo86
nvmeddbcheck87
nvpassword87
nvpluginaccess88
nvpgdbpasswd88
nvreport89
nvscheddbcheck89
nvsendmail90
nvsendopmsg91
Using the nvreport utility92
About nvreport utility92
Syntax92
Options93
Report classes93
Plain text template files98
Formatting the reports99
Obtaining the real name99
Using the format option	100
Using the sort option	101
Using the include option	101
Using the title option	104
Creating external report files	104
Selecting the template file	104
Specifying the outputdir	105
Specifying the appendoutput option	105
Using the title option	105
HTML template files	106
About Dell115
Contacting Dell115
Technical Support Resources115

Introduction

- [About Dell™ NetVault™ Backup](#)
- [About this document](#)
- [Target audience](#)
- [Recommended additional reading](#)

About Dell™ NetVault™ Backup

Dell NetVault Backup (NetVault Backup) offers the most advanced, cross-platform data protection capabilities on the market as well as unsurpassed ease of use, out-of-the-box deployment, and pain-free scalability. NetVault Backup allows you to safeguard your data and applications in both physical and virtual environments from one intuitive user interface and to protect a massive number of servers that contain many petabytes of data. NetVault Backup also features heterogeneous support, so you can safeguard data on a wide range of operating systems, applications, databases, processor architectures, and networked storage devices. Such cross-platform versatility makes it easy for you to tailor NetVault Backup to match the ever-changing and growing landscape of your IT infrastructure.

Key benefits

- Simple, out-of-the-box deployment for fast time to value
- Protection for both physical and virtual environments for cost savings
- Heterogeneous server support for flexibility to adjust to changing conditions
- Extensive application support
- Disk-based backup and deduplication to significantly improve storage efficiency
- Seamless integration with the Dell DR Series appliances for source-side deduplication and WAN-optimized replication
- Comprehensive Network Attached Storage (NAS) protection to safeguard critical data
- Powerful, flexible encryption when and where you need it
- Bare metal recovery to drastically reduce the time it takes to recover a failed disk drive
- Extensive storage attachment options allow for distributed backup targets and workload
- Dynamic device sharing to optimize backup data transfers and reduce points of failure

Feature summary

- **Back up to disk and tape:** Leverage disk- and tape-based backups to a wide range of storage targets, including NAS devices and third-party deduplication appliances. NetVault Backup also allows you to move data from one storage target to another for off-site storage and disaster recovery purposes.
- **Data deduplication:** Reduce your data storage footprint by up to 90 percent with deduplication provided by Dell™ NetVault™ SmartDisk (NetVault SmartDisk). Its patented byte-level, variable-block size deduplication packs up to 12 times more protected data into the same storage area.

NetVault Backup also integrates seamlessly with the Dell DR Series disk backup appliances, enabling you to take full advantage of the powerful deduplication, compression, and replication capabilities offered by these appliances.

- **Virtualization support:** Extend advanced data protection to VMware® and Hyper-V® environments. NetVault Backup gives you consistent, reliable, point-and-click backup and restore for virtual environments without requiring you to be an expert.
- **Application protection:** Ensure the availability of business-critical applications such as Oracle®, SQL Server®, Exchange, SharePoint®, MySQL, PostgreSQL, Domino®, DB2®, Informix®, SAP®, and Sybase® with application plug-ins. These plug-ins complement native solutions to save you time on integration. No scripting is required to run backup and recovery jobs.
- **NAS protection:** Get advanced data protection for information stored on NAS appliances, including those made by Dell, EMC®, Hitachi, IBM®, NetApp, and Sun. You can reduce traffic over the LAN and maximize performance by backing up data using Network Data Management Protocol (NDMP). NetVault Backup supports many different storage topologies and configurations, allowing you to perform backups directly to a locally attached SCSI device, a SAN-attached device, or a storage device elsewhere on the network.
- **Enterprise-wide control:** Give backup administrators the flexibility to define, manage, and monitor jobs from remote locations of their choice. Automated features for global event notification and policy-based job management simplify their tasks across heterogeneous storage networks.
- **Strong security:** Meet regulatory requirements without sacrificing backup windows or deduplication performance with encryption plug-ins for CAST-128, AES-256, and CAST-256 algorithm support. Flexible job-level encryption lets you easily select which data to encrypt.
- **Flexible storage attachment:** Avoid data transfers over the network by attaching a target storage device directly to a source server. With LAN-free backups, you can easily distribute the workload throughout the backup domain.
- **Dynamically shared device:** Share stand-alone and library-based tape drives among backup server and clients in SAN or shared-SCSI environments. This capability allows you to optimize workloads and maximize your equipment investments.
- **Simple, straight-forward licensing:** License NetVault Backup by capacity or by component. This option gives you incredible flexibility to choose the model that best meets the organization's needs.

About this document

This guide provides information about using the NetVault Backup command-line utilities. For information about using the NetVault WebUI, see the *Dell NetVault Backup Administrator's Guide*.

IMPORTANT:

- NetVault Backup uses a PostgreSQL database to store the system data. The NetVault Database is created on the server during installation. You should not attempt to modify the NetVault Database directly using any PostgreSQL tools unless directed by Dell Software Technical Support. Improper changes to the database can cause irrecoverable data corruption. Before modifying the NetVault Database, make sure that you create a backup copy of the database. For more information about backing up the NetVault Database, see the *Dell NetVault Backup Plug-in for Databases*.
- NetVault Backup stores the system configuration settings in “.cfg” files in the config directory (<NetVault Backup home>\config on Windows and <NetVault Backup Home>/config on Linux). The settings in these files should only be modified under the guidance of Dell Software Technical Support. Improper changes to these files can cause errors and other unexpected behavior. Before modifying a configuration file, make sure that you create a backup copy of the file.

Target audience

This guide is intended for backup administrators and other technical personnel who are responsible for designing and implementing a backup strategy for the organization. A good understanding of the operating systems on which the NetVault Backup Server and Clients are running is assumed.

Recommended additional reading

- *Dell NetVault Backup Installation Guide*: This guide provides information about installing the NetVault Backup Server and Client software.
- *Dell NetVault Backup Administrator's Guide*: This guide describes how to configure and use NetVault Backup to protect your data. It provides comprehensive information about all NetVault Backup features and functionality.
- *Dell NetVault Backup Command Line Interface Reference Guide*: This guide provides information about using the NetVault Backup command-line utilities.
- *Dell NetVault Backup Plug-in for FileSystem User's Guide*: This guide provides information about installing, configuring, and using NetVault Backup Plug-in for FileSystem.
- *Dell NetVault Backup Built-in Plug-ins User's Guide*: This guide provides information about configuring and using the following plug-ins:
 - Dell NetVault Backup Plug-in for Consolidation
 - Dell NetVault Backup Plug-in for Data Copy
 - Dell NetVault Backup Plug-in for Databases
 - Dell NetVault Backup Plug-in for Raw Devices

You can download these guides from <https://support.software.dell.com/>.

Getting started

- [About NetVault Backup Command Line Interface](#)
- [Working with command-line utilities](#)
- [Starting and stopping the NetVault Backup Service](#)

About NetVault Backup Command Line Interface

NetVault Backup offers a Command Line Interface that can be used to configure and manage your NetVault Backup system from command prompt or terminal session. You can use the NetVault Backup CLI to perform various tasks such as the following:

- Start and stop the NetVault Backup Service
- Configure performance, security, and other options
- Manage clients, storage devices, and storage media
- Perform backups and restores
- Generate and view reports

The NetVault Backup CLI is automatically installed on the NetVault Server and Client machines.

Working with command-line utilities

The command-line utilities are located in the util directory (<NetVault Backup home>\util on Windows and <NetVault Backup Home>/util on Linux). A few specialized utilities are also located in the bin directory (<NetVault Backup home>\bin on Windows and <NetVault Backup Home>/bin on Linux). The CLI commands are non-blocking. The term “non-blocking” means that a response to the command is returned before the action has completed; this allows for continuous running of various commands.

Prerequisites

Before you start a CLI session, verify that the following requirements are met:

- To use the CLI utilities, you must be logged-in with Administrator privileges on Windows and root user privileges on Linux® and UNIX®.
- A NetVault Backup user must have necessary privileges to access and use the CLI utilities. These privileges are assigned from the NetVault WebUI. For more information, see the *Dell NetVault Backup Administrator's Guide*.

Command syntax

The syntax of a command takes the following form:

```
Command -option 1 <Value> -option 2 <Value> [-option 3 <Value> | -option 4 <Value>]  
[-option 5], ...
```

where

- <Value> is a user input variable for an option.
- Options enclosed within square brackets (" []") are optional.
- A pipe (" | ") character between two options indicates that only one of the multiple options listed in the syntax can be used in a command.

Important notes

- The command syntax format must be entered as one line, unless otherwise noted. The order of the options is not important in the syntax.
- Switches can be specified using only the initial letter in their name, provided this letter is unique and no other option for the selected command begins with the same letter.

For example, the following is the command syntax for the `nvbulkblankmedia` utility:

```
nvbulkblankmedia -libraryname <library name> -medialabel <media label>  
-allmedia -password <NetVault Backup password> -wait
```

All the options for this command begin with different letters. So, this command can also be specified as follows:

```
nvbulkblankmedia -l MyLibrary1 -m MyBackupMedia* -p Mypassword -wait
```

where

- "-l" represents the "-libraryname" option
- "-m" represents the "-medialabel" option
- "-p" represents the "-password" option
- The CLI cannot recognize spaces in variable names. Variables that contain spaces must be enclosed within quotation marks (" "); otherwise, the command fails.
- The CLI sees the use of an underscore in its syntax as a replacement for a space. Conflicts arise when a NetVault Backup Server, Client, or backup device name contains an underscore character (" _") and it is referenced in a CLI command.

For example, if you include the name "Test_Server" in a CLI command, NetVault Backup searches for a machine named "Test Server", and the command fails as it is unable to locate the machine.

Variables that contain underscores must be enclosed within quotation marks (" ").

CLI help

To access help about a command, type the command followed by "-help" or "--help", or type the command and press Enter. For example, to access help for `nvblankmedia`, you can use the following methods:

```
nvblankmedia -help  
nvblankmedia --help  
nvblankmedia
```

Command exit status

Various CLI commands return a numeric value when you run them. The return value represents the actual exit status of the command as described in the following table:

Table 1. Command exit status

Exit status	Description
0	Command completed successfully.
1	Command failed.
2	Arguments given in the command are invalid. For example, a variable named in the command is inaccurate.

Environment variables

While using the CLI utilities in a script, you can use the following environment variables.

Table 2. Environment variables

Variable	Description
NETVAULTCLIACCOUNT	Specifies the NetVault Backup user name. The specified account must have privileges to use the CLI utility. <code>NETVAULTCLIACCOUNT=<User Account Name></code> The variable must be included in the script to access the CLI utility.
NETVAULTCLIPASSWORD	Specifies the password for the NetVault Backup user account. <code>NETVAULTCLIPASSWORD=<Password></code> This variable must be included in the script to specify the password for the user account.
NV_HOME	Returns the NetVault Backup installation directory.
NV_JOBCLIENT	Specifies the target client for a job. <code>NV_JOBCLIENT=<Name of the NetVault Backup Client></code>
NV_JOBID	Specifies the Job ID. <code>NV_JOBID=<Job ID></code>
NV_JOBTITLE	Specifies the Job Title. <code>NV_JOBTITLE=<Job title></code>
NV_JOB_WARNINGS	Returns TRUE if a job completes with warnings, else FALSE. <ul style="list-style-type: none">If a backup completes with warnings: <code>NV_JOB_WARNINGS=TRUE</code>If a backup completes successfully: <code>NV_JOB_WARNINGS=FALSE</code> This variable can only be used in a post -script. The mail scripts use this variable, but the variable has general applicability. If a backup completes with warnings, the NV_STATUS variable returns SUCCEEDED, while the NV_JOB_WARNINGS variable returns TRUE. The return value is not localized; it is TRUE or FALSE in English.
NV_OUTPUT_FILE	Returns the user-defined output file for reports.
NV_SERVERNAME	Specifies the NetVault Backup Server Name. <code>NV_SERVERNAME=<Name of the NetVault Backup Server></code>
NV_SESSIONID	Specifies the Session ID of a job. <code>NV_SESSIONID=<Session ID></code>

Table 2. Environment variables

Variable	Description
NV_STATUS	Returns the exit status of a job. It returns either SUCCEEDED or FAILED. <ul style="list-style-type: none">If a backup job completes successfully or completes with warnings: NV_STATUS=SUCCEEDEDIf a backup job fails: NV_STATUS=FAILED This variable can only be used in a post-script. The return value is not localized; it is SUCCEEDED or FAILED in English.
NV_USER_ARG	Specifies the user-defined arguments passed with the pre- or post-scripts.

Starting and stopping the NetVault Backup Service

The NetVault Backup Service is configured to start automatically when the software installation completes on the NetVault Backup Server and Client machines. To manually stop or start the service from CLI, you can use the following commands:

- Linux-based systems:

```
# $NV_HOME/etc/startup.sh start
# $NV_HOME/etc/startup.sh stop
```

- Windows-based systems:

```
C:\ net start "NetVault Process Manager"
C:\ net stop "NetVault Process Manager"
```

Using the command-line utilities

- Client-specific utilities
- Device-specific utilities
- Media-specific utilities
- Job-specific utilities
- Log-specific utilities
- Other utilities

Client-specific utilities

nvclient

Description

Adds one or more NetVault Backup Clients to the NetVault Backup Server, and assigns the clients to the specified client groups. You can also use this utility to add Workstation Clients.

Syntax

```
nvclient [-add] [-list] [-password <NetVault Backup Password>]
[-file <Client List File>] [-workstation | -client <Client Name> ...]
[-group <Client Group Name> ...]
[-log <Log File>] [-failure <Filename to Log Failed Clients List>]
[-quiet] [-verbose] [-abort] [-args] [-timeout <timeout period>]
```

Options

Table 1. nvclient

Option	Description
-add	Adds one or more clients to the NetVault Backup Server.
-list	Lists clients (including Workstation Clients) added to the server.
-password	Specifies NetVault Backup password of the client. This option is required if security is enabled on the client.

Table 1. nvclient

Option	Description
-file	Specifies the name of the input file for batch submission. You can specify client name, password, and group names in the file. Specify one client per line. Example: MyClientList Client-A -password mypwd2 -group Group1 Client-B Client-C -password mypwd2
-workstation	Specifies NetVault Backup names of Workstation Clients that you want to add to the server.
-client	Specifies NetVault Backup names of clients that you want to add to the server.
-group	Specifies names of client groups to which you want to add the clients. Verify that the client groups are created before you add the client.
-log	Specifies the name of the log file.
-failure	Specifies the name of the failed clients list.
-quiet	Suppresses display of output messages on the screen.
-verbose	Displays status and error messages on the screen.
-abort	Aborts the command if licensing does not permit addition of all clients.
-args	Prints program parameters and exits without doing anything.
-timeout	Specifies the amount of time NetVault Backup waits for a client to approve the “add” request. The timeout value is specified in seconds. The default value for this option is 30 seconds. If a client cannot be added within the specified period, an error message is displayed.

Notes

- Client names are case-sensitive.
- A client must be available and running a valid installation of NetVault Backup before it can be added to a server.
- To locate a client that is unavailable, use the `nvclientlist -find <ipaddress>` command. For more information, see [nvclientlist](#).
- Client groups can only be created from the NetVault WebUI. The CLI does not provide any utility to create client groups.

nvclientaccess

Description

Grants access to specified NetVault Backup Clients.

Syntax

```
nvclientaccess [-client <Client Name>] | [-clients <Client Names>] |  
               [-tdclients <Teradata DBS name>] [-password <password>]
```

Options

Table 2. nvclientaccess

Option	Description
-client or -clients	Specifies the names of NetVault Backup Clients to which access is granted.
-tdclients	Specifies the name of the Teradata DBS. You can use this option to grant access to all added clients.
-password	Specifies NetVault Backup password of the client. This option is required if security is enabled on the client.

nvclientadd

Description

Adds a single NetVault Backup Client to the server. You must run this utility on the NetVault Backup Server. This utility does not support Workstation Clients.

Syntax

```
nvclientadd [-client <Client Name> | -clientip <Client IP address>]  
            [-clientgroup <Client Group Name>] [-password <password>]  
            [-timeout <timeout period>] [-version]
```

Options

Table 3. nvclientadd options

Option	Description
-client	Specifies NetVault Backup name of the client that you want to add.
-clientip	Specifies IP Address of the NetVault Backup Client that you want to add.
-clientgroup	Specifies the name of the client group to which you want to add the client. Verify that the client group is created before you add the client.
-password	Specifies NetVault Backup password of the client. This option is required if security is enabled on the client.
-timeout	Specifies the amount of time NetVault Backup waits for the client to approve the “add” request. The timeout value is specified in minutes. If a client cannot be added within the specified period, an error message is displayed
-version	Displays build date of the NetVault Backup distribution installed on the machine.

Notes

- Client names are case-sensitive.
- A client must be available and running a valid installation of NetVault Backup before it can be added to a server.
- To locate a client that is unavailable, use the `nvclientlist -find <ipaddress>` command. For more information, see [nvclientlist](#).
- Client groups can only be created from the NetVault WebUI. The CLI does not provide any utility to create client groups.

nvclientlist

Description

Performs the following functions:

- Lists clients added to the NetVault Backup Server.
- Lists available NetVault Backup machines that can be added as clients.
- Locates a NetVault Backup machine using its resolvable name or IP address.

Syntax

```
nvclientlist [-current [-name <Client Name>]] [-available [-name <Client Name>]]  
              [-find <Resolvable Name or IP address>] [-version]
```

Options

Table 4. nvclientlist

Option	Description
-current	Lists clients that are currently added to the NetVault Backup Server.
-available	Lists available NetVault Backup machines that can be added as clients.
-name	Specifies NetVault Backup name of the client that you want to locate.
-find	Specifies the resolvable name or IP address of the machine that you want to locate.
-version	Displays build date of the NetVault Backup distribution installed on the machine.

nvclientname

Description

Allows you to rename a NetVault Backup Client. You cannot use this utility to change the name of a NetVault Backup Server.

Syntax

```
nvclientname -clientname <New NetVault Backup name>
```

Options

Table 5. nvclientname

Option	Description
-clientname	Specifies the new NetVault Backup name for the client.

nvclientremove

Description

Removes a client from the NetVault Backup Server. You must run this utility on the NetVault Backup Server.

Syntax

```
nvclientremove [-client <NetVault Backup name of the client>] [-version]
```

Options

Table 6. nvclientremove

Option	Description
-client	Specifies NetVault Backup name of the client that you want to remove. You can only specify a single client name with this option.
-version	Displays build date of the NetVault Backup distribution installed on the machine.

Device-specific utilities

asf_load_media

Description

Loads the specified media into the drive and locks it in the drive as Windows Advanced System Format (ASF) media.

Syntax

```
asf_load_media -m <Media Label> | -b <Barcode> -d <Device Name>  
[-s <Server Name>] [-c <Client Name>] [-wait]
```

Options

Table 7. asf_load_media

Option	Description
-m	Specifies the label of the target media item.
-b	Specifies the barcode of the target media item
-d	Specifies the name of the target drive.
-s	Specifies the name of the NetVault Backup machine to which the target device is locally attached. If the device is locally attached to a client (SmartClient), use this option to specify the client name.
-c	Specifies the name of the NetVault Backup Client to which the target device is locally attached.
-wait	Waits until the task has completed.

asf_release_drive

Description

Releases lock placed by the “asf_load_media” command and allows NetVault Backup to use the drive and the media.

Syntax

```
asf_release_drive -d <Device Name> [-s <Server Name>] [-c <Client Name>]
```

Options

Table 8. asf_release_drive

Option	Description
-d	Specifies the name of the target drive.
-s	Specifies the name of the NetVault Backup Server. Use this option if the device is locally attached to the server.
-c	Specifies the name of the NetVault Backup Client. Use this option if the device is attached to a client or remote NetVault Backup Server.

nvacslsmedia

Description

Performs the following functions:

- Allocates media to an ACSLS Library.
- De-allocates specified media.
- Ejects a piece of media

Syntax

```
nvacslsmedia [-allocate | -deallocate | -eject] [-medialabel <Media Label>]  
[-cap <acs>,<lsm>,<cap>] -libraryname <Library Name> [-servername <Server Name>]  
[-range <range-media >] [-file <Filename >] [-version]
```

Options

Table 9. nvacslsmedia

Option	Description
-allocate	Allocates specified media items.
-deallocate	De-allocates specified media items.
-eject	Ejects the specified media items through the specified Cartridge Access Port (CAP).

Table 9. nvacslsmedia

Option	Description
-cap	Specifies the Cartridge Access Port (CAP) through which to eject the media items. Provide the ACS number of the library, LSM number of the robotic unit that controls the library, and physical number of the CAP. Use comma to separate the numeric values. Example: -cap 0,0,0
-medialabel	Specifies the label or barcode of the media items that you want to allocate, de-allocate, or eject from the library. For multiple labels or barcodes, provide a comma-separated list.
-libraryname	Specifies the name of the target library.
-servername	Specifies the name of the NetVault Backup Server that administers the job. This option is required when a remote server administers the job. It can be omitted when a local server administers the job. The server name is case-sensitive.
-range	Specifies a range of media labels or barcode values that correspond to the pieces of media that you want to de-allocate. Use a hyphen (without any spaces) between the values.
-file	Specifies the name of the file that contains a list of media labels or barcodes corresponding to the set of media items that you want to de-allocate. Only one media label or barcode can be specified per line.
-version	Displays build date of the NetVault Backup distribution installed on the machine.

nvaddfiler

Description

Adds an NDMP filer to the NetVault Backup Server.

Syntax

```
nvaddfiler [-servername <Server Name>] [-clientname <Client Name>]
[-pluginname <Plug-in Name>] -filename <Filer Name> -address <IP address or FQDN>
[-port <Port number>] -account <User Name> -password <Password>
[-description <Description>] [-utf8 <Boolean>]
```

Options

Table 10. nvaddfiler

Option	Description
-servername	Specifies the name of the NetVault Backup Server that administers the job. This option is required when a remote server administers the job. It can be omitted when a local server administers the job. The server name is case-sensitive.
-clientname	Specifies the name of the NetVault Backup Client to which the filer is added. This option can be omitted if you want to add the filer to the local machine. If you specify -servername, you must also specify -clientname even if they are the same machine.
-pluginname	Specifies the plug-in name. It can be NDMP Client or NDMP SnapMirror to Tape. The default value is NDMP Client.

Table 10. nvaddfiler

Option	Description
-filename	Specifies the filer name. The filer name must be unique. You can assign the actual name of the filer to easily identify it in the NetVault Backup environment. The filer name cannot be changed once it is configured.
-address	Specifies the IP4 address or FQDN of the filer.
-port	Specifies the listen port for the filer. The default value is 10000. Unless otherwise required, do not change listener port for the filer.
-account	Specifies the name of the user account that can be used to log on to the filer. The user account must have necessary permissions to perform NDMP backups and restores.
-password	Specifies the password for the user account.
-description	Provides NDMP filer description when filer type needs to be selected. The description must match the corresponding entry in the <code>ndmpversions.cfg</code> file.
-utf8	Specifies whether UTF-8 conversions are required or not. The default value for this option is FALSE. Set it to TRUE if you want to correctly display the directory and filenames in the set locale on NetVault WebUI. You can use this option only if the file supports UTF-8 encoding. To use this feature, do the following: <ul style="list-style-type: none"> • Enable UTF-8 conversion on the filer. • Set the appropriate language-type on each target volume. • Set the configuration option Codepage for UTF-8 Conversions for the Plug-in for NDMP. For more information about this option, see the <i>Dell NetVault Backup Plug-in for NDMP User's Guide</i>.

Examples

- Add filer "f740" to the local NetVault Backup machine:

```
nvaddfiler -filename f740 -address 10.11.22.53 -account root
          -password mypassword
```

- Add filer "f740" to "Client-A" that is controlled by the local NetVault Backup Server:

```
nvaddfiler -clientname Client-A-filename f740 -address 10.11.22.53 -account
          root -password mypassword
```

- Add filter "f740" to the remote server named "Win-Server":

```
nvaddfiler -servername Win-Server -clientname Win-Server -filename f740
          -address 10.11.22.53 -account root -password mypassword
```

nvcheckdrive

Description

Checks the status of a drive. For example, it can be used to check the status of a drive that was taken offline for some reason. If successful, the specified drive is brought back online so that it is available to NetVault Backup for future jobs.

Syntax

```
nvcheckdrive -servername <Server Name> [-drivename <Drive Name>]  
[-libraryname <Library Name>] [-drivenumber <Drive Number>]
```

Options

Table 11. nvcheckdrive

Option	Description
-servername	Specifies the name of the NetVault Backup Server that administers the job. This option is required when a remote server administers the job. It can be omitted when a local server administers the job. The server name is case-sensitive.
-libraryname	Specifies the name of the target library.
-drivename	Specifies the name of the target drive that you want to check.
-drivenumber	Specifies the drive number of the target drive that you want to check.

Notes

- The option -drivename or -drivenumber must be used with -libraryname to specify the target drive.

Examples

- Check the status of standalone drive "D-1" that is locally attached to the server:

```
nvcheckdrive -drivename D-1
```
- Check the status of "Drive2" in library "NVLibrary" that is locally attached to the client "NVCLIENT1":

```
nvcheckdrive -servername NVCLIENT1 -libraryname NVLibrary -drivename Drive2
```
- Check the status of drive 2 in library "NVLib2" that is locally attached to the remote server "NVSERVER2":

```
nvcheckdrive -servername NVSERVER2 -libraryname NVLib2 -drivenumber 2
```

nvcleandrive

Description

Cleans a library drive. If the number of cleaning lives has been set for the cleaning tape, it is reduced by one when used for this process.

Syntax

```
nvcleandrive -libraryname <Library Name> -librarydrivenumber <Drive Number>
```

Options

Table 12. `nvcleandrive`

Option	Description
-libraryname	Specifies the name of the target library.
-drivenumber	Specifies the drive number of the target drive that you want to clean.

Examples

- Clean drive 1 of the library "SONY LIB-162" using predefined cleaning media:
`nvcleandrive -libraryname "SONY LIB-162" librarydrivenumber 1`

`nvclosedoor`

Description

Closes the door of the specified library.

Syntax

```
nvclosedoor [-servername <Server Name>] -libraryname <Library Name>
```

Options

Table 13. `nvclosedoor`

Option	Description
-servername	Specifies the name of the NetVault Backup Server that administers the job. This option is required when a remote server administers the job. It can be omitted when a local server administers the job. The server name is case-sensitive.
-libraryname	Specifies the name of the target library.

`nvcloseeepport`

Description

Closes the entry/exit port (EEPort) of the specified library.

Syntax

```
nvcloseeepport [-servername <Server Name>] -libraryname <Library Name>  
                [-mediatype <Media Type>]
```

Options

Table 14. `nvcloseeepport`

Option	Description
-servername	Specifies the name of the NetVault Backup Server that administers the job. This option is required when a remote server administers the job. It can be omitted when a local server administers the job. The server name is case-sensitive.
-libraryname	Specifies the name of the target library.
-mediatype	Specifies the type of media in the entry/exit slot.

`nvcloseeepportcleaning`

Description

Closes EE Port of the specified library for importing a cleaning tape.

Syntax

```
nvcloseeepportcleaning [-servername <Server Name>] -libraryname <Library Name>
                        [-mediatype <Media Type>]
```

Options

Table 15. `nvcloseeepportcleaning`

Option	Description
-servername	Specifies the name of the NetVault Backup Server that administers the job. This option is required when a remote server administers the job. It can be omitted when a local server administers the job. The server name is case-sensitive.
-libraryname	Specifies the name of the target library.
-mediatype	Specifies the type of media in the entry/exit slot.

`nvdav`

Description

Performs the following WebDAV-related functions for a NetVault SmartDisk instance:

- Configures WebDAV authentication details.
- Removes WebDAV authentication details.
- Retrieves the user name configured for WebDAV authentication.

Syntax

```
nvdav --server <IP address|hostname> [--set|--remove|--user]
```

Options

Table 16. `nvdav`

Option	Description
<code>--server</code>	Specifies the IP address or resolvable host name of a NetVault SmartDisk instance.
<code>--set</code>	Sets WebDAV credentials for the specified NetVault SmartDisk instance. This option replaces the existing values. The user name and password are requested interactively.
<code>--remove</code>	Removes any existing WebDAV credentials for the specified NetVault SmartDisk instance.
<code>--user</code>	Retrieves the user name configured for WebDAV authentication for the specified NetVault SmartDisk instance. If there are no WebDAV credentials configured for the specified instances, an error message is displayed.

`nvdellrda`

Description

Adds or removes a Dell DR Series system.

Syntax

```
nvdellrda --add --host <Host name or IP Address> [--force]
[--server <NetVault Backup Server Name>] --user <username> --password <password>
--lsu <Container name> [--blocksize <blocksize>]
[--stream-limit <stream limit count>]

--update --device <name> --user <name> --password <password>
[--blocksize <blocksize>] [--server <name>]
[--stream-limit <stream limit count>]

nvdellrda --remove --device <name> [--force] [--server <name>]
```

Options

Table 17. `nvdellrda`

Option	Description
<code>--add</code>	Adds a Dell DR Series system. Use the following options with <code>--add</code> . <ul style="list-style-type: none"><code>--host</code>: Specifies the DNS name or IP address of the Dell DR Series system. The device is not added if the NetVault Backup Server is unable to resolve the host name.<code>--force</code>: Adds a Dell DR Series system even if the device is already added to another NetVault Backup Server with the same name. This option can be useful if you have performed a disaster recovery to rebuild the NetVault Backup Server.<code>--server</code>: Specifies the name of the NetVault Backup Server to which you want to add the Dell DR Series system. This option is not required if you are running the command on the server.

Table 17. nvdelldrda

Option	Description
	<ul style="list-style-type: none"> • --user: Specifies the user account that can be used to log on to the device. On the Dell DR Series system, only one user account exists, and the user ID for that account is backup_user. You can only change the password for this account; you cannot create an account or delete the existing account. • --password: Specifies the password for the user account. • --lsu: Specifies the name of the storage container. Ensure that the container is created before you add the device. The device is not added if the specified container does not exist on the device. Each Dell DR Series system added to NetVault Backup represents a storage container. • --blocksize: Specifies the block size for data transfers. The block size is specified in number of bytes. The default value for this option is 512KiB. • --stream-limit: The default value for this option is 32 streams. This setting applies to all NetVault Backup Servers to which the container is added. If the number of data streams exceeds the defined limit for the container, the Media Manager reports an error ("Device has too many streams"). You can set the soft stream limit to any value between 1 and 100. If the container is added to more than one NetVault Backup Server, set the same soft stream limit on all servers.
--update	<p>Modifies the settings for an existing Dell DR Series system. Use the following options with --update.</p> <ul style="list-style-type: none"> • --device: Specifies the device name. • --user: Specifies the user account that can be used to log on to the device. On the Dell DR Series system, only one user account exists, and the user ID for that account is backup_user. You can only change the password for this account; you cannot create an account or delete the existing account. • --password: Specifies the password for the user account. • --blocksize: Specifies the block size for data transfers. The block size is specified in number of bytes. The default value for this option is 512KiB. • --server: Specifies the name of the NetVault Backup Server to which you want to add the Dell DR Series system. This option is not required if you are running the command on the server. • --stream-limit: The default value for this option is 32 streams. This setting applies to all NetVault Backup Servers to which the container is added. If the number of data streams exceeds the defined limit for the container, the Media Manager reports an error ("Device has too many streams"). You can set the soft stream limit to any value between 1 and 100. If the container is added to more than one NetVault Backup Server, set the same soft stream limit on all servers.
--remove	<p>Removes a Data Domain system. Use the following options with --remove.</p> <ul style="list-style-type: none"> • --device: Specifies the name of the Dell DR Series system as it appears in the NetVault WebUI, CLI, and reports. • --force: Removes a Dell DR Series system even if the device cannot be contacted or some other errors block the removal.

nvddbboost

Description

Adds or removes an EMC Data Domain System.

Syntax

```
nvddbboost --add --host <Host name or IP Address> [--force] [--user <username>]
[--password <password>] [--lsu <LSU name>] [--blocksize <Block size>]
[--server <Server Name>]
```

```
nvddbboost --remove --device <name> [--force] [--server <name>]
```

Options

Table 18. nvddbboost

Option	Description
--add	<p>Adds a Data Domain system. Use the following options with -add.</p> <ul style="list-style-type: none">• --host: Specifies the DNS name or IP address of the Data Domain system. The device is not added if the NetVault Server is unable to resolve the host name.• --force: Adds a Dell DR Series system even if the device is already added to another NetVault Backup Server with the same name. This option can be useful if you have performed a disaster recovery to rebuild the NetVault Backup Server.• --user: Specifies the DD Boost user account that can be used to log on to the device for backups and restores. Ensure that the user account is created on the Data Domain system before the device is added to the server.• --password: Specifies the password for the user account.• --lsu: Specifies the name of the Logical Storage Unit (LSU) for the Data Domain system. If the specified LSU does not exist on the Data Domain system, NetVault Backup automatically creates it when you add the device to the server. You can configure multiple LSUs on a single Data Domain system. Each Data Domains system added to NetVault Backup represents an LSU. The default value for this option is "NVBU."• --blocksize: Specifies the block size for data transfers. The block size in specified in number of bytes. The default value for this option is 131,072 bytes.• --server: Specifies the name of the NetVault Backup Server to which you want to add the Data Domain system. This option is not required if you are running the command on the server.
--remove	<p>Removes a Data Domain system. Use the following options with -remove.</p> <ul style="list-style-type: none">• --device: Specifies the name of the Data Domain system as it appears in the NetVault WebUI, CLI, and reports.• --force: Removes a Data Domain system even if the device cannot be contacted or some other errors block the removal.

Notes

- When you add a Data Domain system, NetVault Backup creates several metadata files on the device. Each NetVault Backup Server (to which you add the Data Domain system) creates its own set of metadata files. NetVault Backup also writes the data transfer statistics to the stats.stnz file. The nvstatsmgr process uses this file and requires that it is regularly updated. However, frequent updates can have a significant performance impact on the system. By default, NetVault Backup updates the file after every 5 seconds or 10 blocks of data transfer. To change the default setting, see the *Dell NetVault Backup Administrator's Guide*.

nvdevice

Description

Performs the following tasks:

- Checks drives
- Cleans drives
- Ejects media
- Brings a drive online
- Takes a drive offline

Syntax

```
nvdevice [-status] [-library <Library Name>] -drive <Drive Number>]
```

```
nvdevice [-status] [-check] [-clean] [-eject] [-online] [-offline]  
          [-library <Library Name>] -drive <Drive Number>
```

```
nvdevice -version
```

Options

Table 19. nvdevice

Option	Description
-status	Shows the status of the specified drive. Use the -library and -drive options to specify the target drive. If you do not specify the library and drive, the command displays the status of all devices attached to the machine.
-check	Checks status of the specified drive. For example, it can be used to check the status of a drive that was taken offline for some reason. If successful, the specified drive is brought back online so that it is available to NetVault Backup for future jobs. Use the -library and -drive options to specify the target drive.
-clean	Sends request for cleaning the specified drive. If the number of cleaning lives has been set for the cleaning tape, it is reduced by one when used for this process. Use the -library and -drive options to specify the target drive.
-eject	Ejects a piece of media from the specified drive. Use the -library and -drive options to specify the target drive.
-online	Brings a drive back online. Use the -library and -drive options to specify the target drive.

Table 19. nvdevice

Option	Description
-offline	Takes a drive offline. Use the -library and -drive options to specify the target drive.
-library	Specifies the name of the target library.
-drive	Specifies the drive number of the target drive.
-version	Displays the version number of the CLI tools.

nvdeviceeject

Description

Ejects a piece of media from the specified drive.

Syntax

```
nvdeviceeject -devicename <Device Name> [-servername <Server Name>]  
[-librarydrivenumber <Drive Number>] [-wait]
```

Options

Table 20. nvdeviceeject

Option	Description
-devicename	Specifies the name of the target device or library.
-servername	Specifies the name of the NetVault Backup Server to which the device is added. When you run this command on the server, this option can be omitted. The server name is case-sensitive.
-librarydrivenumber	Drive number of the target drive in the library
-wait	Waits until the task has completed.

Notes

- The option -librarydrivenumber must be used with -devicename to specify the target drive.
- The device names can be ascertained by inspecting the logs for the backup job.

nvlibrarymodify

Description

Use this utility to perform the following tasks:

- Change the drive status to online or offline
- Remove a library
- Map or unmap drives

- List all library drives
- Add a drive or shared drive

Syntax

```
nvlibrarymodify [-servername <server_name>] -libraryname <library_name>
                [-online "DRIVE <drive_number>"] [-offline "DRIVE <drive_number>"]
                [-remove "DRIVE <drive_number>" ]
[-map "DRIVE <drive_number> <lsm>,<panel>,<drive>" [-name "<Drive_Name>"] ]
                [-unmap "DRIVE <drive_number>" ] [-list]
```

```
nvlibrarymodify -servername <server_name> -libraryname <library_name>
                -librarymachine <library_machine> -drivemachine <drive_machine>
                -drivepath <drive_path> -add "DRIVE <drive_number>"
                -addshared "DRIVE <drive_number>"
```

Options

To change the drive status, map or unmap drives, display library drives, and remove a library, use the following options.

Table 21. nvlibrarymodify – 1

Option	Description
-servername	Specifies the name of the NetVault Backup Server that administers the job. This option is required when a remote server administers the job. It can be omitted when a local server administers the job. The server name is case-sensitive.
-libraryname	Specifies the name library that you want to modify. The library name is mandatory.
-online	Brings a drive back online. Use the "DRIVE <drive_number>" option to specify the target drive.
-offline	Takes a drive offline. Use the "DRIVE <drive_number>" option to specify the target drive.
-remove	Removes a drive. Use the "DRIVE <drive_number>" option to specify the target drive.
-map	Maps a drive to the appropriate LSM, Panel and Drive. Use the "DRIVE <drive_number>" option to specify the target drive. You can also use the optional -name option can be used to specify a drive name. Example -name "ACSLs_Drive-1"
-unmap	Unmaps a drive. Use the "DRIVE <drive_number>" option to specify the target drive.
-list	Displays all drives in the specified library.

To add a drive or shared drive to an existing library configuration, use the following options.

Table 22. nvlibrarymodify – 2

Option	Description
-servername	Specifies the name of the target server.
-libraryname	Specifies the name library that you want to modify.
-librarymachine	Specifies the name of the NetVault Backup Server or Client on which the library resides. It can be any NetVault Backup machine, not necessarily the server. It can also be a NetVault Backup Client with ACSLS drives attached to a third machine.

Table 22. nvlibrarymodify – 2

Option	Description
-drivemachine	Specifies the name of the NetVault Backup Server or Client on which the drive resides. In an ACSLS environment, the drives can reside on a client; the NetVault Backup Server or Client does not control the ACSLS library.
-drivepath	Specifies the name or path of the drive that you want to add. Depending on the drive type, the drive path can be a VTL directory or SCSI target. You can use the <code>nvscandrives</code> utility to obtain a list of available drives on a local or remote NetVault Backup Client. The output of this command provides the drive path as it appears in the NetVault WebUI. For more information, see nvscandrives .
-add	Adds a drive. Use the "DRIVE <drive_number>" option to specify the target drive.
-addshared	Adds a shared drive. Use the "DRIVE <drive_number>" option to specify the target drive

Notes

- When you add a drive using the `nvlibrarymodify` utility, the library configuration is changed as follows:
 - If one or more jobs are running, the drive is appended to the existing library configuration without affecting the running jobs.
 - If no jobs are running, the existing library configuration is removed and the library is re-added.
- This utility cannot be used to modify an existing drive in a library. It can only be used to modify an existing library configuration by adding a drive to it.

Examples

- Add a drive to a VTL named "NewLibrary" located in the directory "/home/qauser1/" on a Linux-based NetVault BackupServer "tstserver":

```
nvlibrarymodify -servername tstserver -libraryname "/home/qauser1/NewLibrary"
-librarymachine tstserver -drivemachine tstserver
-drivepath "/home/qauser1/NewLibrary/drives/2" -add "DRIVE 2"
```

- Add a drive to a SCSI library "winserver: 2-0.4.0 (SONY LIB-304)" that is connected to a Window-based NetVault Backup Server "winserver":

```
nvlibrarymodify -servername winserver -libraryname "2-0.4.0 (SONY LIB-304)"
-librarymachine winserver -drivemachine winserver
-drivepath "2-0.2.0 (SONY SDX-500C)" -add "DRIVE 2"
```

- Add a drive to an NDMP filer-attached device. The device name is "Device f880:mc9(OVERLAND LXB)" and the NetVault Backup Server name is "tstserver":

```
nvlibrarymodify -servername tstserver
-libraryname "Device f880:mc9(OVERLAND LXB)" -librarymachine tstserver
-drivemachine tstserver -drivepath "Tape f880:nrst17a(HP Ultrium 3-SCSI)"
-add "DRIVE 2"
```

- Add a SCSI drive to a Windows-based NetVault Backup Client named "winclient." The ACSLS library is attached to a Linux-based NetVault Backup Server "tstserver":

```
nvlibrarymodify -servername tstserver
-libraryname "ACS0(StorageTek ACSLS/LibStation)"
-librarymachine tstserver -drivemachine winclient
-drivepath "2-0.2.0 (SONY SDX-500C)" -add "DRIVE 2"
```

- Add a SCSI drive to a Windows-based NetVault Backup Client named “winclient.” The ACSLS library is attached to a Windows-based NetVault Backup Client “client2” and controlled by NetVault Backup Server “tstserver”:

```
nvlibrarymodify -servername tstserver
-libraryname "ACS0(StorageTek ACSLS/LibStation)"
-librarymachine client2 -drivemachine winclient
-drivepath "2-0.2.0 (SONY SDX-500C)" -add "DRIVE 2"
```

nvopendoor

Description

Opens the door of the specified library.

Syntax

```
nvopendoor [-servername <server name>] -libraryname <library name>
```

Options

Table 23. nvopendoor

Option	Description
-servername	Specifies the name of the NetVault Backup Server that administers the job. This option is required when a remote server administers the job. It can be omitted when a local server administers the job. The server name is case-sensitive.
-libraryname	Specifies the name of the target library.

nvopeneport

Description

Opens the entry/exit port (EETPort).

Syntax

```
nvopeneport [-servername <server name>] -libraryname <library name>
```

Options

Table 24. nvopeneport

Option	Description
-servername	Specifies the name of the NetVault Backup Server that administers the job. This option is required when a remote server administers the job. It can be omitted when a local server administers the job. The server name is case-sensitive.
-libraryname	Specifies the name of the target library.

nvremovefiler

Description

Removes filer-attached drives for the specified filer.

Syntax

```
nvremovefiler [-servername <server name >] -filename <filer name> [-wait]
```

Options

Table 25. nvremovefiler

Option	Description
-servername	Specifies the name of the NetVault Backup Server that administers the job. This option is required when a remote server administers the job. It can be omitted when a local server administers the job. The server name is case-sensitive.
-filename	Specifies the name of the target filer.
-wait	Waits until the task has completed.

Notes

- This command removes only those drives that are idle or offline. After removing a drive, the message "Device removed DRIVE <#>:<Drive Name>" displayed on the screen and the View Logs page on WebUI.
- Only one attempt is made to remove a filer-attached drive. If the target drive is busy, the message "Failed to delete busy device DRIVE <#>:<Drive Name>" is displayed on the screen and the utility moves on to the next drive.
- If all drives in a library are removed, the node representing the library arm is also removed.

nvresetdrivestats

Description

Resets the statistics for a drive.

Syntax

```
nvresetdrivestats -servername <server name> [-libraryname <library name>]  
[-drivename <drivename>] [-drivenumber <drivenumber>] -action <action>
```


Options

Table 26. `nvresetdrivestats`

Option	Description
<code>-servername</code>	Specifies the name of the NetVault Backup Server that administers the job. This option is required when a remote server administers the job. It can be omitted when a local server administers the job. The server name is case-sensitive.
<code>-libraryname</code>	Specifies the name of the target library.
<code>-drivename</code>	Specifies the name of the target drive.
<code>-drivenumber</code>	Specifies the drive number of the target drive.
<code>-action</code>	Specifies the action that you want to perform. It can be: <ul style="list-style-type: none">• <code>drive</code>: Resets only drive statistics.• <code>clean</code>: Resets only drive cleaning statistics.• <code>all</code>: Resets all statistics for the specified drive.

Notes

- The option `-drivename` or `-drivenumber` must be used with `-libraryname` to specify the target drive.

Examples

- Reset statistics for a standalone drive "TstDrive1" that is locally attached to the NetVault Backup Server:

```
nvresetdrivestats -drivename TstDrive1 -action drive
```

- Reset the cleaning statistics for "Drive 1" in library "NVLibrary" that is locally attached to the NetVault Backup Client "NVCLIENT1":

```
nvresetdrivestats -servername NVCLIENT1 -libraryname NVLibrary  
-drivename "Drive 1" -action clean
```

- Reset all statistics for "Drive 2" in library "NVLib2" that is attached to the remote NetVault Backup Server "NVSERVER2":

```
nvresetdrivestats -servername NVSERVER2 -libraryname NVLib2 -drivenumber 2  
-action all
```

nvscandrives

Description

Displays drives that are available on a local or remote NetVault Backup Server or Client. The output does not include drives that are added as shared devices.

The output of this command provides the drive path as it appears on the WebUI. It can be used to add a drive to an existing library configuration using the `nvlibrarymodify` utility. For more information about this utility, see [nvlibrarymodify](#).

Syntax

```
nvscandrives [-servername <server name>] [-clientname <client name>]  
[-filename <filer name>]
```

Options

Table 27. nvscandives

Option	Description
-servername	Specifies the name of the NetVault Backup Server that administers the job. This option is required when a remote server administers the job. It can be omitted when a local server administers the job. The server name is case-sensitive.
-clientname	Use this option to view the drives attached to a NetVault Backup Client. If you do not provide the client name, the drives available on the server are displayed.
-filename	Use this option view the drives attached to an NDMP filer.

nvsetcleaninglives

Description

Sets the number of lives for a cleaning tape in the specified library.

Before running the `nvsetcleaninglives` command, verify that the slot that you want to use is configured as a Cleaning Slot and a cleaning tape is placed in the slot. For more information about setting a cleaning slot, see the *Dell NetVault Backup Administrator's Guide*.

Syntax

```
nvsetcleaninglives [-servername <server name>] -libraryname <library name>  
                  [-slotnumber <slot number>] [-lives <lives>]
```

Options

Table 28. nvsetcleaninglives

Option	Description
-servername	Specifies the name of the NetVault Backup Server that administers the job. This option is required when a remote server administers the job. It can be omitted when a local server administers the job. The server name is case-sensitive.
-libraryname	Specifies the name of the target library.
-slotnumber	Specifies the cleaning slot number in the library.
-lives	Specifies the number of lives for the cleaning tape.

Examples

- Set the number of lives to 7 for a piece of cleaning media residing in slot 6 of library "ADIC_Library_6"; the library is locally attached to "NVSERVER":

```
nvsetcleaninglives -server NVSERVER -libraryname ADIC_Library_6 -slotnumber 6  
-lives 7
```

nvsetdrivecleaning

Description

Sets cleaning cycle for the specified library.

Syntax

```
nvsetdrivecleaning -libraryname <library name> -librarydrivenumber <drive number>
-days <number of days> -dataxfersize <data transfer size> -hours <number of hours>
-rwerrors <number of read/write errors> [-displayonly [-selectionstate]]
```

Options

Table 29. nvsetdrivecleaning

Option	Description
-libraryname	Specifies the name of the target library.
-librarydrivenumber	Specifies the drive number of the drive for which the cleaning cycle has to be set.
-days	Specifies the maximum number of days the drive can be used before a clean cycle.
-dataxfersize	Specifies the maximum amount of data that be transferred before a clean cycle.
-hours	Specifies the maximum number of hours that the drive can be used until a clean cycle.
-rwerrors	Specifies the maximum number of read/write errors that can occur before a clean cycle.
-displayonly	<p>Displays the current settings for the specified drive.</p> <p>Without the -selectionstate option, the -displayonly option does not show if the settings are being used.</p> <p>Example:</p> <pre>nvsetdrivecleaning -libraryname "LIB1" -librarydrivenumber 2 -displayonly</pre> <p>Output:</p> <pre>Days = 22 Data Transferred (Gb) = 22 Hours of Use = 40 Soft Read/Write Errors (x100) = 1</pre>
-selectionstate	<p>Displays selection state of the options (that is, TRUE or FALSE depending on if the option is selected in the WebUI). This option must be used with -displayonly.</p> <p>Example:</p> <pre>nvsetdrivecleaning -libraryname "LIB1" -librarydrivenumber 2 -displayonly -selectionstate</pre> <p>Output:</p> <pre>TRUE Days = 22 FALSE Data Transferred (Gb) = 22 TRUE Hours of Use = 40 FALSE Soft Read/Write Errors (x100) = 1</pre>

Notes

- You can use "-1" to disable any option.

Examples

- Set Drive 1 of library "SONY LIB-162" to clean itself at the following intervals: 200GB of data transfer, 100 hours of drive usage, or more than 100,000 read/write errors:

```
nvsetdrivecleaning -libraryname "SONY LIB-162" -librarydrivenumber 1 -days -1  
-dataxfersize 200 -hours 100 -rerrors 100000
```

nvsmartdisk

Description

Performs the following functions:

- Adds a NetVault SmartDisk to the NetVault Backup Server.
- Removes a NetVault SmartDisk.
- Lists the machine names of NetVault SmartDisk instances added to the NetVault Backup Server.

Syntax

```
nvsmartdisk --add --host <Host name or IP Address> [--force] [--port <Port Number>]  
[--server <Server Name>]
```

```
nvsmartdisk --remove --device <name> [--force] [--server <name>]
```

```
nvsmartdisk --list
```

Options

Table 30. nvddbboost

Option	Description
--add	Adds a NetVault SmartDisk. Use the following options with -add. <ul style="list-style-type: none">• --host: Specifies the DNS name or IP address of the host on which the NetVault SmartDisk is installed. You must configure this option even if the device is deployed on the NetVault Backup Server. The device is not added if the NetVault Server is unable to resolve the host name.• --force: Adds a NetVault SmartDisk even if the device is already added to another NetVault Backup Server with the same name. This option can be useful if you have performed a disaster recovery to rebuild the NetVault Backup Server.• --port: Specifies the port for communicating with the NetVault SmartDisk instance. This option is only required if device is configured to use a non-default port.• --server: Specifies the name of the NetVault Backup Server to which you want to add the device. This option is not required if you are running the command on the server.

Table 30. nvddbboost

Option	Description
--remove	Removes a NetVault SmartDisk. Use the following options with --remove. <ul style="list-style-type: none"> --device: Specifies the name of the NetVault SmartDisk as it appears in the NetVault WebUI, CLI, and reports. --force: Removes a NetVault SmartDisk even if the device cannot be contacted or some other errors block the removal.
--list	Lists the machine names of all NetVault SmartDisk instances added to the NetVault Backup Server.

nvsvtlgrow

Description

Performs the following functions:

- Displays status and usage details of a specific SVTL or all SVTLs on the current system.
- Performs a test or dummy expansion of an SVTL by a given number of media items of a given size.
- Performs an actual expansion of an SVTL by a given number of media items of a given size.

This utility is located in the <NetVault Backup home>\bin directory.

Syntax

```
nvsvtlgrow display [-device <SVTL Device>]
```

```
nvsvtlgrow test -device <SVTL Device> -size <Media Size> -count <Media Count>
```

```
nvsvtlgrow grow -device <SVTL Device> -size <Media Size> -count <Media Count>
```

Options

Table 31. nvsvtlgrow

Option	Description
display	Displays all SVTLs on the machine. To display the status of a single SVTL on the machine, use the following command: <code>nvsvtlgrow display -device <svtl-device></code>
test	Performs a test expansion. Use the following options with test. <ul style="list-style-type: none"> -device: Specifies the name of the target SVTL. -size: Specifies the size of the media (for example, 800m for 800MB, 40g for 40GB, 2t for 2TB). -count: Specifies the number of media items that you want to add. The utility checks these values against the available space and reports whether it would be possible to create these media items. No changes are made to the SVTL.

Table 31. nvsvtlgrow

Option	Description
grow	<p>Expands the SVTL capacity. Use the following options with grow.</p> <ul style="list-style-type: none"> -device: Specifies the name of the target SVTL. -size: Specifies the size of the media (for example, 800m for 800MB, 40g for 40GB, 2t for 2TB). -count: Specifies the number of media items that you want to add. <p>The nvsvtlgrow utility checks the options and on confirmation from the user adds new media items to expand the SVTL size. Re-add the SVTL or restart the NetVault Backup Service to use the added media.</p>

Media-specific utilities

Important Notes

- To identify a piece of media in a CLI command, you can use its barcode, media label, or slot position within a library.
- If a media label contains spaces, enclose it within quotation marks ("").
- Various operating systems do not support special characters such as the following in a media label:

: ! @ # \$ % ^ & * () > < \ [] { } " "

Therefore, if a CLI command is issued to call out a piece of media whose label contains one of these characters, the command may fail with an error message. Media labels that include any of these characters can only be managed from the WebUI.

nvblankmedia

Description

Blanks a piece of media.

Syntax

```
nvblankmedia [-servername <Server Name>] [-libraryname <Library Name>]
              -barcode <Barcode> | -medialabel <Media Label> |
              -slotspec <Library Name::Slot Number> [-drivename <Standalone Drive Name>] [-wait]
```

Options

Table 32. nvblankmedia

Option	Description
-servername	<p>Specifies the name of the NetVault Backup Server that administers the job.</p> <p>This option is required when a remote server administers the job. It can be omitted when a local server administers the job. The server name is case-sensitive.</p>
-libraryname	Specifies the name of the library that contains the target media item.
-barcode	Specifies the barcode of the target media item.

Table 32. nvblankmedia

Option	Description
-medialabel	<p>Specifies the label of the target media item.</p> <p>Use this option only when searching by media label. If a media label contains spaces, enclose it within quotation marks ("").</p> <p>Example: "Full DB Backups"</p> <p>If the media label is not unique for media in all available devices, use this option with either -libraryname or -drivename.</p>
-slotspec	<p>Specifies the name of the library and slot number where the target media item resides. These two values must be separated using a double colon delimiter ("::"). Use this option only when searching by library slot.</p>
-drivename	<p>Specifies the name of the drive that contains the target media item.</p> <p>This option is ignored when the target media is already loaded in a drive; the media item is blanked even if you specify an incorrect drive.</p>
-wait	<p>Waits until the task has completed.</p>

Notes

- The blanking operation removes the NetVault Backup header from a tape and deletes the media label and removes any group association. After blanking, a tape becomes available to NetVault Backup for storing future backups.
- The blanking operation deletes or erases the backup data residing on a tape. To purposely destroy the data that is stored on a tape, you must blank it from NetVault Backup and have its data securely removed by tools that are designed for such purposes.
- The blanking operation removes the indexes for backups stored on the selected tapes from the NetVault Database.
- When an incorrect library and media pair is specified, the following error message is displayed:

```
Blank request failed! - 'Unable to identify media'
```

Examples

- Blank a piece of media in slot 21 of the library "NV_Library_Large" that is locally attached to a client "NVCLIENT1":

```
nvblankmedia -servername NVCLIENT1 -slotspec 21::"NV_Library_Large"
```
- Blank a piece of media labeled "DB-Backup" in library "Lib-2" that is connected a client named "NVCLIENT2":

```
nvblankmedia -libraryname "NVCLIENT2: Lib-2" -medialabel "DB-Backup"
```

nvbulkblankmedia

Description

Blanks one or more media items in the specified library.

Syntax

```
nvbulkblankmedia -libraryname <Library Name> -medialabel <Media Label>
[-allmedia] -password <Password> [-wait]
```

Options

Table 33. `nvbulkblankmedia`

Option	Description
-libraryname	Specifies the name of the library that contains the target media item.
-barcode	Specifies the barcode of the target media item.
-medialabel	Specifies the label of the target media item. This option supports the wildcard character "*" that can be used to represent a string of characters. If a media label contains the character "*", use the backslash character (\) to escape "*". For example, to blank media items with the label "media*star", use the -medialabel option as follows: <code>-medialabel "media*star"</code>
-allmedia	Blanks all media items in the specified library.
-password	Specifies the password for the NetVault Backup Server. If no password is set for the NetVault Backup Server, provide the system's root or administrator password.
-wait	Waits until the task has completed.

Notes

- The blanking operation removes the NetVault Backup header from a tape and deletes the media label and removes any group association. After blanking, a tape becomes available to NetVault Backup for storing future backups.
- The blanking operation deletes or erases the backup data residing on a tape. To purposely destroy the data that is stored on a tape, you must blank it from NetVault Backup and have its data securely removed by tools that are designed for such purposes.
- The blanking operation removes the indexes for backups stored on the selected tapes from the NetVault Database.
- This command does work on servers on which security is disabled.
- The library name and media labels are case-sensitive.

Examples

- Blank all media that reside in the library "ADICLib_1" and use the label "Full Backup Group 7":

```
nvbulkblankmedia -libraryname ADICLib_1 -medialabel "Full Backup Group 7"  
-password ServerPwd
```
- Blank all media reside in the library "ADICLib_1" and use labels that begin with "C2-Backups":

```
nvbulkblankmedia -libraryname ADICLib_1 -medialabel "C2-Backups*"  
-password ServerPwd
```


nvexportmedia

Description

Exports a piece of media from a tape library to its entry/exit port (EEPort).

Syntax

```
nvexportmedia -servername <Server Name> -barcode <Barcode> |  
-medialabel <Media Label> | -slotspec <Library Name::Slot Number> [-wait]
```

Options

Table 34. nvexportmedia

Option	Description
-servername	Specifies the name of the NetVault Backup Server that administers the job. This option is required when a remote server administers the job. It can be omitted when a local server administers the job. The server name is case-sensitive.
-barcode	Specifies the barcode of the target media item.
-medialabel	Specifies the label of the target media item. Use this option only when searching by media label. If a media label contains spaces, enclose it within quotation marks (" "). Example: "Full DB Backups"
-slotspec	Specifies the name of the library and slot number where the target media item resides. These two values must be separated using a double colon delimiter ("::"). Use this option only when searching by library slot.
-wait	Waits until the task has completed.

nvlabelmedia

Description

Use this utility to label new media items or re-label existing media items.

Syntax

```
nvlabelmedia [-servername <Server Name>] -barcode <Barcode> |  
-medialabel <Media Label> | -slotspec <Library Name::Slot Number>  
-newlabelname <New Media Label> [-newgroupname <New Media Group Name>]  
[-newoffsitelocation <New Offsite Location Name>] [-wait]
```

Options

Table 35. nvlabelmedia

Option	Description
-servername	Specifies the name of the NetVault Backup Server that administers the job. This option is required when a remote server administers the job. It can be omitted when a local server administers the job. The server name is case-sensitive.
-barcode	Specifies the barcode of the target media item.
-medialabel	Specifies the label of the target media item. Use this option only when searching by media label. If a media label contains spaces, enclose it within quotation marks (" "). Example: "Full DB Backups"
-slotspec	Specifies the name of the library and slot number where the target media item resides. These two values must be separated using a double colon delimiter ("::"). Use this option only when searching by library slot.
-newlabelname	Specifies the new label for the selected piece of media. If the new media label contains spaces, use underscores ("_") in their place. Example: "new_label_1"
-newgroupname	Specifies the new media group for the selected media piece of media. If the media group label contains spaces, use underscores ("_") in their place. Example: "new_group_1"
-newoffsitelocation	Specifies the new offsite location for the selected piece of media.
-wait	Waits until the task has completed.

Notes

- To re-label media items that contain existing backups, you first blank it using the nvblankmedia or mark it for reuse using the nvreusmedia command.
- The offsite location of the media can be changed without blanking the media or marking it for re-use. This property is set or changed using the -newoffsitelocation option.

nvlistblankmedia

Description

Displays slots containing blank media items on the specified library.

Syntax

```
nvlistblankmedia -servername <Server Name> -libraryname <Library Name>
```

Options

Table 36. nvlistblankmedia

Option	Description
-servername	Specifies the name of the NetVault Backup Server that administers the job. This option is required when a remote server administers the job. It can be omitted when a local server administers the job. The server name is case-sensitive.
-libraryname	Specifies the name of the target library.

nvlistmedia

Description

Lists media items marked with the following tags:

- Reuse
- Read only
- Unusable
- Bad
- Needs import
- Needs recovery
- Any media group tag

Syntax

```
nvlistmedia [-servername <Server Name>] -libraryname <Library Name>  
-readonly | -reusable | -unusable | -needsimport | -needsrecovery | -bad -group
```

Options

Table 37. nvlistmedia

Option	Description
-servername	Specifies the name of the NetVault Backup Server that administers the job. This option is required when a remote server administers the job. It can be omitted when a local server administers the job. The server name is case-sensitive.
-libraryname	Specifies the name of the target library.
-readonly	Lists read-only media items.
-reusable	Lists media items marked for reuse.
-unusable	Lists media items with the “unusable” tag.
-bad	Lists media items with the “bad” tag.
-needsimport	Lists media items that need to be imported.
-needsrecovery	Lists media items that need recovery.
-group	Lists media items that belong to any media group

nvloadmedia

Description

Use this command to load specific media items to a drive to read the media header or continue using the media from the CLI or from within a script. You can use `nvdeviceject` command to return the media item to a home slot.

Syntax

```
nvloadmedia [-servername <Server Name>] -barcode <Barcode> |  
-medialabel <Media Label> | -slotspec <Library Name::Slot Number> [-wait]
```

Options

Table 38. nvloadmedia

Option	Description
-servername	Specifies the name of the NetVault Backup Server that administers the job. This option is required when a remote server administers the job. It can be omitted when a local server administers the job. The server name is case-sensitive.
-barcode	Specifies the barcode of the target media item.
-medialabel	Specifies the label of the target media item. Use this option only when searching by media label. If a media label contains spaces, enclose it within quotation marks (" "). Example: "Full DB Backups"
-slotspec	Specifies the name of the library and slot number where the target media item resides. These two values must be separated using a double colon delimiter ("::"). Use this option only when searching by library slot.
-wait	Waits until the task has completed.

nvmakemedia

Description

Increases the capacity of a Virtual Tape Library (VTL) by creating additional media files.

A VTL contains the following directories and files:

Table 39. VTL directories and files

Windows	Linux and UNIX	Description
...\<vt>	.../<vtl>	VTL root directory.
...\<vtl>\drives	.../<vtl>/drives	Directory under the VTL root directory where the virtual drives are stored. NetVault Backup creates a subdirectory for each virtual drive in this directory.
...\<vtl>\media	.../<vtl>/media	Directory under the VTL root directory where the virtual media items are stored.

Table 39. VTL directories and files

Windows	Linux and UNIX	Description
...\<vtl>\slots	.../<vtl>/slots	Directory under the VTL root directory where the virtual slots are stored. NetVault Backup creates a subdirectory for each virtual slot in this directory.
...\<vtl>\.serial	.../<vtl>/serial	File residing in the VTL root directory. It contains a list of media barcodes and drive numbers. For example, "404HR-2", where "404HR" is the barcode and "2" is virtual drive number; 404HR-2", where "404HR" is the barcode and "2" is virtual drive 2.
...\<vtl>\drives\<x>\.serial	.../<vtl>/drives/<x>/serial	File residing in each drive subdirectory. It contains the individual media barcode and drive number.
...\<vtl>\slots\<x>\.serial	.../<vtl>/slots/<x>/serial	File residing in each slot subdirectory. It contains barcode for the individual media item. For example, "...404HR001", where "404HR" is the barcode and "001" is the virtual media item.
...\<vtl>\media\<mediafile>	.../<vtl>/media/<mediafile>	Actual virtual media. For example, ...vtl1\media\404HR001.

To add a media item, use the following steps:

- 1 Stop the NetVault Backup Service on the machine where the VTL is located.
- 2 In the slots directory, create a subdirectory which is one number larger than the existing largest numbered virtual slot directory.
- 3 Copy the ".media" file from one of the virtual slot directories to the virtual slot directory created in the previous step.
- 4 Modify the ".media" file in the newly created virtual slot directory from "1Y2NY00*" to "1Y2NY00X", where X represents the new virtual media number.
- 5 Use the `nvmakemedia` command to create the media file.
- 6 Restart the NetVault Backup Service.

Syntax

```
nvmakemedia <file-size> poplib <library>
```

```
nvmakemedia <file-size> mediafiles <filename>
```

Options

Table 40. nvmakemedia

Option	Description
<file-size> poplib <library>	<p>This form of the command verifies all media reference files within the specified <library>, and offers to create the file if the corresponding media data file does not exist. Enter "Y" or "y" to confirm media file creation.</p> <ul style="list-style-type: none">• <file-size>: File size can be an integer value followed by "k" for kilobytes, "m" for megabytes, "g" for gigabytes, or "t" for terabytes. For example, 102400k, 50m, 4g, 2t. The minimum file size allowed is 50m.• <library>: Full path to the target VTL name. <p>Example:</p> <pre>nvmakemedia 50M poplib c:\tst-vtl</pre>
<file-size> mediafiles <filename>	<p>This form of the command creates a media file of the specified size.</p> <ul style="list-style-type: none">• <file-size>: File size can be an integer value followed by "k" for KB, "m" for MB, "g" for GB, or "t" for TB (for example, 102400k, 50m, 4g, 2t). The minimum file size allowed is 50m.• <filename>: Full path to the new media file. The filename is used as the barcode for the media item. <p>Example:</p> <pre>nvmakemedia 50M mediafiles c:\tst-vtl\1Y2NY006</pre>

Notes

- To use this utility on Windows-based systems, you must be logged in with Administrator privileges.
This utility can only be used on systems that are not added to any domain or on systems that are added to the primary domain or a domain where there is a trust relationship with the primary domain.

nvmediadetails

Description

Displays details pertaining to media items and media groups.

Syntax

```
nvmediadetails [-label <Media Label>] [-group <Group Label>] [-all]  
                [-listlabels] [-listgroups] [-version]
```

Options

Table 41. nvmediadetails

Option	Description
-label	<p>Specifies the media a label for the target media item.</p> <p>You can specify a few initial characters to search for media items with matching labels.</p>
-group	<p>Specifies the media group label of the target media item.</p>
-all	<p>Displays details for all media items.</p>

Table 41. nvmediadetails

Option	Description
-listlabels	Displays details for all media items that are assigned a media label. The “-group” option can be used with this option to displays media details for a particular media group.
-listgroups	Lists available media groups.
-version	Displays the build date of the NetVault Backup distribution installed on the machine.

Examples

- Display details for a piece of media labeled “MyTape”:


```
nvmediadetails -label MyTape
```
- Display details of all media items belonging to the Media Group “MyGroup”:

```
nvmediadetails -group MyGroup -all
```

nvremovemedias

Description

Deletes all information about a piece of media from NetVault Database.

 **NOTE:** The target media item must be taken offline before issuing this command.

Syntax

```
nvremovemedias [-medialabel <Media Label>] [-displaymedialist] [-version]
```

Options

Table 42. nvremovemedias

Option	Description
-label	Specifies the media a label for the target media item.
-displaymedialist	Provides a list of media items that have a media label.
-version	Displays the build date of the NetVault Backup distribution installed on the machine.

nvreusemedias

Description

Marks a piece of media for reuse.

Syntax

```
nvreusemedias [-servername <Server Name>] -barcode <Barcode> |  
-medialabel <Media Label> | -slotspec <Library Name::Slot Number>
```

Options

Table 43. nvreusemedia

Option	Description
-servername	Specifies the name of the NetVault Backup Server that administers the job. This option is required when a remote server administers the job. It can be omitted when a local server administers the job. The server name is case-sensitive.
-barcode	Specifies the barcode of the target media item.
-medialabel	Specifies the label of the target media item. Use this option only when searching by media label. If a media label contains spaces, enclose it within quotation marks (" "). Example: "Full DB Backups"
-slotspec	Specifies the name of the library and slot number where the target media item resides. These two values must be separated using a double colon delimiter ("::"). Use this option only when searching by library slot.

Notes

- The indexes for backups stored on the target media item are removed from the NetVault Database when you use this command.
- This utility does not support the ACSLS/ ADIC DAS library systems.
- This utility does not support disk-based storage systems such as NetVault SmartDisk, Dell DR Series System, and Data Domain System.

nvscanmedia

Description

Scans media items.

You can use this utility to import a piece of media from other NetVault Backup devices, including media items residing in devices previously controlled by a different NetVault Backup Server. Before you run this command, the target media items are recognized as FOREIGN. Data cannot be restored from such media items until they are scanned. This utility writes backup indexes for backups stored on the target media item to the NetVault Database unless the index entry is already available in the database.

You cannot use this utility to scan disk-based storage systems such as NetVault SmartDisk, Dell DR Series System, and Data Domain System.

Syntax

```
nvscanmedia [-servername <Server Name>] -barcode <Barcode> |  
-medialabel <Media Label> | -slotspec <Library Name::Slot Number> [-wait]
```


Options

Table 44. nvscanmedia

Option	Description
-servername	Specifies the name of the NetVault Backup Server that administers the job. This option is required when a remote server administers the job. It can be omitted when a local server administers the job. The server name is case-sensitive.
-barcode	Specifies the barcode of the target media item.
-medialabel	Specifies the label of the target media item. Use this option only when searching by media label. If a media label contains spaces, enclose it within quotation marks (" "). Example: "Full DB Backups"
-slotspec	Specifies the name of the library and slot number where the target media item resides. These two values must be separated using a double colon delimiter ("::"). Use this option only when searching by library slot.
-wait	Waits until the task has completed.

nvsyncronizesilomedia

Description

Allocates all the known media in the specified ACSLS library.

Syntax

```
nvsyncronizesilomedia [-servername <Server Name>] -libraryname <Library Name>
```

Options

Table 45. nvsyncronizesilomedia

Option	Description
-servername	Specifies the name of the NetVault Backup Server that administers the job. This option is required when a remote server administers the job. It can be omitted when a local server administers the job. The server name is case-sensitive.
-libraryname	Specifies the name of the target library.

nvupdateserialnumber

Description

Updates the serial number of any drive in the specified library back to its original number.

Syntax

```
nvupdateserialnumber [-servername <Server Name>] -libraryname <Library Name>  
                    [-bayname <Bay Name>] [-checkonly]
```

Options

Table 46. nvupdateserialnumber

Option	Description
-servername	Specifies the name of the NetVault Backup Server that administers the job. This option is required when a remote server administers the job. It can be omitted when a local server administers the job. The server name is case-sensitive.
-libraryname	Specifies the name of the target library.
-bayname	Specifies the name of the drive bay in which the target drive is located.
-checkonly	Checks the media serial number.

Job-specific utilities

- IMPORTANT:** Several utilities described in this section reference a file named `nvsetmodify.cfg`. This configuration file includes a list of options used to define a backup job and the associated code number that can be used to identify the option in the CLI. You can find `nvsetmodify.cfg` in `<NetVault Backup home>\config` on Windows and `<NetVault Backup Home>/config` on Linux. When you use the file, verify that you do not modify the contents in any manner. You can take a printout of this file and use the print for reference purposes. This functionality is intended for highly experienced users. Any attempt to use the values provided in this configuration file must be performed under the guidance of Technical Support.

nvexpiresaveset

Description

Performs the following functions:

- Deletes the specified saveset. Optionally, deletes the duplicates of the specified saveset. The savesets are deleted immediately.
- Marks multiple savesets for deletion. Optionally, includes the duplicates of the specified savesets. The marked savesets are deleted when the Media Manager performs the next "retirement check."

Syntax

```
nvexpiresaveset [-duplicates] -savesetid <Saveset ID>
```

```
nvexpiresaveset [-duplicates] [-success] -markforexpiry -infile <input file>  
-outfile <output file>
```

```
nvexpiresaveset [-version]
```

Options

To delete a specific saveset and its duplicates, use the following options.

Table 47. `nvexpiresaveset` — 1

Option	Description
<code>-savesetid</code>	Specifies the ID of the saveset that you want to delete. Only a single saveset ID is supported this form of the command.
<code>-duplicates</code>	Deletes duplicates of the specified saveset.

To mark multiple savesets and their duplicates for deletion, use the following options.

Table 48. `nvexpiresaveset` — 2

Option	Description
<code>-markforexpiry</code>	Marks savesets specified in the input file (infile) for deletion. The savesets are expired when the Media Manager performs the next “retirement check.” By default, these checks are performed at the interval of 60 minutes. To change the interval between two checks, configure the Retirement Check Granularity in Mins setting in the <code>mediamgr.cfg</code> file. For more information about this setting, see <i>Dell NetVault Backup Administrator's Guide</i> .
<code>-duplicates</code>	Marks duplicates of the specified savesets for deletion.
<code>-success</code>	Includes successful saveset IDs in the output file. Without this option, the utility includes failed saveset IDs in the output file.
<code>-infile</code>	Specifies the name of the input file. The input file contains saveset IDs that you want to mark for deletion. You can use any text editor to create this file. Specify one saveset ID per line. Provide the complete path if the input file is not located in the directory from which you run the utility.
<code>-outfile</code>	Specifies the name of the output file. By default, the file is created in the directory from which you run the utility. Provide the complete path if you want to save the file in a different location.

To view the version of NetVault Backup distribution, use the following option.

- `-version`: Displays the build date of the NetVault Backup distribution installed on the machine.

Examples

- Delete saveset ID 120:

```
nvexpiresaveset -savesetid 120
```
- Delete saveset ID 150 and its duplicates:

```
nvexpiresaveset -duplicates -savesetid 150
```
- Mark savesets included in input file “C:\deletelist.txt” for deletion. Send the default output to “C:\failedlist.txt”:

```
nvexpiresaveset -markforexpiry -infile "c:\deletelist.txt" -outfile "c:\failedlist.txt"
```
- Mark savesets included in the input file “deletelist.txt” and their duplicates for deletion. Send the list of successful savesets to the output file “marked.txt”:

```
nvexpiresaveset -duplicates -success -markforexpiry -infile deletelist.txt -outfile marked.txt
```

nvjobabort

Description

Aborts an active job.

Syntax

```
nvjobabort [-servername <NetVault Backup Server Name>] -jobid <Job ID>
           [-instanceid <Instance ID>]
```

Options

Table 49. nvjobabort

Option	Description
-servername	Specifies the name of the NetVault Backup Server that administers the job. This option is required when a remote server administers the job. It can be omitted when a local server administers the job. The server name is case-sensitive.
-jobid	Specifies the ID of the job that you want abort.
-instanceid	Specifies the ID of the instance that you want to abort. The default value for this option is 1.

nvjobcreate

Description

Create and schedules a backup or restore job. You can also use this utility to save a job definition without scheduling it.

The **nvjobcreate** utility does not provide any option to configure the Restore Options. These options must be included in the Restore Selection Set. The **nvsetcreate** utility provides an option that can be used to specify Restore Options in the Restore Selection Set. For more information, see [nvsetcreate](#).

Syntax

```
nvjobcreate [-servername <NetVault Backup Server Name>] -jobtitle <Job Title> -type
           <Job Type> [-selectionsetname <Backup or Restore Selection Set Name>]
           [-selectionoptionssetname <Backup Options Set Name>]
           [-schedulesetname <Schedule Set Name>] [-backupoption <Backup Option>=<value>]
           [-targetsetname <Target Set Name>] [-advoptsetname <Advanced Options Set Name>]
           [-jobidfile <Output Filename>] -submit -parameters <Parameter Filename> [-version]
```

Options

Table 50. nvjobcreate

Option	Description
-servername	<p>Specifies the name of the NetVault Backup Server that administers the job.</p> <p>This option is required when a remote server administers the job. It can be omitted when a local server administers the job. The server name is case-sensitive.</p>
-jobtitle	<p>Specifies the Job Title.</p>
-type	<p>Specifies the job type: backup or restore. The default value for this option is "backup."</p>
-selectionsetname	<p>Specifies the name of the Backup or Restore Selection Set. You can use the NetVault WebUI or the nvsetcreate utility to create this set.</p>
-selectionoptionsset name	<p>Specifies the name of the Backup Options Set. This option must be specified when creating a backup job.</p> <p>If you do not specify this option while creating a backup job, the job is created successfully. However, when you try to run the job from the CLI or WebUI, it reports an error and fails. When you try to view the job definition from the WebUI, the Manage Job Definitions — View Job page does not show any details.</p>
-schedulesetname	<p>Specifies the name of the Schedule Set. The job is scheduled to run immediately if you omit this option. You can use the NetVault WebUI or the nvsetcreate utility to create this set.</p>
-backupoption	<p>Specifies Backup Options for a job.</p> <p>To use this option, you require the "Tag ID" of the option that you want to set. The Tag ID can either be the backup option name as recognized by the CLI or a numeric value assigned to the option by NetVault Backup. Both of these values are grouped under the [Plugin Options] section in the nvsetmodify.cfg file.</p> <p>The format for specifying this option is:</p> <pre>-backupoption <Tag ID>=<value></pre> <p>Example:</p> <pre>-backupoption <Tag ID>=True/False</pre>
-targetsetname	<p>Specifies the name of the Target Set. You can use the NetVault WebUI or the nvsetcreate utility to create this set. If you do not specify a Target Set, the default target options displayed on the NetVault WebUI are used.</p>
-advoptsssetname	<p>Specifies the name of the Backup or Restore Advanced Options Set. You can use the NetVault WebUI or the nvsetcreate utility to create this set. If you do not specify an Advanced Options Set, the default target options displayed on the NetVault WebUI are used.</p>
-jobidfile	<p>Specifies the name of the output file that stores the Job ID.</p> <p>This option is useful if the nvjobcreate utility is configured to return the exit status instead of Job ID. For more information about the configuration option, see the <i>Dell NetVault Backup Administrator's Guide</i>.</p> <p>You can provide an absolute or a relative path for the file. The file stores the Job ID as a string. You can use a script to read this string. This file must be deleted manually after use.</p>
-submit	<p>Schedules a job and lists it as an active job.</p> <p>If you omit this option, the job definition is only saved and not scheduled to run. You can schedule it later using the nvjobmodify utility.</p>

Table 50. nvjobcreate

Option	Description
-parameters	<p>Reads options from a parameter file.</p> <p>You can use any text editor to create the parameter file. Specify one option with its value per line and omit "-" before the option. Use spaces or tabs to separate the option and values. To include comments, begin the line with a "#" character.</p> <p>Example:</p> <pre># nvjobcreate example file jobtitle cli job 1 selectionsetname cliselset</pre> <p>This file can be used with the -parameters option as follows:</p> <pre>./nvjobcreate -parameters example.txt</pre>
-version	Displays the build date of the NetVault Backup distribution installed on the machine.

Notes

- After using the nvjobcreate command to create one or more jobs, if you run the following nvreport command, the Scheduler may crash:

```
nvreport -class "Defined Jobs" -format "%SelectionOptions"
```

Workaround: From the NetVault WebUI, open the jobs for editing and save them without any changes.

Examples

- Create an Incremental Backup job using the Backup Selection Set "NVCLIENT 1 Full Data Backup" and Schedule Set "Repeating 1." The Job Title is "Incremental Backup of NVCLIENT1" and the job is administered by a local NetVault Backup Server:

```
nvjobcreate -jobtitle "Incremental Backup of NVCLIENT1" -type backup
-selectionsetname "NVCLIENT 1 Full Data Backup"
-backupoption ntfsopt_typeincr=true -schedulesetname "Repeating 1" -submit
```

- Create a restore job using the Restore Selection Set "RestoreFull" and submit the job to run immediately. The Job Title is "Restore of Full Backup" and the backup job was administered by a remote NetVault Backup Server "NVSERVER2."

```
nvjobcreate -jobtitle "Restore of Full Backup" -servername NVSERVER2
-type restore-selectionsetname RestoreFull -submit
```

nvjobdelete

Description

Deletes jobs that match the specified criteria.

Syntax

```
nvjobdelete [-servername <NetVault Backup Server Name>]
            [-jobid <Job ID>] [-type <Job Type>]
[-jobrange <Job ID-Job ID>] [-jobtitle <Job Title>] [-client <Client Name>]
[-plugin <Plug-in Name>] [-selectionsetname <Selection Set Name>]
[-schedulesetname <Schedule Set Name>] [-targetsetname <Target Set Name>]
[-advoptssetname <Advanced Options Set Name>] [-force] [-scheduleonly] [-version]
```

Options

Table 51. nvjobdelete

Option	Description
-servername	Specifies the name of the target NetVault Backup Server.
-jobid	Specifies the ID of the job that you want to delete. Only one Job ID can be specified with this option.
-type	Specifies the type of job that you want to delete: backup or restore. Use this option if you want to delete a specific job type. Omit this option if you want to delete all job types.
-jobrange	Specifies a range of Job IDs corresponding to a series of jobs that you want to delete. Use a hyphen to separate the start and end Job IDs. Example <code>-jobrange 30-45</code>
-jobtitle	Specifies the title of the jobs that you want to delete. Use this option to delete all jobs with a matching title. The title must be enclosed in quotation marks. Example <code>-jobtitle "Full_Backup_1"</code>
-client	Specifies the name of the NetVault Backup Client that served as target for the jobs. It deletes all jobs performed for the specified client. Example <code>-client "NV_Client_MKTG"</code>
-plugin	Specifies the name of the plug-in used to perform the jobs. The plug-in name must be enclosed in quotation marks. Example <code>-plugin "File System"</code>
-selectionsetname	Specifies the name of the Backup or Restore Selection Set that was used to create the jobs.
-schedulesetname	Specifies the name of the Schedule Set that was used to create the jobs.
-targetsetname	Specifies the name of the Target Set that was used to create the jobs.
-advoptsetname	Specifies the name of the Advanced Options Set that was used to create the jobs.
-force	Deletes matching jobs that are scheduled to run. If a job that meets the criteria set by other option is in queue (scheduled to run later), any attempt to delete it fails. Use the "-force" option to delete such jobs.
-scheduleonly	Remove jobs from the job queue without deleting them from the NetVault Database. Use this option in lieu of -force.
-version	Displays the build date of the NetVault Backup distribution installed on the machine.

Notes

- This note applies to the use of the following options with nvjobdelete command:
 - -jobtitle
 - -client
 - -plugin
 - -selectionsetname
 - -schedulesetname

- -targetsetname
- -advoptsetname

When any of these options are used alone in the syntax, all instances of a job that meet the set parameters are deleted. For example, the following command deletes all jobs for the Plug-in for FileSystem:

```
nvjobdelete -plugin "File System"
```

To delete specific jobs, use a combination of options. For example, if you specify the -jobrange option with the -plugin option, only jobs that fall into the specified Job ID range specified are deleted.

Examples

- Delete jobs with the following Job IDs: 1, 5, range 7-12, range 15-19:

```
nvjobdelete -jobid 1 -jobid 5 -jobrange 7-12 -jobrange 15-19
```

- Delete all restore jobs with the Job Title "No Title":

```
nvjobdelete -type restore -jobtitle "No Title"
```

- Delete all jobs for client "Client-A" that use Schedule Set "FirstTuesday":

```
nvjobdelete -client Client-A -schedulesetname FirstTuesday -force
```

nvjobhold

Description

Places a job on hold. You can use the `nvjobresume` utility to resume the job later.

Syntax

```
nvjobhold [-servername <NetVault Backup Server Name>] -jobid <Job ID>
          [-phaseid <Phase ID>] [-version]
```

Options

Table 52. `nvjobhold`

Option	Description
-servername	Specifies the name of the NetVault Backup Server that administers the job. This option is required when a remote server administers the job. It can be omitted when a local server administers the job. The server name is case-sensitive.
-jobid	Specifies the ID of the job that you want to place on hold. Only one Job ID can be specified with this option.
-phaseid	Specifies the phase ID. Use this option to place a particular phase on hold. If you omit this option, all scheduled phases of the specified job are placed on hold.
-version	Displays the build date of the NetVault Backup distribution installed on the machine.

nvjoblist

Description

Displays all active jobs. The output is displayed in fixed column format.

Syntax

```
nvjoblist [-servername <NetVault Backup Server Name>] [-delimiter <Delimiter>]  
          [-title <Job Title>] [-noheader] [-runinfo] [-version]
```

Options

Table 53. nvjoblist

Option	Description
-servername	Specifies the name of the NetVault Backup Server that administers the job. This option is required when a remote server administers the job. It can be omitted when a local server administers the job. The server name is case-sensitive.
-delimiter	Specifies the character that you want to use as a delimiter. By default, a white-space character is used as a delimiter.
-title	Specifies the title of the job. Use this option to display all jobs with a matching title. The Job Title must be enclosed in quotation marks. Example -title "Full_Backup_1"
-noheader	Suppresses display of header row.
-runinfo	Includes run status and next run time in the output.
-version	Displays the version number of the CLI tools and the build date of the NetVault Backup distribution installed on the machine.

nvjobmodify

Description

Modifies a job definition.

Syntax

```
nvjobmodify -jobid <Job ID> -jobname <Job Title> -type <Job Type>  
            [-change <Change Description>] [-submit] [-parameters <Parameter File>]  
            [-assign <Assignment Character>] [-delimit <Delimiter Character>] [-version]
```

Options

Table 54. nvjobmodify

Option	Description
-jobid	<p>Specifies the ID of the job that you want to modify.</p> <p>Example</p> <pre>-jobid 56</pre> <p>This option is not required if you specify the -jobname option.</p>
-jobname	<p>Specifies the title of the job that you want to modify.</p> <p>The Job Title must be enclosed in quotation marks. If two or more jobs on the NetVault Backup Server have the same title, the command fails. In such cases, you must use the -jobid option.</p>
-type	<p>Specifies the type of job that you want to modify (backup or restore)</p>
-change	<p>Specifies the changes that you want to make to the job definition. You can specify any number of values with this option. You can omit this option if you want to submit a job without any changes.</p> <p>The <Change description> variable for the -change option is formatted as follows:</p> <pre><item>[:<field>]=<value></pre> <p><item> can take one of the following values: Title, Set, or Options. <field> calls out a specific field in the item that you want to modify. <value> is the new setting for the selected field.</p> <p>Change items:</p> <ul style="list-style-type: none">• Title: Changes the Job Title.• Set: Changes the set used to define a job. <value> specifies the new set name. <field> may take any of the following values: BS: Backup Selection Set BO: Backup Options Set S: Schedule Set BT: Backup Target Options Set AB: Backup Advanced Options Set RS: Restore Selection Set AR: Restore Advanced Options Set• Options: Modifies the backup options for a job. To use this option, you require the "Tag ID" of the option that you want to set. The Tag ID can either be the backup option name as recognized by the CLI or a numeric value assigned to the option by NetVault Backup. Both of these values are grouped under the [Plugin Options] section in the nvsetmodify.cfg file. The format for specifying this option is: Options:<Tag ID>=<value> Example: Options:<Tag ID>=True/False <p>NOTE: If you specify a trigger name that is used by any other job, an error message ("The Trigger Name is Already in Use. Redefine this Job if this was not Intended.") is displayed when you try to save or submit the job. The message is for information only and does not stop you from saving or submitting the job.</p>
-submit	<p>Schedules a job. This option may also be used on its own to schedule jobs that have been created but not scheduled.</p>

Table 54. nvjobmodify

Option	Description
-parameter	<p>Reads options from a parameter file.</p> <p>You can use any text editor to create the parameter file. Specify one option with its value per line and omit "-" before the option. Use spaces or tabs to separate the option and values. To include comments, begin the line with a "#" character.</p> <p>Example</p> <pre># nvjobmodify example file jobname Backup File System 10-15 type backup change Set:BS=selectionsetcli</pre> <p>This file can be used with the -parameter option as follows:</p> <pre>./nvjobmodify -parameter example.txt</pre>
-assign	<p>Specifies the assignment operator that you want to use in change descriptions. The default assignment operator is the "=" character. This option must be specified if the old or new values contain the "=" character.</p>
-delimit	<p>Specifies the character that you want to use as a delimiter in change descriptions. The default delimiter is the ":" character. This option must be specified if old or new values contain the ":" character.</p>
-version	<p>Displays the build date of the NetVault Backup distribution installed on the machine.</p>

Examples

- Modify the job "Backup File System 10-15" to perform Incremental Backup instead of Full Backup using the Plug-in for FileSystem:

```
nvjobmodify -jobname "Backup File System 10-15"
-change Options:ntfsopt_typeincr=true
```

nvjobresume

Description

Resumes a job that was previously placed on hold. Only one job can be resume with a single use of this command.

Syntax

```
nvjobresume [-servername <NetVault Backup Server Name>] -jobid <Job ID>
[-phaseid <Phaseid>] [-version]
```

Options

Table 55. nvjobresume

Option	Description
-servername	Specifies the name of the NetVault Backup Server that administers the job. This option is required when a remote server administers the job. It can be omitted when a local server administers the job. The server name is case-sensitive.
-jobid	Specifies the ID of the job that you want to resume. Only one Job ID can be specified with this option.
-phaseid	Specifies the phase ID. Use this option if you want to resume a particular job phase. If you omit this option, all known phases of the specified job are resumed.
-version	Displays the build date of the NetVault Backup distribution installed on the machine.

nvjobstart

Description

Runs a job using its Job ID, phase number, and instance number.

Syntax

```
nvjobstart [-servername <NetVault Backup Server Name>] -jobid <Job ID>  
           -phase <Phase ID> -instance <Instance ID> [-wait] [-version]
```

Options

Table 56. nvjobstart

Option	Description
-servername	Specifies the name of the NetVault Backup Server that administers the job. This option is required when a remote server administers the job. It can be omitted when a local server administers the job. The server name is case-sensitive.
-jobid	Specifies the ID of the job that you want to run.
-phaseid	Specifies the Phase ID. The default value for this option is 1.
-instance	Specifies the Instance ID. If this option is not specified or the specified instance does not exist, the last instance of the job is started.
-wait	Waits until the task has completed.
-version	Displays the build date of the NetVault Backup distribution installed on the machine.

Notes

- By default, the `nvjobstart` utility returns the following messages depending on the job exit codes.

Table 57. Default job exit codes and status messages

Exit code	Status message
0	Job completed successfully
1	Job failed with error: 'Job Failed' This message is returned for the following job completion states: <ul style="list-style-type: none">• Job failed• Job completed with warnings• Job aborted• Job stopped• Job died

If you enable the option `nvjobstart Enhanced Job Completion Status`, the utility returns the following codes and messages:

Table 58. Enhanced job exit codes and status messages

Exit code	Status message
0	Job completed successfully
1	Job Failed
2	Job Completed with Warnings
3	Job Aborted
4	Job Stopped
5	Job Died
-1	Job Failed with Undefined Error

For more information about this option, see the *Dell NetVault Backup Administrator's Guide*.

nvpolicy

Description

Performs the following tasks:

- Creates a policy definition
- Displays policy jobs
- Deletes a policy
- Checks whether a policy job exists or not
- Defines clients for a policy job
- Places a policy in quiesced state

Syntax

```
nvpolicy -list [<Policy Name>] -delete <Policy Name> -ack <Policy Name>
-addclient <Policy Name> <client name> [ <Client Name> ... ] -addgroup <Policy Name>
    <Group Name> [ <Group Name> ...] create <Policy Definition File>
    -state <Policy Name> -quiesce <Policy Name>
```

Options

Table 59. nvpolicy

Option	Description
-list	Displays existing policies. To view the list of jobs defined for a policy, use this option with the policy name. For example, the following command lists all jobs defined for policy "p1": nvpolicy -list p1
-delete	Deletes the specified policy.
-ack	Acknowledges errors.
-addclient	Adds clients to the policy definition. For example, the following command adds clients "Client-A" and "Client-B" to the policy "p1": nvpolicy -addclient p1 Client-A Client-B
-addgroup	Adds client groups to the policy definition. For example, the following command adds client groups "Group-A" and "Group-B" to the policy "p1": nvpolicy -addgroup p1 Group-A Group-B
-create	Creates a policy using details specified in the policy definition file. The file must be created in the following format: Example: [Policy] Title=policy3 EvtWarn=Event-Warn-1 EvtFail=Event-Fail-1 Clients=client-1,client-2,client-3,client-4 [Job] Title=MyJob Selection=MySelection Options=MyOption Target=MyTarget Source=MySource Schedule=MySchedule Advanced=MyAdvanced Active=TRUE

NOTE: The Source option is only required when defining a job for the NetVault Backup Plug-in for Consolidation and or NetVault Backup Plug-in for Data Copy.

A policy can contain one or more job definitions. For multiple jobs, include a [Job] section for each job as shown in the following example.

Table 59. nvpolicy

Option	Description
	Example: <pre> [Policy] Title=policy3 EvtWarn=Event-Warn-1 EvtFail=Event-Fail-1 Clients=client1,client2,client3,client4 [Job] Title=MyJob Selection=MySelection Options=MyOption Target=MyTarget Source=MySource Schedule=MySchedule Advanced=MyAdvanced Active=TRUE [Job] Title=MyJob-2 Selection=MySelection-2 Options=MyOption-2 Target=MyTarget-2 Schedule=MySchedule-2 Advanced=MyAdvanced-2 Active=TRUE </pre>
-state	Displays the current state of a policy — Dormant, Active, or Quiescing.
quiesce	Places an active policy in a quiesced state.

nvrestore

Description

Performs the following tasks:

- Displays restore jobs. You can filter the list by date, client, plug-in, or Backup Selection Set used for the job.
- Creates restore jobs. You can also use this utility to relocate or rename data during restore.

Syntax

```
nvrestore -list [-client <NetVault Backup Client Name>] [-plugin <Plug-in Name> |
- select <Selection Set Name>] [-startdate <DD/MM/YY>] [-enddate <DD/MM/YY>]
```

```
nvrestore -create <Saveset> -title <Job Title> -path <Path> [-relocate <Path>]
[-rename <Path>] [-run [-wait]]
```

```
nvrestore -create <Saveset> -definition <Restore Definition File> [-run [-wait]]
```

Options

To list the restore jobs administered by the NetVault Backup Server, use the following options.

Table 60. `nvrestore - 1`

Option	Description
-list	Displays all restore jobs administered by the NetVault Backup Server.
-client	Specifies the name of the target NetVault Backup Client. Use this option filter the list by the specified client.
-plugin	Specifies the plug-in name. Use this option to filter the list by the specified plug-in.
-select	Specifies the name of the Restore Selections Set. Use this option to filter the list by the specified set. NOTE: The <code>-plugin</code> and <code>-select</code> options are mutually exclusive and cannot be used together in the same instance of a <code>nvrestore -list</code> command.
-startdate	Specifies the start date. Use this option to display the jobs performed between the start date and end date. If the end date is not specified, all jobs starting from the start date up to the last job are listed. The valid format for the start date is DD/MM/YY.
-enddate	Specifies the end date. Use this option to display the jobs performed between the start date and end date. If the start date is not specified, all jobs starting from the first job up to the specified end data are listed. The valid format for the start date is DD/MM/YY.

To create a restore job, use the following options.

Table 61. `nvrestore - 2`

Option	Description
-create	Creates and optionally schedules a restore job. Specify the ID of the backup saveset that you want to restore. In addition to the saveset number, you can preface the saveset number with the target client name and the plug-in used, each separated with a colon. Example: <code>NVSERVER:filesystem:59</code> This format helps in reducing the time taken to locate the saveset.
-title	Specifies the Job Title.
-path	Specifies the directory or file that you want to restore. Provide the full path to the items.
-relocate	Relocates the selected items to the specified path or directory. Ensure that the specified path is created before you run the restore job.
-rename	Renames the selected items. You can use this option if you do not want to overwrite existing files or directories.
-run	Runs the job. Without this option, the restore job is created and saved, but it is not scheduled to run.
-wait	Waits until the task has completed. With this option, the utility return a result of "job succeeded" or "job failed" before releasing the prompt for additional commands.

To create a restore job from a job definition file, use the following options.

Table 62. nvrestore - 3

Option	Description
-create	<p>Creates and optionally schedules a restore job.</p> <p>Specify the ID of the backup saveset that you want to restore. In addition to the saveset number, you can preface the saveset number with the target client name and the plug-in used, each separated with a colon.</p> <p>Example: NVSERVER:filesystem:59</p> <p>This format helps in reducing the time taken to locate the saveset.</p>
-definition	<p>Specifies the name of the job definition file. Provide the full file path.</p> <p>The definition file includes a list of files or directories that you want to include or exclude. It must use the following format:</p> <pre>[Restore] Title=<Job Title> Schedule=<Schedule Set name> Advanced=<Advanced Options Set name> [Include] Path=<Full path to restore items> Relocate=<Relocation path> (Ensure that the path is created before you run the job.) Rename=<New name for the item> (You can use this option if you do not want to overwrite existing files or directories.)</pre>
-run	<p>Runs the job. Without this option, the restore job is created and saved, but not scheduled to run.</p>
-wait	<p>Waits until the task has completed.</p> <p>With this option, the utility return a result of "job succeeded" or "job failed" before releasing the prompt for additional commands.</p>

Notes

The following rules apply to Restore Definition File:

- The "Schedule" and "Advanced" entries must be included in the [Restore] stanza even if specific Schedule and Restore Advanced Options Sets are not required. You can use the NetVault WebUI or the nvsetcreate utility to create these sets.
- Only one item can be specified per line in the [Include] stanza.

```
[Include]
```

```
C:\data
```

```
C:\new
```

```
C:\Program Files
```

- For the Rename and Relocate options, a separate [Include] stanza must be created for each item.
Correct

```
[Include]
```

```
path=C:\data\files
```

```
relocate=C:\data\new
```

```
[Include]
path=C:\Program Files
relocate=C:\Old Program Files
```

Incorrect

```
[Include]
path=C:\data\files
path=C:\Program Files
relocate=C:\data\new
relocate=C:\Old Program Files
```

- Both the **Rename** and **Relocate** options can be specified within the same instance of the **[Include]** stanza to perform both operations for a single file or directory.

```
[Include]
path=C:\data\new (data that you want to restore and its original path)
relocate=C:\saved\data (the relocation path)
rename=C:\saved\data\old (the relocation path along with the new directory name)
```

- The relocation directory must exist on the target system before you run the restore job. You can create and save the job without using the “-run” parameter and establish a new directory for relocation in the command, but when you run the job, the target relocation directory must exist.

nvsetcreate

Description

Creates a set.

- ① **NOTE:** The NetVault Backup Plug-in for NDMP (Plug-in for NDMP) allows you to create only Backup Selection Sets using the **nvsetcreate** utility.
While creating a set for the Plug-in for NDMP, if you specify an existing set name, the **nvsetcreate** utility overwrites the set. You can use the **nvsetcreate** utility to modify a set for this plug-in instead of **nvsetmodify**.

Syntax

```
nvsetcreate [-setname <Set Name>] -type <set type> <Set Type Specific Options>
            -assign <Assignment Character> -delimit <Delimiter Character>
            -parameters <Parameter Filename>] [-version]
```

Options

Table 63. nvsetcreate

Option	Description
-setname	Specifies the name of the set that you want to create.
-type	<p>Specifies the set type and set-specific options.</p> <p>The set type can be one of the following:</p> <ul style="list-style-type: none">• BS: Backup Selection Set• BO: Backup Options Set• S: Schedule Set• BT: Backup Target Set• AB: Backup Advanced Options Set• RS: Restore Selection Set• AR: Restore Advanced Options Set <p>To obtain a list of available options for any set type, use the following command:</p> <pre>nvsetcreate -type <set type> -- help</pre> <p>Example:</p> <pre>nvsetcreate -type BS -- help</pre> <p>For information about set-specific options, see the following sections:</p> <ul style="list-style-type: none">• Backup Selection Set• Restore Selection Set• Backup Options Set• Schedule Set• Backup Target Set• Backup Advanced Options Set• Restore Advanced Options Set
-assign	Specifies the assignment operator that you want to use in change descriptions. The default assignment operator is the "=" character. This option must be specified if the old or new values contain the "=" character.
-delimit	Specifies the character that you want to use as a delimiter in change descriptions. The default delimiter is the ":" character. This option must be specified if old or new values contain the ":" character.
-parameters	<p>Reads options from a parameter file.</p> <p>You can use any text editor to create the parameter file. Specify one option with its value per line and omit "-" before the option. Use spaces or tabs to separate the option and values. To include comments, begin the line with a "#" character.</p> <p>Example:</p> <pre># nvsetcreate example file setname workbackup type BS client WinClient</pre> <p>This file can be used with the -parameters option as follows:</p> <pre>./nvsetcreate -parameters example.txt</pre>

Backup Selection Set

Options

Table 64. Backup Selection Set

Option	Description
-client <client>	Specifies the name of the NetVault Backup Client that you want to back up.
-plugin <plug-in name>	Specifies the name of the plug-in that you to use for the backup. The plug-in names must appear exactly as they do on the NetVault WebUI. Example: -plugin "File System"
-include <path>	Specifies the backup path. Include the names of each node under the selected item in the tree as they appear on the NetVault WebUI. Separate the nodes using "/" or "\" depending on the client operating system.
-exclude <path>	Specifies the paths that you want to omit during backup. It must be specified in the same way as the included paths. This option can only be used to exclude items that appear under items that have already been named for inclusion.
-info <path=value[:value[:...]]>	Specifies plug-in information object attached to a node in the selection tree. This information is unavailable to the plug-in at backup time. It can only be specified for nodes where the default values are always added by the plug-in. The type and order of the values is plug-in dependant. For more information, contact Technical Support.
-browsesetting <entry>	Specifies the Tag name and setting for the selected option. Use this option to create Selection Set for filers with limited or no browse capability. To list the tags, type: <code>nvsetcreate -type BS -helpndmptags</code> The available tags are: LEVEL - NDMPC_TAG_LEVEL HIST - NDMPC_TAG_GET_FILE_INFO UPDATE - NDMPC_TAG_UPDATE DIRECT -NDMPC_TAG_DIRECT_IF_POSSIBLE

Notes

- When creating a Selection Set for backing up the root directory using NetVault Backup Plug-in for FileSystem, do not include the last "\" character. Specify only the drive letter. Thus, use the path C: instead of C:\.
Example:
`nvsetcreate -setname testset -type BS -client WINCLIENT1 -plugin "File System" -include "Fixed Drives\C:"`
- When using the -include option in Backup Selection Sets for NetVault Backup Plug-in for Consolidation, NetVault Backup Plug-in for Data Copy, or NetVault Backup Plug-in for Raw Devices, specify the full file path as displayed on the NetVault WebUI.
 - Use "/" to separate the tree items. Regardless of the OS in use, the forward slash ("/") can be used as a separator.
 - Delimit the path with double quotation marks

- Include the complete Saveset Title:

```
/JobTitle(Savesetnum) hh:mm DD MM YYYY
```

Example:

```
nvsetcreate -setname DataCopy1 -type BS -client ukwk1115 -plugin "Data Copy"
-include "Backups/ukwk1115/File System/spanningTapes (Saveset 106) 11:00 31 jul
2011"
```

Examples

- Create a Backup Selection Set for a Windows-based client "WinClient" to back up all files in the "C:\work" directory using the Plug-in for FileSystem, while excluding the file "a.zip":

```
nvsetcreate -setname workbackup -type BS -client WinClient
-plugin "File System" -include "Fixed Drives\C:\work" -exclude "C:\work\a.zip"
```

- Create a Backup Selection Set for Isilon filer (with no browse capability) to perform level 1 backup of the data in the directory "Isilon/ifs/data/testdata/small":

```
nvsetcreate -setname Isilon_Dump1 -type BS -client Interop_r14
-plugin "NDMP Client" -browsesetting NDMPC_TAG_LEVEL=1
-include "Isilon/ifs/data/testdata/small"
```

Restore Selection Set

Options

Table 65. Restore Selection Set

Option	Description
-client <client>	Specifies the name of NetVault Backup Client from which the data was backed up.
-plugin <plug-in name>	Specifies the name of the plug-in that was used to perform the backup. The plug-in names must appear exactly as they do on the NetVault WebUI. Example: -plugin "File System"
-saveset <ID>	Specifies the ID of the saveset that you want to restore. Use this option when you want to restore a particular saveset. Alternatively, use the -title option to restore data from the latest saveset for that backup.
-title <title>	Specifies the title of the backup that you want to restore. If more than one saveset exists for the job, the latest one is used. To restore data from a particular saveset, use the -saveset option.
-timestamp <HH:MM DD MM YYYY>	Specifies the timestamp of the saveset that you want to restore. This option can be used with the "-title" option to create a Restore Selection Set without specifying the saveset ID.
-include <path>	Specifies the path that you want to restore. It should specify the names of each node under the selected item in the tree as they appear on the NetVault WebUI. The nodes must be separated by "/" or "\" depending on the client operating system. NOTE: The -include option must be specified before the -rename option when both options are used in a Restore Selection Set.
-exclude <path>	Specifies the paths that you want to omit during restore. It must be specified in the same way as the included paths. This option can only be used to exclude items that appear under items that have already been named for inclusion.

Table 65. Restore Selection Set

Option	Description
-rename <path> =<new name or path>	<p>Renames or relocates restore items.</p> <p>You can combine both options or use each independently. If you want to rename an item without relocating it, provide only the new name. To relocate an item, provide the full path.</p> <p>When relocating data to a different path, verify that the path exists on the target machine before you run the command.</p> <p>Examples:</p> <ul style="list-style-type: none"> Rename only: -rename /usr/joe/diary=diary.old Relocate only: -rename /usr/joe/diary=/home/joe/diary Rename and Relocate: -rename /usr/joe/diary=/home/joe/diary.old
-restoreoption <option=value>	<p>Specifies Restore Options for a job.</p> <p>To use this option, you require the "Tag ID" of the option that you want to set. The Tag ID can either be the backup option name as recognized by the CLI or a numeric value assigned to the option by NetVault Backup. Both of these values are grouped under the [Plugin Options] section in the nvsetmodify.cfg file.</p> <p>The format for specifying this option is:</p> <p>-restoreoption <Tag ID=value></p>
-restoretarg <client>	<p>Specifies the name of the target client.</p> <p>By default, items are restored to the same client that they were backed up from. When restoring data to an alternate client, ensure that the selected plug-in is installed on the client.</p>
-info <path=value[:value[: ...]]>	<p>Specifies plug-in information object attached to a node in the selection tree. The type and order of the values is plug-in dependant. For more information, contact Technical Support.</p>

Examples

- The following example creates a Restore Selection Set "restorebig" that restores data from saveset ID "320" created with the Plug-in for FileSystem. The data was backed up from client "isp9039." The set includes the entire volume for restore except directory "/a1" and relocates the file "document" from "/usr/var" to "usr/tmp" directory. Lastly, it enables the restore option "Overwrite Newer Files":

```
nvsetcreate -setname restorebig -type RS -client isp9039 -plugin "File System"  
-saveset 320 -include "/" -exclude /a1  
-rename /usr/var/document=/usr/tmp/document  
-restoreoption NVFSOPT_OVERNEW=TRUE
```
- The following example creates a Restore Selection Set using the -timestamp option:

```
nvsetcreate -setname fs_time -client Client-A -type RS -plugin "File System"  
-title fs_full -timestamp "19:25 21 Apr 2014" -include c:\testdata\small\data
```

Backup Options Set

Options

Table 66. Backup Options Set

Option	Description
-client <client>	Specifies the name of the NetVault Backup Client that you want to back up.
-plugin <plug-in name>	Specifies the name of the plug-in that you to use for the backup. The plug-in names must appear exactly as they do on the NetVault WebUI. Example: -plugin "File System"
-backupoption <option=value>: <option=value>	Specifies Backup Options for a job. To use this option, you require the "Tag ID" of the option that you want to set. The Tag ID can either be the backup option name as recognized by the CLI or a numeric value assigned to the option by NetVault Backup. Both of these values are grouped under the [Plugin Options] section in the nvsetmodify.cfg file. The format for specifying this option is: -backupoption <Tag ID>=<Value>
-backupoptionspath <path>	Specifies the backup options path. This option is only applicable if a plug-in can specify different backup option page depending on a selection path within that plug-in. It can be used to specify a particular backup options page from a selection path.

Examples

- Create a Backup Options Set to perform Incremental Backups using Plug-in for FileSystem:

```
nvsetcreate -setname backupoptionset -type BO -client WinClient  
-plugin "File System" -backupoption NTFSOPT_TYPEINCR=true
```

Schedule Set

Options

Table 67. Schedule Set

Option	Description
-schedule <value>	Specifies the schedule type. The supported values are: <ul style="list-style-type: none">immediateoncerepeatingtriggered
-time <hh:mm>	Specifies the start time for the job.
-date <DD-MMM-YYYY>	Specifies the date on which the schedule takes effect.
-weekdays <ddd[,ddd[,...]]>	Specifies the days of week when the job is run. Example: -weekdays Mon, Tue, Wed, Thu, Fri
-weeks <n[,n[,...]]>	Specifies the weeks in a month when the job is run. Use "L" to specify the last week in the month. Example: -weeks 1, 3 L

Table 67. Schedule Set

Option	Description
-monthdays <n[,n[,...]]>	Specifies the dates in the month when the job is run. Use "L" to specify the last day of the month. Example: -monthdays 7, 14, 21, L
-every <n-period>	Specifies the interval at which the job is run. It is specified as number of hours, days, weeks or months. A hyphen (-) is used to separate the numeric value and period. Example: -every 12-month
-trigger <trigger>	Specifies the name of the trigger to run a triggered job.
-priority <number>	Specifies the priority level for a job. This option is used to prioritize resource allocation when two or more jobs are scheduled to run at the same time. The priority level can be set to any value between 1 (highest priority) and 100 (lowest priority). A priority level of zero sets a job to run as a background task. The default value for this option is 30.
-retry <boolean>	Enables or disables job retries after an initial attempt to run the job fails. Set it to TRUE to enable job retries. The default value for this option is FALSE.
-retries <number>	Specifies the maximum number of retries for a job. It can be set to any value between 1 and 10. This option is only valid if -retry is set to TRUE. The default value for this option is 1.
-retrydelay <hh:mm>	Specifies the time delay between retries. It can be set to any value between 00:00 and 23:59. This option is only valid if -retry is set to TRUE. By default, the job is scheduled to run immediately if -retry is set to TRUE and no value is set for this option.

Examples

- Create a Schedule Set "EveryLastTuesday" to run a job at 11:30 P.M. on the last Tuesday of every month:

```
nvsetcreate -type S -setname EveryLastTuesday -schedule repeating -time 23:30
-weekdays tue -weeks L
```

Backup Target Set

Options

Table 68. Backup Target Set

Option	Description
-device	Specifies the name of the target device or library. This option can be used more than once in the command. The default value for this option is "Any Device."
-librarydrivenumber	Specifies the target drive. This option must be preceded by the -device option. Specify each drive that can be used separately using -librarydrivenumber option.
-anymedia	Uses any media regardless of media group associations. If you do not specify this option, only media items that belong to a group are used.
-mid	Uses media with specified media ID.
-group	Uses media associated with specified media group.
-autolabel	Labels blank media. The values that can be used are TRUE or FALSE. The default value for this option is TRUE.
-reusemedia	Specifies media reuse media. The values that can be used with this option are: <ul style="list-style-type: none"> never: Never reuse media any: Reuse any media group: Reuse any media item that belongs to a group
-minimumspace	Specifies minimum space required on a media item for that item to be used for backup. It is specified in MB.

Table 68. Backup Target Set

Option	Description
-protectmedia	Write-protects the media. The values that can be used are TRUE or FALSE. The default value for this option is FALSE.
-firstonmedia	Controls whether backup is first on media. The values that can be used are TRUE or FALSE. The default value for this option is FALSE.
-localdrivesonly	Allows only locally attached devices. The values that can be used are TRUE or FALSE. The default value for this option is FALSE.
-mediarequesttime out	Allows you to set media request timeouts. The values that can be used are TRUE or FALSE. The default value for this option is FALSE.
-mediarequesttime outvalue	Specifies the timeout interval for media requests. It can be set to any value between 00:05 and 23:59. This option is only valid if the option -mediarequesttimeout is set to TRUE. The minimum timeout interval can be 5 minutes. If you specify a value lesser than "00:05" minutes, an error is displayed. The specified value is automatically rounded up to the nearest 5-minute interval. For example, 7 minutes is automatically changed to 10 minutes and 22 minutes is automatically changed to 25 minutes.

Examples

- Create a Backup Target Set that uses either drive 3 or drive 4 of the library "MyDltLib." This set writes to any media, regardless of group, and automatically labels or reuses media as required:

```
nvsetcreate -type BT -setname Drive4 -device MyDltLib -librarydrivenumber 3
            -librarydrivenumber 4 -anymedia -autolabel TRUE -reusemedia any
```

Backup Advanced Options Set

Options

Table 69. Backup Advanced Options Set

Option	Description
backuptype	Specifies the backup type (backup or archive).
-discardtime	Specifies the length of time you want to retain the backup. The backup is automatically discarded after the period elapses. The period can be specified in number of days, weeks or years. Example: -discardtime 26-weeks
-backuplife	Specifies the number of full backups that you want to retain for the job. Older backups are automatically discarded.
encryption	Enables encryption for the backup. The values that can be used are TRUE or FALSE. The default value for this option is FALSE.
-verify	Performs backup verification. The values that can be used are TRUE or FALSE. The default value for this option is FALSE.
-deduplicate	Deduplicates the backup data. The values that can be used are TRUE or FALSE. The default value for this option is FALSE.
-netcompress	Enables network compression for the data transferred between the NetVault Backup Client and Server. The values that can be used are TRUE or FALSE. The default value for this option is FALSE.
-secondarycopy	Creates a secondary copy. The values that can be used are TRUE or FALSE. The default value for this option is FALSE.
-duplicate	Uses the Duplicate Method to create a secondary copy. The values that can be used are TRUE or FALSE. The default value for this option is FALSE.

Table 69. Backup Advanced Options Set

Option	Description
-datacopy	Uses the Data Copy Method to create the secondary copy. The values that can be used are TRUE or FALSE. The default value for this option is FALSE.
-encryptsecondary copy	Encrypts the secondary copy. The values that can be used are TRUE or FALSE. The default value for this option is FALSE.
-migrate	Removes the original backup after the secondary copy is created. The values that can be used are TRUE or FALSE. The default value for this option is FALSE.
-usereplication	<p>Enables transfer of deduplicated data directly from one device to another device of the same type during a Data Copy or Duplicate operation. It provides an efficient method to create secondary copies and offers the following advantages:</p> <ul style="list-style-type: none"> • Copies data in its deduplicated form, which greatly reduces the amount for data transferred over the network. • Copies data directly from the source to the destination without using any resources on the NetVault Backup Server. <p>The following storage devices support optimized replication:</p> <ul style="list-style-type: none"> • NetVault SmartDisk devices: To perform optimized replication, you require NetVault SmartDisk 2.0 or later. If the login credentials configured for the source and destination NetVault SmartDisk Servers do not match, replication fails. To ensure a successful replication, do one of the following: <ul style="list-style-type: none"> - Disable WebDAV authentication on both NetVault SmartDisk Servers. - Enable WebDAV authentication only on the source. - Configure the same login credentials on both servers. <p>NOTE: When copying a backup from a NetVault SmartDisk to a different device type (for example, VTL, Dell DR Series System, or Data Domain System), you must clear this check box. If you do not clear this check box, the Data Copy or Duplicate job fails or stops responding.</p> <ul style="list-style-type: none"> • Dell DR Series Systems: To perform optimized replication, both the source and target DR Series systems must be running the same release version of the DR OS. Replication is not supported between systems that run different releases of the OS. For example, to replicate data from a source system that is running DR OS 2.1.x, the target system must be running the same OS release version. Replication is unsuccessful if the target system is running DR OS release 2.0.x or 3.0.x. <p>NOTE: When optimized replication and backups are performed simultaneously on a Dell DR Series system, the backup throughput is affected.</p> <ul style="list-style-type: none"> • DD Boost-Enabled Data Domain Systems: The secondary copy backups between two DD Boost-Enabled Data Domain Systems use the managed file-level replication feature provided by DD Boost. File-level replication requires the DD Boost Replicator license, which must be installed on both the source and the destination Data Domain systems. • If the source and target Data Domain systems are running different versions of the Data Domain OS, then for replication to be successful, the target system must be running the higher version of the OS.
-duplicateclient	Specifies the name of the NetVault backup Client on which you want to run the secondary copy job. It can be Server, Original, or any NetVault Backup Client.
- duplicatescheduleset	Specifies the name of the Schedule Set for the secondary copy.
-duplicatetargetset	Specifies the name of the Target Set for the secondary copy.
-duplicatesource	Specifies the name of the Source Set for the secondary copy.

Table 69. Backup Advanced Options Set

Option	Description
-allowstreamstoshare media	Enables streams to share media. The values that can be used are TRUE or FALSE. The default value for this option is FALSE. This option is only valid if the -secondarycopy option is set to TRUE.
-duplicatelife	Specifies the retention period for secondary copy. If you omit this option, the lifetime of the original (specified using the -discardtime option) is used.
-offlineindexafter	Specifies the retention period for online index. The backup index is automatically deleted from the NetVault Database after the period elapses. This period can be specified in number of days, weeks, or years. Examples: -offlineindexafter 2-days -offlineindexafter 24-weeks
-prescript	Specifies the name of the script file that you want to run before the job starts. The file must be stored in the NetVault Backup "scripts" directory.
-prescriptarg	Specifies the run-time parameters for the script.
-postscript	Specifies the name of the script file that you want to run before the job completes. The file must be stored in the NetVault Backup "scripts" directory.
-postscriptarg	Specifies the run-time parameters for the script.

Examples

- Create an Advanced Options set "AdvOptBU" with a backup life of 5 full backups. Enable network compression and backup verification, and run a postscript entitled "jobdone":

```
nvsetcreate -type AB -setname AdvOptBU -backuplife 5 -netcompress TRUE
-verify TRUE -postscript jobdone
```

Restore Advanced Options Set

Options

Table 70. Restore Advanced Options Set

Option	Description
-netcompress	Enables network compression for the data transferred between the NetVault Backup Client and Server. The values that can be used are TRUE or FALSE. The default value for this option is FALSE.
-prescript	Specifies the name of the script file that you want to run before the job starts. The file must be stored in the NetVault Backup "scripts" directory.
-prescriptarg	Specifies the run-time parameters for the script.
-postscript	Specifies the name of the script file that you want to run before the job completes. The file must be stored in the NetVault Backup "scripts" directory.
-postscriptarg	Specifies the run-time parameters for the script.

nvsetdelete

Description

Deletes a set.

Syntax

```
nvsetdelete -setname <Set Name> [-type <Set Type>] [-version]
```

Options

Table 71. nvsetdelete

Option	Description
-setname	Specifies the name of the set that you want to delete.
-type	Specifies the set type. It can be one of the following: <ul style="list-style-type: none">• BS: Backup Selection Set• BO: Backup Options Set• S: Schedule Set• BT: Backup Target Set• AB: Backup Advanced Options Set• RS: Restore Selection Set• AR: Restore Advanced Options Set
-version	Displays the build date of the NetVault Backup distribution installed on the machine.

nvsetexport

Description

Exports a set to an output file.

Syntax

```
nvsetexport [-setname <Set Name>] -type <Set Type> -file <Output File> [-version]
```

Options

Table 72. nvsetexport

Option	Description
-setname	Specifies the name of the set that you want to export.
-type	Specifies the set type. It can be one of the following: <ul style="list-style-type: none">• BS: Backup Selection Set• BO: Backup Options Set• S: Schedule Set• BT: Backup Target Set• AB: Backup Advanced Options Set• RS: Restore Selection Set• AR: Restore Advanced Options Set
-file	Specifies the name of the output file.
-version	Displays the build date of the NetVault Backup distribution installed on the machine.

Examples

- Export all Schedule Sets to the file "schedules.nss":

```
nvsetexport -type S -file schedules.nss
```
- Export the Backup Selection Sets "Blackbird" and "Robin" to the file "bandr.nss":

```
nvsetexport -type BS -setname Blackbird -setname Robin - file bandr.nss
```

nvsetimport

Description

Import the specified sets from an input file to the NetVault Backup Server.

Syntax

```
nvsetimport -file <Input Filename> [-setname <Set Name>[=<new name>]]  
[-assign <Assignment Character>] [-version]
```

Options

Table 73. nvsetimport

Option	Description
-file	Specifies the name of the input file.
-setname[=<newname>]	Specifies the names of the sets that you want to import from the input file. To import multiple sets, specify each set name separately using the -setname option. You can rename each set while importing them to NetVault Backup. If you omit this option, all sets available in the input file are imported, each retaining their original name. The existing sets with the same name are overwritten.

Table 73. nvsetimport

Option	Description
-assign	Specifies the assignment operator that you want to use in change descriptions. The default assignment operator is the "=" character. This option must be specified if any value contains the "=" character.
-version	Displays the build date of the NetVault Backup distribution installed on the machine.

Examples

- Import all sets from the file "schedules.nss":

```
nvsetimport -file schedules.nss
```
- Import the set "Robin" from the file "bandr.nss", renaming the imported set to "Ptarmigan":

```
nvsetimport -file bandr.nss -setname Robin=Ptarmigan
```
- Import the set "Blackbird" from file "bandr.nss", renaming the imported set to "b=k":

```
nvsetimport -file bandr.nss -assign @ -setname Blackbird@b=k
```

nvsetmodify

Description

Modifies a set.

Syntax

```
nvsetmodify -setname <set name> -type <set type> -change <change description>
[-parameters <parameter file>] [-assign <assignment character>]
[-delimit <delimiter character>] [-version]
```

Options

Table 74. nvsetmodify

Option	Description
-setname	Specifies the name of the set that you want to modify.
-type	<p>Specifies the set type. It can be one of the following:</p> <ul style="list-style-type: none"> • BS: Backup Selection Set • BO: Backup Options Set • RS: Restore Selection Set <p>The nvsetmodify utility does not support the following set types:</p> <ul style="list-style-type: none"> • S: Schedule Set • BT: Backup Target Set • AB: Backup Advanced Options Set • AR: Restore Advanced Options Set <p>To modify these sets, you can use the following methods:</p> <ul style="list-style-type: none"> • Use the nvsetcreate utility to create a set with the same name. This utility overwrites the existing set. • Use the NetVault WebUI to modify the set.

Table 74. nvsetmodify

Option	Description
-change	<p>Specifies the changes that you want to make. This option can be used more than once. The <code><change description></code> variable is formatted as follows:</p> <pre><item>[:<field>][:<old value>]=<new value></pre> <p><code><item></code> can be set to one of the following values</p> <p><code><field></code> specifies the field in the item that is to be modified.</p> <p><code><old value></code> specifies the old setting for the selected item.</p> <p><code><new value></code> specifies the new setting for the selected item.</p> <p>Change items:</p> <ul style="list-style-type: none"> • tree: Modifies items in the selection tree. The "tree" item applies only to Backup and Restore Selection Sets. For the "tree" item, the "<code><field></code>" variable can be set to the following values: <ul style="list-style-type: none"> - path: For more information, see path. - rename: For more information, see rename. - info: For more information, see info. - <node name or ID> for inclusion: For more information, see <Node Name> or <ID>. • Options: Adds or modifies the restore options if the plug-in provides any. To use this option, you require the "Tag ID" of the option that you want to set. The Tag ID can either be the backup option name as recognized by the CLI or a numeric value assigned to the option by NetVault Backup. Both of these values are grouped under the [Plugin Options] section in the <code>nvsetmodify.cfg</code> file. The format for specifying this option is: <pre>Options:<Tag ID>=True/False</pre> • Target: Changes items in the target tree (Restore Selection Sets only). The <code><field></code> variable is used to specify the type to be changed. The only permitted value is a valid NetVault Backup Client name. The <code><new value></code> specifies the new target Client. <p>NOTE: If no "<code><new value></code>" variable is specified, anything that is selected or omitted in the "<code><old value></code>" is considered de-selected when you run the command.</p> <p>path</p> <p>Modifies the client name, the plug-in name, or a single node in the selection path. To change the path, set the old and new variables as follows:</p> <ul style="list-style-type: none"> • Client: <pre><old value> = Name of the current NetVault Backup Client</pre> <pre><new value> = Name of the new NetVault Backup Client. Ensure that the client is added to the NetVault Backup Server.</pre> • Plug-in: <pre><old value> = Name of the current NetVault Backup Plug-in</pre> <pre><new value> = Name of the new NetVault Backup Plug-in. Ensure that the new plug-in is installed on the NetVault Backup Server or Client for which the set is defined.</pre> • Selection path: <pre><old value> = Full path to the node, from the plug-in root node to the node that you want to change. Depending on the client OS, use the backslash (\) character (Windows) slash (/) character (Linux/UNIX) as the path separator.</pre> <pre><new value> = Name of the new node</pre>

Table 74. nvsetmodify

Option	Description
	<p>Example:</p> <p>A Backup Selection Set for the Plug-in for FileSystem includes the following selection path on Windows:</p> <pre>Fixed Drives\C:\work\t1\dump\a</pre> <p>To change the directory "t1" to "t2" in this path, the variables are set as follows:</p> <pre><old value> = Fixed Drives\C:\work\t1 <new value> = t2</pre> <p>On Linux Clients, the Plug-in for FileSystem does not include any predefined level-3 nodes ("Fixed Drives", "Removable Drives", and others). Therefore, a similar selection on Linux/UNIX Client includes the following nodes:</p> <pre>/work /t1/dump/a</pre> <p>To change the directory "t1" to "t2" in this path, the variables are set as follows:</p> <pre><old value> =/work/t1 <new value> =t2</pre> <p>rename</p> <p>Adds or modifies a rename or relocation command to a Restore Selection Set.</p> <ul style="list-style-type: none"> To add a new rename or relocation command, set the variables as follows: <pre><old value> = Current name or path of the rename or relocation target <new value> = New name or path for the rename or relocation target</pre> To modify an existing rename or relocation command, set the variables as follows: <pre><old value> = Current rename or relocation syntax <new value> = New rename or relocation syntax</pre> <p>info</p> <p>Modifies the plug-in information object attached to a node in the selection tree. To use this option, set the variables as follows:</p> <pre><old value>= Full path to the item, from the plug-in root node to the applicable item. <new value> = New values for the plug-in information object, separated by colons (":"). To leave any field unchanged, specify a double colon ("::") as the new value.</pre> <p><Node Name> or <ID></p> <p>Includes an item in the backup or restore job. The item can either be the "node name" as recognized by the CLI or a numeric "ID" assigned to the node by NetVault Backup. Both of these values are grouped under the [Tree Nodes] section in the nvsetmodify.cfg file.</p> <p>To use this option, set the variables as follows:</p> <pre><old value> = Node Name or Node ID of the current node. If the selection tree for the target NetVault Backup Client contains multiple nodes of the given type, specify the Node Name instead of the Node ID. <new value> = Node name or ID of the new root node.</pre>

Table 74. nvsetmodify

Option	Description
-parameters	<p>Reads options from a parameter file.</p> <p>You can use any text editor to create the parameter file. Specify one option with its value per line and omit "-" before the option. Use spaces or tabs to separate the option and values. To include comments, begin the line with a "#" character.</p> <p>Example:</p> <pre># nvsetmodify example file setname BackSet1 type BS</pre> <p>This file can be used with the -parameters option as follows:</p> <pre>./nvsetmodify -parameters example.txt</pre>
-assign	Specifies the assignment operator that you want to use in change descriptions. The default assignment operator is the "=" character. This option must be specified if the old or new values contain the "=" character.
-delimit	Specifies the character that you want to use as a delimiter in change descriptions. The default delimiter is the ":" character. This option must be specified if old or new values contain the ":" character.
-version	Displays the build date of the NetVault Backup distribution installed on the machine.

Examples

- Modify the Backup Selection Set "BS-Set1" to change the NetVault Backup Client from "Client-A" to "Client-B":

```
nvsetmodify -setname BS-Set1 -type BS -change Tree:path:Client-A=Client-B
```

- Modify the Backup Selection Set "BS-Set1" to change the plug-in from "File System" to "Data Copy":

```
nvsetmodify -setname BS-Set1 -type BS -change "Tree:path:File System=Data Copy"
```

- Modify the Backup Selection Set "BS-Set1" to change the directory "t1" to "t2" in the selection path "Fixed Drives\C:\work\t1\dump\A":

```
nvsetmodify -setname BS-Set1 -type BS
-change "Tree@path\Fixed Drives\C:\work\t1=t2" -delimit @
```

In this example, the -delimit option is used to set the character "@" as the delimiter because the path includes ":" which is the default delimiter.

- Modify the Backup Selection Set "BS-Set1" to change the directory "t1" to "t2" in the selection path "/work/t1/dump/a":

```
nvsetmodify -setname BS-Set1 -type BS -change "Tree:path:/work/t1=t2"
```

- Modify the Backup Selection Set "BS-Set1" to change the drive node from "C:\" to "D:\" in the selection path "Fixed Drives\C:\work\t1\dump\A":

```
nvsetmodify -setname BackupSetName -type BS
-change "Tree@path\Fixed Drives\C:\=D:\" -delimit @
```

In this example, an extra backslash character is added to the new value D:\ to escape the first backslash character. If you do not include it, then the sequence D:\" would be interpreted as D:; the first backslash would be used to escape the quotation mark (").

- Modify the Backup Selection Set "BS-Set1" to change the Network Share path from "\\Server1\A" to "\\Server2\b":

```
nvsetmodify -setname BackupSetName -type BS
-change "Tree@path\Network Shares\\Server1\A=\\Server2\b\" -delimit @
```

- Modify the Backup Selection Set “BS-Set1” to change the “Fixed Drives” node to “Removable Drives”:

```
nvsetmodify -setname BackupSetName -type BS
-change "Tree:path:Fixed Drives=Removable Drives"
```

NOTE: The Plug-in for File System (Windows only) and a few other plug-ins (Plug-in for Consolidation, Plug-in for Data Copy, Plug-in for Databases, and Plug-in for Raw Devices) include pre-defined level-3 nodes. You can obtain the exact names of these nodes from the NetVault WebUI. To prevent any user errors, the `nvsetmodify` utility checks for the correctness of new values specified for level-3 nodes. An error message is displayed if you specify an incorrect value for these nodes. The utility does not perform any checks for the correctness or existence of nodes below level-3.

- Modify the Restore Selection Set “RestoreSet1” (created for the Plug-in for FileSystem) to make the following changes:
 - Change the target client from “WinClient1” to “WinClient2”
 - Relocate the directory “C:\Mail” to “C:\MyMail”
 - Set the Restore Option “Overwrite Newer Files”

```
nvsetmodify -setname RestoreSet1 -type RS
-change target:client:WinClient1=WinClient2
-change options:nvfs_opt_overnew=true -change @tree@path@c:\mail=c:\MyMail
```

nvtrigger

Description

Triggers a job that has already been defined and saved using the Triggered scheduling option.

This utility is located in the `bin` directory.

Syntax

```
nvtrigger [-server <server name>] [-wait] -verbose -killonexit <trigger name>
```

Options

Table 75. `nvjobstart`

Option	Description
-servername	Specifies the name of the NetVault Backup Server that administers the job. This option is required when a remote server administers the job. It can be omitted when a local server administers the job. The server name is case-sensitive.
-wait	Waits until the task has completed.
-verbose	Displays additional information when the job starts and completes. When the job starts, the details such as the Job ID, Instance ID, Job Title, and Start Time are displayed. When the job completes, the end time is displayed.
-killonexit	Aborts a job by terminating the trigger execution. This option must be used with the -wait option.
<trigger name>	Specifies the trigger name. This option must be the last option when the tool is invoked as shown in the following example: <pre>nvtrigger -server <server name> -wait -verbose -killonexit <triggername></pre>

Notes

- The `nvtrigger` utility returns the following exit codes and messages when the job it is associated with completes execution:
 - 0: Backup Completed
 - 1: Backup Failed
 - 2: Backup Completed with Warnings
 - 3: Backup Aborted
- Without the `-wait` option, the `nvtrigger` utility can support multiple jobs. With this option, the utility can only be used to trigger a single job. This limitation also applies to `-wait -killonexit` options. Therefore, you cannot use this option for policy jobs that contains multiple job definitions.
- If you specify the `-wait` option in a script, control is returned to the script only after the triggered job completes. If you do not specify this option, control is returned immediately back to the script even if the triggered job is still running.

Log-specific utilities

nvlogdump

Description

Dumps NetVault Backup logs to a text or binary file.

Syntax

```
nvlogdump [-jobid <Job ID>] [-filename <Dump File>] [-text]
          [-starttime <Start Time>] [-endtime <End Time>]
```

Options

Table 76. `nvlogdump`

Option	Description
-jobid	Specifies the job ID for which logs are exported.
-filename	<p>Specifies the name of the file to which logs are exported.</p> <p>By default, NetVault Backup creates the binary files in the following location:</p> <ul style="list-style-type: none">• Windows: <NetVault Backup home>\log\ dumps\binary• Linux: <NetVault Backup home>/log/dumps/binary <p>By default, NetVault Backup creates the text files in the following location:</p> <ul style="list-style-type: none">• Windows: <NetVault Backup home>\log\ dumps\text• Linux: <NetVault Backup home>/log/dumps/text <p>If you omit the <code>-filename</code> option, NetVault Backup creates a file named <code>CLI_DUMP_<YYYYMMDD>_<HHMMSS></code> in the specified format. The binary file has the extension ".nlg"; the text file does not have any extension.</p>
-text	Exports logs in text format. If you omit this option, then logs are dumped in binary format.

Table 76. nvlogdump

Option	Description
-starttime	Specifies the time that serves as the starting point for the log dump. The format to specify start time is YYYYMMDDHHMMSS.
-endtime	Specifies the time that serves as the stopping point for the log dump. The format to specify end time is YYYYMMDDHHMMSS.

Notes

At least the **jobid** option or a combination of the **starttime** and **endtime** options must be specified to properly use this utility. A combination of the options **jobid**, **starttime**, and **endtime** can be specified to dump logs for a particular job that were generated within the given period.

Examples

- Dump logs for Job ID 50, starting from August 1, 2014, 20:33:04, to a binary file named "nvlogdmp.nlg":
`nvlogdump -filename c:\temp\nvlogdmp -starttime 20140801203304 -jobid 50`

nvlogpurge

Description

Purges log entries up to the specified time.

Syntax

```
nvlogpurge -purgetime <End Time>
```

Options

Table 77. nvlogpurge

Option	Description
-purgetime	Specifies the time that serves as the end point for the log purge. The format to specify purge time is YYYYMMDDHHMMSS.

nvreadlog

Description

Displays log messages.

Syntax

```
nvreadlog [-h] [-b <days>] [-m] [-d <delimiter string>] [-o <messages>]
```

Options

Table 78. nvreadlog

Option	Description
-h	Exits after showing historic log messages.
-b	Specifies the start date; it is specified as the number of days before the current date.
-m	<p>Starts the output from midnight preceding the number of days specified with the -b option. You must use this option with the -b option.</p> <p>For example, at 3 P.M., you specify -b 1, logs starting from 3 P.M. the day before are displayed. With the -m option, log messages starting from the midnight of previous day are displayed.</p> <p>If you specify -m without the -b option or with -b 0, log messages starting from the midnight of current day are displayed. If you issue this command at 3 P.M., 15 hours of logs are displayed.</p>
-d	Specifies one or more characters that you want to use as delimiters. For example, -d followed by two spaces would separate each displayed item with two spaces.
-o	<p>Displays specific messages. For example, if you specify -o failed, only messages that contain the word "failed" are displayed.</p> <p>You can specify multiple strings using comma as a separator.</p>

Notes

- As "-h" is a command option, use the full command "-help" to view help for this command:

```
nvreadlog -help
```

Other utilities

bonedate

Description

Displays the BakBone date and time in use on the current machine. It is obtained from the machine configured as the BakBone Time Server. For more information about BakBone Time, see the *Dell NetVault Backup Administrator's Guide*.

Syntax

```
bonedate
```

getmachineid

Description

Finds machine ID of the NetVault Backup Server or Client machine on which this utility is run. Machine ID is required to obtain permanent license keys for NetVault Backup products.

Syntax

```
getmachineid
```

installplugin

Description

Installs NetVault Backup plug-ins on the server or client machines. This utility is located in the **bin** directory.

Syntax

```
installplugin <Full path to the .npk installation file>
```

Notes

- Verify that you provide the full file path to the “.npk” installation file. Enclose the path within quotation marks (“”) if it contains any spaces.

licenseinstall

Description

Installs product license keys. This utility is located in the **bin** directory.

Syntax

```
licenseinstall <key string> | <.npk file that contains the key>
```

nvlicenseinfo

Description

Provides license information for the NetVault Backup Server.

Syntax

```
nvlicenseinfo
```

nvmeddbcheck

Description

Verifies the structural, entity, and referential integrity of the Media Database. It checks the following:

- Raw file structure
- Database table integrity
- Inter-table references and dependencies

The nvmeddbcheck utility can take one of the following arguments: List or Check.

Syntax

```
nvmeddbcheck <List | Check> [-v <warning level>]
```

Options

Table 79. nvmeddbcheck

Option	Description
List	Displays a line of output for every backup record, new stream, old stream, session, segment, media, and backup index in the database. You can use this option to determine which records should be deleted.
Check	Performs database checks and displays the status.
-v	Specifies the minimum warning level for the error messages that are displayed. The warning levels can be: <ul style="list-style-type: none">• all: All messages• back: Background messages• inf: Information messages• job: Job messages• warn: Warnings• error: Errors• severe: Severe errors

nvpassword

Description

Changes NetVault Backup password for server or client on which this utility is run. This utility is available in the <NetVault Backup home>\bin directory.

Syntax

```
nvpassword <new password>
```

Notes

- The password cannot contain the following characters:
< > & # |

nvpluginaccess

Description

Enables CLI backups and generation of CLI-based reports for plug-ins that require the use of database-related utility (for example, “onbar” for Informix database users and “rman” for Oracle). For more information, see the relevant plug-in user’s guide.

Syntax

```
nvpluginaccess [-remove -client <client names>] | [-client <client name>  
[-account <account name> -password <account password>]]
```

Options

Table 80. nvpluginaccess

Option	Description
-client	Specifies the name of the NetVault Backup Client.
-account	Specifies the name of the NetVault Backup user account that you want to use with this command. The specified user account must be granted all privileges in NetVault Backup.
-password	Specifies the password for the user account.

nvpgdbpasswd

Description

Use this utility to change the password for the PostgreSQL database superuser.

(The password is initially set when you install or upgrade the NetVault Backup Server software.)

Syntax

```
nvpgdbpasswd store <password>
```

```
nvpgdbpasswd change <current password> <new password>
```


Options

Table 81. `nvpgdbpasswd`

Option	Description
<code>store <password></code>	Updates the PostgreSQL database superuser password in the <code>pgdb.cfg</code> file (NetVault Backup configuration file). It does not change the superuser password in the PostgreSQL Database itself; it just updates the <code>pgdb.cfg</code> file. You can use this option to update the password in the configuration file after the password is changed in the database using any PostgreSQL native tool (for example, the <code>psql</code> utility).
<code>change <current password> <new password></code>	Changes the database superuser password both in the PostgreSQL DB and in the <code>pgdb.cfg</code> file. You must specify both the current password and the new password with this option.

Notes

- Before updating the superuser password, you must stop the NetVault Backup Service.

`nvreport`

Allows you to generate and view canned reports from the command-line interface. For more information about using the reporting functionality, see [Using the `nvreport` utility](#).

`nvscheddbcheck`

Description

Verifies the structural, entity, and referential integrity of the Scheduler Database. It checks the following:

- Raw file structure
- Database table integrity
- Inter-table references and dependencies

The `nvscheddbcheck` utility can take one of the following arguments: List or Check.

Syntax

```
nvscheddbcheck <List | Check> [-v <warning level>]
```

Options

Table 82. `nvscheddbcheck`

Option	Description
List	Prints a line of output for every backup record, new stream, old stream, session, segment, media, and backup index in the database. You can use this option to determine which records should be deleted.

Table 82. nvscheddbcheck

Option	Description
Check	Performs database checks and displays the status.
-v	Specifies the minimum warning level for the error messages that are displayed. The warning levels can be: <ul style="list-style-type: none"> all: All messages back: Background messages inf: Information messages job: Job messages warn: Warnings error: Errors severe: Severe errors

nvsendmail

Description

Sends an email to the specified address.

Syntax

```
nvsendmail [-d <dest_address>] [-r <real_name>] [-s <subject>] [-f <message_file>]
           [-a <attach_file>] [-m] [-n]
```

Options

Table 83. nvsendmail

Option	Description
-d	Specifies the email address of the intended recipient.
-r	Specifies the actual name of the intended recipient.
-s	Specifies the subject line of the email.
-f	Specifies the email message file that you want to send.
-a	Specifies the attachment that you want to send. Provide the full path for the attachment file.
-m	Forces mime format.
-n	Specifies notification mode in which the necessary parameters are obtained from the host environment.

nvsendopmsg

Description

Sends an operator message.

Syntax

```
nvsendopmsg [-n] [-test]
```

Options

Table 84. nvsendopmsg

Option	Description
-n	Sends notification from environment variables.
-test	Sends a test message.

Using the nvreport utility

- [About nvreport utility](#)
- [Report classes](#)
- [Plain text template files](#)
- [Formatting the reports](#)
- [Creating external report files](#)
- [HTML template files](#)

About nvreport utility

The **nvreport** utility allows you to generate and view canned reports from the command-line interface. These reports provide information about the backup and restore jobs, storage devices, clients, media utilization, and other aspects of NetVault Backup.

To access help for **nvreport**, type:

```
nvreport -help
```

The **nvreport** utility uses “template” files to output the report data. The template files determine the content, layout, and format of the report. The report templates are located in the <NetVault Backup home>\reports\templates directory.

There are two methods to specify a template file to generate a report:

- **Using the actual filename:** You can use the “-templatefile” option to specify the actual template file that you want to use. With this option, you must provide the full file path for the template file.
- **Using the “nice name”:** Each template file has an alternate name value known as its “nice name.” This name is used for the template file in the NetVault WebUI. Specify this “Nice Name” with the “-templatename” option.

To access help for the template files, type:

```
nvreport -help templatename
```

Syntax

```
nvreport -server <server name> -class <class name> -templatename <template name>
```

```
nvreport -server <server name> -class <class name> -templatefile <full file path>
```

Options

Table 1. nvreport

Option	Description
-server	<p>Specifies the name of the NetVault Backup Server that administers the job.</p> <p>This option is required when a remote server administers the job. It can be omitted when a local server administers the job. The server name is case-sensitive.</p>
-class	<p>Specifies the report class. Class names are case-insensitive.</p> <p>The main purpose of a class is to organize the individual report components or template files into groups. These template files are used to generate the reports.</p> <p>When a class name is specified with the -class option, the default template file associated with the class is used to run a report.</p> <p>Example:</p> <pre>nvreport -class Clients</pre> <p>For more information about the available report classes, see Report classes</p>
-templatename	<p>Specifies the “nice name” of the template file.</p> <p>Example:</p> <pre>nvreport -templatename "Client Machines - cli default template"</pre> <p>Note the following:</p> <ul style="list-style-type: none">• If the “nice name” contains any spaces, enclose the variable in quotation marks (“ ”).• To locate the “nice name” for a template file, open the file in a text editor and note the string in the “%NICENAME” line <p>For more information, see Plain text template files.</p>
-templatefile	<p>Specifies the name of the template file. You must specify the full file path with this option.</p> <p>Example:</p> <pre>nvreport -templatefile C:\NetVaultBackup\reports\templates\logslidefault</pre> <p>Note the following:</p> <ul style="list-style-type: none">• The report templates are located in the <NetVault Backup home>\reports\templates directory.• If the file path contains any spaces, enclose the variable in quotation marks <p>For more information, see Plain text template files.</p>

Report classes

The following table provides a brief description of the report classes available in NetVault Backup.

Table 2. Report classes

Report class	Output
Advanced Options	Displays all Advanced Options Sets and their details.
Audits	Displays all operations attempted by a specific user account with their result (“Yes”, if granted; “No”, if denied) and date and time each operation was attempted.
Backup Targets	Displays all Backup Target Sets and their details.

Table 2. Report classes

Report class	Output
Client Groups	<p>Lists all client groups. The report includes:</p> <ul style="list-style-type: none"> • Group name • Group description • All current clients are member of this group ("Yes" or "No") • Client group members
Clients	<p>Displays the status of the added clients. The report includes:</p> <ul style="list-style-type: none"> • Client name • NetVault Backup version • Accessibility status ("Yes" or "No") • Client status ("Up" or "Down")
Defined Jobs	<p>Displays all job definitions. The report includes:</p> <ul style="list-style-type: none"> • Job ID • Job title • NetVault Backup Client name • Policy name (if applicable) • Plug-in name • Job type (Backup, Restore, or Report) • Schedule Set name • Selection Set name • Backup Target Set name • Advanced Options Set name
Drive Events	<p>Lists events related to drives controlled of the server. The report includes:</p> <ul style="list-style-type: none"> • Time • Date • Drive name • Event type, like start write, stop write
Drive Performance Statistics	<p>Displays the performance statistics for all drives controlled by the server. The report includes:</p> <ul style="list-style-type: none"> • Time at which the drive was accessed • Date on which the drive was accessed • Drive Name • Job ID • Instance ID • Average data transfer rate (kb/sec)
Drives	<p>Lists all drives accessible to NetVault Backup. The report includes:</p> <ul style="list-style-type: none"> • Drive Name • Product Name • Vendor Name • Drive status (Online or Offline) • Machine to which the drive or library is locally attached • Data written by this drive • Data read by this drive
Entry/Exit Ports	<p>Lists all entry/exit ports (EPorts) that exist in any libraries controlled of the server. The report also includes the details of media items residing in the E/E port.</p>

Table 2. Report classes

Report class	Output
Job History	<p>Provides a summary of jobs performed during the specified period. The report includes:</p> <ul style="list-style-type: none"> • Start date • Start time • Job ID • Instance ID • Phase ID • Job title • Job type (Backup, Restore, or Report) • Exit status of the job ("Completed", "Completed with errors" or "Failed") • Run length
Libraries	<p>Lists all libraries controlled by the server. The report includes:</p> <ul style="list-style-type: none"> • Library ID • Library name • Library status (Online or Offline) • Controlling NetVault Backup Server
Library Drives	<p>Lists all drives controlled by the server. The report also includes the details of media items residing in the drive.</p>
Library Slots	<p>Lists all slots that exist in libraries controlled by the server. The report also includes the details of media items residing in the slots.</p>
License Capabilities	<p>Provides a summary of available and used licenses for NetVault Backup.</p>
Media	<p>Lists media items in use by devices controlled by the server. The report includes:</p> <ul style="list-style-type: none"> • Group label • Media label • Amount of space available • Amount of space used • Media format (MTF=Windows or UTF8=Linux/ UNIX) • Needs import ("Yes" indicates that the media item is marked as Foreign and it needs to be scanned to read the on-tape indices into the NetVault Database) • Needs recovery ("Yes" indicates that the contents on the tape are considered suspect and it needs to be scanned for backups for which indexes are not recorded in NetVault Database) • Media item is marked unusable (Yes, if marked as unusable; No, if not marked as unusable)
Media Capacities	<p>Displays the media capacity details for media items available in the libraries and drives controlled by the server.</p>

Table 2. Report classes

Report class	Output
Media Job Contents	<p>Lists all backup savesets stored on available media. The report includes:</p> <ul style="list-style-type: none"> • Media label • Group label • Media barcode • Job title • NetVault Backup Client name • Job start date • Job start time • Amount of data transferred to media for the job • Saveset expiry date • Saveset expiry time
Media Requests	<p>Displays media request details. The report includes:</p> <ul style="list-style-type: none"> • Media request date • Media request time • Job ID • Request status
Media Segment Contents	<p>Provides a summary of media segments. The report includes:</p> <ul style="list-style-type: none"> • Media label • Media barcode • Job title • NetVault Backup Client name • Backup date • Backup time • Segment length
Media Transfer Requests	<p>Displays all transfer requests. The details include:</p> <ul style="list-style-type: none"> • Job ID • Instance ID • Type of transfer request ("Read" or "Write") • Request ID • Amount of data transferred
NetVault Event Types	Displays all event types.
NetVault Events	<p>Displays all events raised during the specified period. The report includes:</p> <ul style="list-style-type: none"> • Date and time • Event name • Event class • Event description • Event message
NetVault Logs	Displays all log messages. Based on the number of log entries that exist in the NetVault Database, it may take several minutes for this command to display the results.
Notifications	<p>Lists all events for which any notification method is set. The report includes:</p> <ul style="list-style-type: none"> • Event class • Event • User account to which the notification profile belongs (if applicable.) • Notification method

Table 2. Report classes

Report class	Output
Operator Messages	<p>Displays all outstanding operator messages. The report includes:</p> <ul style="list-style-type: none"> • Message ID • Date and time • Outstanding ("Yes", if outstanding; "No", if acknowledged) <p>If all the operator messages have been acknowledged or deleted, this report returns no information.</p>
Policies	<p>Provides a summary of backup policies. The report includes:</p> <ul style="list-style-type: none"> • Policy name • Total number of jobs created within the policy • Total number of clients added to the policy. • Current status of the policy: <ul style="list-style-type: none"> - OK: If all jobs in the policy have run successfully - Warnings: If one or more jobs have completed with warnings - Errors: If errors have occurred • List of clients added to the policy • Events defined for failed jobs • Events defined for jobs completed with warnings
Policy Clients	<p>Lists all clients included in a policy. The report includes:</p> <ul style="list-style-type: none"> • Policy name • Client name • Policy status <ul style="list-style-type: none"> - OK: If all of the Clients in the policy are accessible - Errors: If errors have occurred
Policy Jobs	<p>Lists all jobs included in a policy. The report includes:</p> <ul style="list-style-type: none"> • Policy name • Job title • Backup Selection Set name • Whether the job is active
Privileges	<p>Lists the privileges currently granted to each user.</p>
Report Templates	<p>Displays all report template files that are saved in the <code>templates</code> subdirectory (<code><NetVault Backup home>\reports\templates</code> on Windows and <code><NetVault Backup home>/reports/templates</code> on Linux). The report includes:</p> <ul style="list-style-type: none"> • Template filename • Class name • Output type (Plain text, HTML, or CSV)
Schedule Sets	<p>Displays all Schedule Sets and their details.</p>
Segments	<p>Lists all segments for a backup job. The report includes:</p> <ul style="list-style-type: none"> • Job ID • Instance ID • Offset, in bytes(starting point on the media where the segment of the job exists) • Overall size of the segment, in bytes • Media label • Media barcode
Selection Option Sets	<p>Displays all Backup Options Sets and their details.</p>

Table 2. Report classes

Report class	Output
Selection Sets	Displays all Selection Sets and their details
Users	Lists all NetVault Backup users. The report includes: <ul style="list-style-type: none"> • User name • Real name • User Identification Number (the IDs for the default users are: "Default = 0" and "Administrator = 1") • Workstation • Last date on which the user accessed NetVault Backup • Last time at which the user accessed NetVault Backup

Plain text template files

The following table provides the "nice name" and filename of the plain text template files.

Table 3. Plain text template files

Class name	Template file "nice name"	Template filename
Advanced Options	Advanced Options - cli default template	advancedoptionsclidefault
Audits	Audits - cli default template	auditclidefault
Backup Targets	Backup Targets - cli default template	backuptargetsclidefault
Client Groups	Client Groups - cli default template	groupsclidefault
Clients	Client Machines - cli default template	clientsclidefault
Defined Jobs	Defined Jobs - cli default template	jobdefinitionsclidefault
Drive Events	Drive Events - cli default template	driveeventsclidefault
Drive Performance Statistics	Drive Performance Statistics - cli default template	driveperformanceclidefault
Drives	Drives - cli default template	drivesclidefault
Entry/Exit Ports	Entry/Exit Ports - cli default template	entryexitportsclidefault
Job History	Executed Job History - cli default template	jobhistoryclidefault
Libraries	Libraries - cli default template	librariesclidefault
Library Drives	Library Drives - cli default template	librarydrivesclidefault
Library Slots	Library Slots - cli default template	libraryslotsclidefault
License Capabilities	This Server's License Capabilities - cli default template	licensecapsclidefault
Media	Media - cli default template	mediaclidefault
Media Capacities	Media Capacities - cli default template	mediacapacitiesclidefault
Media Job Contents	Media Contents Query - Textual	mediajobcontentsclidefault
Media Requests	Media Requests - cli default template	mediarequestsclidefault
Media Segment Contents	Media Segment Contents Query - Textual	mediasegmentcontentsclidefault
Media Transfer Requests	Media Transfer Requests - cli default template	mediatransfersclidefault
NetVault Event Types	NVBU Event Types - cli default template	eventtypesclidefault
NetVault Events	NVBU Events - cli default template	eventsclidefault
NetVault Logs	NVBU Logs - cli default template	logsclidefault
Notifications	User's Selected Notifications - cli default template	notificationsclidefault

Table 3. Plain text template files

Class name	Template file “nice name”	Template filename
Operator Messages	Operator Messages - cli default template	operatormessagesclidefault
Policies	Policies - cli default template	policiesclidefault
Policy Clients	Policy Clients - cli default template	policyclientsclidefault
Policy Jobs	Policy Jobs - cli default template	policyjobsclidefault
Privileges	Granted Privileges - cli default template	privilegesclidefault
Report Templates	Report Templates Installed on System	reporttemplatesclidefault
Schedule Sets	Schedule Sets - cli default template	schedulesclidefault
Segments	Segments - cli default template	segmentsclidefault
Selection Option Sets	Selection Option Sets - cli default template	seloptionsclidefault
Selection Sets	Selection Sets - cli default template	selectionsclidefault
Users	Users - cli default template	usersclidefault

Formatting the reports

The `nvreport` utility provides several options to format the layout and content of a report. The following sections outline the use of these options.

NOTE: Unless otherwise noted, the description of the options offered in this section assume that they are being used with report templates that use a “Plain Text” output type. These templates include “clidefault” or “- cli default template” in their filename. You can view these reports from a terminal session window.

Obtaining the real name

When a report is run and viewed from the CLI, the output includes several columns. The column header, referred to as “Field Name”, may not be the same as the “real name” of the column set up in the template file that is used to run the report. You must use the real name with the formatting options covered in this section.

You can use one of the following methods to find the real names:

- [Using the help option](#)
- [Using the template file](#)

Using the help option

To obtain a list of valid field names for a canned report class, type the following command:

```
nvreport -help fields [class name]
```

The output includes four columns: Real name, Field name, Data type, and Description.

This command displays all fields that are available with the specified canned report. It includes even those fields that are not displayed when you run the report. You can include these additional fields using the `format` option. For more information, see [Adding or removing columns](#).

To determine the default fields for a template file, follow these steps:

- 1 Run the report and note the default Field Name of each column.
- 2 Run the `nvreport -help fields [Class Name]` command.
- 3 Locate the appropriate Field Name in the list, and cross-reference its Real Name.

Using the template file

Open the template file in a text editor. In this file, the %FORMAT line provides the Real Name for the fields. You can find the template files in <NetVault Backup home>\reports\templates on Windows and <NetVault Backup home>/reports/templates on Linux.

The %FORMAT line of a template file only includes Real Names for the fields displayed when a report is run.

Sample template file:

```
%CLASS "Media"

%NICENAME "Media - cli default template"

%FORMAT "%MEDIAGROUP %LABEL %SPACELEFT %SPACEUSED

%MEDIAFORMAT %NEEDSIMPORT %NEEDSRECOVERY %UNUSABLE"

%SORT %MEDIAGROUP+ %LABEL+

%OUTPUTTYPE 0

%HEADERNAME "Default"

%FOOTERNAME "Default"
```

Using the format option

By default, a report is displayed in a pre-defined layout when run in the terminal window. You can use the -format option to specify the number of characters that are displayed in a column, insert a line break, or add or remove columns. The formatting options are described in the following sections:

- [Specifying maximum characters for a column](#)
- [Inserting a line break](#)
- [Adding or removing columns](#)

When you use the -format option, you must use the real name of the fields. Each name must be prefixed with a "%" symbol. If the real name includes the "%" symbol, use the escape sequence "%" when specifying the name. Moreover, you must specify all required fields in the syntax. If you omit any field in the syntax, it is not displayed in the output.

Specifying maximum characters for a column

To specify the maximum numbers of characters for a column, append two colons and a number to the Real Name:

```
-format "%<Real Name>::<Max characters>
```

Example:

```
nvreport -class "Media Requests" -format "%Date %JOBID %TRANSITION::3"
```

Inserting a line break

To include a line break between each entry in the report output, append "%\n" to the end of the list of fields named with the -format option:

```
-format "%<Real Name> %<Real Name> %\n
```

Example:

```
nvreport -class "Media Requests" -format "%Date %Time %JOBID %TRANSITION %\n"
```

Adding or removing columns

Some template files offer several additional fields that can be included in the output using the `-format` option. To add a column, obtain the full list of the available fields for a template file using the `nvreport -help field <class name>` command. Review the information offered in the Description column for each field, and include the applicable fields. Verify that you use the real name of the field.

The following example uses the “drives” canned report. It includes all the default fields and additionally displays the number of Write Errors for the drive.

Example:

```
nvreport -class drives -format "%DriveName %Product %Vendor %Status %DriveMachine  
%DriveDataWritten %DriveDataRead %DriveWriteErrors"
```

Using the sort option

The `-sort` option can be used to sort the entries on a selected field. A sort expression is specified in the following format:

```
-sort "[%field name] [+/-]"
```

- **[field name]:** Field on which the report is sorted.
- **[+/-]:** Use + to sort the output in ascending order of the specified field, or - to sort the output in descending order.

A report can be sorted by any field a class offers. Even a Real Name for the field that is not displayed in the output can be used for sorting the output.

When you use the `-sort` option, you must use the real name of the fields. Each name must be prefixed with a “%” symbol. If the real name includes the “%” symbol, use the escape sequence “%%” when specifying the name.

Example:

```
nvreport -class "Job History" -sort "%TITLE+"
```

You can specify multiple fields with the “`-sort`” option. The resulting report prioritizes the sort based on the order of the field names in the syntax. When using multiple sort fields, enclose all fields in quotation marks (“ ”).

Example:

```
nvreport -class "Job History" -sort "%TITLE+ %EXITSTATUS"
```

Using the include option

The `-include` option can be used to filter the data for a report. A filter expression is specified in the following format:

```
-include "[%field name] [operator] [constant]"
```

- **[field name]:** Real Name of the field.
- **[operator]:** The operator can be any of the following:
 - > (greater than)
 - >= (greater than or equal to)
 - < (less than)
 - <= (less than or equal to)
 - = (equal to)
 - != (not equal to)

- **[constant]**: The value to which the [field name] value is compared. For example, to include only entries that apply to the job assigned the Job ID of "42", you would include "42" as the [constant].

To join multiple filter expressions, use "AND" and "OR". In addition, use parenthesis to indicate the priority of the arguments.

Examples:

- `nvreport -class "Job History" -include "%JOBDEFINITIONID = 42`
- `nvreport -class "Job History" -include "(%JOBDEFINITIONID > 50 AND %INSTANCEID < 5) OR %TYPE = restore`

Constant types

Table 4. Constant types

Constant type	Description
Timepassed	<p>Use to compare fields that contain time interval values. For example, the amount of time it took to run a backup job. The value can be specified in the following formats:</p> <ul style="list-style-type: none"> • HH:MM:SS • HHMMSS
Boolean	<p>Use to compare fields that contain boolean values. Examples of boolean values:</p> <ul style="list-style-type: none"> • Yes or No • True or False
Date	<p>Use to compare fields that contain date values.</p> <p>Example:</p> <pre>nvreport -class "job history" -include "%STARTDATE >=[Date]"</pre> <p>The value can be specified in the following formats:</p> <ul style="list-style-type: none"> • YYYY/MM/DD • YYYYMMDD • now-[number value][time variable (YE = Year, MO = Month, WE = Week, DA = Date, HO = Hour, MI = Minute, SE = Second)] <p>For example, "now-1YE" would be one year ago.</p>
Daysinweek	<p>Use to compare fields that contain a day of the week.</p> <p>The value can be specified in the following format:</p> <ul style="list-style-type: none"> • Sunday = "SU" • Monday = "MO" • Tuesday = "TU" • Wednesday = "WE" • Thursday = "TH" • Friday = "FR" • Saturday = "SA"
Daysinmonth	<p>Use to compare fields that contain a specific date in the month. For multiple values use a comma separator and enclose all values in quotation marks.</p>

Table 4. Constant types

Constant type	Description
hdwmycount	<p>Use to compare fields that contain the count (total number) of Hours, Days, Weeks, Months and Years.</p> <p>The value can be specified in the following format: [#H] [#D] [#W] [#M] [#Y]</p> <p>For example, "12H 2W 10M 18Y" indicates 12 hours, two weeks, 10 months, and 18 years.</p> <p>Each time variable can be added or omitted as required.</p>
Integer (large value)	Use to compare fields that contain large integer values (for example, 764874497498723497)
Number	<p>Use to compare fields that store a numeric value.</p> <p>Example:</p> <pre>nvreport -class "job history" -include %INSTANCEID = 2</pre>
pluginscreen	N/A
selectiontree	N/A
String	<p>Use to compare fields that contain a string value.</p> <p>Example:</p> <pre>nvreport -class "job history" -include "%EXITSTATUS !=Failed"</pre> <p>Strings of text with spaces must be enclosed in quotation marks.</p>
Systime	<p>Use to compare fields that contain system time.</p> <p>The value can be specified in the following format:</p> <ul style="list-style-type: none"> • HH:MM:SS • HHMMSS (221011) • Past Time: now-[number value][time variable (YE = Year, MO = Month, WE = Week, DA = Date, HO = Hour, MI = Minute, SE = Second)]. <p>For example, "now-30mi" would be 30 hours ago.</p>
Time	<p>Use to compare fields that contain any time value.</p> <p>Example</p> <pre>nvreport -class "job history" -include "%STARTTIME >= [Time]"</pre> <p>The value can be specified in the following format:</p> <ul style="list-style-type: none"> • HH:MM:SS • HHMMSS (221011) • Past Time: now-[number value][time variable (YE = Year, MO = Month, WE = Week, DA = Date, HO = Hour, MI = Minute, SE = Second)]. <p>For example, "now-12ho" would be 12 hours ago.</p>
Unique	N/A
weeksmonth	<p>Use to compare fields that store a specific week in the month.</p> <p>The value can be specified in the following format: [Week Number]: Required week numbers</p> <p>"L" refers to the last week in the month. For example, 134L would include the first, third, fourth, and last week in the month.</p>

Using the title option

When a report is run and viewed from the command line, it is given the default title Report “CLI Report” in the output. The `-title` option can be used to change the report title. The `-title` option is specified in the following format:

```
-title <NewReport Title>
```

If a title is to contain any spaces, the entire value must be enclosed in quotation marks. While the “`-title`” option can be used to label a CLI-output report, it is better suited to label a report that is output to file, and viewed outside of the CLI.

Creating external report files

The report files generated using the `nvreport` utility can be saved to the `output` subdirectory in the `reports` directory (<NetVault Backup home>\reports\output on Windows and <NetVault Backup home>/reports/output on Linux) and used as required. For example, they can be opened for viewing in a browser or sent as email attachments. The procedure for creating an external report file includes the steps outlined in the following sections:

- [Selecting the template file](#)
- [Specifying the outputdir](#)
- [Specifying the appendoutput option](#)
- [Using the title option](#)

Selecting the template file

There are two types of report template files.

- **HTML template files:** These templates are used to by the NetVault WebUI. You can use them with the `-outputdir` option to create HTML-based external files. For more information about these templates, see [HTML template files](#).
- **Plain text template files:** These templates are used by the CLI utilities to display output in the terminal window. You can use them with the `-outputdir` option to create plain text external files. The plain-text template files contain the text “`clidefault`” in their filename or “cli default file” or “textual” in their “Nice Name.” For more information about these templates, see [Plain text template files](#).

Use the following options to create the report file:

- `-templatename`: Specifies the “nice name” of the template file
- `-templatefile`: Specifies the name of the template file. You must specify the full file path with this option. The report templates are located in the <NetVault Backup home>\reports\ templates directory.

① **NOTE:** While it is possible to use the “`-class`” option to generate a report file for viewing outside the terminal session window, we recommend that you avoid using it. The “`-class`” option is designed to be used with a default template file and create a report for viewing in the terminal session window. You may not obtain the desired result in an external report with the “`-class`” option.

Specifying the outputdir

The output directory is created in <NetVault Backup home>\reports\output on Windows and <NetVault Backup home>/reports/output on Linux.

The syntax for this option is:

```
-outputdir <name for subdirectory>
```

Example:

```
nvreport -templatename "Executed Job History" -outputdir "Test01"
```

Note the following:

- If an existing subdirectory is specified with the "-outputdir" option, it is overwritten.
The following command creates a subdirectory named "report" and saves the report file "output.html" in this directory:

```
nvreport -templatename "Client Groups" -outputdir report
```


When you generate another report, it overwrites the existing "report" subdirectory and the "output.html" file with the new file:

```
nvreport -templatename "Defined Jobs" -outputdir report
```


If you do not want to overwrite an existing report file, specify a new directory or use the -appendoutput option.
- The HTML report templates contain various artwork files in their layout. When you use an HTML template, the artwork files are automatically copied to the new subdirectory.

Specifying the appendoutput option

If an existing subdirectory is specified with the -outputdir option, it is overwritten when a new report is generated. To retain the contents in an existing report file, use the -appendoutput option. It allows you to append the new report data to the existing report file.

Example:

```
nvreport -templatename "Restore Summary" -outputdir "Test01" -appendoutput
```

Note the following:

- The -appendoutput option must be used with the -outputdir option.
- This option allows you to combine two different types of templates.
- This option allows you to combine the HTML and plain text output types.

Using the title option

The -title option can be used with the -outputdir option to assign a user-defined title to the saved report file. This syntax for using this option is:

```
-title <NewReport Title>
```

If a title is to contain any spaces, the entire value must be enclosed in quotation marks.

Example:

```
nvreport -templatename "Historic Jobs - By Date" -outputdir "Test01"  
-title "Job History - By Date"
```

Note the following:

- This option can be used with the `-outputdir` option to add a title to any format of template (HTML or plain text).
- When used with the `-appendoutput` option, the `-title` option is used as the title of the report that is appended to the existing "output.html" file. The existing report maintains its existing title.

HTML template files

The following table provides the "nice name" and filename of the HTML template files.

Table 5. HTML template files

Template filename	Nice name	Description
activejobs	Currently Active Jobs	Lists all active jobs. The report includes: <ul style="list-style-type: none">• Job ID• Job title• Client name• Policy name• Running status (for example, Writing to Media)
alldrives	All Drives	Lists all drives controlled by the NetVault Backup Server. The report includes: <ul style="list-style-type: none">• Name of the machine to which the drive is attached• Drive Name• Drive status (online or offline)• Amount of data read (zero if no jobs are active)• Amount of data written• Number of read errors• Number of write errors• Last write date• Last read date• Last clean date• Amount of data written since it was last cleaned• Number of times the drive has been used since it was last cleaned
allfailedpolicyjobs	Failed Policy Jobs	Provides a summary of failed policy jobs for the specified period. The report includes: <ul style="list-style-type: none">• Policy name• Client name• Job title• Plug-in name• Start date• Start time• Run length• Exit status

Table 5. HTML template files

Template filename	Nice name	Description
clientgroups	Client Groups	Lists all client groups. The report includes: <ul style="list-style-type: none"> • Group name • Group description • All current clients are member of this group ("Yes" or "No") • Client group members
clientstatuses	Client Statuses	Displays the status of added clients. The report includes: <ul style="list-style-type: none"> • Client name • NetVault Backup version • Client accessibility status ("Yes" or "No") • Client status ("Up" or "Down")
errorlogs	Recent Error Logs	Lists error logs generated during the specified period. The report includes: <ul style="list-style-type: none"> • Date and time • Client name • Job ID • Instance ID • Error message • Warning level
events	NetVault Events	Lists events raised during the specified period. The report includes: <ul style="list-style-type: none"> • Date and time • Event name • Event class • Event description • Event message
expiredofflinemedia	Expired Offline Media	Lists expired offline media. The report includes: <ul style="list-style-type: none"> • Media label • Media group label • Barcode • Last read or write date • Offsite location
failedrequests	Failed ULA Requests	Provides a summary of failed user requests for the specified period.

Table 5. HTML template files

Template filename	Nice name	Description
fullonlinemedia	Full Online Media	<p>Lists online storage devices that are full. The report includes:</p> <ul style="list-style-type: none"> • Media label • Media group label • Barcode • Last read or write date • Media expiry date • Library name • Slot number • Offsite location • Needs import ("Yes" indicates that the media item is marked as Foreign and it needs to be scanned to read the on-tape indices into the NetVault Database)
globalnotifications	Global Notifications	<p>Lists events that are included in the global notification profile. The report includes:</p> <ul style="list-style-type: none"> • Event class • Configured notification environment • Event • Notification method
historicjobs	Historic Jobs - By Date	<p>Displays date-wise summary of jobs performed during the specified period. The report includes:</p> <ul style="list-style-type: none"> • Start date and time • Run length
historicjobsbysize	Historic Jobs - By Size	<p>Displays size-wise summary of jobs performed during the specified period. The report includes:</p> <ul style="list-style-type: none"> • Job ID • Job title • Instance ID • NetVault Backup Client name • Selection Set name • Backup size • Exit status • Start date and time • Run length
jobdefinitions	Defined Jobs	<p>Displays all job definitions. The report includes:</p> <ul style="list-style-type: none"> • Job ID • Job title • NetVault Backup Client name • Policy name (if applicable) • Plug-in name • Job type (Backup, Restore, or Report) • Schedule Set name • Selection Set name • Backup Target Set name • Advanced Options Set name

Table 5. HTML template files

Template filename	Nice name	Description
jobhistory	Executed Job History	Provides a summary of jobs performed during the specified period. The report includes: <ul style="list-style-type: none"> • Start date and time • End time • Job ID • Instance ID • Phase ID • Job title • Job type (Backup, Restore, or Report) • Exit status of the job ("Completed", "Completed with errors" or "Failed") • Run length
libraryblankcounts	Blank Media Items In Libraries	Displays the number of blank media items residing in the libraries controlled by the NetVault Backup Server. The report includes: <ul style="list-style-type: none"> • Library name • Blank media count
librarycontents	Libraries' Media Contents	Provides a summary of currently online media items. The report includes: <ul style="list-style-type: none"> • Library name • Drive name • Slot number • Media label • Barcode • Media group label • Amount of space used and left
logs	NetVault Logs	Displays system logs generated during the specified period. The report includes: <ul style="list-style-type: none"> • Job ID • Log class • Warning level • Date and time • Client that generated the log • Log message
mediacontentsquery	Media Contents Query	Provides a summary of data stored on individual media items. The report includes: <ul style="list-style-type: none"> • Media label • Media group label • Barcode • Job title • Client name • Plug-in name • Start date and time • Backup type • Backup size • Media expiry date and time

Table 5. HTML template files

Template filename	Nice name	Description
mediageneral	Media — General	<p>Provides a summary of used media items. The report includes:</p> <ul style="list-style-type: none"> • Media label • Barcode • Media type (tape or disk file) • Media format (MTF=Windows or UTF8=Linux/UNIX) • Name of the machine to which the drive is attached • Amount of space available • Amount of space used • Media item is marked unusable (Yes, if marked as unusable; No, if not marked as unusable) • Media item is marked read-only (Yes, if marked as read-only; No, if not marked as read-only)
mediasegmentcontentsquery	Media Segment Contents Query	<p>Provides a summary of data stored on each segment. The report includes:</p> <ul style="list-style-type: none"> • Media label • Barcode • Job title • Client name • Plug-in name • Backup date • Backup time • Length of the segment (in number of bytes)
mediautilization	Media Utilization	<p>Displays the storage utilization statistics for devices controlled by the NetVault Backup Server. The report includes:</p> <ul style="list-style-type: none"> • Media label • Barcode • Media group label • Amount of space available • Amount of space used
notifications	Users' Selected Notifications	<p>Lists all events that have been included in any user notification profile. The report includes:</p> <ul style="list-style-type: none"> • Event name • Event description
offlinedevices	Offline Devices	<p>Lists devices that are currently offline.</p>
outstandingopmsgs	Outstanding Operator Messages	<p>Lists operator messages that have not been acknowledged. The report includes:</p> <ul style="list-style-type: none"> • Date and time • Operator message text <p>If all messages have been acknowledged or deleted, this report returns no information</p>

Table 5. HTML template files

Template filename	Nice name	Description
overnight_jobs_failed	Failed Overnight Backup Jobs	Provides a summary of overnight backup jobs that failed. The report includes: <ul style="list-style-type: none"> • Job ID • Job title • Client name • Policy name • Exit status
overnight_jobs_failed_count	Count Of Failed Overnight Backup Jobs	Displays the total number of the overnight backup jobs that failed (for example, "0 backup jobs failed").
overnight_jobs_successful_count	Count Of Successful Overnight Backup Jobs	Displays the total number of the overnight backup jobs that completed successfully (for example, "12 backup jobs finished successfully").
overnight_jobs_total_data_stored	Count of Data Stored In Overnight Jobs	Displays the total amount of the data stored in overnight jobs (for example, "Approx. 348GB of data was stored").
overnight_jobs_warnings_count	Count Of Overnight Backup Jobs Finished With Warnings	Displays the total number of the overnight backup jobs that completed with warnings (for example, "1 backup job finished with warnings").
policiessummary	Policy Basics	Provides a summary of backup policies. The report includes: <ul style="list-style-type: none"> • Policy name • Total number of jobs created within the policy • Total number of clients added to the policy • Policy status: <ul style="list-style-type: none"> - OK: All policy jobs have completed successfully - Warnings: One or more policy jobs have completed with warnings - Errors: One or more policy jobs have failed • List of clients added to the policy • Events defined for failed jobs • Events defined for jobs completed with warnings
restoresummary	Restore Summary	Provides a summary of all restore jobs. The report includes: <ul style="list-style-type: none"> • Start date and time • Client name • Job title • Job ID • Instance ID • Run length • Exit status
serverlicensecapabilities	Server License Capabilities And Usage	Displays available and used licenses for NetVault Backup. The report includes: <ul style="list-style-type: none"> • License description (for example, number of clients allowed, number of library units, and others) • Available licenses • Used licenses

Table 5. HTML template files

Template filename	Nice name	Description
serverlicenseflags	Server License Flags	Lists the functionality offered by current Server License type.
single_job_drives_events	Single Job's Drive Events	Displays the transfer rates for the drives used in a specific job.
single_job_logs	Single Job's Logs	Displays the log entries for a particular job. The report includes: <ul style="list-style-type: none"> • Date and time of log entry • Log class • Warning level • Client that generated the log • Log message
single_job_media	Media Used by Single Backup	Displays the media usage details for a particular job. The report includes: <ul style="list-style-type: none"> • Barcode • Media label • Media type (tape or disk file) • Offsite location
single_job_media_transfers	Single Job's Media Transfers	Displays the data transfer details for a particular job. The report includes: <ul style="list-style-type: none"> • Date and time the media transfer request was received • Date and time the requested media transfer began • Date and time the requested media transfer completed • Type of media transfer (read or write0) • Amount of data transferred
single_job_summary	Single Job Main Summary	Provides a summary of a particular job. The report includes: <ul style="list-style-type: none"> • Job ID • Job title • Job type (backup, restore, or report) • Plug-in name • Instance ID • Start date and time • End date and time • Exit status • Size of data transferred • Transfer rate (applies only to backup jobs)
single_job_xfer_rates	Single Job's Data Transfer Rate	Displays the data transfer rate for a particular job. The report includes: <ul style="list-style-type: none"> • Date and time of event • Drive name • Drive events

Table 5. HTML template files

Template filename	Nice name	Description
singlepolicybytecounts	Policy Totals	Displays the backup size and transfer rate for a backup policy. The report includes: <ul style="list-style-type: none"> • Total backup size • Average backup size • Total transfer rate • Average transfer rate
singlepolicyclients	Policy Clients	Lists all clients included in a policy. The report includes: <ul style="list-style-type: none"> • Policy name • Client name • Policy status: <ul style="list-style-type: none"> - OK: All policy jobs have completed successfully - Warnings: One or more policy jobs have completed with warnings - Errors: One or more policy jobs have failed
singlepolicyfailedjobs	Failed Jobs Within Single Policy	Lists all failed jobs for a backup policy. The report includes: <ul style="list-style-type: none"> • Policy name • Client name • Job title • Plug-in name • Start date • Start time • Run length • Exit status
singlepolicyjobs	Defined Policy Jobs	Provides a summary of jobs added to a policy. The report includes: <ul style="list-style-type: none"> • Job name • Policy name • Whether the job is currently active • Backup Selection Set name • Backup Options Set name • Schedule Set name • Target Set name • Advanced Options Set name
singlepolicystatus	Policy Status Information	Displays the status of a particular policy. The report includes: <ul style="list-style-type: none"> • Policy name • Number of clients added to the policy • Number of jobs added to the policy • Failed jobs • Jobs completed with warnings • Policy status
singleusersaudittrail	Single User's Audit Trail	Displays auditor logs for the specified user account.

Table 5. HTML template files

Template filename	Nice name	Description
userdefinedeventtypes	User-Defined Event Types	Lists all user-defined events. The report includes: <ul style="list-style-type: none"> • Event class • Event • Notification method • Configured notification environment (if applicable)
userdetails	User Details	Displays the details of NetVault Backup users. The report includes: <ul style="list-style-type: none"> • Account name • Real name • Description • Location • Contact information • Last logon date and time
userprivileges	User Privileges	Lists privileges granted to individual users.
usersmediausage	Quotas And Media Usage	Provides a summary of used and assigned media quota for each user account. The report includes: <ul style="list-style-type: none"> • Account name • Media quota • Media used
workstationclientfailedjobs	Failed Workstation Client Jobs	Lists all failed backups jobs for Workstation Clients.
workstationclienthistoricjobsbyclient	Workstation Client Jobs — By Client	Displays client-wise summary of Workstation client backup jobs.
workstationclienthistoricjobsbydate	Workstation Client Jobs — By Date	Displays date-wise summary of Workstation client backup jobs (latest first).
workstationclientinactiveforaweek	Workstation Clients Inactive For A Week	Lists Workstation Clients that have not had a backup attempted for more than seven (7) days. This report can be used to determine which Workstation Clients have not connected to the network where the NetVault Backup Server resides long enough for a backup to occur. It helps you to identify the workstation data that may be at risk by not being protected for long-term retention or disaster recovery.
workstationclientsuccessfuljobs	Workstation Client Successful Backup Jobs	Lists Workstation Client backups that completed successfully.

Dell listens to customers and delivers worldwide innovative technology, business solutions and services they trust and value. For more information, visit www.software.dell.com.

Contacting Dell

Technical Support:
[Online Support](#)

Product Questions and Sales:
(800) 306-9329

Email:
info@software.dell.com

Technical Support Resources

Technical support is available to customers who have purchased Dell software with a valid maintenance contract and to customers who have trial versions. To access the Support Portal, go to <https://support.software.dell.com/>.

The Support Portal provides self-help tools you can use to solve problems quickly and independently, 24 hours a day, 365 days a year. In addition, the portal provides direct access to product support engineers through an online Service Request system.

The site enables you to:

- Create, update, and manage Service Requests (cases)
- View Knowledge Base articles
- Obtain product notifications
- Download software. For trial software, go to [Trial Downloads](#).
- View how-to videos
- Engage in community discussions
- Chat with a support engineer