

## Scrollbar attribute's

Sr.No.	Option & Description
1	<b>activebackground</b> The color of the slider and arrowheads when the mouse is over them.
2	<b>bg</b> The color of the slider and arrowheads when the mouse is not over them.
3	<b>bd</b> The width of the 3-d borders around the entire perimeter of the trough, and also the width of the 3-d effects on the arrowheads and slider. Default is no border around the trough, and a 2-pixel border around the arrowheads and slider.
4	<b>command</b> A procedure to be called whenever the scrollbar is moved.
5	<b>cursor</b> The cursor that appears when the mouse is over the scrollbar.
6	<b>elementborderwidth</b> The width of the borders around the arrowheads and slider. The default is <code>elementborderwidth=-1</code> , which means to use the value of the <code>borderwidth</code> option.
7	<b>highlightbackground</b> The color of the focus highlight when the scrollbar does not have focus.
8	<b>highlightcolor</b> The color of the focus highlight when the scrollbar has the focus.
9	<b>highlightthickness</b>

## Scrollbar attribute's

	<p>The thickness of the focus highlight. Default is 1. Set to 0 to suppress display of the focus highlight.</p>
10	<p><b>jump</b></p> <p>This option controls what happens when a user drags the slider. Normally (jump=0), every small drag of the slider causes the command callback to be called. If you set this option to 1, the callback isn't called until the user releases the mouse button.</p>
11	<p><b>orient</b></p> <p>Set orient=HORIZONTAL for a horizontal scrollbar, orient=VERTICAL for a vertical one.</p>
12	<p><b>repeatdelay</b></p> <p>This option controls how long button 1 has to be held down in the trough before the slider starts moving in that direction repeatedly. Default is repeatdelay=300, and the units are milliseconds.</p>
13	<p><b>repeatinterval</b></p> <p>repeatinterval</p>
14	<p><b>takefocus</b></p> <p>Normally, you can tab the focus through a scrollbar widget. Set takefocus=0 if you don't want this behavior.</p>
15	<p><b>troughcolor</b></p> <p>The color of the trough.</p>
16	<p><b>width</b></p> <p>Width of the scrollbar (its y dimension if horizontal, and its x dimension if vertical). Default is 16.</p>

# Scrollbar attribute's

## Methods

Scrollbar objects have these methods –

Sr.No.	Method & Description
1	<b>get()</b>  Returns two numbers (a, b) describing the current position of the slider. The a value gives the position of the left or top edge of the slider, for horizontal and vertical scrollbars respectively; the b value gives the position of the right or bottom edge.
2	<b>set ( first, last )</b>  To connect a scrollbar to another widget w, set w's xscrollcommand or yscrollcommand to the scrollbar's set() method. The arguments have the same meaning as the values returned by the get() method.