

# 第三方平台对接Nginx配置方法

## 简介

WebRTC (Web Real-Time Communication) 是一种支持网页浏览器进行实时语音对话或视频聊天的技术。

由于WebRTC技术在实现实时通信时涉及敏感的用户数据和媒体流，为了确保这些数据的安全传输，避免潜在的安全威胁，如中间人攻击和数据泄露等，WebRTC规范要求所有使用WebRTC的应用都必须在HTTPS环境下运行。

HTTPS通过SSL/TLS加密，为数据传输提供了安全的通道，保证了用户信息在互联网上的传输过程中不被窃听或篡改。

因此，开发和部署时，必须确保服务器支持并强制使用HTTPS协议。

## nginx.conf server的配置

### 1、配置服务器地址和端口

```
1 # 配置服务器ip地址
2 set $dispatch_server_ip 'https://120.xx.xxx.xx:443'; // 配置为应急指挥调度平台所在
   的ip地址和端口
```

### 2、允许头部使用下划线

```
1 # 允许头部使用下划线的
2 underscores_in_headers on;
```

## nginx.conf location的配置

### 请求接口的代理配置

```
1 # 请求接口代理
2 location /api/v2 {
3     proxy_ssl_verify    off;
4     proxy_redirect      off;
5     proxy_set_header    Host                $host;
6     proxy_set_header    X-Real-IP          $remote_addr;
7     proxy_set_header    X-Forwarded-For    $proxy_add_x_forwarded_for;
8     proxy_pass            $dispatch_server_ip;
9 }
```

## 事件上报的代理配置

```
1 # 事件上报代理
2 location /socket.io {
3     proxy_ssl_verify    off;
4     proxy_set_header    Upgrade          $http_upgrade;
5     proxy_set_header    Connection      "upgrade";
6     proxy_http_version  1.1;
7     proxy_pass           $dispatch_server_ip;
8 }
```

## WebRTC的代理配置

```
1 # webrtc代理
2 location /webrtcMedia {
3     proxy_ssl_verify    off;
4     proxy_set_header    Upgrade          $http_upgrade;
5     proxy_set_header    Connection      "upgrade";
6     proxy_http_version  1.1;
7     proxy_pass           $dispatch_server_ip;
8 }
```

## 视频播放的代理配置

```
1 # 视频播放代理
2 location /rtspplay {
3     proxy_ssl_verify    off;
4     proxy_set_header    Upgrade          $http_upgrade;
5     proxy_set_header    Connection      "upgrade";
6     proxy_http_version  1.1;
7     proxy_pass           $dispatch_server_ip;
8 }
```

## SSE的代理配置【可选】

```
1 # SSE代理
2 location /stream {
3     proxy_ssl_verify    off;
4     proxy_set_header    Host                $host;
5     proxy_set_header    Upgrade            $http_upgrade;
6     proxy_set_header    Connection        "upgrade";
7     proxy_set_header    X-Real-IP         $remote_addr;
8     proxy_set_header    X-Forwarded-For   $proxy_add_x_forwarded_for;
9     proxy_set_header    X-Forwarded-Proto $scheme;
10    proxy_cache           off;
11    proxy_buffering        off;
12    proxy_http_version     1.1;
```

```
13     chunked_transfer_encoding      off;
14     proxy_pass $dispatch_server_ip;
15 }
```

## nginx.conf配置demo

```
1  # 应急指挥调度系统Nginx代理配置
2  server {
3      listen      2443 ssl; # 监听的端口
4      server_name localhost;
5
6      ssl_certificate      192.168.1.200.pem; # 自签证书
7      ssl_certificate_key  192.168.1.200.key; # 自签证书
8
9      ssl_session_cache    shared:SSL:1m;
10     ssl_session_timeout  5m;
11     ssl_ciphers           HIGH:!aNULL:!MD5;
12     ssl_prefer_server_ciphers on;
13
14     # 允许头部使用下划线的
15     underscores_in_headers on;
16
17     # 配置服务器ip地址和端口
18     set $dispatch_server_ip 'https://120.xx.xxx.xxx:443';
19
20     # 页面demo
21     location /demo {
22         alias    html;
23         index    index.html index.htm;
24     }
25
26     # 请求接口代理
27     location /api/v2 {
28         proxy_ssl_verify    off;
29         proxy_redirect      off;
30         proxy_set_header    Host                $host;
31         proxy_set_header    X-Real-IP          $remote_addr;
32         proxy_set_header    X-Forwarded-For    $proxy_add_x_forwarded_for;
33         proxy_pass $dispatch_server_ip;
34     }
35
36     # 事件上报代理
37     location /socket.io {
38         proxy_ssl_verify    off;
39         proxy_set_header    Upgrade            $http_upgrade;
40         proxy_set_header    Connection        "upgrade";
41         proxy_http_version  1.1;
42         proxy_pass $dispatch_server_ip;
43     }
44
45     # webrtc代理
```

```

46     location /webrtcMedia {
47         proxy_ssl_verify    off;
48         proxy_set_header    Upgrade          $http_upgrade;
49         proxy_set_header    Connection      "upgrade";
50         proxy_http_version  1.1;
51         proxy_pass           $dispatch_server_ip;
52     }
53
54     # 视频播放代理
55     location /rtspplay {
56         proxy_ssl_verify    off;
57         proxy_set_header    Upgrade          $http_upgrade;
58         proxy_set_header    Connection      "upgrade";
59         proxy_http_version  1.1;
60         proxy_pass           $dispatch_server_ip;
61     }
62
63     # SSE代理
64     location /stream {
65         proxy_ssl_verify    off;
66         proxy_set_header    Host            $host;
67         proxy_set_header    Upgrade          $http_upgrade;
68         proxy_set_header    Connection      "upgrade";
69         proxy_set_header    X-Real-IP       $remote_addr;
70         proxy_set_header    X-Forwarded-For $proxy_add_x_forwarded_for;
71         proxy_set_header    X-Forwarded-Proto $scheme;
72         proxy_cache          off;
73         proxy_buffering      off;
74         proxy_http_version   1.1;
75         chunked_transfer_encoding off;
76         proxy_pass           $dispatch_server_ip;
77     }
78
79 }

```

## dispatch-sdk.js的初始化配置

详情请看 `demo/html/assets/index.js`

```

1  var serverAddr = "https://192.168.1.10:2443"; # 配置nginx配置的服务器和端口
2
3  //创建sdk客户端
4  var client = DispRTC.createClient({
5      proxy: true, // 是否为代理服务器
6      server: serverAddr, // 服务器地址
7      token: token, //token = JSON.parse(sessionStorage.getItem("DispRTC-
      token")).content; sdk的token
8  });

```