

Table Of Contents

Table Of Contents 1

Task: View / Display FreeBSD Routing Table 2

Task: FreeBSD Set a default route 2

How do I save routing information to a configuration file? 2

Task: Start and Stop FreeBSD Configured Interfaces 3

Further readings: 3

[Home](#) > [Faq](#) > [FreeBSD](#)

FreeBSD Set a Default Route / Gateway

Posted by [Vivek Gite](#) <vivek@nixcraft.com>



Q. How do I modify or set a default route for my FreeBSD server? How do I make default route configuration persistent?

A. The route command is used under FreeBSD to manually manipulate the network routing tables. It provides six commands:

=> **add** : Add a route.

=> **flush** : Remove all routes.

=> **delete** : Delete a specific route.

=> **change** : Change aspects of a route (such as its gateway).

=> **get** : Lookup and display the route for a destination.

=> **monitor** : Continuously report any changes to the routing information base, routing lookup misses, or suspected network partitionings.

Task: View / Display FreeBSD Routing Table

Use netstat command with -r option:

```
$ netstat -r
$ netstat -rn
```

Output:

```
Routing tables

Internet:
Destination      Gateway          Flags    Refs      Use  Netif  Expire
default          61.221.xx.yy    UGS        0       247    em1
10               10.10.110.5     UGS        0        50    em0
10.10.110/26     link#1          UC         0         0    em0
10.10.110.5      00:1b:0d:e6:58:40 UHLW       2         0    em0    1145
61.221.xx.yy/29  link#2          UC         0         0    em1
61.221.xx.yy     00:1b:0d:e6:57:c0 UHLW       2         0    em1    1055
61.221.xx/24     link#2          UC         0         0    em1
127.0.0.1        127.0.0.1       UH         0         0    lo0
```

The first two line displays default routes.

Task: FreeBSD Set a default route

All network packets that cannot be sent according to the previous entries of the routing table are sent through the following default gateway:

```
# route add default 192.168.1.254
```

How do I save routing information to a configuration file?

If you reboot FreeBSD box, the routing configuration will be lost i.e. the routing information will not persist. You need to edit /etc/rc.conf file to set default route:

```
# vi /etc/rc.conf
```

Set default route by editing defaultrouter variable:

```
defaultrouter="192.168.1.254"
```

Save and close the file.

Task: Start and Stop FreeBSD Configured Interfaces

To apply changes to a configuration file, [you need to stop and restart the corresponding FreeBSD networking interface](#) [2]. The following command will also update routing information:

```
# /etc/rc.d/netif restart  
# /etc/rc.d/routing stop  
# /etc/rc.d/routing start
```

Further readings:

- Read man pages netstat, route, rc.conf

4000+ howtos and counting! Want to read more Linux / UNIX howtos, tips and tricks? Subscribe to our [daily email](#) newsletter or [weekly newsletter](#) to make sure you don't miss a single tip/tricks. Alternatively, subscribe via [RSS/XML](#) feed.

Article printed from Frequently Asked Questions About Linux / UNIX: <http://www.cyberciti.biz/faq/>

URL to article: <http://www.cyberciti.biz/faq/freebsd-setup-default-routing-with-route-command/>

URLs in this post:

[1] Image: <http://www.cyberciti.biz/faq/faq/category/freebsd/>

[2] you need to stop and restart the corresponding FreeBSD networking interface: <http://www.cyberciti.biz/tips/freebsd-how-to-start-restart-stop-network-service.html>