

Table Of Contents

| | |
|--|---|
| Table Of Contents | 1 |
| HP-UX xntpd server configuration | 2 |
| SAM - GUI Admin Tool | 3 |

[Home](#) > [Faq](#) > [HP-UX Unix](#)

HP-UX UNIX Configure an NTP Server

Posted by [Vivek Gite](#) <vivek@nixcraft.com>

[1]

Q. How do I configure an NTP (network time protocol) Server under HP-UX UNIX server as my applications rely on the system clock accuracy to get current time / run reports?

A. NTP is used for time synchronization. Many applications such as backup shell/perl scripts, make utility and others depends upon accurate system time.

HP-UX xntpd server configuration

xntpd server (daemon) is used by HP-UX. Open file /etc/rc.config.d/netdaemons:

```
# vi /etc/rc.config.d/netdaemons
```

Make sure following variables are defined and XNTPD is set to 1:

```
export NTPDATE_SERVER='ntp.mycorp.com pool.ntp.org in.pool.ntp.org'
export XNTPD=1
export XNTPD_ARGS=
```

Save and close the file. Where,

- **NTPDATE_SERVER** : **space-separated list of timeserver / IPs** - If server uses the radio clock / system time, **leave the NTPDATE_SERVER blank**.
- **XNTPD** : set it to 1 to enable NTP
- **XNTPD_ARGS** : set options, see man page

Make sure correct timezone is setup in /etc/TIMEZONE file (look for TZ variable):

```
# vi /etc/TIMEZONE
```

Save and close the file. Open /etc/ntp.conf file:

```
vi /etc/ntp.conf
```

Make sure server are defined:

```
server unix-box-ntp
server delhi-ntp
peer delhi-noc-ntp
driftfile /etc/ntp.drift
```

Close and save the file. Where,

- **server** : ntp server used (poll) to obtain time
- **peer** : a peer relationship with another ntp server
- **driftfile** : track local clock time (drift of the local clock)

Start HP-UX ntp service:

```
# /sbin/init.d/xntpd start
# /sbin/init.d/xntpd stop <-- stop ntp service
```

Verify that everything is working fine:

```
# ntpq -p
```

Watch out log file /var/adm/syslog/syslog.log for errors:

```
# tail -f /var/adm/syslog/syslog.log
```

Make sure xntpd is running:

```
# ps -ef | grep xntpd
```

SAM - GUI Admin Tool

=> SAM can also be used to configure NTP service under HP-UX, just start SAM and open time window.

4000+ howtos and counting! Want to read more Linux / UNIX howtos, tips and tricks? Subscribe to our [daily email](#) newsletter or [weekly newsletter](#) to make sure you don't miss a single tip/tricks. Alternatively, subscribe via [RSS/XML](#) feed.

Article printed from Frequently Asked Questions About Linux / UNIX: <http://www.cyberciti.biz/faq/>

URL to article: <http://www.cyberciti.biz/faq/howto-configure-hpux-unix-xntpd-ntp-server/>

URLs in this post:

[1] Image: <http://www.cyberciti.biz/faq/faq/category/unix/>

Copyright © 2006-2010 [nixCraft](#). All rights reserved. This print / pdf version is for personal non-commercial use only. More details <http://www.cyberciti.biz/tips/copyright>.