

- Lab 4 : Routing and switching
- Lecturer : Prof. Oumaima FADI
- T.A: Prof. Abdoulghaniyu HARAZEEM

Lab 7 – Routing and switching

Objective:

In this exercise, you will practice configuring IPv6 addresses on a router, servers, and clients. You will also practice checking IPv6 addressing.

We will focus on the following:

- Part 1: Configure IPv6 Addressing on the Router
- Part 2: Configure IPv6 Addressing on Servers
- Part 3: Configure IPv6 Addressing on Clients
- Part 4: Test and Verify Network Connectivity

Instructions:


1. The lab report must be submitted one week after the session in electronic format to Moodle platform
2. The lab must be done in class in groups of maximum 2 students.
3. Groups should remain the same for both reports and upcoming labs.

Note: Use Router 1941, if serial is missing, add the WIC-2T or HWIC-2T Network Card

Ip table & topology

Device	Interface	IP Address	Default Gateway
R1	G0/0	2001:db8:1:1::1/64	N/A
		fe80::1	
	G0/1	2001:db8:1:2::1/64	N/A
		fe80::1	
	S0/0/0	2001:db8:1:a001::2/64	N/A
		fe80::1	
Sales	NIC	2001:db8:1:1::2/64	fe80::1
Billing	NIC	2001:db8:1:1::3/64	fe80::1
Accounting	NIC	2001:db8:1:1::4/64	fe80::1
Design	NIC	2001:db8:1:2::2/64	fe80::1
Engineering	NIC	2001:db8:1:2::3/64	fe80::1
CAD	NIC	2001:db8:1:2::4/64	fe80::1
ISP	S0/0/0	2001:db8:1:a001::1	

- Lab 4 : Routing and switching
- Lecturer : Prof. Oumaima FADI
- T.A: Prof. Abdoulghaniyu HARAZEEM



Part 1: Configure IPv6 Addressing on the Router

Step 1: Allow the router to forward IPv6 packets.

- Click R1, and then click the CLI tab. Press Enter.
- Switch to privileged execution mode.
- Enter the ipv6 unicast-routing global configuration command. This command must be entered to allow the router to transmit IPv6 packets.

```
R1(config)# ipv6 unicast-routing
```

Step 2: Configure IPv6 addressing to GigabitEthernet0/0.

- Enter the necessary commands to enter the interface configuration mode for GigabitEthernet0/0.
- Configure the IPv6 address using the following command:

```
R1(config-if)# ipv6 address 2001:db8:1:1::1/64
```

- Configure the link-local IPv6 address using the following command:

```
R1(config-if)# ipv6 address fe80::1 link-local
```

- Lab 4 : Routing and switching
- Lecturer : Prof. Oumaima FADI
- T.A: Prof. Abdoulghaniyu HARAZEEM

- Enable the interface.

```
R1(config-if)# no shutdown
```

Step 3: Configure IPv6 addressing to GigabitEthernet0/1.

- Enter the necessary commands to enter the interface configuration mode for GigabitEthernet0/1.
- Check the address table to determine the IPv6 address.
- Configure the IPv6 address, link-local address and enable the interface.

Step 4: Configure IPv6 addressing to Serial0/0/0.

- Enter the necessary commands to enter the interface configuration mode for Serial0/0/0.
- Check the address table to determine the IPv6 address.
- Configure the IPv6 address, link-local address and enable the interface.

Step 5: Check the IPv6 addressing on R1.

It is recommended that you verify the addressing when it is complete by comparing the configured values with the values in the address table.

- Exit configuration mode on R1.
- Verify the configured addressing by running the following command:

```
R1# show ipv6 interface brief
```

- If any addresses are incorrect, repeat the above steps as necessary to make corrections.

Note: To change addressing with IPv6, you must remove the incorrect address otherwise the correct address and the incorrect address will remain configured on the interface.

Example:

```
R1(config-if)# no ipv6 address 2001:db8:1:5::1/64
```

- Save the router configuration in NVRAM.

Part 2: Configure IPv6 Addressing on Servers

Step 1: Configure IPv6 addressing on the Accounting server.

- Click Accounting, and then click the Desktop tab > IP Configuration.

- Lab 4 : Routing and switching
- Lecturer : Prof. Oumaima FADI
- T.A: Prof. Abdoulghaniyu HARAZEEM

- Configure the IPv6 address to `2001:db8:1:1::4` with the /64 prefix.
- Configure the IPv6 gateway to the `link-local` address, `fe80::1`.

Step 2: Configure IPv6 addressing on the CAD server.

Configure the CAD server with addresses as was done in step 1. Check the address table for which addresses to use.

Part 3: Configure IPv6 Addressing on Clients

Step 1: Configure IPv6 addressing on the Sales and Billing clients.

- Click Billing and select the Desktop tab, and then select IP Configuration.
- Configure the IPv6 address to `2001:db8:1:1::3` with the /64 prefix.
- Configure the IPv6 gateway to the `link-local` address, `fe80::1`.
- Repeat steps 1a through 1c for the Sales customer. Check the address table to determine the IPv6 address.

Step 2: Configure IPv6 addressing on the Engineering and Design clients.

- Click Engineering and select the Desktop tab, and then select IP Configuration.
- Set the IPv6 address to `2001:db8:1:2::3` with the /64 prefix.
- Configure the IPv6 gateway to the `link-local` address, `fe80::1`.
- Repeat steps 2a through 2c for design. Check the address table to determine the IPv6 address.

Part 4: Test and verify network connectivity

Step 1: Open the server web pages from the clients.

- Click Sales and click the Desktop tab. Close the IP Configuration window, if applicable.
- Click Web Browser. Enter `2001:db8:1:1::4` in the URL box and click Go. The Accounting website should appear.
- Enter `2001:db8:1:1::4` in the URL box and click Go. The CAD website should appear.
- Repeat steps 1a through 1c for other customers.

Step 2: Ping the ISP

- Lab 4 : Routing and switching
- Lecturer : Prof. Oumaima FADI
- T.A: Prof. Abdoulghaniyu HARAZEEM

- a. Click on any client.
- b. Click the Desktop > Command > Prompt tab.
- c. Test the connectivity with the ISP by running the following command:

```
PC> ping 2001:db8:1:a001::1
```

- d. Repeat the ping command with other clients until full connectivity has been verified.