

CCNA 200-301

Command Reference

Table of Contents

Volume-01 Chapter-04	7
Enable mode EXEC command	7
Special Types	8
Volume-01 Chapter-05	9
Volume-01 Chapter-06	10
Securing User Mode and Privileged Mode with Simple Passwords	10
Securing User Mode Access with Local Usernames and Passwords	10
Securing Remote Access with Secure Shell (SSH)	11
Configuring IPv4 on a Switch	11
Volume-01 Chapter-07	13
Configuring Speed, Duplex and Description	13
Configure multiple interfaces with the int range command	13
Administrative disabling an interface with shutdown	13
Removing configuration with the no command	14
Interface status code	14
Volume-01 Chapter-08	15
Creating VLANs and Assigning Access VLANs to an Interface	15
Shorter VLAN Configuration	15
Changes from Dynamic Auto to Dynamic Desirable	15
Configuring the Voice and Data VLAN on Ports Connected to Phones	16
Troubleshooting VLANs and VLAN Trunks	16
Additional Commands	16
Volume-01 Chapter-10	17
Configuring a Manual Layer 2 EtherChannel	17
Configuring Dynamic EtherChannels (Using PAgP)	17
Configuring Dynamic EtherChannels (Using LACP)	17
Etherchannel Load Balance	18

Additional commands	18
Volume-01 Chapter-15	19
Router Interface	19
Configuring IP Addresses on Cisco Routers	19
Volume-01 Chapter-16	20
Connected and Local Routes	20
Static Network Routes	20
Static Host Routes	20
Floating Static Routes	21
Static Default Routes	21
Permanently Adding Static Routes to the IP Routing Table	21
Volume-01 Chapter-17	22
Router Configuration for the 802.1Q Encapsulation	22
Router Configuration Using Native VLAN 10	22
Configuring Routing Using Switch SVIs	23
Configuring Interface G0/1 on Switch as a Routed Port	23
Implementing Layer 3 EtherChannels	24
Volume-01 Chapter-18	25
Standard ping	25
Testing the Reverse Route Using the Extended Ping	25
Standard traceroute	25
Extended traceroute Command	25
Telnet	25
SSH	25
Volume-01 Chapter-20	26
OSPF Single-Area Configuration	26
Configuring the OSPF Router ID	26
Implementing Multiarea OSPF	27
OSPF Interface Configuration	27

OSPF Default Routes	27
OSPF Passive Interfaces	28
Confirming OSPF Interface Costs	28
OSPF Load Balancing	28
Volume-01 Chapter-21	29
Influencing DR/BDR Election Using OSPF Priority	29
OSPF Network Type Point-to-Point	29
Shutting Down the OSPF Process	29
Additional Commands	30
Volume-01 Chapter-24	31
Configuring the full 128-bit address	31
Configuring IPv6 using eui-64	31
Dynamic Unicast address configuration	31
Creating Link-local address	32
Configuring and verifying IPv6 anycast address	32
Volume-01 Chapter-25	33
Static Routes Using the Outgoing Interface	33
Static Routes Using Next-Hop IPv6 Address	33
Static Route with a Link-Local Next-Hop Address	33
Static Default Route	33
Static Host IPv6 Routes	34
Floating Static IPv6 Routes	34
Volume-02 Chapter-02	35
Matching the Exact IP Address	35
Finding the Right Wildcard Mask to Match a Subnet	35
Matching Any/All Addresses	35
Standard Numbered ACL Example-01	35
Standard Numbered ACL Example-02	35
Creating Log Messages for ACL Statistics	36

Volume-02 Chapter-03	37
Extended access-list Commands	37
Matching TCP and UDP Port Numbers	37
Extended IP Access Lists: Example 1	37
Extended IP Access Lists: Example 2	37
Named IP Access Lists	38
Removing One Command from a Named ACL	38
Editing ACLs Using Sequence Numbers	39
Adding to and Displaying a Numbered ACL Configuration	40
Volume-02 Chapter-05	41
Sample Login Security Configuration	41
Encrypting IOS Password	41
Encoding the Enable Passwords with Hashes	41
Encoding Types for the username secret Command	42
VTY Access Control Using the access-class Command	42
Volume-02 Chapter-06	43
Variations on Port Security Configuration	43
Port-security automatic recovery	43
Volume-02 Chapter-07	44
Configuring DHCP Relay on Router	44
Configuring a Switch as DHCP Client	44
Configuring a Router as DHCP Client	44
Host IP Settings on Windows	45
Host IP Settings on MAC	45
Host IP Settings on Linux	45
Volume-02 Chapter-08	46
Configuring DHCP Snooping on a Layer 2 Switch	46
Limiting DHCP Message Rates	46
Configuring Dynamic ARP Inspection on a Layer 2 Switch	46

Limiting DAI Message Rates	47
Configuring Optional DAI Message Checks	47
Volume-02 Chapter-09	48
Disabling Timestamps and Enabling Sequence Numbers	48
Syslog Configuration	48
NTP Configuration - Setting the Date/Time	48
NTP Using a Loopback Interface	49
CDP	49
LLDP	50
Volume-02 Chapter-10	51
Static NAT	51
Dynamic NAT	51
NAT Overload (PAT) Configuration	52
Volume-02 Chapter-12	53
Cisco IOS File Systems on a Router	53
Copying a New IOS Image from tftp	53
Verifying IOS Code Integrity with MD5	53
Installing a New IOS with FTP	53
Additional Command	53

Volume-01 Chapter-04

Enable mode EXEC command

EXEC Command

```
SW1# undebug all
SW1# no debug all
SW1# reload
SW1# copy running-config startup-config
SW1# copy startup-config running-config
SW1# enable
SW1# configure terminal
SW1# write erase
SW1# erase startup-config
SW1# erase nvram:
```

Show Command

```
SW1# show running-config
SW1# show startup-config
SW1# show mac address-table dynamic
```

Configuration Command

```
hostname SW1
enable secret cisco
line console 0
  password kibria
  login
int f0/1
  speed 100
```

Special Types

exit (Moves back to the next higher mode)
end (Exits configuration mode and goes back to enable mode)
ctrl+z (Same as end)
disable (Moves the user from enable mode to user mode)
quit (Disconnects the user from the CLI session)

Volume-01 Chpater-05

Configuration Command

```
mac address-table aging-time 40 [vlan 2]
```

Here 40 is seconds.

Show Command

```
sh mac address-table
```

```
sh mac address-table dynamic
```

```
sh mac address-table dynamic int g0/1
```

```
sh mac address-table dynamic vlan 2
```

```
sh mac address-table dynamic address 1111.2222.3333
```

```
sh mac address-table count
```

```
sh mac address-table aging-time
```

```
clear mac address-table dynamic
```

```
clear mac address-table dynamic int g0/1
```

```
clear mac address-table dynamic vlan 2
```

```
celar mac address-table address 1111.2222.3333
```

```
sh int status
```

```
sh int g0/1 counters
```

Volume-01 Chapter-06

Securing User Mode and Privileged Mode with Simple Passwords

Configuration Command

```
line console 0
  password cisco
  login

line vty 0 15
  password cisco2
  login

enable secret kibria
```

Show Command

```
sh run
sh run | begin line vty
```

Securing User Mode Access with Local Usernames and Passwords

Configuration Command

```
username rahim password dhaka
username karim password cumilla

line console 0
  login local
  no password

line vty 0 15
  login local
  no password
```

Show Command

```
#telnet 10.9.9.10
```

Securing Remote Access with Secure Shell (SSH)

Configuration Command

```
hostname SW1
ip domain-name example.com
crypto key generate rsa [modulus 360..2048]
1024
ip ssh version 2

username rahim password dhaka
username karim password cumilla
line vty 0 15
  transport input {all | ssh | ssh telnet | none}
  login local
```

Show Command

```
sh ip ssh
sh ssh
sh crypto key mypubkey rsa
```

Configuring IPv4 on a Switch

Configuration Command

```
int vlan 1
  ip address 192.168.1.200 255.255.255.0
  no shut

ip default-gateway 192.168.1.1
ip name-server 8.8.8.8 [9.9.9.9]
```

Show Command

```
sh ip default-gateway
sh int vlan 1
```

Configuring a Switch to Learn Its IP Address with DHCP

Configuration Command

```
int vlan 1  
ip address dhcp
```

Show Command

```
sh dhcp lease
```

logging synchronous, exec-timeout, no ip domain-lookup

Configuration Command

```
no ip domain-lookup  
  
line console 0  
  exec-timeout 0 0  
  logging synchronous  
  history size 20  
line vty 0 15  
  exec-timeout 0 0 (minutes [seconds])  
  logging synchronous  
  history size 20  
  
[no] logging console
```

Show Command

```
sh history  
terminal history size 10
```

Volume-01 Chapter-07

Configuring Speed, Duplex and Description

Configuration Command

```
int g0/1
  duplex {auto | full | half}
  speed {auto | 10 | 100 | 1000}
  description Link to SW2
```

Show Command

```
sh int status
```

Configure multiple interfaces with the int range command

Configuration Command

```
int range f0/1-10
  description Link to end user
```

Show Command

```
sh run
```

Administrative disabling an interface with shutdown

Configuration Command

```
int g0/1
  shut
```

Show Command

```
sh int g0/1
sh int g0/1 status
```

Removing configuration with the no command

Configuration Command

```
int g0/1
  no shut
  no speed
  no duplex
  no description
```

Show Command

```
sh run | int g0/1
```

Interface status code

Show Command

```
sh int
sh int description
sh mac address-table static [int g0/1]
```

Volume-01 Chapter-08

Creating VLANs and Assigning Access VLANs to an Interface

Configuration Command

```
SW1(config)# vlan 2
SW1(config-vlan)# name Freds-vlan
SW1(config-vlan)# exit
SW1(config)# interface range fastethernet 0/13 - 14
SW1(config-if)# switchport mode access
SW1(config-if)# switchport access vlan 2
```

Show Command

```
show vlan brief
show vlan id 2
```

Shorter VLAN Configuration

Configuration Command

```
SW1(config)# interface range Fastethernet 0/15 - 16
SW1(config-if-range)# switchport access vlan 3
% Access VLAN does not exist. Creating vlan 3
```

Show Command

```
show vlan brief
```

Changes from Dynamic Auto to Dynamic Desirable

Configuration Command

```
SW1(config)# interface gigabit 0/1
SW1(config-if)# switchport mode dynamic desirable
```

Show Command

```
show interfaces gigabit 0/1 switchport
show interfaces trunk
```

Configuring the Voice and Data VLAN on Ports Connected to Phones

Configuration Command

```
SW1(config)# vlan 10
SW1(config-vlan)# vlan 11
SW1(config-vlan)# interface range FastEthernet0/1 - 4
SW1(config-if)# switchport mode access
SW1(config-if)# switchport access vlan 10
SW1(config-if)# switchport voice vlan 11
```

Show Command

```
show interfaces FastEthernet 0/4 switchport
show interfaces trunk
show interfaces F0/4 trunk
```

Troubleshooting VLANs and VLAN Trunks

Configuration Command

```
SW2(config)# no shutdown vlan 10
SW2(config)# shutdown vlan 20
SW2(config)# vlan 30
SW2(config-vlan)# no shutdown
SW2(config-vlan)# vlan 40
SW2(config-vlan)# shutdown
```

Show Command

```
sh vlan brief
show interfaces gigabit0/2 switchport
```

Additional Commands

Configuration Command

```
vtp mode {server | client | transparent | off}
int g0/1
    switchport mode {access | dynamic {auto|desirable} | trunk}
    switchport trunk encapsulation {dot1q | isl | negotiate}
    switchport nonegotiate
    switchport trunk allowed vlan {all | add | except | remove}
vlan-list
```

Show Command

```
sh vlan [brief | id 2 | name eng | summary]
sh vtp status
```


Volume-01 Chapter-10

Configuring a Manual Layer 2 EtherChannel

Configuration Command

```
SW1(config)# interface fa 0/14  
SW1(config-if)# channel-group 1 mode on
```

Show Command

```
sh spanning-tree vlan 10  
sh etherchannel 1 summary
```

Configuring Dynamic EtherChannels (Using PAgP)

Configuration Command

```
On SW1:  
int range g0/1-2  
channel-group 1 mode desirable  
On SW2:  
int range g0/1-2  
channel-group 1 mode {desirable | auto}
```

Show Command

```
show etherchannel 1 port-channel  
show etherchannel summary
```

Configuring Dynamic EtherChannels (Using LACP)

Configuration Command

```
On SW1:  
int range g0/1-2  
channel-group 1 mode active  
On SW2:  
int range g0/1-2  
channel-group 1 mode {active | passive}
```

Show Command

```
show etherchannel 1 port-channel  
show etherchannel summary
```

Etherchannel Load Balance

Configuration Command

```
SW1(config)# port-channel load-balance src-dst-mac
```

Show Command

```
SW1# show etherchannel load-balance
EtherChannel Load-Balancing Configuration:
src-dst-mac
```

```
SW1# test etherchannel load-balance interface po1 mac
0200.0000.0001 0200.1111.1111
Would select Gi1/0/22 of Po1
```

```
SW1# test etherchannel load-balance interface po1 mac
0200.0000.0001 0200.1111.1112
Would select Gi1/0/24 of Po1
```

```
SW1# test etherchannel load-balance interface po1 mac
0200.0000.0001 0200.1111.1113
Would select Gi1/0/23 of Po1
```

Additional commands

Configuration Command

```
spanning-tree mode {pvst | rapid-pvst | mst}
spanning-tree vlan 10 root primary
spanning-tree vlan 11 root secondary
spanning-tree vlan 12 priority priority
spanning-tree vlan 13 cost cost
spanning-tree vlan 14 port-priority priority
```

Show Command

```
sh spanning-tree
sh spanning-tree vlan 10
sh etherchannel [channel-group-number]
sh etherchannel {brief | detail | port | port-channel | summary}
```

Volume-01 Chapter-15

Router Interface

Configuration Command

```
interface ethernet 0
interface fastethernet 0/1
interface gigabitethernet 0/0
interface gigabitethernet 0/1/0
interface serial 1/0/1
```

Show Command

```
sh ip int brief
sh int g0/1
```

Configuring IP Addresses on Cisco Routers

Configuration Command

```
interface G0/0
  ip address 172.16.1.1 255.255.255.0
  no shutdown
```

Show Command

```
sh protocols
```

Volume-01 Chapter-16

Connected and Local Routes

Configuration Command

```
[no] ip routing  
  
interface GigabitEthernet0/1/0  
  ip address 172.16.5.1 255.255.255.0  
  no shut
```

Show Command

```
show ip route  
show ip arp  
sh arp  
clear ip arp 10.1.1.1
```

Static Network Routes

Configuration Command

```
ip route 172.16.2.0 255.255.255.0 S0/0/0  
ip route 172.16.3.0 255.255.255.0 172.16.5.3
```

Show Command

```
sh ip route  
show ip route {static | ospf | connected}
```

Static Host Routes

Configuration Command

```
ip route 10.1.1.0 255.255.255.0 10.2.2.2  
ip route 10.1.1.9 255.255.255.255 10.9.9.9
```

Show Command

```
sh ip route  
show ip route {static | ospf | connected}
```

Floating Static Routes

Configuration Command

```
ip route 172.16.2.0 255.255.255.0 172.16.5.3 130
```

Show Command

```
show ip route 172.16.2.0
```

Static Default Routes

Configuration Command

```
ip route 0.0.0.0 0.0.0.0 g0/1
```

Show Command

```
show ip route
```

Permanently Adding Static Routes to the IP Routing Table

Configuration Command

```
ip route 172.16.2.0 255.255.255.0 S0/0/0 permanent  
ip route 172.16.3.0 255.255.255.0 172.16.5.3 permanent
```

Show Command

```
show ip route ospf
```

Volume-01 Chapter-17

Router Configuration for the 802.1Q Encapsulation

Configuration Command

```
interface gigabitethernet 0/0.10
  encapsulation dot1q 10
  ip address 10.1.10.1 255.255.255.0
```

```
interface gigabitethernet 0/0.20
  encapsulation dot1q 20
  ip address 10.1.20.1 255.255.255.0
```

Show Command

```
sh ip int brief | include 0/0
sh vlans
```

Router Configuration Using Native VLAN 10

Configuration Command

First option: put the native VLAN IP address on the physical interface

```
interface gigabitethernet 0/0
  ip address 10.1.10.1 255.255.255.0
  no shut
interface gigabitethernet 0/0.20
  encapsulation dot1q 20
  ip address 10.1.20.1 255.255.255.0
```

Second option: add the native keyword

```
interface gigabitethernet 0/0.10
  encapsulation dot1q 10 native
  ip address 10.1.10.1 255.255.255.0
interface gigabitethernet 0/0.20
  encapsulation dot1q 20
  ip address 10.1.20.1 255.255.255.0
```

Show Command

```
sh ip int brief | include 0/0
sh vlans
```

Configuring Routing Using Switch SVIs

Configuration Command

```
sdm prefer lanbase-routing
reload
ip routing

interface vlan 10
  ip address 10.1.10.1 255.255.255.0
  no shut
interface vlan 20
  ip address 10.1.20.1 255.255.255.0
  no shut

SW1(config)# no vlan 20
SW1(config)# vlan 30
SW1(config-vlan)# shutdown
```

Show Command

```
sh ip route
sh int status
show ip interface brief | include Vlan
```

Configuring Interface G0/1 on Switch as a Routed Port

Configuration Command

```
ip routing

interface vlan 10
  ip address 10.1.10.1 255.255.255.0
  no shut
interface vlan 20
  ip address 10.1.20.1 255.255.255.0
  no shut

interface gigabitethernet 0/1
  no switchport
  ip address 10.1.30.1 255.255.255.0
  no shut
```

Show Command

```
sh int g0/1
sh int status
sh ip route
sh int g0/1 switchport
```

Implementing Layer 3 EtherChannels

Configuration Command

On SW1 interface g0/1 and g0/2:

```
int g0/1
  no switchport
  no ip address
  channel-group 1 mode on
  no shut
int g0/2
  no switchport
  no ip address
  channel-group 1 mode on
  no shut

int port-channel 1
  no switchport
  ip address 10.1.10.1 255.255.255.0
  no shut
```

Show Command

```
sh int status
sh int port-channel 1
sh ip route
sh etherchannel 12 summary
```


Volume-01 Chapter-18

Standard ping

```
ping 172.16.2.101
```

Testing the Reverse Route Using the Extended Ping

```
R1# ping
Protocol [ip]:
Target IP address: 172.16.2.101
Repeat count [5]:
Datagram size [100]:
Timeout in seconds [2]:
Extended commands [n]: y
Source address or interface: 172.16.1.1
```

Standard traceroute

```
traceroute 172.16.2.101
```

Extended traceroute Command

```
R1# traceroute
Protocol [ip]:
Target IP address: 172.16.2.101
Source address: 172.16.1.1
Numeric display [n]:
Timeout in seconds [3]:
```

Telnet

```
telnet 10.1.2.2
```

SSH

```
ssh -l wendell 10.1.2.2
```

Volume-01 Chapter-20

OSPF Single-Area Configuration

Configuration Command

```
router ospf 1
 network 10.0.0.0 0.255.255.255 area 0
```

Show Command

```
sh ip route
sh ip route ospf
sh ip route subnet mask
sh ip route | section subnet
sh ip ospf rib
sh ip ospf neighbor
sh ip ospf neighbor g0/1
sh ip ospf database
sh ip ospf interface
sh ip ospf interface g0/1
sh ip ospf interface brief
sh run
sh ip protocols
```

Configuring the OSPF Router ID

Configuration Command

R1 Configuration first

```
router ospf 1
 router-id 1.1.1.1
 network 10.1.0.0 0.0.255.255 area 0
```

R2 Configuration next

```
interface Loopback2
 ip address 2.2.2.2 255.255.255.255
```

Show Command

```
sh ip ospf
```

Implementing Multiarea OSPF

Configuration Command

```
router ospf 1
  network 10.1.1.1 0.0.0.0 area 0
  network 10.1.2.1 0.0.0.0 area 0
  network 10.1.12.1 0.0.0.0 area 23
  network 10.1.13.1 0.0.0.0 area 23
  network 10.1.14.1 0.0.0.0 area 4
```

Show Command

```
sh ip ospf
```

OSPF Interface Configuration

Configuration Command

```
R1(config)# router ospf 1
R1(config-router)# no network 10.0.0.0 0.255.255.255 area 0

R1(config-router)# interface g0/0.1
R1(config-subif)# ip ospf 1 area 0
R1(config-subif)# interface g0/0.2
R1(config-subif)# ip ospf 1 area 0

R1(config-subif)# interface g0/0/0
R1(config-if)# ip ospf 1 area 0
```

Show Command

```
sh ip protocols
sh ip ospf int g0/0/0
```

OSPF Default Routes

Configuration Command

```
ip route 0.0.0.0 0.0.0.0 192.0.2.1
default-information originate
```

Show Command

```
sh ip route ospf
sh ip route static
```

OSPF Passive Interfaces

Configuration Command

First, make each subinterface passive directly

```
router ospf 1
  passive-interface GigabitEthernet0/0.1
  passive-interface GigabitEthernet0/0.2
```

Or, change the default to passive, and make the other interfaces not be passive

```
router ospf 1
  passive-interface default
  no passive-interface GigabitEthernet0/0/0
  no passive-interface GigabitEthernet0/1/0
  no passive-interface GigabitEthernet0/2/0
```

Show Command

```
sh ip ospf int brief
sh ip ospf int g0/0
```

Confirming OSPF Interface Costs

Configuration Command

```
R1(config)# interface g0/0/0
R1(config-if)# ip ospf cost 4
R1(config-if)# interface g0/1/0
R1(config-if)# ip ospf cost 5

router ospf 1
  auto-cost reference-bandwidth ref-bw-mbps
int g0/1
  bandwidth bw-kbps
```

Show Command

```
show ip ospf interface brief
```

OSPF Load Balancing

Configuration Command

```
route ospf 1
  maximum-paths 6
```

Volume-01 Chapter-21

Influencing DR/BDR Election Using OSPF Priority

Configuration Command

```
R1(config)# interface g0/0
R1(config-if)# ip ospf priority 99
```

Show Command

```
show ip ospf interface g0/0 | include Priority
show ip ospf neighbor
show ip ospf interface brief
```

OSPF Network Type Point-to-Point

Configuration Command

```
R1(config)# interface g0/0/0
R1(config-if)# ip ospf network point-to-point
```

Show Command

```
show ip ospf interface g0/0/0
sh ip ospf int brief
sh ip ospf neighbor
```

Shutting Down the OSPF Process

Configuration Command

```
router ospf 1
shutdown
```

Show Command

```
sh ip ospf int brief
sh ip ospf
sh ip ospf neighbor
sh ip ospf database
```

Additional Commands

Configuration Command

```
router ospf 1
  passive-interface g0/1
int g0/1
  ip ospf hello-interval seconds
  ip ospf dead-interval seconds
```

Volume-01 Chapter-24

Configuring the full 128-bit address

Configuration Command

```
ipv6 unicast-routing
int g0/1
    ipv6 address 2001:db8:1:1::1/64
    no shut
```

Show Command

```
sh ipv6 int
sh ipv6 int brief
sh ipv6 int g0/1
sh ipv6 route connected
```

Configuring IPv6 using eui-64

Configuration Command

```
int g0/1
    ipv6 address 2001:db8:1:1::1/64 eui-64
```

Dynamic Unicast address configuration

Configuration Command

```
int g0/1
    ipv6 address dhcp
int g0/1
    ipv6 address autoconfig
```

Creating Link-local address

Configuration Command

```
int g0/1
  ipv6 address fe80::1 link-local
int g0/1
  ipv6 enable
```

Show Command

```
sh ipv6 int brief
```

Configuring and verifying IPv6 anycast address

Configuration Command

```
int g0/1
  ipv6 address 2001:1:1:1::/64
  ipv6 address 2001:1:1:2::99/128 anycast
```

Show Command

```
sh ipv6 int g0/1
sh ipv6 int g0/1 brief
```


Volume-01 Chapter-25

Static Routes Using the Outgoing Interface

Configuration Command

```
ipv6 route 2001:db8:1111:2::/64 S0/0/0
```

Show Command

```
show ipv6 route static  
show ipv6 route 2001:db8:1111:2::22
```

Static Routes Using Next-Hop IPv6 Address

Configuration Command

```
ipv6 route 2001:db8:1111:2::/64 2001:DB8:1111:4::2
```

Show Command

```
show ipv6 route static  
show ipv6 route 2001:db8:1111:2::22/64
```

Static Route with a Link-Local Next-Hop Address

Configuration Command

```
ipv6 route 2001:db8:1111:2::/64 S0/0/0 FE80::FF:FE00:2
```

Show Command

```
show ipv6 route static  
show ipv6 route 2001:db8:1111:2::22
```

Static Default Route

Configuration Command

```
ipv6 route ::/0 S0/0/1
```

Show Command

```
show ipv6 route static
```

Static Host IPv6 Routes

Configuration Command

with R2's link-local address as next-hop, with an outgoing interface.

```
R1(config)# ipv6 route 2001:db8:1111:2::22/128 S0/0/0 FE80::FF:FE00:2
```

but with R2's global unicast address as next-hop, and no outgoing interface.

```
R1(config)# ipv6 route 2001:db8:1111:2::22/128 2001:DB8:1111:4::2
```

Show Command

```
show ipv6 route
```

Floating Static IPv6 Routes

Configuration Command

```
ipv6 route 2001:db8:1111:7::/64 2001:db8:1111:9::3 130
```

Show Command

```
show ipv6 route static
show ipv6 route 2001:db8:1111:7::/64
show running-config | include ipv6 route
show ipv6 neighbors
```

Volume-02 Chapter-02

Matching the Exact IP Address

Configuration Command

```
access-list 1 permit host 10.1.1.1
```

Finding the Right Wildcard Mask to Match a Subnet

Configuration Command

```
access-list 1 permit 172.16.8.0 0.0.3.255  
access-list 1 deny 10.1.1.0 0.0.0.255
```

Matching Any/All Addresses

Configuration Command

```
access-list 1 permit any
```

Standard Numbered ACL Example-01

Configuration Command

```
R2(config)# access-list 1 permit 10.1.1.1  
R2(config)# access-list 1 deny 10.1.1.0 0.0.0.255  
R2(config)# access-list 1 permit 10.0.0.0 0.255.255.255  
R2(config)# interface S0/0/1  
R2(config-if)# ip access-group 1 in
```

Show Command

```
R2# show running-config  
sh access-lists  
sh ip access-lists  
sh ip int s0/0/1
```

Standard Numbered ACL Example-02

Configuration Command

```
access-list 2 remark This ACL permits server S1 traffic to host A's subnet  
access-list 2 permit 10.2.2.1  
access-list 3 remark This ACL permits server S2 traffic to host C's subnet  
access-list 3 permit 10.2.2.2  
interface F0/0  
    ip access-group 2 out  
interface F0/1  
    ip access-group 3 out
```

Creating Log Messages for ACL Statistics

Configuration Command

```
access-list 2 permit 10.2.2.1 log  
interface F0/0  
  ip access-group 2 out
```

Show Command

```
R2# show running-config
```

Volume-02 Chapter-03

Extended access-list Commands

Configuration Command

```
access-list 101 deny tcp any any
access-list 101 deny udp any any
access-list 101 deny icmp any any
access-list 101 deny ip host 1.1.1.1 host 2.2.2.2
access-list 101 deny udp 1.1.1.0 0.0.0.255 any
```

Matching TCP and UDP Port Numbers

Configuration Command

```
access-list 101 deny tcp any gt 49151 host 10.1.1.1 eq 23
access-list 101 deny tcp any host 10.1.1.1 eq 23
access-list 101 deny tcp any host 10.1.1.1 eq telnet
access-list 101 deny udp 1.0.0.0 0.255.255.255 lt 1023 any
```

Extended IP Access Lists: Example 1

Configuration Command

```
interface Serial0
  ip address 172.16.12.1 255.255.255.0
  ip access-group 101 in
interface Serial1
  ip address 172.16.13.1 255.255.255.0
  ip access-group 101 in
access-list 101 deny tcp host 172.16.3.10 172.16.1.0 0.0.0.255 eq ftp
access-list 101 deny tcp host 172.16.2.10 host 172.16.1.100 eq www
access-list 101 permit ip any any
```

Extended IP Access Lists: Example 2

Configuration Command

```
interface ethernet 0
  ip access-group 110 in
access-list 110 deny ip host 10.1.2.1 10.1.1.0 0.0.0.255
access-list 110 deny ip 10.1.2.0 0.0.0.255 10.1.3.0 0.0.0.255
access-list 110 permit ip any any
```

Named IP Access Lists

Configuration Command

```
Router(config)# ip access-list extended barney
Router(config-ext-nacl)# permit tcp host 10.1.1.2 eq www any
Router(config-ext-nacl)# deny udp host 10.1.1.1 10.1.2.0 0.0.0.255
Router(config-ext-nacl)# deny ip 10.1.3.0 0.0.0.255 10.1.2.0 0.0.0.255
Router(config-ext-nacl)# deny ip 10.1.2.0 0.0.0.255 10.2.3.0 0.0.0.255
Router(config-ext-nacl)# permit ip any any
Router(config-ext-nacl)# interface serial1
Router(config-if)# ip access-group barney out
```

Show Command

```
Router# show running-config
```

Removing One Command from a Named ACL

Configuration Command

```
Router(config)# ip access-list extended barney
Router(config-ext-nacl)# no deny ip 10.1.2.0 0.0.0.255 10.2.3.0 0.0.0.255
```

Show Command

```
Router# show access-list
```

Editing ACLs Using Sequence Numbers

Configuration Command

Step 1: The 3-line Standard Numbered IP ACL is configured.

```
R1(config)# ip access-list standard 24
R1(config-std-nacl)# permit 10.1.1.0 0.0.0.255
R1(config-std-nacl)# permit 10.1.2.0 0.0.0.255
R1(config-std-nacl)# permit 10.1.3.0 0.0.0.255
```

Step 2: Displaying the ACL's contents, without leaving configuration mode.

```
R1(config-std-nacl)# do show ip access-lists 24
Standard IP access list 24
10 permit 10.1.1.0, wildcard bits 0.0.0.255
20 permit 10.1.2.0, wildcard bits 0.0.0.255
30 permit 10.1.3.0, wildcard bits 0.0.0.255
```

Step 3: Still in ACL 24 configuration mode, the line with sequence number 20 is deleted.

```
R1(config-std-nacl)# no 20
```

Step 4: Displaying the ACL's contents again, without leaving configuration mode. Note that line number 20 is no longer listed.

```
R1(config-std-nacl)#do show ip access-lists 24
Standard IP access list 24
10 permit 10.1.1.0, wildcard bits 0.0.0.255
30 permit 10.1.3.0, wildcard bits 0.0.0.255
```

Step 5: Inserting a new first line in the ACL.

```
R1(config-std-nacl)# 5 deny 10.1.1.1
```

Step 6: Displaying the ACL's contents one last time, with the new statement.

```
R1(config-std-nacl)# do show ip access-lists 24
Standard IP access list 24
5 deny 10.1.1.1
10 permit 10.1.1.0, wildcard bits 0.0.0.255
30 permit 10.1.3.0, wildcard bits 0.0.0.255
```

Adding to and Displaying a Numbered ACL Configuration

Configuration Command

```
R1# show running-config
access-list 24 deny 10.1.1.1
access-list 24 permit 10.1.1.0 0.0.0.255
access-list 24 permit 10.1.3.0 0.0.0.255
```

Adding a new access-list 24 global command

```
R1(config)# access-list 24 permit 10.1.4.0 0.0.0.255
```

```
R1# show ip access-lists 24
5 deny 10.1.1.1
10 permit 10.1.1.0, wildcard bits 0.0.0.255
30 permit 10.1.3.0, wildcard bits 0.0.0.255
40 permit 10.1.4.0, wildcard bits 0.0.0.255
```


Volume-02 Chapter-05

Sample Login Security Configuration

Configuration Command

```
enable secret ccna

line vty 0 15
  transport input telnet
  password kibria
  login

username rahim password dhaka
hostname SW1
ip domain-name example.com
crypto key generate rsa [modulus 512|768|1024]
line vty 0 15
  transport input {telnet|ssh|all|none}
  login local
```

Encrypting IOS Password

Configuration Command

```
SW1(config)# service password-encryption [no]
```

Show Command

```
Switch3# show running-config | section line con 0
```

Encoding the Enable Passwords with Hashes

Configuration Command

```
SW1(config)# enable secret fred
SW1# show running-config | include enable secret
enable secret 5 $1$ZGMA$e8cmvkz4UjiJhVp7.maLE1
SW1(config)# no enable secret [no enable password]

enable [algorithm type md5] secret dhaka01
enable algorithm-type sha256 secret dhaka02
enable algorithm-type scrypt secret dhaka03
```

Show Command

```
R1# show running-config | include enable
```

Encoding Types for the username secret Command

Configuration Command

```
username rahim [algorithm type md5] secret dhaka01
username karim algorithm type sha256 secret dhaka02
username abdul algorithm type scrypt secret dhaka03
```

VTY Access Control Using the access-class Command

Configuration Command

```
access-list 1 permit 10.1.1.0 0.0.0.255
line vty 0 4
  password cisco
  login
  access-class 1 in
```

Show Command

```
sh run | section vty
sh run | section con
sh run | include enable
```

Volume-02 Chapter-06

Variations on Port Security Configuration

Configuration Command

```
interface FastEthernet0/1
  switchport mode access
  switchport port-security
  switchport port-security mac-address 0200.1111.1111
interface FastEthernet0/2
  switchport mode access
  switchport port-security
  switchport port-security mac-address sticky
interface FastEthernet0/3
  switchport mode access
  switchport port-security
interface FastEthernet0/4
  switchport mode trunk
  switchport port-security
  switchport port-security maximum 8
  switchport portsecurity violation {protect | restrict | shutdown}
```

Show Command

```
SW1# show running-config
SW1# show running-config interface f0/2
SW1# show port-security interface fastEthernet 0/1
SW1# show mac address-table secure interface F0/2
SW1# show mac address-table dynamic interface F0/2
SW1# show mac address-table static interface F0/2
SW1# show port-security
SW1# show interfaces Fa0/13 status
```

Port-security automatic recovery

Configuration Command

```
errdisable recovery cause psecure-violation
errdisable recovery interval seconds
```

Volume-02 Chapter-07

Configuring DHCP Relay on Router

Configuration Command

```
int g0/1
  ip helper-address 172.16.2.11
```

Show Command

```
sh int g0/1
```

Configuring a Switch as DHCP Client

Configuration Command

```
int vlan 1
  ip address dhcp
  no shut
```

Show Command

```
sh int vlan 1
sh dhcp lease
sh ip default-gateway
sh arp
sh ip arp
```

Configuring a Router as DHCP Client

Configuration Command

```
int g0/1
  ip address dhcp
```

Show Command

```
sh ip route static
```

Host IP Settings on Windows

```
ipconfig  
ipconfig /all  
netstat -rn (show ip routing table)
```

Host IP Settings on MAC

```
ifconfig (similar to windows ipconfig /all)  
networksetup -getinfo Ethernet  
networksetup -getdnsservers Ethernet  
netstat -rn
```

Host IP Settings on Linux

```
ifconfig wlan0  
ip address  
netstat -rn  
ip route
```

arp -a (windows, mac, linux list the host ARP table)

Volume-02 Chapter-08

Configuring DHCP Snooping on a Layer 2 Switch

Configuration Command

```
ip dhcp snooping
ip dhcp snooping vlan 11
no ip dhcp snooping information option
interface GigabitEthernet1/0/2
    ip dhcp snooping trust [no]
```

Show Command

```
SW1# show ip dhcp snooping
```

Limiting DHCP Message Rates

Configuration Command

```
errdisable recovery cause dhcp-rate-limit
errdisable recovery interval 30
interface GigabitEthernet1/0/2
    ip dhcp snooping limit rate 10(number) [no]
```

Show Command

```
sh ip dhcp snooping
```

Configuring Dynamic ARP Inspection on a Layer 2 Switch

Configuration Command

```
ip arp inspection vlan 11
interface GigabitEthernet1/0/2
    ip arp inspection trust
```

Show Command

```
sh ip arp inspection
sh ip dhcp snooping binding
sh ip arp inspection statistics
sh ip dhcp snooping statistics
```

Limiting DAI Message Rates

Configuration Command

```
errdisable recovery cause arp-inspection
errdisable recovery interval seconds
interface GigabitEthernet1/0/2
    ip arp inspection limit rate 8
    ip arp inspection limit rate none
interface GigabitEthernet1/0/3
    ip arp inspection limit rate 8 burst interval 4
```

Show Command

```
sh ip arp inspection interfaces
```

Configuring Optional DAI Message Checks

Configuration Command

```
ip arp inspection validate {dst-mac | ip | src-mac}
```

Show Command

```
sh ip arp inspection
```

Volume-02 Chapter-09

Disabling Timestamps and Enabling Sequence Numbers

Configuration Command

```
R1(config)# no service timestamps
R1(config)# service sequence-numbers
```

Syslog Configuration

Configuration Command

All global conf command:

```
logging console 7 [no]
logging monitor debug [#terminal monitor] [no]
logging buffered 4 [no]
logging host 172.16.3.9 [no]
logging trap warning | debugging
```

Show Command

```
sh logging
sh log
clear logging
sh process
sh process cpu
```

NTP Configuration - Setting the Date/Time

Configuration Command

```
clock timezone EST -5
clock summer-time EDT recurring
#clock set 20:50:42 5 March 2024
```

```
ntp master 2
ntp server 172.16.3.3
```

Show Command

```
sh clock
sh ntp status
sh ntp associations
```


NTP Using a Loopback Interface

Configuration Command

```
ntp server 172.16.9.9
int loopback 0
  ip address 172.16.9.9 255.255.255.0
ntp master 4
ntp source loopback 0
```

Show Command

```
sh int loopback 0
```

CDP

Configuration Command

```
cdp run
no cdp run
int g0/1
  cdp enable [no]
cdp timer sec
cdp holdtime sec
```

Show Command

```
sh cdp
sh cdp int g0/1
sh cdp traffic
sh cdp neighbors
sh cdp neighbors detail
sh cdp entry host-name
```

LLDP

Configuration Command

```
lldp run
no lldp run
interface gigabitEthernet1/0/19
    lldp transmit
    lldp receive
interface gigabitEthernet1/0/20
    lldp receive
lldp timer sec
lldp holdtime sec
```

Show Command

```
sh lldp
sh lldp int g0/1
sh lldp traffic
sh lldp neighbors
sh lldp neighbors details
sh lldp entry host-name
```

Volume-02 Chapter-10

Static NAT

Configuration Command

```
interface GigabitEthernet0/0
  ip address 10.1.1.3 255.255.255.0
  ip nat inside
interface Serial0/0/0
  ip address 200.1.1.251 255.255.255.0
  ip nat outside
ip nat inside source static 10.1.1.2 200.1.1.2
ip nat inside source static 10.1.1.1 200.1.1.1
```

Show Command

```
sh ip nat translations
sh ip nat statistics
```

Dynamic NAT

Configuration Command

```
interface GigabitEthernet0/0
  ip address 10.1.1.3 255.255.255.0
  ip nat inside
interface Serial0/0/0
  ip address 200.1.1.251 255.255.255.0
  ip nat outside
ip nat pool fred 200.1.1.1 200.1.1.2 netmask 255.255.255.252
ip nat inside source list 1 pool fred
access-list 1 permit 10.1.1.2
access-list 1 permit 10.1.1.1
```

Show Command

```
sh ip nat translations
sh ip nat statistics
debug ip nat
```

NAT Overload (PAT) Configuration

Configuration Command

```
interface GigabitEthernet0/0
  ip address 10.1.1.3 255.255.255.0
  ip nat inside
interface Serial0/0/0
  ip address 200.1.1.249 255.255.255.252
  ip nat outside
ip nat inside source list 1 interface Serial0/0/0 overload
access-list 1 permit 10.1.1.2
access-list 1 permit 10.1.1.1
```

Show Command

```
sh ip nat translations
sh ip nat statistics
clear ip nat translation {*| [inside global-ip local-ip] | [outside local-ip global-ip]}
```

Volume-02 Chapter-12

Cisco IOS File Systems on a Router

```
sh file systems
```

Copying a New IOS Image from tftp

```
R2# copy tftp flash
Address or name of remote host []? 2.2.2.1
Source filename []? c2900-universalk9-mz.SPA.152-4.M1.bin
Destination filename [c2900-universalk9-mz.SPA.152-4.M1.bin ]?

sh flash
#dir flash0:
```

Verifying IOS Code Integrity with MD5

```
#verify /md5 flash0:c2900-universalk9-mz.SPA.154-3.M3.bin [MD5-hash]
```

Installing a New IOS with FTP

```
R1#copy ftp://wendell:odom@192.168.1.170/c2900-universalk9-
mz.SPA.155-2.T1.bin flash
Destination filename [c2900-universalk9-mz.SPA.155-2.T1.bin]?
```

If I set up username and password then: (global command)

```
ip ftp username wendell
ip ftp password odom
#copy ftp://192.168.1.170/...
```

Additional Command

```
boot system flash [flash-fs:][filename]
boot system {ftp|tftp} filename [ip-address]
```

[The End]