

Indenting Text or Code

When you type text or code, it is indented automatically according to the selected text editor or code style preferences. Select a block to indent it when you press **Tab**. Press **Shift+Tab** to decrease the indentation. You can disable automatic indentation.

You can specify indentation for:

- › QML files
- › Other text files


To fix the indentation in the file currently open in the editor, select options in the **Edit > Advanced** menu or use [keyboard shortcuts](#):


- › To automatically indent the highlighted text, select **Auto-indent Selection** or press **Ctrl+I**.
- › To automatically format the highlighted text, select **Auto-format Selection** or press **Ctrl+;**.
- › To adjust the wrapping of the selected paragraph, select **Rewrap Paragraph** or press **Ctrl+E** followed by **R**.
- › To toggle text wrapping, select **Enable Text Wrapping** or press **Ctrl+E** followed by **Ctrl+W**.
- › To visualize whitespace in the editor, select **Visualize Whitespace** or press **Ctrl+E** followed by **Ctrl+V**.
- › To clear all whitespace characters from the currently open file, select **Clean Whitespace**.

Specifying Indentation Settings


You can also specify indentation separately for each project. You can specify several sets of code style settings and easily switch between them. In addition, you can import and export code style settings.

To automatically fix indentation according to the indentation settings when you save the file, select **Edit > Preferences > Text Editor > Behavior > Clean whitespace > Clean indentation**. Select the **Skip clean whitespace for file types** check box to exclude the specified file types.





To visualize whitespace in the editor, select **Edit > Preferences > Text Editor > Display > Visualize whitespace**.




margin at column field. To use a context-specific margin when available, select the **Use context-specific margin** check box.


Indenting QML Files

To specify settings for the Qt Quick editor:

1. Select **Edit > Preferences > Qt Quick**.
2. In the **Current settings** field, select the settings to modify and click **Copy**.



3. Give a name to the settings and click **OK**.
4. Click **Edit** to specify code style settings for the project.






You can specify how to interpret the **Tab** key presses and how to align continuation lines.

In **Line length**, you can adjust the maximum line length for code lines.

To specify different settings for a particular project, select **Projects > Code Style**.

Indenting Other Text Files

To specify indentation settings for text files that do not contain C++ or QML code (such as Python code files), select **Edit > Preferences > Text Editor > Behavior**.



To specify different settings for a particular project, select **Projects > Editor**.

You can specify how to interpret the **Tab** and **Backspace** key presses and how to align continuation lines.

Specifying Tab Settings

You can specify tab settings at the following levels:

- › For all QML files
- › For all other text files
- › For QML files in a project
- › For other text files in a project

You can specify tab policy and tab size in the **Tabs and Indentation** group. In the **Tab policy** field, select whether to use only spaces or only tabs for indentation, or to use a mixture of them.

By default, the tab length in code editor is 8 spaces and the indent size is 4 spaces. You can specify the tab length and indent size separately for each project and for different types of files.

You can have continuation lines aligned with the previous line. In the **Align continuation lines** field, select **Not at all** to disable automatic alignment and indent continuation lines to the logical depth. To always use spaces for alignment, select **With Spaces**. To follow the **Tab policy**, select **With Regular Indent**.

Setting Typing Preferences

When you type text or code, it is indented automatically according to the selected text editor or code style preferences. To set typing preferences, select **Edit > Preferences > Text Editor > Behavior > Typing**.

To disable automatic indentation, deselect the **Enable automatic indentation** check box.

You can specify how the indentation is decreased when you press **Backspace** in the **Backspace indentation** field. To go back one space at a time, select **None**. To decrease indentation in leading white space by one level, select **Follows Previous Indents**. To move back one tab length if the character to the left of the cursor is a space, select **Unindents**.

You can specify whether the **Tab** key automatically indents text when you press it. To automatically indent text, select **Always** in the **Tab key performs auto-indent** field. To only indent text when the cursor is located within leading white space, select **In Leading White Space**.

Your highlight definition file can contain definitions for both multi and single line comments. To apply the single line comment definition when commenting out a selection, select **Prefer single line comments**.

[< Completing Code](#)[Using Qt Quick Toolbars >](#)[Contact Us](#)

Company

[About Us](#)[Investors](#)[Newsroom](#)[Careers](#)[Office Locations](#)

Licensing

[Terms & Conditions](#)[Open Source](#)[FAQ](#)



Support

- Support Services
- Professional Services
- Partners
- Training

Community

- Contribute to Qt
- Forum
- Wiki
- Downloads
- Marketplace

For Customers

- Support Center
- Downloads
- Qt Login
- Contact Us
- Customer Success