

# DHAKA

```
Router>en
Router#erase startup-config
Router#reload
Would you like to enter the initial configuration dialog? [yes/no]: no
```

```
Router>en
Router#conf t
Router(config)#hostname DHAKA
DHAKA(config)#no ip domain-lookup
DHAKA(config)#enable secret dhaka
DHAKA(config)#banner motd &
*****
!!!AUTHORIZED ACCESS ONLY!!!
!!!DHAKA!!!
*****
&
DHAKA(config)#line console 0
DHAKA(config-line)#password dhaka
DHAKA(config-line)#login
DHAKA(config-line)#exit
DHAKA(config)#line vty 0 4
DHAKA(config-line)#password dhaka
DHAKA(config-line)#login
DHAKA(config-line)#exit
DHAKA(config)#interface fastethernet 0/0
DHAKA(config-if)#ip address 192.168.0.1 255.255.248.0
DHAKA(config-if)#no shut
DHAKA(config-if)#interface serial 0/0/0
DHAKA(config-if)#ip address 192.168.20.153 255.255.255.252
DHAKA(config-if)#clock rate 64000
DHAKA(config-if)#no shut
DHAKA(config-if)#interface serial 0/0/1
DHAKA(config-if)#ip address 192.168.20.138 255.255.255.252
DHAKA(config-if)#clock rate 64000
DHAKA(config-if)#no shut
DHAKA(config-if)#interface serial 0/1/0
DHAKA(config-if)#ip address 192.168.20.141 255.255.255.252
DHAKA(config-if)#clock rate 64000
DHAKA(config-if)#no shut
DHAKA(config-if)#interface serial 0/1/1
DHAKA(config-if)#ip address 192.168.20.134 255.255.255.252
DHAKA(config-if)#clock rate 64000
DHAKA(config-if)#no shut
DHAKA(config-if)#end
```

```
DHAKA#copy running-config startup-config
```

```
DHAKA#conf t
DHAKA(config)#interface f0/0
DHAKA(config-if)#ip helper-address 192.168.0.3
DHAKA(config-if)#no shut
DHAKA(config-if)#end
```

```
DHAKA#copy run start
```

```
DHAKA#conf t
DHAKA(config)#router rip
DHAKA(config-router)#version 2
DHAKA(config-router)#no auto-summary
DHAKA(config-router)#network 192.168.0.0
DHAKA(config-router)#network 192.168.20.132
DHAKA(config-router)#network 192.168.20.136
DHAKA(config-router)#network 192.168.20.140
DHAKA(config-router)#network 192.168.20.152
DHAKA(config-router)#passive-interface f0/0
DHAKA(config-router)#end
```

```
DHAKA#copy run start
```

```
DHAKA#
```

# KHULNA

```
Router>en
Router#erase startup-config
Router#reload
Would you like to enter the initial configuration dialog? [yes/no]: no
```

```
Router>en
Router#conf t
Router(config)#hostname KHULNA
KHULNA(config)#no ip domain-lookup
KHULNA(config)#enable secret khulna
KHULNA(config)#banner motd &
*****
!!!AUTHORIZED ACCESS ONLY!!!
!!!KHULNA!!!
*****
&
KHULNA(config)#line console 0
KHULNA(config-line)#password khulna
KHULNA(config-line)login
KHULNA(config-line)exit
KHULNA(config)#line vty 0 4
KHULNA(config-line)password khulna
KHULNA(config-line)login
KHULNA(config-line)exit
KHULNA(config)#interface fastethernet 0/0
KHULNA(config-if)#ip address 192.168.8.1 255.255.252.0
KHULNA(config-if)#no shut
KHULNA(config-if)#interface serial 0/0/0
KHULNA(config-if)#ip address 192.168.20.129 255.255.255.252
KHULNA(config-if)#clock rate 64000
KHULNA(config-if)#no shut
KHULNA(config-if)#interface serial 0/0/1
KHULNA(config-if)#ip address 192.168.20.149 255.255.255.252
KHULNA(config-if)#no shut
KHULNA(config-if)#interface serial 0/1/1
KHULNA(config-if)#ip address 192.168.20.133 255.255.255.252
KHULNA(config-if)#no shut
KHULNA(config-if)#end

KHULNA#copy running-config startup-config

KHULNA#conf t
KHULNA (config)#ip route 192.168.16.0 255.255.254.0 s0/0/1
KHULNA (config)#end
```

KHULNA #copy run start

KHULNA#conf t

KHULNA(config)#ip route 192.168.12.0 255.255.252.0 s0/1/1

KHULNA(config)#ip route 192.168.12.0 255.255.252.0 s0/0/0 10

KHULNA(config)#end

KHULNA#copy run start

KHULNA#conf t

KHULNA(config)# router rip

KHULNA(config-router)#version 2

KHULNA(config-router)#no auto-summary

KHULNA(config-router)#network 192.168.8.0

KHULNA(config-router)#network 192.168.20.132

KHULNA(config-router)#network 192.168.20.148

KHULNA(config-router)#passive-interface f0/0

KHULNA(config-router)#passive-interface s0/0/0

KHULNA(config-router)#default-information originate

KHULNA(config-router)#end

KHULNA#copy run start

KHULNA#

# RAJSHAHI

```
Router>en
Router#erase startup-config
Router#reload
Would you like to enter the initial configuration dialog? [yes/no]: no
```

```
Router>en
Router#conf t
Router(config)#hostname RAJSHAHI
RAJSHAHI(config)#no ip domain-lookup
RAJSHAHI(config)#enable secret rajshahi
RAJSHAHI(config)#banner motd &
*****
!!!AUTHORIZED ACCESS ONLY!!!
!!!RAJSHAHI!!!
*****
&
RAJSHAHI(config)#line console 0
RAJSHAHI(config-line)#password rajshahi
RAJSHAHI(config-line)#login
RAJSHAHI(config-line)#exit
RAJSHAHI(config)#line vty 0 4
RAJSHAHI(config-line)#password rajshahi
RAJSHAHI(config-line)#login
RAJSHAHI(config-line)#exit
RAJSHAHI(config)#interface fastethernet 0/0
RAJSHAHI(config-if)#ip address 192.168.12.1 255.255.252.0
RAJSHAHI(config-if)#no shut
RAJSHAHI(config-if)#interface serial 0/0/0
RAJSHAHI(config-if)#ip address 192.168.20.130 255.255.255.252
RAJSHAHI(config-if)#no shut
RAJSHAHI(config-if)#interface serial 0/0/1
RAJSHAHI(config-if)#ip address 192.168.20.137 255.255.255.252
RAJSHAHI(config-if)#no shut
RAJSHAHI(config-if)#end

RAJSHAHI#copy running-config startup-config

RAJSHAHI# (config)#ip route 0.0.0.0 0.0.0.0 Serial0/0/1
RAJSHAHI(config)#ip route 0.0.0.0 0.0.0.0 Serial0/0/0 10
RAJSHAHI(config)#end

RAJSHAHI#copy run start

RAJSHAHI#conf t
RAJSHAHI(config)#router rip
```

```
RAJSHAHI(config-router)#version 2
RAJSHAHI(config-router)#no auto-summary
RAJSHAHI(config-router)#network 192.168.12.0
RAJSHAHI(config-router)#network 192.168.20.136
RAJSHAHI(config-router)#passive-interface f0/0
RAJSHAHI(config-router)#passive-interface s0/0/0
RAJSHAHI(config-router)#default-information originate
RAJSHAHI(config-router)#redistribute static
RAJSHAHI(config-router)#end
```

```
RAJSHAHI#copy run start
```

```
RAJSHAHI#
```

# CHITTAGONG

```
Router>en
Router#erase startup-config
Router#reload
Would you like to enter the initial configuration dialog? [yes/no]: no
```

```
Router>en
Router#conf t
Router(config)#hostname CHITTAGONG
CHITTAGONG(config)#no ip domain-lookup
CHITTAGONG(config)#enable secret chittagong
CHITTAGONG(config)#banner motd &
*****

!!!AUTHORIZED ACCESS ONLY!!!
!!!CHITTAGONG!!!
*****

&
CHITTAGONG(config)#line console 0
CHITTAGONG(config-line)#password chittagong
CHITTAGONG(config-line)#login
CHITTAGONG(config-line)#exit
CHITTAGONG(config)#line vty 0 4
CHITTAGONG(config-line)#password chittagong
CHITTAGONG(config-line)#login
CHITTAGONG(config-line)#exit
CHITTAGONG(config)#interface fastethernet 0/0
CHITTAGONG(config-if)#ip address 192.168.16.1 255.255.254.0
CHITTAGONG(config-if)#no shut
CHITTAGONG(config-if)#interface serial 0/0/0
CHITTAGONG(config-if)#ip address 192.168.20.145 255.255.255.252
CHITTAGONG(config-if)#clock rate 64000
CHITTAGONG(config-if)#no shut
CHITTAGONG(config-if)#interface serial 0/0/1
CHITTAGONG(config-if)#ip address 192.168.20.150 255.255.255.252
CHITTAGONG(config-if)#clock rate 64000
CHITTAGONG(config-if)#no shut
CHITTAGONG(config-if)#interface serial 0/1/0
CHITTAGONG(config-if)#ip address 192.168.20.142 255.255.255.252
CHITTAGONG(config-if)#no shut
CHITTAGONG(config-if)#end

CHITTAGONG#copy running-config startup-config

CHITTAGONG#conf t
CHITTAGONG(config)#ip route 0.0.0.0 0.0.0.0 s0/1/0
CHITTAGONG(config)#ip route 192.168.8.0 255.255.252.0 s0/0/1
```

```
CHITTAGONG(config)#ip route 192.168.20.0 255.255.255.18 s0/0/0
CHITTAGONG(config)#end
```

```
CHITTAGONG#copy run start
```

```
CHITTAGONG#conf t
CHITTAGONG(config)#router rip
CHITTAGONG(config-router)#version 2
CHITTAGONG(config-router)#no auto-summary
CHITTAGONG(config-router)#network 192.168.16.0
CHITTAGONG(config-router)#network 192.168.20.140
CHITTAGONG(config-router)#passive-interface f0/0
CHITTAGONG(config-router)#default-information originate
CHITTAGONG(config-router)#redistribute static
CHITTAGONG(config-router)#end
```

```
CHITTAGONG#copy run start
```

```
CHITTAGONG#
```



# SYLHET

```
Router>en
Router#erase startup-config
Router#reload
Would you like to enter the initial configuration dialog? [yes/no]: no
```

```
Router>en
Router#conf t
Router(config)#hostname SYLHET
SYLHET(config)#no ip domain-lookup
SYLHET(config)#enable secret sylhet
SYLHET(config)#banner motd &
*****
!!!AUTHORIZED ACCESS ONLY!!!
!!!SYLHET!!!
*****
&
SYLHET(config)#line console 0
SYLHET(config-line)#password sylhet
SYLHET(config-line)#login
SYLHET(config-line)#exit
SYLHET(config)#line vty 0 4
SYLHET(config-line)#password sylhet
SYLHET(config-line)#login
SYLHET(config-line)#exit
SYLHET(config)#interface fastethernet 0/0
SYLHET(config-if)#ip address 192.168.18.1 255.255.254.0
SYLHET(config-if)#no shut
SYLHET(config-if)#interface serial 0/0/0
SYLHET(config-if)#ip address 192.168.20.154 255.255.255.252
SYLHET(config-if)#no shut
SYLHET(config-if)#end
```

```
SYLHET#copy running-config startup-config
```

```
SYLHET#conf t
SYLHET(config)#router rip
SYLHET(config-router)#version 2
SYLHET(config-router)#no auto-summary
SYLHET(config-router)#network 192.168.18.0
SYLHET(config-router)#network 192.168.20.152
SYLHET(config-router)#passive-interface f0/0
SYLHET(config-router)#end
```

```
SYLHET#copy run start
```

SYLHET#

# RANGPUR

```
Router>en
Router#erase startup-config
Router#reload
Would you like to enter the initial configuration dialog? [yes/no]: no
```

```
Router>en
Router#conf t
Router(config)#hostname RANGPUR
RANGPUR(config)#no ip domain-lookup
RANGPUR(config)#enable secret rangpur
RANGPUR(config)#banner motd &
*****
!!!AUTHORIZED ACCESS ONLY!!!
!!!RANGPUR!!!
*****
&
RANGPUR(config)#line console 0
RANGPUR(config-line)#password rangpur
RANGPUR(config-line)#login
RANGPUR(config-line)#exit
RANGPUR(config)#line vty 0 4
RANGPUR(config-line)#password rangpur
RANGPUR(config-line)#login
RANGPUR(config-line)#exit
RANGPUR(config)#interface fastethernet 0/0
RANGPUR(config-if)#ip address 192.168.20.1 255.255.255.128
RANGPUR(config-if)#no shut
RANGPUR(config-if)#interface serial 0/0/0
RANGPUR(config-if)#ip address 192.168.20.146 255.255.255.252
RANGPUR(config-if)#no shut
RANGPUR(config-if)#end

RANGPUR#copy running-config startup-config

RANGPUR#conf t
RANGPUR(config)#ip route 0.0.0.0 0.0.0.0 s0/0/0
RANGPUR(config)#end

RANGPUR#copy run start

RANGPUR#
```