

# FF\_SAVEBORR\_GRID Example for Generating Asset Grid

back to [Fan's Intro Math for Econ](#), [Matlab Examples](#), or [Dynamic Asset Repositories](#)

This is the example vignette for function: `ff_saveborr_grid` from the [MEconTools Package](#). This function generates variously spaced savings/borrowing states/choices grid.

## Test FF\_SAVEBORR\_GRID Defaults

Call the function with defaults.

```
ff_saveborr_grid();
```

```
-----
XXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXX
CONTAINER NAME: mp_container_map ND Array (Matrix etc)
XXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXX
      i      idx      ndim      numel      rowN      colN      sum      mean      std      coefvari      min      ma
      --      --      --      --      --      --      --      --      --      --      --      --
ar_fl_saveborr  1      1      2      25      25      1      216.7      8.668      13.363      1.5417      0      50

xxx TABLE:ar_fl_saveborr xxxxxxxxxxxxxxxxxxxx
      c1
      --
r1      0
r2      0.029558
r3      0.067855
r4      0.11748
r5      0.18177
r6      0.26507
r7      0.37301
r8      0.51286
r9      0.69407
r10     0.92885
r11     1.2331
r12     1.6272
r13     2.1379
r14     2.7996
r15     3.657
r16     4.7679
r17     6.2072
r18     8.0722
r19     10.489
r20     13.62
r21     17.676
r22     22.932
r23     29.743
r24     38.567
r25     50


-----
XXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXX
CONTAINER NAME: mp_container_map Scalars
XXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXX
      i      idx      value
      --      --      --
grid_evenlog_threshold  1      2      1
grid_log10space_x1      2      3      0.3
```


grid_log10space_x2	3	4	3
grid_powerspace_power	4	5	3

## Test FF\_SAVEBORR\_GRID Default Linear Grid, Log Grid, Power Grid, Threshold Grid

Call the function with defaults.

```
% Same min and max and grid points
[fl_a_min, fl_a_max, it_a_points] = deal(0,50,25);
% Four types of grid points
st_grid_type = 'grid_linspace';
[ar_fl_saveborr_linspace] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type);
st_grid_type = 'grid_log10space';
[ar_fl_saveborr_log10space] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type);
st_grid_type = 'grid_powerspace';
[ar_fl_saveborr_powerspace] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type);
st_grid_type = 'grid_evenlog';
[ar_fl_saveborr_evenlog] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type);
% draw four types of lines jointly
mt_value = [ar_fl_saveborr_linspace'; ar_fl_saveborr_log10space'; ...
    ar_fl_saveborr_powerspace'; ar_fl_saveborr_evenlog'];
ar_row_grid = ["grid linspace", "grid log10space", "grid powerspace", "grid evenlog"];
ar_col_grid = 1:it_a_points;
mp_support_graph = containers.Map('KeyType', 'char', 'ValueType', 'any');
mp_support_graph('cl_st_graph_title') = {'Four Asset Grids with Default Parameters'};
mp_support_graph('cl_st_ytitle') = {'Asset Grid Points'};
mp_support_graph('cl_st_xtitle') = {'Asset Grid Counter'};
mp_support_graph('bl_graph_logy') = true; % do not log
ff_graph_grid(mt_value, ar_row_grid, ar_col_grid, mp_support_graph);
```







## Test FF\_SAVEBORR\_GRID Log Grid Changing Parameters

Log grid, same min and max, change log X1 and X2 points

```
% Same min and max and grid points
[fl_a_min, fl_a_max, it_a_points] = deal(0,50,25);
st_grid_type = 'grid_log10space';
% Four types of grid points
mp_grid_control = containers.Map('KeyType','char','ValueType','any');
mp_grid_control('grid_log10space_x1') = 0.1;
mp_grid_control('grid_log10space_x2') = 1;
[ar_fl_log10space_a] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_control);
mp_grid_control('grid_log10space_x1') = 0.1/2;
mp_grid_control('grid_log10space_x2') = 1*2;
[ar_fl_log10space_b] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_control);
mp_grid_control('grid_log10space_x1') = 0.1/4;
mp_grid_control('grid_log10space_x2') = 1*4;
[ar_fl_log10space_c] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_control);
mp_grid_control('grid_log10space_x1') = 0.1/6;
mp_grid_control('grid_log10space_x2') = 1*6;
[ar_fl_log10space_d] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_control);
% draw four types of lines jointly
mt_value = [ar_fl_log10space_a'; ar_fl_log10space_b'; ...
            ar_fl_log10space_c'; ar_fl_log10space_d'];
ar_row_grid = [...
    "log10space:x1=0.1/1, x2=1", ...
    "log10space:x1=0.1/2, x2=2", ...
    "log10space:x1=0.1/4, x2=3", ...
    "log10space:x1=0.1/6, x2=4"];
ar_col_grid = 1:it_a_points;
mp_support_graph = containers.Map('KeyType','char','ValueType','any');
mp_support_graph('cl_st_graph_title') = {'Asset Grids with Log 10 Grid Varying Controls'};
mp_support_graph('cl_st_ytitle') = {'Asset Grid Points'};
mp_support_graph('cl_st_xtitle') = {'Asset Grid Counter'};
```

```
mp_support_graph('bl_graph_logy') = true; % do not log
ff_graph_grid(mt_value, ar_row_grid, ar_col_grid, mp_support_graph);
```



## Test FF\_SAVEBORR\_GRID Power Grid Changing Parameters


Log grid, same min and max, change log X1 and X2 points


```
% Same min and max and grid points
[fl_a_min, fl_a_max, it_a_points] = deal(0,50,25);
st_grid_type = 'grid_powerspace';
% Four types of grid points
mp_grid_control = containers.Map('KeyType','char', 'ValueType','any');
mp_grid_control('grid_powerspace_power') = 1;
[ar_fl_powerspace_a] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_
mp_grid_control('grid_powerspace_power') = 2;
```

```

[ar_fl_powerspace_b] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_
mp_grid_control('grid_powerspace_power') = 4;
[ar_fl_powerspace_c] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_
mp_grid_control('grid_powerspace_power') = 6;
[ar_fl_powerspace_d] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_
% draw four types of lines jointly
mt_value = [ar_fl_powerspace_a'; ar_fl_powerspace_b'; ...
    ar_fl_powerspace_c'; ar_fl_powerspace_d'];
ar_row_grid = [...
    "powerspace:power=1", ...
    "powerspace:power=2", ...
    "powerspace:power=4", ...
    "powerspace:power=6"];
ar_col_grid = 1:it_a_points;
mp_support_graph = containers.Map('KeyType', 'char', 'ValueType', 'any');
mp_support_graph('cl_st_graph_title') = {'Asset Grids with Power Grid Varying Controls'};
mp_support_graph('cl_st_ytitle') = {'Asset Grid Points'};
mp_support_graph('cl_st_xtitle') = {'Asset Grid Counter'};
mp_support_graph('bl_graph_logy') = true; % do not log
ff_graph_grid(mt_value, ar_row_grid, ar_col_grid, mp_support_graph);

```





## Test FF\_SAVEBORR\_GRID Threshold Grid Changing Parameters

Threshold Grid, Changing Threshold Levels. Initial segments below threshold are linspace, then logspace.

```
% Same min and max and grid points
[fl_a_min, fl_a_max, it_a_points] = deal(0,50,25);
st_grid_type = 'grid_evenlog';
% Four types of grid points
mp_grid_control = containers.Map('KeyType','char','ValueType','any');
mp_grid_control('grid_evenlog_threshold') = 0.50;
[ar_fl_evenlog_a] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_control);
mp_grid_control('grid_evenlog_threshold') = 1.00;
[ar_fl_evenlog_b] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_control);
mp_grid_control('grid_evenlog_threshold') = 2;
[ar_fl_evenlog_c] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_control);
mp_grid_control('grid_evenlog_threshold') = 5;
[ar_fl_evenlog_d] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_control);
% draw four types of lines jointly
mt_value = [ar_fl_evenlog_a'; ar_fl_evenlog_b'; ...
            ar_fl_evenlog_c'; ar_fl_evenlog_d'];
ar_row_grid = [...
    "evenlog:threshold=0.5", ...
    "evenlog:threshold=1.0", ...
    "evenlog:threshold=2.0", ...
    "evenlog:threshold=5.0"];
ar_col_grid = 1:it_a_points;
mp_support_graph = containers.Map('KeyType','char','ValueType','any');
mp_support_graph('cl_st_graph_title') = {'Asset Grids with Threshold Grid Varying Controls'};
mp_support_graph('cl_st_ytitle') = {'Asset Grid Points'};
mp_support_graph('cl_st_xtitle') = {'Asset Grid Counter'};
mp_support_graph('bl_graph_logy') = true; % do not log
ff_graph_grid(mt_value, ar_row_grid, ar_col_grid, mp_support_graph);
```

