

# FF\_SAVEBORR\_GRID Example for Generating Asset Grid

back to [Fan's Intro Math for Econ](#), [Matlab Examples](#), or [Dynamic Asset Repositories](#)

This is the example vignette for function: `ff_saveborr_grid` from the [MEconTools Package](#). This function generates variously spaced savings/borrowing states/choices grid.

## Test FF\_SAVEBORR\_GRID Defaults

Call the function with defaults.

```
ff_saveborr_grid();
```

```
-----
XXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXX
CONTAINER NAME: mp_container_map ND Array (Matrix etc)
XXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXX
      i      idx      ndim      numel      rowN      colN      sum      mean      std      coefvari      min
      -      -      -      -      -      -      -      -      -      -      -
ar_fl_saveborr  1      1      2      25      25      1      385.93      15.437      15.324      0.99265      1

xxx TABLE:ar_fl_saveborr xxxxxxxxxxxxxxxxxxxx
      c1
      -
r1      1
r2      1.0174
r3      1.0982
r4      1.2707
r5      1.5557
r6      1.9707
r7      2.5312
r8      3.2512
r9      4.1434
r10     5.2196
r11     6.4912
r12     7.9687
r13     9.6621
r14     11.581
r15     13.735
r16     16.132
r17     18.781
r18     21.691
r19     24.87
r20     28.324
r21     32.063
r22     36.093
r23     40.421
r24     45.054
r25     50


-----
XXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXX
CONTAINER NAME: mp_container_map Scalars
XXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXX
      i      idx      value
      -      -      -
grid_evenlog_threshold  1      2      1
grid_log10space_x1      2      3      0.3
```



grid_log10space_x2	3	4	3
grid_powerspace_power	4	5	2.5



## Test FF\_SAVEBORR\_GRID Default Linear Grid, Log Grid, Power Grid, Threshold Grid



Call the function with defaults.


```
% Same min and max and grid points
[fl_a_min, fl_a_max, it_a_points] = deal(0,50,25);
% Four types of grid points
st_grid_type = 'grid_linspace';
[ar_fl_saveborr_linspace] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type);
st_grid_type = 'grid_log10space';
[ar_fl_saveborr_log10space] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type);
st_grid_type = 'grid_powerspace';
```











```
[ar_fl_saveborr_powerspace] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type);
st_grid_type = 'grid_evenlog';
[ar_fl_saveborr_evenlog] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type);
% draw four types of lines jointly
mt_value = [ar_fl_saveborr_linspace'; ar_fl_saveborr_log10space'; ...
            ar_fl_saveborr_powerspace'; ar_fl_saveborr_evenlog'];
ar_row_grid = ["grid linspace", "grid log10space", "grid powerspace", "grid evenlog"];
ar_col_grid = 1:it_a_points;
mp_support_graph = containers.Map('KeyType', 'char', 'ValueType', 'any');
mp_support_graph('cl_st_graph_title') = {'Four Asset Grids with Default Parameters'};
mp_support_graph('cl_st_ytitle') = {'Asset Grid Points'};
mp_support_graph('cl_st_xtitle') = {'Asset Grid Counter'};
mp_support_graph('bl_graph_logy') = true; % do not log
ff_graph_grid(mt_value, ar_row_grid, ar_col_grid, mp_support_graph);
```

## Test FF\_SAVEBORR\_GRID Log Grid Changing Parameters

Log grid, same min and max, change log X1 and X2 points

```
% Same min and max and grid points
[fl_a_min, fl_a_max, it_a_points] = deal(0,50,25);
st_grid_type = 'grid_log10space';
% Four types of grid points
mp_grid_control = containers.Map('KeyType', 'char', 'ValueType', 'any');
mp_grid_control('grid_log10space_x1') = 0.1;
mp_grid_control('grid_log10space_x2') = 1;
[ar_fl_log10space_a] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_control);
mp_grid_control('grid_log10space_x1') = 0.1/2;
mp_grid_control('grid_log10space_x2') = 1*2;
[ar_fl_log10space_b] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_control);
mp_grid_control('grid_log10space_x1') = 0.1/4;
mp_grid_control('grid_log10space_x2') = 1*4;
[ar_fl_log10space_c] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_control);
mp_grid_control('grid_log10space_x1') = 0.1/6;
```

```

mp_grid_control('grid_log10space_x2') = 1*6;
[ar_fl_log10space_d] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_
% draw four types of lines jointly
mt_value = [ar_fl_log10space_a'; ar_fl_log10space_b'; ...
    ar_fl_log10space_c'; ar_fl_log10space_d'];
ar_row_grid = [...
    "log10space:x1=0.1/1, x2=1", ...
    "log10space:x1=0.1/2, x2=2", ...
    "log10space:x1=0.1/4, x2=3", ...
    "log10space:x1=0.1/6, x2=4"];
ar_col_grid = 1:it_a_points;
mp_support_graph = containers.Map('KeyType', 'char', 'ValueType', 'any');
mp_support_graph('cl_st_graph_title') = {'Asset Grids with Log 10 Grid Varying Controls'};
mp_support_graph('cl_st_ytitle') = {'Asset Grid Points'};
mp_support_graph('cl_st_xtitle') = {'Asset Grid Counter'};
mp_support_graph('bl_graph_logy') = true; % do not log
ff_graph_grid(mt_value, ar_row_grid, ar_col_grid, mp_support_graph);

```

## Test FF\_SAVEBORR\_GRID Power Grid Changing Parameters

Log grid, same min and max, change log X1 and X2 points

```

% Same min and max and grid points
[fl_a_min, fl_a_max, it_a_points] = deal(0,50,25);
st_grid_type = 'grid_powerspace';
% Four types of grid points
mp_grid_control = containers.Map('KeyType', 'char', 'ValueType', 'any');
mp_grid_control('grid_powerspace_power') = 1;
[ar_fl_powerspace_a] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_
mp_grid_control('grid_powerspace_power') = 2;
[ar_fl_powerspace_b] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_
mp_grid_control('grid_powerspace_power') = 4;
[ar_fl_powerspace_c] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_
mp_grid_control('grid_powerspace_power') = 6;
[ar_fl_powerspace_d] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_
% draw four types of lines jointly
mt_value = [ar_fl_powerspace_a'; ar_fl_powerspace_b'; ...
    ar_fl_powerspace_c'; ar_fl_powerspace_d'];
ar_row_grid = [...
    "powerspace:power=1", ...
    "powerspace:power=2", ...
    "powerspace:power=4", ...
    "powerspace:power=6"];
ar_col_grid = 1:it_a_points;
mp_support_graph = containers.Map('KeyType', 'char', 'ValueType', 'any');
mp_support_graph('cl_st_graph_title') = {'Asset Grids with Power Grid Varying Controls'};
mp_support_graph('cl_st_ytitle') = {'Asset Grid Points'};
mp_support_graph('cl_st_xtitle') = {'Asset Grid Counter'};
mp_support_graph('bl_graph_logy') = true; % do not log
ff_graph_grid(mt_value, ar_row_grid, ar_col_grid, mp_support_graph);

```

## Test FF\_SAVEBORR\_GRID Threshold Grid Changing Parameters

Threshold Grid, Changing Threshold Levels. Initial segments below threshold are linspace, then logspace.

```
% Same min and max and grid points
[fl_a_min, fl_a_max, it_a_points] = deal(0,50,25);
st_grid_type = 'grid_evenlog';
% Four types of grid points
mp_grid_control = containers.Map('KeyType','char','ValueType','any');
mp_grid_control('grid_evenlog_threshold') = 0.50;
[ar_fl_evenlog_a] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_control);
mp_grid_control('grid_evenlog_threshold') = 1.00;
[ar_fl_evenlog_b] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_control);
mp_grid_control('grid_evenlog_threshold') = 2;
[ar_fl_evenlog_c] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_control);
mp_grid_control('grid_evenlog_threshold') = 5;
[ar_fl_evenlog_d] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_control);
% draw four types of lines jointly
mt_value = [ar_fl_evenlog_a'; ar_fl_evenlog_b'; ...
            ar_fl_evenlog_c'; ar_fl_evenlog_d'];
ar_row_grid = [...
    "evenlog:threshold=0.5", ...
    "evenlog:threshold=1.0", ...
    "evenlog:threshold=2.0", ...
    "evenlog:threshold=5.0"];
ar_col_grid = 1:it_a_points;
mp_support_graph = containers.Map('KeyType','char','ValueType','any');
mp_support_graph('cl_st_graph_title') = {'Asset Grids with Threshold Grid Varying Controls'};
mp_support_graph('cl_st_ytitle') = {'Asset Grid Points'};
mp_support_graph('cl_st_xtitle') = {'Asset Grid Counter'};
mp_support_graph('bl_graph_logy') = true; % do not log
ff_graph_grid(mt_value, ar_row_grid, ar_col_grid, mp_support_graph);
```