


[Skip to content](#)


Node Parts

All nodes in Blender are based on a similar construction. This applies to [any type of node](#). These parts include the title, sockets, properties and more.





Title

The title shows the name/type of the node; it can be overridden by changing the node's [Label](#). On the left side of the title is the *collapse* toggle which can be used to collapse the node. This can also be done with `H`.



How a node appears when collapsed.

Preview


Previews are an overlay that shows a small image above the node displaying the node result. Not all nodes support previews, but the ones that do can be toggled using the / icons in the top right-hand corner of the node next to the title.

Previews can be disabled for the whole node tree by using [Previews](#) overlay toggle.

Sockets

Sockets are input and output values for the node. They appear as little colored circles on either side of the node. Unused sockets can be hidden with `Ctrl-H`.

Each socket is color-coded depending on what type of data it handles.



Built-in

Shader (bright green)

Used for shaders in [Cycles](#) and [Eevee](#).

Geometry (turquoise)

Used in [Geometry Nodes](#).

Data

Boolean (light pink)

Used to pass a true or false value.

Color (yellow)

Indicates that the socket accepts/produces color information. The colors may or may not have an alpha component depending on the node tree type.

Float (gray)

Indicates that the socket accepts/produces floating-point numbers. It can either be a single value or a so-called “value map”. (You can think of a value map as a grayscale image where the brightness of a pixel represents its value.) If a single value is used as an input for a “value map” socket, all points of the map are set to this same value.

Integer (lime green)

Used to pass an integer value (a number without a fractional component).

String (light blue)

Used to pass a text value.

Vector (dark blue)

Indicates vector, coordinate and normal information.

Rotation (pink)

Indicates a rotation/quaternion.

Matrix (dark pink)

Indicates a 4×4 matrix of float values, it is often used to represent a [Transformation Matrix](#).

Data-Blocks

Collection (white)

Used to pass a collection data-block.

Object (orange)

Used to pass an object data-block.

Material (salmon)

Used to pass a material data-block.

Texture (pink)

Used to pass a texture data-block.

Image (apricot)

Used to pass an image data-block.

Inputs

The inputs are located on the bottom left side of the node, and provide the data the node needs to perform its function. Each input socket, except for the green shader input, when disconnected, has a default value which can be edited via a color, numeric, or vector interface input. In the screenshot of the node above, the second color option is set by a color interface input.

Some nodes have special sockets that can accept multiple inputs. These sockets will have an ellipsis shape rather than a circle to indicate their special behavior.

Outputs

The outputs are located on the top right side of the node, and can be connected to the input of nodes further down the node tree.

Conversion

Some socket types can be converted to others either implicitly or explicitly. Implicit conversion happens automatically without the need of a conversion node. For example, Float sockets and Color sockets can be linked to each other.

Once a socket conversion is made, data may be lost and cannot be retrieved later down the node tree. Implicit socket conversion can sometimes change the data units as well. When plugging a *Value* input node into an angle socket, it'll default to use radians regardless of the scene's [Units](#). This happens because the Value node has no unit while the angle input does.


Valid conversions:

- Between color and vector – mapping between color channels and vector components.
- Between color and float – the color data is converted to its grayscale equivalent.
- Color/float/vector to Shader – implicitly converts to color and gives the result of using an Emission node.
- Between float and integer – integers simply become floats, floats are truncated.
- Between float and vector – when a float becomes a vector the value is used for each component. When a vector becomes a float the average of the components is taken.
- Between float and boolean – values greater than 0 are true, true maps to 1, and false maps to 0.
- Between rotations and matrices.

Explicit conversion requires the use of a conversion node such as the [Shader To RGB Node](#) or the [RGB to BW Node](#) node. The [Math Node](#) node also contains some functions to convert between degrees and radians.

Properties

Many nodes have settings which can affect the way they interact with inputs and outputs. Node settings are located below the outputs and above any inputs.



An example of the controls on the Chroma Key node.