

GUI – CONFIGURE SIZE & LOCATION for Multi-Column List Patterns

Revision history

| | | |
|------------|-----------------|---|
| 2018-05-14 | Robin Lamacraft | Original draft |
| 2018-05-15 | Rod Thompson | Inserted graphic, actions |
| 2018-05-23 | Rod Thompson | New graphic, add Event Actions |
| 2018-07-10 | Rod Thompson | Add SCOPE Add REQUIRED SERVICES – Dependencies Add PROCESS FLOW CHART Revise Warning Message Add USE CASES |
| 2018-07-15 | Rod Thompson | Add detail under mockup graphic Amend ACTIONS |
| 2018-09-21 | Rod Thompson | Amend Title (include Location) Add to SCOPE Add WINDOWS INTERACTION MAP Add Issues Update USE CASE Add TESTING |

SCOPE

This GUI module is called only from the GUI Select Configuration window. Its purpose is to allow the user to change the size and location of the target window.

In a ‘new project creation’, it is expected that the process of ‘configuration’ of each window will occur immediately following the creation of the Viewpoint.

This module allows the User to define the SIZE and LOCATION of a selected window (created in the Viewpoint process). The data is saved in the Window Configuration. The module may be used at any time thereafter to amend the Size and Location. The drag and drop processes familiar to MS Windows users may alternatively be used for the same purpose.

Other modules in the GUI_Configuration set provide configuration for the Focus, Columns, Rows and Output. All are used to fully configure a DATA Window.

Issues:

- 1) Why display the Window Target Data Origin Type?
Appears to be no real benefit in determining size and location of the window



CONFIGURATION SETTINGS – CONFIGURE SIZE

| GUI ELEMENT USE | ELEMENT TYPE | DESCRIPTION |
|-----------------|------------------|--|
| TOP BAR | HEADING TEXT | blank or translation of “Configure Size and Location” |
| TOP BAR | RIGHT BUTTON | Only a “X” to “Close” the window; equivalent of “Cancel” |
| LABEL | FIXED PLAIN TEXT | <Target Window Name> |
| CHOICE 1 | RADIO BUTTON | <Window Configuration Name> Also set on opening |
| CHOICE 2 | RADIO BUTTON | “Default Settings” – rarely used |

| GUI ELEMENT USE | ELEMENT TYPE | DESCRIPTION |
|-----------------------|------------------------------|--|
| LABEL | FIXED PLAIN TEXT | "Window Target Data Origin Type" e.g. "Person Events Properties" –provided from the display window definition |
| LABEL | FIXED PLAIN TEXT | "Minimum Window Width (pixels)" |
| MIN WINDOW WIDTH | PLAIN POSITIVE INTEGER VALUE | If empty then use default |
| LABEL | FIXED PLAIN TEXT | "Default Window Width (pixels)" |
| DEFAULT WINDOW WIDTH | PLAIN POSITIVE INTEGER VALUE | If empty then use default |
| LABEL | FIXED PLAIN TEXT | "Minimum Window Height (pixels)" |
| MIN WINDOW HEIGHT | PLAIN POSITIVE INTEGER VALUE | If empty then use default |
| LABEL | FIXED PLAIN TEXT | "Default Window Height (pixels)" |
| DEFAULT WINDOW HEIGHT | PLAIN POSITIVE INTEGER VALUE | If empty then use default |
| COMMAND 1 | BUTTON | "Accept" button – accepts edits and closes the window returning the window that made the request |
| COMMAND 2 | BUTTON | "Cancel" button – ignore edits, but if there have been some edits made, then the user will be warned that those edits will be lost, then close the window before returning to the window that made the request |

Configure Size and Location

X

Target Window Name

☒ Window Configuration Name
 ☐ Default Settings

Window Target Data Origin Type

Size

Minimum Window Width (pixels)

Default Window Width (pixels)

Minimum Window Height (pixels)

Default Window Height (pixels)

Min Window Width

Default Window Width

Min Window Height

Default Window Height

Location

X Offset (pixels)

Y Offset (pixels)

Window top left corner from HRE Viewpoint top left corner

X-Offset

Y-Offset

Accept

Cancel

CONFIGURE SIZE AND LOCATION Window – Mockup


Shape, Size, Color, Layout etc. determined in design.

On screen location

Always inherited from the calling window

150 pixels down and to the right of the left-hand top corner of the calling window.

Not User changeable



ACTIONS

The fundamental operations are:

1. Open the window according to its saved window Layout (BR_WindowConfig)
2. Display the configuration states and settings applicable to each
3. Allow the user to edit the window size settings
Changes made by the User to the selected configuration properties should be actioned in the display of the calling window immediately after the property is changed (with an Enter key after input of the new value)
4. Allow user acceptance or cancellation of changes.
Changes 'accepted' are saved to the Window Configuration.

USED BY

All HRE users.

DATA CONTROLLED BY THIS MODULE

1. None.

REQUIRED DATA CONTROLLED BY OTHER MODULES

1. None.

REQUIRED SERVICES – Dependencies

| First-Order Dependencies | Second-Order Dependencies (if not already listed) | Higher-Order Dependencies (if not already listed) |
|--------------------------|--|--|
| 05.40 GUI_Reminder | 03.68 GUI_SelectConfiguration | |
| | 05.02 GUI_EncodedStringEdit | 05.08 GUI_FieldDefinitionEdit |
| | | 05.42 GUI_SubstitutionEdit |
| | | 07.26 BR_Substitution |
| | | 07.24 BR_Setting |
| | | 07.17 BR_WindowConfig |
| | 07.01 BR_EncodedString | NIL |
| | 07.24 BR_Setting | BR_AppData |
| | | BR_UserData |
| | | 07.02 BR_EntityLink |
| | 07.17 BR_WindowConfig | 07.06 BR_GuiElement |
| | | 07.02 BR_EntityLink |
| | | 07.29 BR_Translation |
| | | BR_FieldTranslation |
| | | 07.16 BR_MessagePatterns |
| | 07.02 BR_EntityLink | NIL |
| 05.14 GUI_Help | 03.68 GUI_Select Configuration | |
| | 07.24 BR_Setting | |
| | 07.17 BR_WindowConfig | |
| | 07.11 BR_Logging | |
| | 07.07 BR_Help | |
| | 07.02 BR_EntityLink | |
| 07.17 BR_WindowConfig | 07.06 BR_GuiElement | 07.01 BR_EncodedString |
| | | 07.02 BR_EntityLink |
| | | BR_FieldTranslation |


| First-Order Dependencies | Second-Order Dependencies (if not already listed) | Higher-Order Dependencies (if not already listed) |
|--------------------------|--|--|
| | | 07.16 BR_MessagePatterns |
| | 07.02 BR_EntityLink | NIL |
| | 07.29 BR_Translation | 07.02 BR_EntityLink |
| | | BR_Field |
| | | 07.06 BR_GuiElement |
| | | 07.16 BR_MessagePatterns |
| | BR_FieldTranslation | |
| | 07.16 BR_MessagePatterns | 07.02 BR_EntityLink |
| | | 07.01 BR_EncodedString |
| | | 07.11 BR_Logging |
| | | Call Stack |
| | | 07.24 BR_Setting |
| | | GUI_Translation |

EVENT ACTIONS

- 1) Keyboard actions
Overtyping or entry of revised numbers in each of the fields is an 'Edit' to that value
- 2) Mouse actions
Left key
 - a. Mouse key click on each icon (actions detailed below)
 - b. Mouse key click on the 'un-checked' radio button, selects that button, and 'de-selects' the other
 - c. Mouse key click on each button, operates the buttonRight key
To be determined
- 3) Icon actions
 - a. left mouse key click on 'X' icon:
(closes the window)
NOTE: Same action as in use of the 'Cancel' button
 - b. left mouse key click on 'Reminder' icon:
(opens 'Reminder' window for this 'Configure Size and Location' window)
 - c. left mouse click on 'Help' icon:
(opens the Help System, searches for the section on 'Configure Size' window)
- 4) Keyboard shortcuts
To be determined

WARNING CONDITIONS

1. Where a configuration has been edited, if the user seeks to 'cancel', or to use the 'X'-close window icon; then a warning message is displayed.



Text Version

WARNING

Use of the Cancel button or a Window Close will result in loss of the editing on these configurations.

Press CANCEL to return to this window for further attention.


Press OK to proceed with the Cancel process, which closes this window.

Location: Centred on the Configure Size window.


ERROR CONDITIONS

1. Need to record the condition that raised the error, example message and possible next steps.

WINDOWS INTERACTION MAP



PROCESS FLOW CHART



USE CASES

1) Window – Person List

Details below

Use Case 1

Window - Person List (rename of TMG Project Explorer)

| | |
|--------------------------------|-------------------------|
| Target Window Name | Explorer |
| Window Configuration Name | RT-Person Explorer 1 |
| Window Target Data Origin Type | Person Event Properties |
| Minimum Window Width (pixels) | 200 |
| Default Window Width (pixels) | 100 |
| Minimum Window Height (pixels) | 500 |
| Default Window Height (pixels) | 200 |
| X Offset (pixels) | 5 |
| Y Offset (pixels) | 5 |

Note:

Need some checking within the software.

- 1) Is the Minimum Height or Width input greater than the respective default?
- 2) Are the Minimum Height or Width inputs greater than the Viewpoint Height or Width respectively?
- 3) Are the X and Y offsets positive?

TESTING

Testing to prove the functionality of this module in use with the Select Configuration module of the HRE application.

Limited 'Project' functionality (see below).

Prior testing of the module in the code development process is assumed.

| <u>General requirements</u> | <u>Code element requirements</u> |
|-----------------------------|----------------------------------|
| HRE installation | Main GUI |
| 1) Single computer | Viewpoints |
| | Project New |
| | Project Open |
| | Project Close |
| | ExitHRE |

Process

1) Run HRE

- a. Open HRE
- b. Create a new Project
- c. Create a simple Viewpoint with multiple Data windows
- d. Select a Window, and invoke the Select Configuration module by using the Configuration icon
- e. Test the functionality of the module
- f. Close the Configuration
- g. Close the Project
- h. Exit HRE

2) Check result (how?)

See Test Plan document

