

Here are some examples showing custom date formats and how you would specify them using the **LoadWave /R** flag:

October 11, 1999	/R={English, 2, 4, 1, 1, "Month DayOfMonth, Year", 40}
Oct 11, 1999	/R={English, 2, 3, 1, 1, "Month DayOfMonth, Year", 40}
11 October 1999	/R={English, 2, 4, 1, 1, "DayOfMonth Month Year", 40}
11 Oct 1999	/R={English, 2, 3, 1, 1, "DayOfMonth Month Year", 40}
10/11/99	/R={English, 1, 2, 1, 1, "Month/DayOfMonth/Year", 40}
11-10-99	/R={English, 1, 2, 2, 1, "DayOfMonth-Month-Year", 40}
11-Jun-99	/R={English, 1, 3, 2, 1, "DayOfMonth-Month-Year", 40}
991011	/R={English,1,2,2,1,"YearMonthDayOfMonth", 40}

When loading data as delimited text, if you use a date format containing a comma, such as "October 11, 1999", you must use the **/V** flag to make sure that LoadWave will not treat the comma as a delimiter.

When loading a date format that consists entirely of digits, such as 991011, you must use the **LoadWave/B** flag to tell LoadWave that the data is a date. Otherwise, LoadWave will treat it as a regular number.

### Specifying Characteristics of Individual Columns

The LoadWave **/B=columnInfoStr** flag provides information to LoadWave for each column in a delimited text (/J), fixed field text (/F) or general text (/G) file. The flag overrides LoadWave's normal behavior. In most cases, you will not need to use it. **/B** is useful in user-defined functions when you need additional control.

*columnInfoStr* is constructed as follows:

```
"<column info>;<column info>; . . .;<column info>;"
```

## Chapter II-9 — Importing and Exporting Data

where <column info> consists of one or more of the following:

C=<number>	The number of columns controlled by this column info specification. <number> is an integer greater than or equal to one.
F=<format>	<p>A code that specifies the data type of the column or columns. &lt;format&gt; is an integer from -2 to 10. The meaning of the &lt;format&gt; is:</p> <p>-2: Text. The column will be loaded into a text wave.</p> <p>-1: Format unknown. Igor will deduce the format.</p> <p>0 to 5: Numeric.</p> <p>6: Date</p> <p>7: Time</p> <p>8: Date/Time</p> <p>9: Octal number</p> <p>10: Hexadecimal number</p> <p>The F= flag is used for delimited text and fixed field text files only. It is ignored for general text files.</p>
N=<name>	<p>A name to use for the column. &lt;name&gt; can be a standard name (e.g., wave0) or a quoted liberal name (e.g., 'Heart Rate'). If &lt;name&gt; is '_skip_' then LoadWave will skip the column.</p> <p>The N= flag works for delimited text, fixed field text and general text files.</p> <p>See <b>LoadWave Generation of Wave Names</b> on page II-142 for further discussion.</p>
T=<numtype>	<p>A number that specifies what the numeric type for the column should be. This flag overrides the LoadWave/D flag. It has no effect on columns whose format is text. &lt;numtype&gt; must be one of the following:</p> <p>2: 32-bit float</p> <p>4: 64-bit float</p> <p>8: 8-bit signed integer</p> <p>16: 16-bit signed integer</p> <p>32: 32-bit signed integer</p> <p>72: 8-bit unsigned integer</p> <p>80: 16-bit unsigned integer</p> <p>96: 32-bit unsigned integer</p>
W=<width>	<p>The column field width for fixed field files. &lt;width&gt; is an integer greater than or equal to one. Fixed width files are FORTRAN-style files in which a fixed number of bytes is allocated for each column and spaces are used as padding.</p> <p>The W= flag is used for fixed field text only.</p>

Here is an example of the /B=*columnInfoStr* flag:

```
/B="C=1,F=-2,T=2,W=20,N=Factory; C=1,F=6,W=16,T=4,N=MfgDate;  
C=1,F=0,W=16,T=2,N=TotalUnits; C=1,F=0,W=16,T=2,N=DefectiveUnits;"
```

This example is shown on two lines but in a real command it would be on a single line. In a procedure, it could be written as:

```
String columnInfoStr = ""  
columnInfoStr += "C=1,F=-2,T=2,W=20,N=Factory;"
```

```
columnInfoStr += "C=1,F=6,T=4,W=16,N=MfgDate;";
columnInfoStr += "C=1,F=0,T=2,W=16,N=TotalUnits;";
columnInfoStr += "C=1,F=0,T=2,W=16,N=DefectiveUnits;";
columnInfoStr += "C=1,F=0,T=2,W=16,N=DefectiveUnits;";
```

Note that each flag inside the quoted string ends with either a comma or a semicolon. The comma separates one flag from the next within a particular column info specification. The semicolon marks the end of a column info specification. The trailing semicolon is required. Spaces and tabs are permitted within the string.

This example provides information about a file containing four columns.

The first column info specification is "C=1;F=2,T=2,W=20,N=Factory;". This indicates that the specification applies to one column, that the column format is text, that the numeric format is single-precision floating point (but this has no effect on text columns), that the column data is in a fixed field width of 20 bytes, and that the wave created for this column is to be named Factory.

The second column info specification is "C=1;F=6,T=4,W=16,N=MfgDate;". This indicates that the specification applies to one column, that the column format is date, that the numeric format is double-precision floating point (double precision should always be used for dates), that the column data is in a fixed field width of 16 bytes, and that the wave created for this column is to be named MfgDate.

The third column info specification is "C=1;F=0,T=2,W=16,N=TotalUnits;". This indicates that the specification applies to one column, that the column format is numeric, that the numeric format is single-precision floating point, that the column data is in a fixed field width of 16 bytes, and that the wave created for this column is to be named TotalUnits.

The fourth column info specification is the same as the third except that the wave name is DefectiveUnits.

All of the items in a column specification are optional. The default value for each item in the column info specification is as follows:

C=<number>	C=1. Specifies that the column info describes one column.
F=<format>	F=-1. Determines the format as dictated by the /K flag. If /K=0 is used, LoadWave will automatically determine the column format.
N=<name>	N=_auto_. Generates the wave name as it would if the /B flag were omitted.
T=<numtype>	Defaults to T=4 (double precision) if the LoadWave/D flag is used or to T=2 (single precision) if the /D flag is omitted.
W=<width>	W=0. For a fixed width file, LoadWave will use the default field width specified by the /F flag unless you provide an explicit field width greater than 0 using W=<width>.

Taking advantage of the default values, we could abbreviate the example as follows:

```
/B="F=-2,W=20,N=Factory; F=6,T=4,W=16,N=MfgDate;
W=16,N=TotalUnits; W=16,N=DefectiveUnits;";
```

If the file were not a fixed field text file, we would omit the W= flag and the example would become:

```
/B="F=-2,N=Factory; F=6,T=4,N=MfgDate; N=TotalUnits; N=DefectiveUnits;";
```

Here are some more examples and discussion that illustrate the use of the /B=*columnInfoStr* flag.

In this example, the /B flag is used solely to specify the name to use for the waves created from the columns in the file:

```
/B="N=WaveLength; N=Absorbance;";
```

## Chapter II-9 — Importing and Exporting Data

The wave names in the previous example are standard names. If you want to use liberal names, such as names containing spaces or dots, you must use single quotes. For example:

```
/B="N='Wave Number'; N='Reflection Angle';"
```

The name that you specify via N= can not be used if overwrite is off and there is already a wave with this name or if the name conflicts with a macro, function or operation or variable. In these cases, LoadWave generates a unique name by adding one or more digits to the name specified by the N= flag for the column in question. You can avoid the problem of a conflict with another wave name by using the overwrite (/O) flag or by loading your data into a newly-created data folder. You can minimize the likelihood of a name conflict with a function, operation or variable by avoiding vague names.

If you specify the same name in two N= flags, LoadWave will generate an error, so make sure that the names are unique.

Except if the specified name is '\_skip\_', the N= flag generates a name for one column only, even if the C= flag is used to specify multiple columns. Consider this example:

```
/B="C=10,N=Test;"
```

This ostensibly uses the name Test for 10 columns. However, wave names must be unique, so LoadWave will not do this. It will use the name Test for just the first column and the other columns will receive default names.

You can load a subset of the columns in the file using the /L flag. Even if you do this, the column info specifications that you provide via the /B flag start from the first column in the file, not from the first column to be loaded. For example, if you are using /L to skip columns 0 and 1, you must skip columns 0 and 1 in the column info specification, like this:

```
// Skip column 0 and 1 and name the successive columns  
/L={0,0,0,2,0} /B="C=2;N=Column2;N=Column3;"
```

The "C=2;" part accepts default specifications for columns 0 and 1 and the subsequent specifications apply to subsequent columns.

You can achieve the same thing using /B without /L, like this:

```
/B="C=2,N='_skip_';N=Column2;N=Column3;"
```

Also, when loading data into a matrix wave, LoadWave uses only one name. If you specify more than one name, only the first is used. If you are loading data into a matrix and also skipping columns, the explanation above about skipping applies.

In this example, the /B flag solely specifies the format of each column in the file. The file in question starts with a text column, followed by a date column, followed by 3 numeric columns.

```
/B="F=-2; F=6; C=3,F=0"
```

In most cases, it is not necessary to use the F= flag because LoadWave can automatically deduce the formats. The flag is useful for those cases where it deduces the column formats incorrectly. It is also useful to force LoadWave to interpret a column as octal or hexadecimal because LoadWave can not automatically deduce these formats.

The numeric codes (0...10) used by the F= flag are the same as the codes used by the ModifyTable operation. If you create a table using the /E flag, the F= flag controls the numeric format of table columns.

The code -1 is not a real column format code. If you use F=-1 for a particular column, LoadWave will deduce the format for that column from the column text.

In this example, the /B flag is used solely to specify the width of each column in a fixed field file. This file contains a 20 byte column followed by ten 16 byte columns followed by three 24 byte columns.

```
/B="C=1,W=20; C=10,W=16; C=3,W=24"
```