



Red Hat Enterprise Linux 8

Using the desktop environment in RHEL 8

Configuring and customizing the GNOME 3 desktop environment on RHEL 8

Red Hat Enterprise Linux 8 Using the desktop environment in RHEL 8

Configuring and customizing the GNOME 3 desktop environment on RHEL 8

Legal Notice

Copyright © 2021 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

<http://creativecommons.org/licenses/by-sa/3.0/>

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, the Red Hat logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux[®] is the registered trademark of Linus Torvalds in the United States and other countries.

Java[®] is a registered trademark of Oracle and/or its affiliates.

XFS[®] is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL[®] is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js[®] is an official trademark of Joyent. Red Hat is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack[®] Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

Abstract

This document describes how to customize and use GNOME 3, which is the only desktop environment available in RHEL 8. The basics of using GNOME Shell and displaying the graphics are given, as well as the instructions for system administrators for configuring GNOME on a low level and customizing the desktop environment for multiple users. The documentation also describes how to handle selected system administration tasks using the desktop environment.

Table of Contents

MAKING OPEN SOURCE MORE INCLUSIVE	7
PROVIDING FEEDBACK ON RED HAT DOCUMENTATION	8
CHAPTER 1. GETTING STARTED WITH GNOME	9
1.1. WHAT GNOME 3 IS	9
1.2. GNOME ENVIRONMENTS, BACK ENDS, AND DISPLAY PROTOCOLS	9
1.3. LAUNCHING APPLICATIONS IN GNOME	9
1.3.1. Launching an application in GNOME Standard	9
1.3.2. Launching an application in GNOME Classic	10
1.3.3. Launching an application in GNOME using a command	11
1.4. MANAGING DESKTOP ICONS	11
1.4.1. Desktop icons in RHEL 8	11
1.4.2. Enabling desktop icons in GNOME Standard	12
1.4.3. Creating a desktop icon for a file	12
1.5. DISABLING THE HOT CORNER FUNCTIONALITY ON GNOME SHELL	13
1.5.1. Disabling the hot corner functionality for a single user	13
1.5.1.1. Disabling hot corner using dconf Editor	13
1.5.1.2. Disabling hot corner using gsettings	15
1.5.2. Disabling the hot corner functionality for all users	15
1.6. CONFIGURING SOUND IN GNOME	16
1.6.1. Sound configuration tools in GNOME	16
1.6.2. Accessing sound configuration in GNOME Control Center	17
1.6.3. Sound options in GNOME Control Center	18
1.7. HANDLING GRAPHICS AND PHOTOS	19
1.8. HANDLING PRINTING	20
1.8.1. Starting GNOME control center for setting up printing	20
1.8.2. Adding a new printer in GNOME Control Center	21
1.8.3. Configuring a printer in GNOME Control Center	23
Displaying printer's settings menu	23
Displaying and modifying printer's details	24
Setting the default printer	25
Removing a printer	25
1.8.4. Printing a test page in GNOME Control Center	26
1.8.5. Setting print options using GNOME Control Center	26
1.9. SHARING MEDIA BETWEEN APPLICATIONS	27
1.10. CUSTOMIZING GNOME SHELL ENVIRONMENT WITH THE TWEAKS TOOL	27
CHAPTER 2. OVERVIEW OF GNOME ENVIRONMENTS	30
2.1. GNOME ENVIRONMENTS, BACK ENDS, AND DISPLAY PROTOCOLS	30
2.2. GNOME STANDARD	30
2.3. GNOME CLASSIC	31
2.4. ENABLING WINDOW OVERVIEW IN GNOME CLASSIC	33
2.5. GRAPHICS BACK ENDS IN RHEL 8	35
2.6. KEY DIFFERENCES BETWEEN THE WAYLAND AND X11 PROTOCOL	36
2.7. CURRENT WAYLAND LIMITATIONS	37
Nvidia drivers	37
Remote desktop	37
X Display Manager	37
Additional limitations	37
2.8. SELECTING GNOME ENVIRONMENT AND DISPLAY PROTOCOL	38

CHAPTER 3. INSTALLING APPLICATIONS IN GNOME	40
3.1. THE GNOME SOFTWARE APPLICATION	40
3.2. INSTALLING AN APPLICATION USING GNOME SOFTWARE	40
3.3. INSTALLING AN APPLICATION TO OPEN A FILE TYPE	42
3.4. INSTALLING AN RPM PACKAGE IN GNOME	42
3.5. INSTALLING AN APPLICATION FROM THE APPLICATION SEARCH IN GNOME	43
3.6. ADDITIONAL RESOURCES	44
CHAPTER 4. REGISTERING THE SYSTEM FOR UPDATES USING GNOME	45
4.1. REGISTERING A SYSTEM USING RED HAT ACCOUNT ON GNOME	45
4.2. REGISTERING A SYSTEM USING AN ACTIVATION KEY ON GNOME	45
4.3. UNREGISTERING THE SYSTEM USING GNOME	46
CHAPTER 5. ACCESSING THE DESKTOP REMOTELY	47
5.1. REMOTE DESKTOP ACCESS OPTIONS	47
5.2. REMOTELY ACCESSING THE DESKTOP AS A SINGLE USER	47
5.2.1. Enabling desktop sharing on the server using GNOME	47
5.2.2. Connecting to a shared desktop using GNOME	51
5.2.3. Disabling encryption in GNOME VNC	53
5.3. REMOTELY ACCESSING THE DESKTOP AS MULTIPLE USERS	54
5.3.1. The mapping of port and display numbers to users in VNC	54
5.3.2. VNC server configuration files	55
5.3.3. Enabling multi-user VNC access on the server	56
5.3.4. Connecting to the VNC server as multiple users	57
5.4. REMOTELY ACCESSING AN INDIVIDUAL APPLICATION	58
5.4.1. Enabling X11 forwarding on the server	58
5.4.2. Launching an application remotely using X11 forwarding	58
CHAPTER 6. CONFIGURING GNOME AT LOW LEVEL	60
6.1. INTRODUCTION TO CONFIGURING GNOME	60
6.2. MANAGING USER AND SYSTEM GNOME SETTINGS	60
6.3. DISPLAYING GSETTINGS VALUES FOR DESKTOP APPLICATIONS	60
6.4. USING DCONF PROFILES	62
6.4.1. Introduction to dconf profiles	62
6.4.2. Selecting a dconf profile	62
6.5. CONFIGURING CUSTOM DEFAULT VALUES	63
6.6. LOCKING DOWN SPECIFIC SETTINGS	64
6.7. STORING USER SETTINGS OVER NFS	65
6.8. SETTING GSETTINGS KEYS PROPERTIES	65
6.9. WORKING WITH GSETTINGS KEYS ON COMMAND LINE	66
6.9.1. Setting key value	66
6.9.2. Monitoring key changes	66
6.9.3. Checking whether key is writable	67
6.9.4. Checking key valid values	67
6.9.5. Checking description of valid key values	68
6.9.6. Querying key value	68
6.9.7. Resetting key value	68
6.9.8. Resetting schema	69
6.9.9. Listing installed non-relocatable schemas	69
6.9.10. Listing schema keys	70
6.9.11. Listing schema children	70
6.9.12. Listing schema's keys and values	70
6.10. ACKNOWLEDGEMENTS	71

CHAPTER 7. CONFIGURING FILE ASSOCIATIONS	72
7.1. MULTIPURPOSE INTERNET MAIL EXTENSION TYPES	72
MIME database	72
7.2. ADDING A CUSTOM MIME TYPE FOR ALL USERS	72
7.3. ADDING A CUSTOM MIME TYPE FOR INDIVIDUAL USERS	74
7.4. OPTIONS TO OVERRIDE DEFAULT MIME TYPES	75
7.5. OVERRIDING DEFAULT REGISTERED APPLICATION FOR ALL THE USERS	75
7.6. OVERRIDING DEFAULT REGISTERED APPLICATION FOR INDIVIDUAL USERS	76
CHAPTER 8. CUSTOMIZING DESKTOP APPEARANCE	78
8.1. CUSTOMIZING DESKTOP BACKGROUNDS	78
8.1.1. Customizing the default desktop background	78
8.1.2. Adding extra backgrounds	79
Example implementation of org.gnome.desktop.background GSettings keys	79
8.1.3. Setting the screen shield	80
Troubleshooting	80
8.2. USING GNOME SHELL EXTENSIONS TO CUSTOMIZE DESKTOP ENVIRONMENT	81
8.2.1. Overview of GNOME Shell extensions	81
8.2.2. Enabling machine-wide extensions	82
8.2.3. Locking down enabled extensions	83
8.2.4. Setting up mandatory extensions	84
CHAPTER 9. CUSTOMIZING GNOME DESKTOP FEATURES	85
9.1. CHANGING THE LANGUAGE USING DESKTOP GUI	85
9.2. ENABLING THE CTRL+ALT+BACKSPACE SHORTCUT	87
9.3. DISABLING COMMAND-LINE ACCESS	88
9.3.1. Setting the org.gnome.desktop.lockdown.disable-command-line Key	88
9.3.2. Disabling virtual terminal switching on X.Org	89
9.4. PREVENTING THE COMPUTER FROM SUSPENDING WHEN CLOSING THE LID	89
9.5. CHANGING BEHAVIOR WHEN PRESSING THE POWER BUTTON IN GRAPHICAL TARGET MODE	90
CHAPTER 10. ENABLING CHINESE, JAPANESE, OR KOREAN TEXT INPUT	92
10.1. INPUT METHODS	92
10.2. AVAILABLE INPUT METHOD ENGINES	92
10.3. INSTALLING INPUT METHOD ENGINES	92
10.4. SWITCHING THE INPUT METHOD IN GNOME	92
CHAPTER 11. INPUTTING UNCOMMON CHARACTERS USING THE COMPOSE KEY	98
11.1. ENABLING THE COMPOSE KEY	98
11.1.1. Enabling the Compose key for an individual user with the Tweaks application	98
11.1.2. Enabling the Compose key for an individual user using GSettings	99
11.1.3. Enabling the Compose key for all users	99
11.2. USING THE COMPOSE KEY TO INPUT CHARACTERS	99
11.3. THE COMPOSE KEY SEQUENCES	100
CHAPTER 12. MANAGING STORAGE VOLUMES IN GNOME	101
12.1. THE GVFS SYSTEM	101
12.2. THE FORMAT OF THE GVFS URI STRING	101
12.3. MOUNTING A STORAGE VOLUME IN GNOME	101
12.4. UNMOUNTING A STORAGE VOLUME IN GNOME	102
12.5. OVERVIEW OF FUSE DAEMON IN GVFS	102
12.6. GIO TOOLS AND XDG-UTILS IN GNOME	102
12.7. EXECUTING THE GIO COMMANDS	104
12.8. OVERVIEW OF GVFS METADATA	104

12.9. SETTING CUSTOM GIO METADATA ATTRIBUTE	105
12.10. PASSWORD MANAGEMENT OF GVFS MOUNTS	106
12.11. ACCESSING GVFS MOUNTS THAT REQUIRE AUTHENTICATION	106
12.12. GVFS BACK ENDS	106
12.13. TROUBLESHOOTING VOLUME MANAGEMENT IN GNOME	108
12.13.1. Troubleshooting access to GVFS locations from non-GIO clients	108
12.13.2. Troubleshooting an invisible connected USB disk	109
12.13.3. Troubleshooting unknown or unwanted partitions listed in Files	109
12.13.4. Troubleshooting if a connection to the remote GVFS file system is unavailable	109
12.13.5. Troubleshooting a busy disk in GNOME	110
CHAPTER 13. MANAGING BOOKMARKS IN GNOME	111
13.1. BOOKMARKS IN GNOME	111
13.2. ADDING A BOOKMARK IN FILES	111
13.3. BOOKMARKS FOR ALL GNOME USERS	111
CHAPTER 14. CUSTOMIZING DEFAULT FAVORITE APPLICATIONS	113
14.1. SETTING DIFFERENT FAVORITE APPLICATIONS FOR INDIVIDUAL USERS	113
14.2. SETTING THE SAME FAVORITE APPLICATIONS FOR ALL USERS	113
CHAPTER 15. AUTHENTICATING THE USER IN THE DESKTOP ENVIRONMENT	115
15.1. USING ENTERPRISE CREDENTIALS TO AUTHENTICATE IN GNOME	115
15.1.1. Logging in with Enterprise Credentials in GNOME	115
15.1.2. Configuring enterprise credentials at the GNOME welcome screen	115
15.1.3. Adding an authenticated user with enterprise credentials in GNOME	116
15.1.4. Troubleshooting enterprise login in GNOME	116
15.2. ENABLING SMART CARD AUTHENTICATION	117
15.2.1. Configuring smart card authentication in GDM using the GUI	117
15.2.2. Configuring smart card authentication in GDM using the command line	117
15.2.3. Enabling the smart card authentication method in the system	118
15.3. FINGERPRINT AUTHENTICATION	118
CHAPTER 16. LOCKING DOWN SELECTED TASKS	119
16.1. LOCKING DOWN PRINTING	119
16.2. LOCKING FILE SAVING ON DISK	120
16.3. LOCKING REPARTITIONING	120
16.4. LOCKING DOWN USER LOGOUT AND USER SWITCHING	121
CHAPTER 17. RESTRICTING THE SESSION TO A SINGLE APPLICATION	124
17.1. SINGLE-APPLICATION MODE	124
17.2. ENABLING SINGLE-APPLICATION MODE	124
CHAPTER 18. MANAGING USER SESSIONS	126
18.1. WHAT GDM IS	126
18.2. RESTARTING GDM	126
18.3. ADDING AN AUTOSTART APPLICATION FOR ALL USERS	126
18.4. CONFIGURING AUTOMATIC LOGIN	127
18.5. CONFIGURING AUTOMATIC LOGOUT	127
18.6. SETTING SCREEN BRIGHTNESS AND IDLE TIME	129
Configuring the drop in the brightness level	129
Setting brightness level	129
Setting idle time	130
18.7. LOCKING THE SCREEN WHEN THE USER IS IDLE	130
18.8. SCREENCAST RECORDING	131

CHAPTER 19. CONFIGURING THE DESKTOP ENVIRONMENT FOR ACCESSIBILITY	132
19.1. CONFIGURING THE BRLTTY SERVICE	132
19.1.1. Enabling the brlTTY service	132
19.1.2. Authorizing users of a Braille display device	133
19.1.2.1. Authorizing users of a Braille display device with brlTTY.conf	133
19.1.2.2. Authorizing users of a Braille display device with brlapi.key	133
19.1.3. Setting the driver for a Braille display device	134
19.1.4. Configuring a Braille display device	135
19.1.4.1. Supported types of Braille display device	135
19.1.4.2. Setting specific parameters for Braille display devices	135
19.1.4.2.1. Setting the text table	136
19.1.4.2.2. Setting the contraction table	136
19.2. SWITCHING ON THE ALWAYS SHOW UNIVERSAL ACCESS MENU	136
19.3. ENABLING THE FESTIVAL SPEECH SYNTHESIS SYSTEM	138
19.3.1. Enabling Festival	138
19.3.2. Enabling the required voice	139
CHAPTER 20. TABLETS	140
20.1. PREPARING A TABLET DEFINITION FILE	140
20.2. ADDING SUPPORT FOR A NEW TABLET	142
20.3. WHERE IS THE WACOM TABLET CONFIGURATION STORED	143
20.4. LISTING AVAILABLE WACOM TABLET CONFIGURATION PATHS	143
CHAPTER 21. INSTALLING APPLICATIONS USING FLATPAK	145
21.1. THE FLATPAK TECHNOLOGY	145
21.2. SETTING UP FLATPAK	145
21.3. ENABLING THE RED HAT FLATPAK REMOTE	145
21.4. SEARCHING FOR FLATPAK APPLICATIONS	146
21.5. INSTALLING FLATPAK APPLICATIONS	147
21.6. LAUNCHING FLATPAK APPLICATIONS	147
21.7. UPDATING FLATPAK APPLICATIONS	147
21.8. INSTALLING FLATPAK APPLICATIONS IN THE GRAPHICAL INTERFACE	148
21.9. UPDATING FLATPAK APPLICATIONS IN THE GRAPHICAL INTERFACE	149

MAKING OPEN SOURCE MORE INCLUSIVE

Red Hat is committed to replacing problematic language in our code, documentation, and web properties. We are beginning with these four terms: master, slave, blacklist, and whitelist. Because of the enormity of this endeavor, these changes will be implemented gradually over several upcoming releases. For more details, see [our CTO Chris Wright's message](#).

PROVIDING FEEDBACK ON RED HAT DOCUMENTATION

We appreciate your input on our documentation. Please let us know how we could make it better. To do so:

- For simple comments on specific passages:
 1. Make sure you are viewing the documentation in the *Multi-page HTML* format. In addition, ensure you see the **Feedback** button in the upper right corner of the document.
 2. Use your mouse cursor to highlight the part of text that you want to comment on.
 3. Click the **Add Feedback** pop-up that appears below the highlighted text.
 4. Follow the displayed instructions.
- For submitting more complex feedback, create a Bugzilla ticket:
 1. Go to the [Bugzilla](#) website.
 2. As the Component, use **Documentation**.
 3. Fill in the **Description** field with your suggestion for improvement. Include a link to the relevant part(s) of documentation.
 4. Click **Submit Bug**.

CHAPTER 1. GETTING STARTED WITH GNOME

1.1. WHAT GNOME 3 IS

Red Hat Enterprise Linux 8 is shipped with the default desktop environment GNOME 3.

GNOME 3 represents a presentation layer that provides a graphical user interface as well as the focused working environment, which enables you to access all your work from one place.

1.2. GNOME ENVIRONMENTS, BACK ENDS, AND DISPLAY PROTOCOLS

GNOME 3 provides two user environments:

- GNOME Standard
- GNOME Classic

Both environments can use two different protocols as their graphical back ends:

- The **X11** protocol, which uses **X.Org** as the display server.
- The **Wayland** protocol, which uses **GNOME Shell** as the **Wayland** compositor and display server.

This solution of display server is further referred as **GNOME Shell on Wayland**

The default combination in RHEL 8 is GNOME Standard environment using **GNOME Shell on Wayland** as the display server. However, due to certain **Wayland** limitations, you might want to switch the graphics protocol stack to **X11**. You may also want to switch from GNOME Standard to GNOME Classic.

Additional resources

- For more information about graphics based on the **Wayland** protocol, see [Section 2.6, “Key differences between the Wayland and X11 protocol”](#).
- For information on how to switch the environments, see [Section 2.8, “Selecting GNOME environment and display protocol”](#).

1.3. LAUNCHING APPLICATIONS IN GNOME

This section describes various approaches that you can use to launch available applications in GNOME 3.

1.3.1. Launching an application in GNOME Standard

This procedure launches a graphical application in the GNOME Standard user environment.

Prerequisites

- You are using the GNOME Standard environment.

Procedure

1. Go to the **Activities Overview** screen.

2. Find the application using either of the following ways:

- Click the **Show Applications** icon in the vertical bar on the left side. Optionally, you can choose between displaying all or just the frequent applications by using the **Frequent** or **All** switch at the bottom of the screen.



- Start typing the name of the required application in the search entry.

3. Click an application from the displayed list.

1.3.2. Launching an application in GNOME Classic

This procedure launches a graphical application in the GNOME Classic user environment.

Prerequisites

- You are using the GNOME Classic environment.

Procedure

1. Go to the **Applications** menu.
2. Choose the required application from the available categories, which include:
 - Favorites
 - Accessories
 - Internet
 - Office
 - Sound & Video

- Sundry
- System Tools
- Utilities

1.3.3. Launching an application in GNOME using a command


This procedure launches a graphical application in GNOME by entering a command.

Prerequisites

- You know the command that starts the application.

Procedure

1. Open a command prompt using either of the following ways:
 - Open a terminal.
 - Press the **Alt+F2** shortcut to open the **Enter a Command** screen.



2. Write the command in the command prompt.
3. Confirm the command by pressing **Enter**.

1.4. MANAGING DESKTOP ICONS

You can enable the desktop icons functionality and move files to the desktop.

1.4.1. Desktop icons in RHEL 8

In RHEL 8, the **Files** application no longer provides the desktop icons functionality. Instead, desktop icons are provided by the **Desktop icons** GNOME Shell extension, which is available from the **gnome-shell-extension-desktop-icons** package.

Desktop icons in GNOME Classic

The GNOME Classic environment includes the **gnome-shell-extension-desktop-icons** package by default. Desktop icons are always on, and you cannot turn them off.

Desktop icons in GNOME Standard

In GNOME Standard, desktop icons are disabled by default.

If you have only the GNOME Standard environment available, and not GNOME Classic, you must install the **gnome-shell-extension-desktop-icons** package.

1.4.2. Enabling desktop icons in GNOME Standard


This procedure enables the desktop icons functionality in the GNOME Standard environment.

Procedure

1. Install the **gnome-shell-extension-desktop-icons** package:

```
# yum install gnome-shell-extension-desktop-icons
```

2. Open the **Tweaks** application.
3. Select **Extensions** → **Desktop icons**, and enable the extension.



1.4.3. Creating a desktop icon for a file

This procedure creates a desktop icon for an existing file.

Prerequisites

- The **Desktop icons** extension is enabled.

Procedure

- Move the selected file into the `~/Desktop/` directory.

Verification steps

- Check that the icon for the file appears on the desktop.

1.5. DISABLING THE HOT CORNER FUNCTIONALITY ON GNOME SHELL

The GNOME environment provides the hot corner functionality, which is enabled by default. This means that when you move the cursor to the area of the top left corner and press the cursor in this area, the **Activities Overview** menu opens automatically.

However, you may want to disable this feature to not open **Activities Overview** unintentionally.

To do so, you can use the following tools:

- The **dconf Editor** application
- The **gsettings** command-line utility
- The **No topleft hot corner** extension

The selection of the tool might depend on whether you want to disable the hot corner functionality for a single user or for all users on the system. By using **dconf Editor** or **gsettings**, you can disable hot corner only for a single user. To disable hot corner system-wide, use the **No topleft hot corner** extension.

1.5.1. Disabling the hot corner functionality for a single user

To disable the hot corner functionality for a single user, you can use either the **dconf Editor** application or the **gsettings** command-line utility.

1.5.1.1. Disabling hot corner using dconf Editor

To disable the hot corner functionality using the **dconf Editor** application, follow this procedure.

Prerequisites

- The **dconf Editor** application is installed on the system:


```
# yum install dconf-editor
```

Procedure

1. Open the **dconf Editor** application.

2. Choose the **org.gnome.desktop.interface** menu.
3. Find the **enable-hot-corners** option.
This option is by default set to **On**.


Default settings of enable-hot-corners



4. Set **enable-hot-corners** to **False**.
You can do this either by:

- Setting **enable-hot-corners** to **Off** in the same window.
- Clicking the line with **enable-hot-corners**, and proceeding to a new window. In the new window, you can switch the hot corner feature off.

Switching the hot corner functionality off



Additional resources

- For more information on **dconf Editor** application, see [Section 6.3, “Displaying GSettings values for desktop applications”](#).

1.5.1.2. Disabling hot corner using gsettings

To disable the hot corner functionality using the **gsettings** command-line utility, follow this procedure.

Procedure

- Disable the hot corner feature:

```
$ gsettings set org.gnome.desktop.interface enable-hot-corners false
```

Verification steps

- Optionally, verify that the hot corner feature is disabled:

```
$ gsettings get org.gnome.desktop.interface enable-hot-corners
false
```

1.5.2. Disabling the hot corner functionality for all users

With the GNOME Shell extension called **No topleft hot corner** provided by the **gnome-shell-extension-no-hot-corner** package, you can disable the hot corner feature system-wide.

Prerequisites

- The **gnome-shell-extension-no-hot-corner** package is installed on the system:

```
# yum install gnome-shell-extension-no-hot-corner
```

Procedure

1. Enable the **No topleft hot corner** extension by switching it on in the **Tweaks** tool.
For more information on how to use **Tweaks**, see [Section 1.10, “Customizing GNOME Shell environment with the Tweaks tool”](#).
2. Log out, and restart the user session so that the extension can take effect.

1.6. CONFIGURING SOUND IN GNOME

You can configure sound volume and other sound options in GNOME.


1.6.1. Sound configuration tools in GNOME

In RHEL 8, the **PulseAudio** sound server handles sound output and input. **PulseAudio** lets programs output the audio using the **pulseaudio** daemon.

To configure sound, you can use one of the following graphical applications in GNOME:


System menu

System menu is located in the top-right screen corner. It enables you only to set the intensity of the sound output or sound input through the sound bar. The sound bar for input sound is available only if you are running an application that is using an internal microphone (built-in audio), such as some teleconference tools.



Tweaks

Tweaks enables you to configure only volume over-amplification.



GNOME Control Center

GNOME Control Center provides more options to configure sound.

Additional resources


- For more information on **PulseAudio**, see the **pulseaudio** man page.

1.6.2. Accessing sound configuration in GNOME Control Center

This procedure opens the sound configuration screen in the **GNOME Control Center** application.

Procedure

1. Launch **GNOME Control Center**.
You can use one of the approaches described in [Section 1.3, “Launching applications in GNOME”](#). Alternatively, you can also launch it from the **System menu** by clicking on its icon.



2. In **GNOME Control Center**, choose **Sound** from the left vertical bar.

1.6.3. Sound options in GNOME Control Center

Through the **GNOME Control Center Sound** menu, you can configure the following sound options:

Output and Input

The **Output** and **Input** menus show only the built-in audio devices unless you connect any external device that can handle sound.

The **Output** menu enables you to select the required profile from available analog or digital profiles that are displayed depending on available output devices.


Sound Effects

The **Sound Effects** menu sets the volume and theme of system audio alerts.

Applications

The **Applications** menu shows all currently running applications that can process sound, and allows you to amplify or lower the sound of a particular application.

The Output tab on the sound configuration screen




1.7. HANDLING GRAPHICS AND PHOTOS


GNOME Shell provides multiple tools to handle graphics and photography.

You can check the available tools under the **Graphics & Photography** menu in GNOME Software:

1. Open the GNOME software.



2. Go to **Graphics & Photography**.



The available tools include:

- **Photos**
For accessing, organizing and sharing your photos.
- **GNU Image Manipulation Program**
For creating images and editing photographs.
- **Inkspace**
For creating and editing scalable vector graphics images.
- **XSane**
For scanning images with a scanner.
- **LibreOffice Draw**
For create and editing drawings, flow charts, and logos.


1.8. HANDLING PRINTING

In GNOME, you can set up printing using the **GNOME Control Center** GUI.

1.8.1. Starting GNOME control center for setting up printing

Procedure


1. Use one of the approaches described in [Section 1.3, “Launching applications in GNOME”](#) to start the **GNOME Control Center** GUI.
Moreover, you can also start the GNOME Control center from the **system menu** in the top right corner by clicking on the "Settings" icon.



2. When the **GNOME Control center** GUI appears, go to:

Devices → Printers

Figure 1.1. GNOME Control center configuration tool




1.8.2. Adding a new printer in GNOME Control Center

This section describes how to add a new printer using the **GNOME Control Center** GUI.

Prerequisites


To be able to add a new printer using the **GNOME Control Center** GUI, you must click on **Unlock**, which appears on the right side of the top bar, and authenticate as one of the following users:

- Superuser
- Any user with the administrative access provided by **sudo** (users listed within **/etc/sudoers**)
- Any user belonging to the **printadmin** group in **/etc/group**





Procedure

1. Open the Add Printer dialog.



2. Select one of the available printers (including also network printers), or enter printer IP address or the hostname of a printer server.




1.8.3. Configuring a printer in GNOME Control Center

This section describes how to configure a new printer, and how to maintain a configuration of a printer using the **GNOME Control Center** GUI.

Displaying printer's settings menu

Procedure


- Click the "settings" button on the right to display a settings menu for the selected printer:



Displaying and modifying printer's details


Procedure

- Click **Printer Details** to display and modify selected printer's settings:



With this menu you can:


- Search for Drivers**
 GNOME Control Center communicates with **PackageKit** that searches for a suitable driver suitable in available repositories.
- Select from Database**
 This option enables you to select a suitable driver from databases that have already been installed on the system.
- Install PPD File**
 This option enables you to select from a list of available postscript printer description (PPD) files that can be used as a driver for your printer.



Setting the default printer

Procedure


- Click **Use Printer by Default** to set the selected printer as the default printer:



Removing a printer

Procedure

- Click **Remove Printer** to remove the selected printer:



1.8.4. Printing a test page in GNOME Control Center

This section describes how to print a test page to make sure that the printer functions properly.


You might want to print a test page if one of the below prerequisites is met.

Prerequisites

- A printer has been set up.
- A printer configuration has been changed.

Procedure

1. Click the "settings" button on the right to display a settings menu for the selected printer:




2. Click **Printing Options → Test Page**

1.8.5. Setting print options using GNOME Control Center

This section describes how to set print options using the **GNOME Control Center** GUI.

Procedure

1. Click the "settings" button on the right to display a settings menu for the selected printer:



2. Click **Printing Options**

1.9. SHARING MEDIA BETWEEN APPLICATIONS

Red Hat Enterprise Linux 8 includes the PipeWire media server, which ensures access to multimedia devices and media sharing between applications.

When running a remote desktop session on **GNOME Shell on Wayland**, PipeWire and the VNC server is used. The functionality of remote desktop session is provided by the **gnome-remote-desktop** and **pipewire** packages.

On **X.Org**, just VNC is needed to run a remote desktop session. This functionality on **X.Org** is provided by the **vin** package.

PipeWire is used also with teleconference tools such as BlueJeans when running on **GNOME Shell on Wayland**. In such case, the **pipewire service** is activated automatically when you start sharing your screen within the teleconference tool.

To check the status of the **pipewire service**, run:


```
~]$ systemctl --user status pipewire
```

1.10. CUSTOMIZING GNOME SHELL ENVIRONMENT WITH THE TWEAKS TOOL


You can customize the GNOME Shell environment for a particular user by using the **Tweaks** tool.

1. Open **Tweaks**.
2. To choose the required item that you want to customize, use the vertical menu on the left. For example you can choose the applications to start automatically when you log in by using the **Startup Applications** menu, or you can customize your top bar appearance by using the **Top Bar** menu.


The Tweaks tool



Customizing startup applications in Tweaks



Customizing the appearance of your top bar in Tweaks



CHAPTER 2. OVERVIEW OF GNOME ENVIRONMENTS

You can switch between several user interfaces in GNOME. Additionally, GNOME can run on several different graphics back ends.

2.1. GNOME ENVIRONMENTS, BACK ENDS, AND DISPLAY PROTOCOLS

GNOME 3 provides two user environments:

- GNOME Standard
- GNOME Classic

Both environments can use two different protocols as their graphical back ends:

- The **X11** protocol, which uses **X.Org** as the display server.
- The **Wayland** protocol, which uses **GNOME Shell** as the **Wayland** compositor and display server.

This solution of display server is further referred as **GNOME Shell on Wayland**

The default combination in RHEL 8 is GNOME Standard environment using **GNOME Shell on Wayland** as the display server. However, due to certain **Wayland** limitations, you might want to switch the graphics protocol stack to **X11**. You may also want to switch from GNOME Standard to GNOME Classic.

Additional resources

- For more information about graphics based on the **Wayland** protocol, see [Section 2.6, “Key differences between the Wayland and X11 protocol”](#).
- For information on how to switch the environments, see [Section 2.8, “Selecting GNOME environment and display protocol”](#).

2.2. GNOME STANDARD

GNOME Standard user interface includes these major components:

Top bar

The horizontal bar at the top of the screen provides access to some of the basic functions of GNOME Standard, such as the **Activities Overview**, clock and calendar, system status icons, and the **system menu**.

System menu

The **system menu** is located in the top right corner, and enables you:

- Updating settings
- Controlling the sound bar
- Finding information about your Wi-Fi connection
- Switching user
- Logging out

- Turning off the computer

Activities Overview

The **Activities Overview** features windows and applications views that let the user run applications and windows and switch between them.

The **search entry** at the top allows for searching various items available on the desktop, including applications, documents, files, and configuration tools.


The vertical bar on the left side contains a list of favorite and running applications. You can add or remove applications from the default list of favorites according to your needs.

The workspace list displayed on the right side allows the user to switch between multiple workspaces, or move applications and windows from one workspace to another.

Message tray

The **message tray** provides access to pending notifications. The **message tray** shows when the user presses **Super+M**.

The GNOME 3 Standard Desktop



2.3. GNOME CLASSIC

GNOME Classic represents a mode for users who prefer a more traditional desktop experience that is similar to GNOME 2 environment used with Red Hat Enterprise Linux 6. It is based on GNOME 3 technologies, and at the same time it includes multiple features similar to GNOME 2.

GNOME Classic user interface consists of these major components:

Applications and Places

The **Applications** menu is displayed at the top left of the screen. It gives the user access to applications organized into categories. If you enable window overview, you can also open the **Activities Overview** from that menu.

The **Places** menu is displayed next to the **Applications** menu on the top bar. It gives the user quick access to important folders, for example **Downloads** or **Pictures**.

Taskbar

The **taskbar** is displayed at the bottom of the screen, and features:

- A window list
- A notification icon displayed next to the window list
- A short identifier for the current workspace and total number of available workspaces displayed next to the notification icon

Four available workspaces

In GNOME Classic, the number of workspaces available to the user is by default set to 4.

Minimize and maximize buttons

Window titlebars in GNOME Classic feature the minimize and maximize buttons that let the user quickly minimize the windows to the window list, or maximize them to take up all of the space on the desktop.

A traditional **Super+Tab** window switcher


In GNOME Classic, windows in the **Super+Tab** window switcher are not grouped by application.

System menu

The **system menu** is located in the top right corner, and enables the following actions:

- Updating settings
- Controlling the sound bar
- Finding information about your Wi-Fi connection
- Switching user
- Logging out
- Turning off the computer


The GNOME 3 Classic desktop with the Rhythmbox application and the Favorites submenu of the Applications menu



In GNOME Classic, the overview of windows that are open is not available by default. You can see the list of all open windows in the **taskbar** at the bottom of the screen. However, you can enable the windows overview similar to what is by default available in GNOME Standard by changing the default settings of the GNOME Classic environment as described in [Section 2.4, “Enabling window overview in GNOME Classic”](#).

2.4. ENABLING WINDOW OVERVIEW IN GNOME CLASSIC

In GNOME Classic, the overview of open windows is not available by default. This procedure enables the window overview for all users on the system.



IMPORTANT

Enabling the window overview by this procedure is not a permanent change. Each update of the **gnome-classic-session** package overwrites the configuration file to the default settings, which disable the window overview.

To keep the window overview enabled, apply the procedure after each update of **gnome-classic-session**.

Procedure

1. Open the `/usr/share/gnome-shell/modes/classic.json` file as the **root** user.
2. Find the following line in the file:


```
"hasOverview": false
```
3. Change the line to the following:

```
"hasOverview": true
```
4. Save changes, and close the `/usr/share/gnome-shell/modes/classic.json` file.
5. Restart the user session.

Verification steps

1. In your GNOME Classic session, open multiple windows.
2. Press the **Super** key to open the window overview.
3. In the overview, check that:
 - The **Dash** (the vertical panel on the left side of the screen) is displayed.
 - The bottom panel is not displayed.
 - The workspace switcher is displayed on the right side of the screen.


Window overview with "hasOverview": true



With the default settings ("**hasOverview**": **false**), the overview has the following features:

- The **Dash** is not displayed.
- The bottom panel is displayed. It includes the **Window picker** button in its left part and the workspace switcher in its right part.

Window overview with "hasOverview": false



2.5. GRAPHICS BACK ENDS IN RHEL 8

In RHEL 8, you can choose between two protocols to build a graphical user interface:

X11

The **X11** protocol uses **X.Org** as the display server. Displaying graphics based on this protocol works the same way as in RHEL 7, where this was the only option.

Wayland

The **Wayland** protocol on RHEL 8 uses **GNOME Shell** as its compositor and display server, which is further referred as **GNOME Shell on Wayland**. Displaying graphics based on the **Wayland** protocol has some differences and limitation compared to **X11**.

New installations of RHEL 8 automatically select **GNOME Shell on Wayland**. However, you can switch to **X.Org**, or select the required combination of GNOME environment and display server as described in [Section 2.8, “Selecting GNOME environment and display protocol”](#).

Note that there are also a few environments where **X.Org** is preferred over **GNOME Shell on Wayland** such as:

- Cirrus graphics used in a VM environment
- Matrox graphics
- Aspeed graphics
- QXL graphics used in a VM environment
- Nvidia graphics when used with the proprietary driver



IMPORTANT

The Nvidia graphics by default use **nouveau**, which is an open source driver. **nouveau** is supported on **Wayland**, hence you can use Nvidia graphics with **nouveau** on **GNOME Shell on Wayland** without any limitations. However, using Nvidia graphics with proprietary Nvidia binary drivers is not supported on **GNOME Shell on Wayland**. In this case, you need to switch to **X.Org** as described in [Section 2.8, “Selecting GNOME environment and display protocol”](#).

Additional resources

- You can find the current list of environments for which Wayland is not available in the `/usr/lib/udev/rules.d/61-gdm.rules` file.
- For additional information on the **Wayland** project, see [Wayland documentation](#).

2.6. KEY DIFFERENCES BETWEEN THE WAYLAND AND X11 PROTOCOL

X11 applications

Client applications need to be ported to the **Wayland** protocol or use a graphical toolkit that has a **Wayland** backend, such as GTK, to be able to work natively with the compositor and display server based on **Wayland**.

Legacy **X11** applications that cannot be ported to **Wayland** automatically use **Xwayland** as a proxy between the **X11** legacy clients and the **Wayland** compositor. **Xwayland** functions both as an **X11** server and a **Wayland** client. The role of **Xwayland** is to translate the **X11** protocol into the **Wayland** protocol and reversely, so that **X11** legacy applications can work with the display server based on **Wayland**.

On **GNOME Shell on Wayland**, **Xwayland** is started automatically at startup, which ensures that most **X11** legacy applications work as expected when using **GNOME Shell on Wayland**. However, the **X11** and **Wayland** protocols are different, and hence some clients relying on **X11**-specific features may behave differently under **Xwayland**. For such specific clients, you can switch to the **X.Org** display server as described in [Section 2.8, “Selecting GNOME environment and display protocol”](#).

libinput

Red Hat Enterprise Linux 8 uses a new unified input stack, **libinput**, which manages all common device types, such as mice, touchpads, touchscreens, tablets, trackballs and pointing sticks. This unified stack is used both by the **X.Org** and by the **GNOME Shell on Wayland** compositor.

GNOME Shell on Wayland uses **libinput** directly for all devices, and no switchable driver support is available. Under **X.Org**, **libinput** is implemented as the **X.Org libinput** driver, and driver support is outlined below.

Mice, touchscreens, trackballs, pointing sticks

Red Hat Enterprise Linux 8 uses the **X.Org libinput** driver for these devices. The **X.Org evdev** driver, which was used in Red Hat Enterprise Linux 7, is available as fallback where required.

Touchpads

Red Hat Enterprise Linux 8 uses the **X.Org libinput** driver for touchpads. The **X.Org synaptics** driver, which was used for touchpads in Red Hat Enterprise Linux 7, is no longer available.

Graphics tablets

Red Hat Enterprise Linux 8 continues using the **X.Org wacom** driver, which was used for tablet devices in Red Hat Enterprise Linux 7. However, the **X.Org libinput** driver is available where required.

Other input devices

Red Hat Enterprise Linux 7 used the **X.Org evdev** driver for other input devices that are not included in the above categories. Red Hat Enterprise Linux 8 uses the **X.Org libinput** driver by default but can fall back to the **X.Org evdev** driver if a device is incompatible with **libinput**.

Gestures

GNOME Shell on Wayland supports new touchpad and touchscreen gestures. These gestures include:

- Switching workspaces by dragging up or down with four fingers.
- Opening the **Activities** overview by bringing three fingers closer together.

2.7. CURRENT WAYLAND LIMITATIONS

Nvidia drivers

Proprietary Nvidia binary drivers are not supported with **GNOME Shell on Wayland**. To avoid any complications while using the Nvidia GPU, **GNOME Shell** automatically falls back to **X.Org**, which means that the login screen does not provide any option based on the **Wayland** protocol.



NOTE

The **nouveau** driver is still supported and is the default driver for Nvidia graphics.

Remote desktop

With **GNOME Shell on Wayland**, VNC support is provided by the **gnome-remote-desktop** package. Remote access using VNC via **gnome-remote-desktop** currently requires an already logged in session, and only the primary monitor is accessible. Screen sharing with **GNOME Shell on Wayland** is possible using the PipeWire media server. For more details on the PipeWire media server, see [PipeWire project](#).

For more advanced VNC usage, you need to switch to **X.org**, where traditional VNC tools are available. For more information, see [Section 2.8, “Selecting GNOME environment and display protocol”](#).

X Display Manager

The X Display Manager Control Protocol (XDMCP) is not supported with **GNOME Shell on Wayland**.

Hence, it is not possible to use the X display manager to start a session on the **X.Org** display server from the same or another computer.

Additional limitations

The following additional limitations related to the **Wayland** protocol should be noted:

- **X.Org** screen manipulation utilities are not available.
- The **xrandr** utility is not supported because **Wayland** handles layout, rotations, and resolutions differently.
- **GNOME Shell** cannot be restarted using the **Alt+F2 r** shortcut.
- Due to stability issues, using **X.org** instead of **Wayland** is recommended in virtual environments. The graphics based on the **Wayland** protocol are not available for virtual machines that use the **qxl** driver.

- **Wayland** does not support the custom or niche input devices that cannot be handled by the **libinput** driver.

Additional resources

- You can find the current list of environments for which Wayland-based graphics are unavailable in the `/usr/lib/udev/rules.d/61-gdm.rules` file.

2.8. SELECTING GNOME ENVIRONMENT AND DISPLAY PROTOCOL

The default desktop environment for Red Hat Enterprise Linux 8 is GNOME Standard with **GNOME Shell on Wayland** as the display server. However, due to certain limitations of **Wayland**, you might want to switch the graphics protocol stack. You might also want to switch from GNOME Standard to GNOME Classic.


Procedure

1. From the login screen (GDM), click the cogwheel next to the **Sign In** button.



NOTE

You cannot access this option from the lock screen. The login screen appears when you first start Red Hat Enterprise Linux 8 or when you log out of your current session.



2. From the drop-down menu that appears, select the option that you prefer.

**NOTE**

Note that in the menu that appears on the login screen, the **X.Org** display server is marked as **X11** display server.

**IMPORTANT**

The change of GNOME environment and graphics protocol stack resulting from the above procedure is persistent across user logouts, and also when powering off or rebooting the computer.

CHAPTER 3. INSTALLING APPLICATIONS IN GNOME

This section describes various approaches that you can use to install a new application in GNOME 3.

Prerequisites

- You have administrator permissions on the system.

3.1. THE GNOME SOFTWARE APPLICATION

GNOME Software is a utility that enables you to install and update applications and GNOME Shell extensions through a graphical environment.


GNOME Software is based on the PackageKit technology, which serves as its back end. GNOME Software offers mainly the desktop applications, which are the applications that include the ***.desktop** file. The available applications are grouped into multiple categories according to their purpose.

3.2. INSTALLING AN APPLICATION USING GNOME SOFTWARE


This procedure installs a graphical application using the GNOME Software installer.

Procedure


1. Launch the **GNOME Software** application.
2. Find the application to be installed in the available categories:
 - Audio & Video
 - Communication & News
 - Productivity
 - Graphics & Photography
 - Add-ons
Add-ons include for example GNOME Shell extensions, codecs, or fonts.
 - Developer Tools
 - Utilities



3. Click the selected application.



4. Click the **Install** button.



3.3. INSTALLING AN APPLICATION TO OPEN A FILE TYPE

This procedure installs an application that can open a given file type.

Procedure

1. Try opening a file that is associated with an application that is currently not installed on your system.
2. GNOME automatically identifies the suitable application that can open the file, and offers to download the application.

3.4. INSTALLING AN RPM PACKAGE IN GNOME

This paragraph is the procedure module introduction: a short description of the procedure.

Procedure

1. Download the required RPM package.
2. In the **Files** application, open the directory that stores the downloaded RPM package.



NOTE

By default, downloaded files are stored in the **/home/user/Downloads/** directory.


3. Double-click the icon of the RPM package to install it.

3.5. INSTALLING AN APPLICATION FROM THE APPLICATION SEARCH IN GNOME

This procedure installs a graphical application that you find in the GNOME application search.


Procedure

1. Open the **Activities Overview** screen.
2. Start typing the name of the required application in the search entry.




GNOME automatically finds the application in a repository, and displays the application's icon.

3. Click the application's icon to open **GNOME Software**.



4. Click the icon of the application again.



5. Click **Install** to finish the installation in **GNOME Software**.

3.6. ADDITIONAL RESOURCES

- For installing software on the command line, see [Installing software with yum](#).

CHAPTER 4. REGISTERING THE SYSTEM FOR UPDATES USING GNOME

You must register your system in order to get software updates for your system.

This section explains how you can register your system using GNOME.

Prerequisites

- A valid account with Red Hat customer portal
See the [Create a Red Hat Login](#) page for new user registration.
- Activation Key or keys, if you are registering the system with activation key
- A registration server, if you are registering system using the registration server

4.1. REGISTERING A SYSTEM USING RED HAT ACCOUNT ON GNOME

Follow the steps in this procedure to enroll your system with your Red Hat account.

Prerequisites

- A valid account on Red Hat customer portal.
See the [Create a Red Hat Login](#) page for new user registration.

Procedure

1. Go to the **system menu**, which is accessible from the top-right screen corner and click the **Settings** icon.
2. In the **Details** → **About** section, click **Register**.
3. Select **Registration Server**.
4. If you are not using the Red Hat server, enter the server address in the **URL** field.
5. In the **Registration Type** menu, select **Red Hat Account**
6. Under **Registration Details**:
 - Enter your Red hat account user name in the **Login** field,
 - Enter your Red hat account password in the **Password** field.
 - Enter the name of your organization in the **Organization** field.
7. Click **Register**.

4.2. REGISTERING A SYSTEM USING AN ACTIVATION KEY ON GNOME

Follow the steps in this procedure to register your system with an activation key. You can get the activation key from your organization administrator.

Prerequisites

- Activation key or keys.
See the [Activation Keys](#) page for creating new activation keys.

Procedure

1. Go to the **system menu**, which is accessible from the top-right screen corner and click the **Settings** icon.
2. In the **Details → About** section, click **Register**.
3. Select **Registration Server**.
4. Enter **URL** to the customized server, if you are not using the Red Hat server.
5. In the **Registration Type** menu, select **Activation Keys**.
6. Under **Registration Details**:
 - Enter **Activation Keys**.
Separate multiple keys by a comma (,).
 - Enter the name or ID of your organization in the **Organization** field.
7. Click **Register**

4.3. UNREGISTERING THE SYSTEM USING GNOME

Follow the steps in this procedure to unregister your system. After unregistering, your system no longer receives software updates.

Procedure

1. Go to the **system menu**, which is accessible from the top-right screen corner and click the **Settings** icon.
2. In the **Details → About** section, click **Details**.
The **Registration Details** screen appears.
3. Click **Unregister**.
A warning appears about the impact of unregistering the system.
4. Click **Unregister**.

Additional resources

- [Registering the system and managing subscription using the command line or web console](#)
- [Creating Red Hat Customer Portal Activation Keys](#)
- [Understanding Activation Keys](#)
- [Registering Systems with Activation keys](#)

CHAPTER 5. ACCESSING THE DESKTOP REMOTELY

You can connect to the desktop on a RHEL server from a remote client.

5.1. REMOTE DESKTOP ACCESS OPTIONS

RHEL provides several options for remotely connecting to the desktop. Each option fits a different use case:

Single-user access using GNOME tools

This method enables remote access on the client and the server using graphical GNOME applications. It configures a Virtual Network Computing (VNC) session so that only a single user can connect to the desktop on the server at a given time.

Depending on the session type, this method uses different components to implement screen sharing:

- In an X11 session, it uses the **vino** component.
- In a Wayland session, it uses the **gnome-remote-desktop** component.
This method always uses display number 0. As a consequence, the VNC session always connects to the user who is logged into the server system.

The VNC client application must support **tls_anon** connections. For example, you can use the **Remote Desktop Viewer (vinagre)** application on Linux systems. Before you can connect from Microsoft Windows clients, such as **RealVNC**, you must disable the VNC encryption on the server.

Multi-user access using command-line tools

This method configures a VNC session so that multiple remote clients can connect to the server in parallel. You must first enable the VNC access on the client and the server using command-line tools. Any VNC client application can connect to a server configured using this method.

Accessing a single application using X11 forwarding over SSH

This method executes an SSH command on the client that launches an individual graphical on the server. The application window opens on the client.

This method is useful when you do not require a full remote desktop session.

5.2. REMOTELY ACCESSING THE DESKTOP AS A SINGLE USER

You can remotely connect to the desktop on a RHEL server using graphical GNOME applications. Only a single user can connect to the desktop on the server at a given time.

5.2.1. Enabling desktop sharing on the server using GNOME

This procedure configures a RHEL server to enable a remote desktop connection from a single client.

Procedure

1. Configure a firewall rule to enable VNC access to the server:


```
# firewall-cmd --permanent --add-service=vnc-server
```

2. Reload firewall rules:

```
# firewall-cmd --reload
```


3. Open **Settings** in GNOME.

4. Navigate to the **Sharing** menu:




5. Click **Screen Sharing**.


The screen sharing configuration opens:



6. Click the switch button in the window header to enable screen sharing:



7. Select the **Allow connections to control the screen** check box.
8. Under **Access Options**, select the **Require a password** option.
9. Set a password in the **Password** field.
Remote clients must enter this password when connecting to the desktop on the server.



5.2.2. Connecting to a shared desktop using GNOME

This procedure connects to a remote desktop session using the **Remote Desktop Viewer** application (**vinagre**). It connects to the graphical session of the user that is currently logged in on the server.

Prerequisites


- A user is logged into the GNOME graphical session on the server.
- The desktop sharing is enabled on the server. For details, see [Section 5.2.1, “Enabling desktop sharing on the server using GNOME”](#).

Procedure


1. Install the **Remote Desktop Viewer** application on the client:

```
# yum install vinagre
```

2. Launch the **Remote Desktop Viewer** application (**vinagre**).
3. Click **Connect**.



4. In the **Protocol** menu, select **VNC**.
5. In the **Host** field, enter the IP address of the server.



6. Click **Connect**.

Verification steps

1. On the client, check that you can see the shared server desktop.
2. On the server, a screen sharing indicator appears on the right side of the top panel:



You can control the screen sharing in the system menu.

5.2.3. Disabling encryption in GNOME VNC

You can disable encryption in the GNOME remote desktop solution. This enables VNC clients that do not support the encryption to connect to the server.

Procedure

1. As the server user, set the `/org/gnome/desktop/remote-desktop/vnc/encryption` GSettings key to `['none']`:

```
$ gsettings set org.gnome.desktop.remote-desktop.vnc encryption "[none]"
```

2. Optional: Red Hat recommends that you tunnel the VNC connection over SSH to your VNC port. As a result, the SSH tunnel keeps the connection encrypted.
For example:

- a. On the client, configure the port forwarding:

```
# ssh -N -T -L 5901:server-ip-address:5901
```

- b. Connect to the VNC session on the **localhost:5901** address.

5.3. REMOTELY ACCESSING THE DESKTOP AS MULTIPLE USERS

You can remotely connect to the desktop on a RHEL server and open multiple sessions as different users at the same time.

5.3.1. The mapping of port and display numbers to users in VNC

With VNC, the client can connect to the desktop sessions of different users on the server. A display number and a TCP port number are attached to each server user that exports a VNC session. The client uses the port number to specify which server user it connects to.

If several clients connect using the same port number, they all open a VNC session to the same server user.

You must configure a mapping for each server user that exports a VNC session. For every such user, you must pick a unique port and display number.

The recommended mapping

Red Hat recommends that you start with port number 5902 and display number 2 for the first user, and increment the numbers by one for each additional server user.

Port number 5900 and display number 0 represent the server user that is currently logged into the graphical session. You cannot start a VNC server for the user who is already logged into the graphical session.

Table 5.1. Port and display number pairs

Port number	Display number	Note
5900	0	The logged-in user
5901	1	
5902	2	The first recommended VNC user
5903	3	
...	...	



IMPORTANT

Red Hat recommends that you do not configure the **root** user to export a VNC session. A **root** VNC session is unsafe and certain elements of the session might not work as expected.

Firewall rules

You must open the selected ports in your firewall configuration. Allowing the **vnc-server** service in your firewall opens ports from 5900 to 5903. If you need to enable access to additional server users, you must open ports above 5903 by manually specifying the port numbers.

5.3.2. VNC server configuration files

Several configuration files affect the behavior of the VNC server. You can configure the user mapping and various global options.

General options

You can configure general options of the VNC server in the **/etc/tigervnc/vncserver-config-defaults** configuration file. The file uses the following format:

```
option1=value
option2
```

For example:

```
session=gnome
alwaysshared
securitytypes=vncauth,tlsvnc
desktop=sandbox
geometry=2000x1200
```

The priority of configuration files

The VNC server reads the following files for general options, in order from most important to least important:

1. **/etc/tigervnc/vncserver-config-mandatory**
This file replaces the default configuration and has a higher priority than the per-user configuration. It is intended for system administrators who want to enforce particular VNC options.
2. **\$HOME/.vnc/config**
Individual users can override the default VNC configuration in this file.
3. **/etc/tigervnc/vncserver-config-defaults**
This file stores the default VNC configuration.

User mapping

You can configure the mapping between users and their associated port and display numbers in the **/etc/tigervnc/vncserver.users** configuration file. The file uses the following format:

```
:number=user
```

For example:

```
:2=test  
:3=vncuser
```

Additional resources

- For a list of available configuration options, see the **Xvnc(1)** man page.

5.3.3. Enabling multi-user VNC access on the server

This procedure configures a RHEL server so that multiple users can open VNC sessions on it at the same time.

Prerequisites

- If you previously configured VNC using systemd unit files, remove any outdated VNC configuration:

```
[root]# rm /etc/systemd/system/vncserver@.service
```

Procedure

1. Install the VNC server:

```
[root]# yum install tigervnc-server
```

2. Map users to display and port numbers.

In the **/etc/tigervnc/vncserver.users** configuration file, add a line for each server user that will export a VNC session:

```
:user-number=user-name
```

- Replace *user-number* with the port and display number mapped to the selected existing user.
- Replace *user-name* with the user name of the selected existing user.

For example:

```
:2=vncuser
```

3. Open TCP ports 5900 to 5903 in the firewall:

```
[root]# firewall-cmd --permanent --add-service=vnc-server
```

4. Reload the firewall rules:

```
[root]# firewall-cmd --reload
```

5. Add the following lines to the **/etc/tigervnc/vncserver-config-defaults** configuration file:

```
session=gnome
alwaysshared
```

This configuration has the following effects:

- The VNC server starts the GNOME session when a remote user logs in.
 - Multiple users can connect to the VNC server at the same time.
6. As each server user that exports a VNC session, set the VNC password for the user:

```
[regular-user]$ vncpasswd
```

Remote clients must enter this password when connecting to the desktop on the server.

7. If you previously configured VNC for the user, ensure that the configuration files have the correct **SELinux** context:

```
[regular-user]$ restorecon -RFv ~/.vnc
```

8. Enable and start the VNC server unit for the regular user:

```
[root]# systemctl enable --now vncserver@:user-number
```

9. If the server uses the proprietary Nvidia driver, disable Wayland:
 - a. Uncomment the **WaylandEnable=False** line in the `/etc/gdm/custom.conf` configuration file.
 - b. Add the **DefaultSession=gnome-xorg.desktop** option to the **[daemon]** section of the configuration file.
 - c. Reboot the server.

Additional resources

- To enable VNC access to more than two server users, open TCP ports above 5903. For details, see [Controlling ports using CLI](#) or [Opening ports using GUI](#).

5.3.4. Connecting to the VNC server as multiple users

This procedure connects to a remote desktop session using the **vncviewer** application. You can open multiple connections to the remote desktop at the same time.

Prerequisites

- Remote desktop access for multiple users is enabled on the server. For details, see [Section 5.3.3, “Enabling multi-user VNC access on the server”](#).

Procedure

1. Install the VNC client:

```
# yum install tigervnc
```

2. Connect to the VNC server:

```
$ vncviewer --shared server-ip:display
```

- Replace *server-ip* with the IP address of the server that you are connecting to.
- Replace *display* with the display number where the server user exports the VNC session.

5.4. REMOTELY ACCESSING AN INDIVIDUAL APPLICATION

You can remotely launch a graphical application on a RHEL server and use it from the remote client.


5.4.1. Enabling X11 forwarding on the server

This procedure configures a RHEL server so that remote clients can use graphical applications on the server over SSH.

Procedure

1. Install basic X11 packages:

```
# yum install xorg-x11-xauth xorg-x11-fonts-* xorg-x11-utils dbus-x11
```



NOTE

Your applications might rely on additional graphical libraries.

2. Check that the **X11Forwarding** option is enabled in the `/etc/ssh/sshd_config` configuration file:

```
X11Forwarding yes
```

The option is enabled by default in RHEL. Your organization might have disabled it.

3. Restart the **sshd** service:

```
# systemctl restart sshd.service
```

5.4.2. Launching an application remotely using X11 forwarding

This procedure accesses a graphical application on a RHEL server from a remote client using SSH.

Prerequisites

- X11 forwarding over SSH is enabled on the server. For details, see [Section 5.4.1, “Enabling X11 forwarding on the server”](#).
- Ensure that an X11 display server is running on your system:
 - On RHEL, X11 is available by default in the graphical interface.
 - On Microsoft Windows, install an X11 server such as Xming.

- On macOS, install the XQuartz X11 server.

Procedure

1. Log in to the server using SSH:

```
[local-user]$ ssh -X -Y remote-server
```

2. Launch the application from the command line:

```
[remote-user]$ application-binary
```

CHAPTER 6. CONFIGURING GNOME AT LOW LEVEL

6.1. INTRODUCTION TO CONFIGURING GNOME

To be able to configure the GNOME Desktop Environment, you need to understand these basic terms:

- `dconf`
- `GSettings`
- `gsettings`

dconf has two different meanings.

Firstly, **dconf** is a key-based Binary Large Object (BLOB) database for storing GNOME configurations. **dconf** manages user settings such as GDM, application, and proxy settings, and serves as the back end for **GSettings**.

Secondly, **dconf** is a command-line utility which is used for reading and writing individual values or entire directories from and to a dconf database.

GSettings is a high-level API for application settings which serves as the front end for dconf.

gsettings is a command-line tool which is used to view and change user settings.

6.2. MANAGING USER AND SYSTEM GNOME SETTINGS

dconf allows system administrators and users several levels of control over GNOME configuration:

- Administrators can define default settings that apply to all users.
- Users can override the defaults with their own settings.
- Administrators can also lock settings to prevent users from overriding them.

6.3. DISPLAYING GSETTINGS VALUES FOR DESKTOP APPLICATIONS

Viewing and editing of the **GSettings** values can be achieved with one of the following tools:

- `dconf-editor` GUI tool
- `gsettings` command-line utility


The **dconf-editor** application and **gsettings** utility have the following in common:

- allow browsing and changing options for system and application preferences
- allow to change preferences
- can be run by regular users, because both tools are intended to browse and modify the current user's **GSettings** database

The **dconf-editor** provides a GUI for browsing the settings and their editing. It presents the hierarchy of settings in a tree-view and also displays additional information about each setting, including the description, type and default value.

The **gsettings** utility can be used to display and set dconf values. **gsettings** utility supports Bash completion for commands and settings. This tool also allows you to automate configuration in shell scripts.

Figure 6.1. dconf-editor showing org.gnome.desktop.background GSettings keys



Prerequisites

- The **dconf-editor** is not installed on the system by default. To install it, run the following command as the **root** user:

```
~]# yum install dconf-editor
```

Procedure

- To list GSettings values in the GUI, open the **dconf-editor** application.
- To list a specific GSettings value on the command line, use the following command:

```
$ gsettings get schema key
```

For example:

```
$ gsettings get org.gnome.desktop.background picture-uri
```

Additional resources

- For more information on the **dconf-editor** tool, see the **dconf-editor(1)** man page and the [dconf-editor Project documentation](#).
- For more information on the **gsettings** utility, see the **gsettings(1)** man page.

6.4. USING DCONF PROFILES

The dconf system stores configuration in several different databases. You can configure dconf profiles, which specify the databases that dconf uses.

6.4.1. Introduction to dconf profiles

A dconf profile is a list of system's hardware and software configuration databases, which the dconf system collects.

The dconf profiles allow you to compare identical systems to troubleshoot hardware or software problems.

The dconf system stores its profiles in the text files which can be located either within the **/etc/dconf/profile/** directory or elsewhere. The **\$DCONF_PROFILE** environment variable can specify a relative path to the file from **/etc/dconf/profile/**, or an absolute path, such as in a user's home directory.

Note that key pairs which are set in a dconf profile override the default settings.

6.4.2. Selecting a dconf profile

On startup, **dconf** consults the **\$DCONF_PROFILE** environment to find the name of the dconf profile to open. The result depends on whether the variable is set or not:

- If set, **dconf** attempts to open the profile named in the variable and aborts if this step fails.
- If not set, **dconf** attempts to open the profile named **user** and uses an internal hard-wired configuration if this step fails.

Each line in a dconf profile specifies one dconf database.

The first line indicates the database used to write changes. The remaining lines show read-only databases.

The following is a sample profile stored in **/etc/dconf/profile/user**:

```
user-db:user
system-db:local
system-db:site
```

In this example, the dconf profile specifies three databases. **user** is the name of the user database which can be found in **~/.config/dconf**, and **local** and **site** are system databases, located in **/etc/dconf/db/**.



NOTE

To apply a new dconf user profile to the user's session, you need to log out and log in, because the dconf profile for a session is determined at login.

**WARNING**

As a user or application developer, do not manipulate dconf directly. To manipulate dconf, always use the **dconf-editor** or the **gsettings** utility. The only exception to use dconf directly is when setting system-wide default configurations, because the aforementioned tools do not allow to manipulate such configurations.

6.5. CONFIGURING CUSTOM DEFAULT VALUES

Machine-wide default settings can be set by providing a default for a key in a dconf profile. These defaults can be overridden by the user.

Prerequisites

- the user profile exists
- the value for the key was added to a dconf database

Procedure

For example, to set the default background:

1. Create the user profile in **/etc/dconf/profile/user**:

```
user-db:user
system-db:local
```

where **local** is the name of a dconf database.

2. Create a keyfile for the local database in **/etc/dconf/db/local.d/01-background**, which contains the following default settings:

```
# dconf path

[org/gnome/desktop/background]

# GSettings key names and their corresponding values
picture-uri='file:///usr/local/share/backgrounds/wallpaper.jpg'
picture-options='scaled'
primary-color='000000'
secondary-color='FFFFFF'
```

In the default setting of the keyfile, the following GSettings keys are used:

Table 6.1. org.gnome.desktop.background schemas GSettings Keys

Key Name	Possible Values	Description
----------	-----------------	-------------

Key Name	Possible Values	Description
picture-options	"none", "wallpaper", "centered", "scaled", "stretched", "zoom", "spanned"	Determines how the image set by wallpaper_filename is rendered.
picture-uri	filename with the path	URI to use for the background image. Note that the backend only supports local file:// URIs.
primary-color	default: 000000	Left or Top color when drawing gradients, or the solid color.
secondary-color	default: FFFFFFFF	Right or Bottom color when drawing gradients, not used for solid color.

3. Edit the keyfile according to your preferences.
For more information, see [Section 6.3, “Displaying GSettings values for desktop applications”](#).
4. Update the system databases:

```
~]# dconf update
```

When the user profile is created or changed, the user needs to log out and log in again before the changes will be applied.

Additional resources

- If you want to avoid creating a user profile, you can use the **dconf** command-line utility to read and write individual values or entire directories from and to a dconf database. For more information, see the **dconf(1)** man page.

6.6. LOCKING DOWN SPECIFIC SETTINGS

By using the lockdown mode in dconf, you can prevent users from changing specific settings.

Without enforcing the system settings using a lockdown, any settings that users make take precedence over the system settings. User can thus override the system settings with their own.

Procedure

To lock down a GSettings key:

1. Create a locks subdirectory in the keyfile directory such as **/etc/dconf/db/local.d/locks/**.
2. Add any number of files with keys that you want to lock into this directory.

Example 6.1. Locking the settings for the default wallpaper

1. Set a default wallpaper.
2. Create a new **/etc/dconf/db/local.d/locks/** directory.

3. Create a new file in **/etc/dconf/db/local.d/locks/00-default-wallpaper** with the following contents, listing one key per line:

```
# Prevent users from changing values for the following keys:
/org/gnome/desktop/background/picture-uri
/org/gnome/desktop/background/picture-options
/org/gnome/desktop/background/primary-color
/org/gnome/desktop/background/secondary-color
```

4. Update the system databases:

```
~]# dconf update
```

6.7. STORING USER SETTINGS OVER NFS

For **dconf** to work correctly when using Network File System (NFS) home directories, the **dconf keyfile back end** must be used.

Note that **dconf keyfile back end** only works properly if the **glib2-fam** package is installed. Without this package, notifications on configuration changes made on remote machines are not displayed properly.

With Red Hat Enterprise Linux 8, **glib2-fam** is available in the BaseOs repository.

To set the **dconf keyfile back end**

1. Ensure that the **glib2-fam** package is installed on the system.
To verify whether the package is installed on the system:

```
~]# yum list installed
```

If **glib2-fam** is not in the list of installed packages, install it by running:

```
~]# yum install glib2-fam
```

2. Create or edit the **/etc/dconf/profile/user** file on every client.
3. At the very beginning of **/etc/dconf/profile/user file**, add the following line:

```
service-db:keyfile/user
```

The **dconf keyfile back end** takes effect the next time that the user logs in. It polls the keyfile to determine whether updates have been made, so settings may not be updated immediately.

6.8. SETTING GSETTINGS KEYS PROPERTIES

This section describes how to set GSettings keys properties for a single-logged user.

Each GSettings key can have only one value in a dconf database. Setting the same key to a different value at a different place of the dconf database overrides the previous value.

Values of some keys are of array type. For array type, you can specify the value of the key as a list of multiple elements separated by a comma.

To set a GSettings key of array type, follow this syntax:

```
key=['option1', 'option2']
```

The following example shows setting of the **org.gnome.desktop.input-sources.xkb-options** GSettings key whose value is of array type:

Example settings of the org.gnome.desktop.input-sources.xkb-options GSettings Key

```
[org/gnome/desktop/input-sources]
# Enable Ctrl-Alt-Backspace for all users
# Set the Right Alt key as the Compose key and enable it
xkb-options=['terminate:ctrl_alt_bksp', 'compose:ralt']
```

6.9. WORKING WITH GSETTINGS KEYS ON COMMAND LINE

This section focuses on using of the **gsettings** command to configure, manipulate and manage the GSettings keys. The most frequent use cases that can be resolved by using the **gsettings** command are shown.

6.9.1. Setting key value

To set a value of a key:

```
gsettings set SCHEMA [:PATH] KEY
```

Note that the value is specified as a serialised GVariant.

Example 6.2. Adding selected applications into the favorite applications key

To add selected applications among your favorite applications:

```
$ gsettings set org.gnome.shell favorite-apps "[firefox.desktop, 'evolution.desktop',
'rhythmbox.desktop', 'shotwell.desktop', 'org.gnome.Nautilus.desktop',
'org.gnome.Software.desktop', 'yelp.desktop', 'org.gnome.Terminal.desktop',
'org.gnome.clocks.desktop']"
```

If the operation succeeds, no return code is shown. As a result, all listed applications are added to favorite applications. The change is valid immediately.

6.9.2. Monitoring key changes

To monitor a key for changes and print values that changed:

```
gsettings monitor SCHEMA [:PATH] [KEY]
```

Note that if the KEY argument is not specified, all keys in the schema are monitored. Monitoring continues until the process is terminated.

Example 6.3. Monitoring changes of the favorite applications key

To monitor the changes of the **favorite applications** key, open two terminals and run:

In the first terminal:

```
$ gsettings monitor org.gnome.shell favorite-apps
```

In the second terminal:

```
$ gsettings set org.gnome.shell favorite-apps "[firefox.desktop, 'evolution.desktop',
'rhythmbox.desktop', 'shotwell.desktop', 'org.gnome.Nautilus.desktop',
'org.gnome.Software.desktop', 'yelp.desktop', 'org.gnome.Terminal.desktop']"
```

As a result, a notification whether and how **favorite applications** changed is displayed in the first terminal:

```
favorite-apps: ['firefox.desktop', 'evolution.desktop', 'rhythmbox.desktop', 'shotwell.desktop',
'org.gnome.Nautilus.desktop', 'org.gnome.Software.desktop', 'yelp.desktop',
'org.gnome.Terminal.desktop']
```

6.9.3. Checking whether key is writable

To check whether a key is writable:

```
gsettings writable SCHEMA [:PATH] KEY
```

Example 6.4. Checking whether the favorite applications key is writable

To check whether the **favorite applications** key is writable:

```
$ gsettings writable org.gnome.shell favorite-apps
```

As a result, the return code shows **True**.

6.9.4. Checking key valid values

To check the range of valid values for a key:

```
gsettings range SCHEMA [:PATH] KEY
```

Example 6.5. Checking the range of valid values for the remember-mount-password key

To check valid values for the **remember-mount-password** key:

```
$ gsettings range org.gnome.shell remember-mount-password
```

As a result, the return code displays type of the key value, which is **type b** in this particular case. For more information, see [GNOME developer](#).

6.9.5. Checking description of valid key values

To check the description of valid values for a key:

```
gsettings describe SCHEMA [:PATH] KEY
```

Example 6.6. Checking the description of valid values for the picture-uri key

To check the description of valid values for the **picture-uri** key:

```
$ gsettings describe org.gnome.desktop.screensaver picture-uri
```

As a result, the following output is displayed:

```
URI to use for the background image. Note that the backend only supports local file:// URIs.
```

6.9.6. Querying key value

To get the value of a key:

```
gsettings get SCHEMA [:PATH] KEY VALUE
```

Note that the value is displayed as a serialised GVariant.

Example 6.7. Querying value of the remember-mount-password key

To get value of the **remember-mount-password** key:

```
$ gsettings get org.gnome.shell remember-mount-password
```

As a result, the return code displays **false**.

6.9.7. Resetting key value

To reset the value of a key:

```
gsettings reset SCHEMA [:PATH] KEY
```

If resetting succeeds, no return code is displayed. Default values are in stored dconf and gsettings-desktop-schemas files.

Example 6.8. Resetting the lock-delay key to its default value

The default value of the **lock-delay** key is 0, and it is stored in the **/usr/share/glib-2.0/schemas/org.gnome.desktop.screensaver.gschema.xml** file.

Users can set the value of **lock-delay** as needed.

For example, to set the **lock-delay** key for screensaver to 200:


```
$ gsettings set org.gnome.desktop.screensaver lock-delay 200
```

To reset the **lock-delay** key for screensaver to its default value:

```
$ gsettings reset org.gnome.desktop.screensaver lock-delay
```

As a result, the value of **lock-delay** value is set to 0.

6.9.8. Resetting schema

To reset a schema:

```
gsettings reset-recursive SCHEMA [:PATH]
```

Example 6.9. Resetting the org.gnome.desktop.screensaver schema to its defaults

To reset the **org.gnome.desktop.screensaver** schema to its defaults:

```
$ gsettings reset-recursive org.gnome.desktop.screensaver
```

As a result, the **lock-delay** value is reset to 0, and other keys within the **org.gnome.desktop.screensaver** schema that were changed by user are reset to their defaults as well.

6.9.9. Listing installed non-relocatable schemas

To list installed schemas that are non-relocatable:

```
gsettings list-schemas [--print-paths]
```

If the **[--print-paths]** argument is specified, the path where each schema is mapped is printed as well.

Example 6.10. Listing installed non-relocatable schemas

To list all schemas installed on your system that are non-relocatable:

```
$ gsettings list-schemas
```

As a result, a full list of schemas is returned. The following list is truncated.

```
org.gnome.rhythmbox.library
org.gnome.shell.overrides
org.gnome.system.proxy.https
org.gnome.clocks
org.gnome.eog.fullscreen
org.gnome.login-screen
org.gnome.eog.view
```

6.9.10. Listing schema keys

To list the keys that are in the selected schema:

```
gsettings list-keys SCHEMA [:PATH]
```

Example 6.11. Listing keys in the **org.gnome.shell** schema

To list keys in the **org.gnome.shell** schema:

```
$ gsettings list-keys org.gnome.shell
```

As a result, a list of keys is returned. The following list is truncated.

```
enabled-extensions
command-history
remember-mount-password
always-show-log-out
had-bluetooth-devices-setup
looking-glass-history
disable-user-extensions
app-picker-view
disable-extension-version-validation
development-tools
favorite-apps
```

6.9.11. Listing schema children

To list children of a selected schema:

```
gsettings list-children SCHEMA [:PATH]
```

Note that the list is empty if there are no children.

Example 6.12. Listing children of the **org.gnome.shell** schema

To list children of the **org.gnome.shell** schema:

```
$ gsettings list-children org.gnome.shell
```

As a result, the following output is returned:

```
keyboard org.gnome.shell.keyboard
keybindings org.gnome.shell.keybindings
```

6.9.12. Listing schema's keys and values

To list keys and values of a selected schema recursively:

```
gsettings list-recursively [SCHEMA [:PATH]]
```

Note that if the schema whose keys you want to list is not specified, all keys within all schemas are listed.

Example 6.13. Listing keys and values recursively

To list keys and values in all schemas recursively:

```
$ gsettings list-recursively
```

As a result, all key and values in all schemas on system are listed, as shown below. Note that the following list is truncated.

```
org.gnome.nautilus.desktop network-icon-visible false
org.gnome.nautilus.desktop font "
org.gnome.nautilus.desktop network-icon-name 'Network Servers'
org.gnome.nautilus.desktop home-icon-name 'Home'
org.gnome.nautilus.desktop volumes-visible true
org.gnome.Vinagre always-enable-listening false
org.gnome.Vinagre always-show-tabs false
org.gnome.Vinagre show-accelers false
org.gnome.Vinagre history-size 15
org.gnome.Vinagre shared-flag true
```

6.10. ACKNOWLEDGEMENTS

Certain portions of this text first appeared in the [GNOME Desktop System Administration Guide](#). Copyright © 2014 The GNOME Project, Michael Hill, Jim Campbell, Jeremy Bicha, Ekaterina Gerasimova, minnie_eg, Aruna Sankaranarayanan, Sindhu S, Shobha Tyagi, Shaun McCance, David King, and others. Licensed under a [Creative Commons Attribution-ShareAlike 3.0 Unported License](#).

The editors of this Red Hat Enterprise Linux 8 documentation would like to thank the GNOME community members for their valuable contributions to the GNOME Desktop System Administration Guide.

CHAPTER 7. CONFIGURING FILE ASSOCIATIONS

This section provides information on configuring RHEL to open or access files with different formats.

In GNOME, MIME (Multipurpose Internet Mail Extension) types help to identify the format of a file and applications to use to open these files.

7.1. MULTIPURPOSE INTERNET MAIL EXTENSION TYPES

The GNOME desktop uses MIME types to:

- Determine which application should open a specific file format by default.
- Register other applications that can open files of a specific format.
- Set a string describing the type of a file, for example, in a file properties dialog of the files application.
- Set an icon representing a specific file format, for example, in a file properties dialog of the files application.

MIME type names follow a given format:

media-type/subtype-identifier

For example, **image/jpeg**.

Here **image** is a media type and **jpeg** is the subtype identifier.

GNOME follows Multipurpose Internet Mail Extension (MIME) info specification from the [Freedesktop.org](https://freedesktop.org) to determine:

- The machine-wide and user-specific location to store all the MIME type specification files.
- How to register a MIME type so that the desktop environment knows which application you can use to open a specific file format.
- How users can change which applications should open with what file formats.

MIME database

The MIME database is a collection of all the MIME type specification files that GNOME uses to store information about known MIME types.

The most important part of the MIME database from the system administrator's point of view is the **/usr/share/mime/packages/** directory, where the MIME type-related files specifying information on known MIME types are stored. One example of such a file is **/usr/share/mime/packages/freedesktop.org.xml**, specifying information about the standard MIME types available on the system, by default. The shared-mime-info package provides this file.

Additional resources

- For detailed information describing the MIME type system, see Shared MIME Info specifications on the [Freedesktop website](https://freedesktop.org).

7.2. ADDING A CUSTOM MIME TYPE FOR ALL USERS

You must create a new MIME type specification file in the `/usr/share/mime/packages/` directory and a `.desktop` file in the `/usr/share/applications/` directory to add a custom MIME type for all the users on the system and register a default application for that MIME type.

Procedure

1. Create the `/usr/share/mime/packages/application-x-newtype.xml` file with following content:

```
<?xml version="1.0" encoding="UTF-8"?>

<mime-info xmlns="http://www.freedesktop.org/standards/shared-mime-info">
  <mime-type type="application/x-newtype">
    <comment>new mime type</comment>
    <glob pattern="*.xyz"/>
  </mime-type>
</mime-info>
```

The sample `application-x-newtype.xml` file here defines a new MIME type `application/x-newtype` and assigns file names with the `.xyz` extension to that MIME type.

2. Create a new `.desktop` file named, for example, `myapplication1.desktop` in the `/usr/share/applications/` with following content:

```
[Desktop Entry]
Type=Application
MimeType=application/x-newtype
Name=My Application 1
Exec=myapplication1
```

The sample `myapplication1.desktop` file here associates the `application/x-newtype` MIME type with an application named **My Application 1**. It is run by a command `myapplication1`.

3. As a root user, update the MIME database for your changes to take effect.

```
# update-mime-database /usr/share/mime
```

4. As a root user, update the application database.

```
# update-desktop-database /usr/share/applications
```

Verification steps

1. To verify that you have successfully associated `*.xyz` files with the `application/x-newtype` MIME type, first create an empty file, for example `test.xyz` and execute the following commands:

```
$ touch test.xyz

$ gvfs-info test.xyz | grep "standard::content-type"
standard::content-type: application/x-newtype
```

2. To verify `myapplication1.desktop` is correctly set as the default registered application for the `application/x-newtype` MIME type, execute following command:

```
$ gio mime --query application/x-newtype
```

```

Default application for 'application/x-newtype': myapplication1.desktop
Registered applications:
  myapplication1.desktop
Recommended applications:
  myapplication1.desktop

```

7.3. ADDING A CUSTOM MIME TYPE FOR INDIVIDUAL USERS

You must create a new MIME type specification file in the `~/.local/share/mime/packages/` directory and a **.desktop** file in the `~/.local/share/applications/` directory to add a custom MIME type for individual users and register a default application for that MIME type.

Procedure

1. Create the `~/.local/share/mime/packages/application-x-newtype.xml` file with following content:

```

<?xml version="1.0" encoding="UTF-8"?>
<mime-info xmlns="http://www.freedesktop.org/standards/shared-mime-info">
  <mime-type type="application/x-newtype">
    <comment>new mime type</comment>
    <glob pattern="*.xyz"/>
  </mime-type>
</mime-info>

```

The sample **application-x-newtype.xml** file here defines a new MIME type **application/x-newtype** and assigns file names with the **.xyz** extension to that MIME type.

2. Create a new **.desktop** file named, for example, **myapplication1.desktop**, and place it in the `~/.local/share/applications/` directory with following content:

```

[Desktop Entry]
Type=Application
MimeType=application/x-newtype
Name=My Application 1
Exec=myapplication1

```

The sample **myapplication1.desktop** file above associates the **application/x-newtype** MIME type with an application named My Application 1. It is run by a command **myapplication1**.

3. Update the MIME database for your changes to take effect:

```
$ update-mime-database ~/.local/share/mime
```

4. Update the application database:

```
$ update-desktop-database ~/.local/share/applications
```

Verification steps

1. To verify that you have successfully associated ***.xyz** files with the **application/x-newtype** MIME type, first create an empty file, for example, **test.xyz** and execute the following commands:

■

```
$ touch test.xyz
```

```
$ gvfs-info test.xyz | grep "standard::content-type"
standard::content-type: application/x-newtype
```

2. To verify that **myapplication1.desktop** is correctly set as the default registered application for the **application/x-newtype** MIME type, execute following command:

```
$ gio mime --query application/x-newtype
Default application for 'application/x-newtype': myapplication1.desktop
Registered applications:
  myapplication1.desktop
Recommended applications:
  myapplication1.desktop
```

7.4. OPTIONS TO OVERRIDE DEFAULT MIME TYPES

By default, the package-installed **/usr/share/applications/mimeapps.list** and **/usr/share/applications/gnome-mimeapps.list** files specify which application is registered to open specific MIME types.

System administrators can create the **/etc/xdg/mimeapps.list** or **/etc/xdg/gnome-mimeapps.list** file with a list of MIME types they want to override with the default registered application.

Local users can create the **~/.local/share/applications/mimeapps.list** or **~/.local/share/applications/gnome-mimeapps.list** file with a list of MIME types for which they want to override the default registered application.

Configurations are applied in the following order:

1. **/usr/share/applications/**
2. **/etc/xdg/**
3. **~/.local/share/application/**

Within a particular location, the configurations are applied in the following order:

1. **mimeapps.list**
2. **gnome-mimeapps.list**

7.5. OVERRIDING DEFAULT REGISTERED APPLICATION FOR ALL THE USERS

As a system administrator, you can update the configuration based on the requirements. System administrator's configuration takes precedence over default package configuration. Within each, the desktop-specific configuration takes precedence over the configuration that does not specify the desktop environment.

Procedure

1. Consult the **/usr/share/applications/mimeapps.list** file to determine the MIME types for which you want to change the default registered application. For example, the following sample of the

mimeapps.list file specifies the default registered application for the **text/html** and **application/xhtml+xml** MIME types:

```
[Default Applications]
text/html=firefox.desktop
application/xhtml+xml=firefox.desktop
```

This example above specifies default application (Firefox) by specifying its corresponding **.desktop** file (**firefox.desktop**). You can find **.desktop** files for other applications in the **/usr/share/applications/** directory.

2. Create the **/etc/xdg/mimeapps.list** file and specify the MIME types and their corresponding default registered applications in this file.

```
[Default Applications]
text/html=myapplication1.desktop
application/xhtml+xml=myapplication2.desktop
```

This example above sets the default registered application for the **text/html** MIME type to **myapplication1.desktop** and **application/xhtml+xml** MIME type to **myapplication2.desktop**.

Verification steps

- For these settings to function correctly, ensure that both the **myapplication1.desktop** and **myapplication2.desktop** files are placed in the **/usr/share/applications/** directory.
- Execute the **gio mime query** command to verify that the default registered application is set correctly.

```
$ gio mime text/html
Default application for 'text/html': myapplication1.desktop
Registered applications:
myapplication1.desktop
firefox.desktop
Recommended applications:
myapplication1.desktop
firefox.desktop
```

7.6. OVERRIDING DEFAULT REGISTERED APPLICATION FOR INDIVIDUAL USERS

Individual users can also update the configuration based on the requirements. This configuration takes precedence over the system administrator's configuration and the system administrator's configuration takes precedence over the package configuration. Within each, the desktop-specific configuration takes precedence over the configuration that does not specify the desktop environment.

Procedure

1. Consult the **/usr/share/applications/mimeapps.list** file to determine the MIME types for which you want to change the default registered application. For example, the following sample of the **mimeapps.list** file specifies the default registered application for the **text/html** and **application/xhtml+xml** MIME types:


```
[Default Applications]
text/html=firefox.desktop
application/xhtml+xml=firefox.desktop
```

This example above specifies default application (Firefox) by specifying its corresponding **.desktop** file (**firefox.desktop**). You can find **.desktop** files for other applications in the **/usr/share/applications/** directory.

2. Create the **~/.local/share/applications/mimeapps.list** file and specify the MIME types and their corresponding default registered applications in this file.

```
[Default Applications]
text/html=myapplication1.desktop
application/xhtml+xml=myapplication2.desktop
```

This example above sets the default registered application for the **text/html** MIME type to **myapplication1.desktop** and **application/xhtml+xml** MIME type to **myapplication2.desktop**.

Verification steps

- For these settings to function correctly, ensure that both the **myapplication1.desktop** and **myapplication2.desktop** files are placed in the **/usr/share/applications/** directory.
- Execute the **gio mime query** command to verify that the default registered application is set correctly.

```
$ gio mime text/html
Default application for 'text/html': myapplication1.desktop
Registered applications:
  myapplication1.desktop
  firefox.desktop
Recommended applications:
  myapplication1.desktop
  firefox.desktop
```

CHAPTER 8. CUSTOMIZING DESKTOP APPEARANCE

This section explains how system administrators can customize appearance of the desktop environment for different users of the system.

8.1. CUSTOMIZING DESKTOP BACKGROUNDS

As a system administrator, you can configure the default desktop background, add extra backgrounds, or add multiple backgrounds using the **dconf** utility.

If the users of the system are not permitted to change background from the defaults, system administrator needs to lock the settings using the **locks** directory. Otherwise, each user can customize the background according to their preferences.

8.1.1. Customizing the default desktop background

You can configure the default desktop background and its appearance by setting the relevant GSettings keys in the **org.gnome.desktop.background** schema.

For more information about **GSettings**, see [Section 6.1, “Introduction to configuring GNOME”](#).

Use the following procedure to set the default background:

Procedure

1. Create a local database for machine-wide settings in **/etc/dconf/db/local.d/00-background**:

```
# Specify the dconf path
[org/gnome/desktop/background]

# Specify the path to the desktop background image file
picture-uri='file:///usr/local/share/backgrounds/wallpaper.jpg'
# Specify one of the rendering options for the background image:
# 'none', 'wallpaper', 'centered', 'scaled', 'stretched', 'zoom', 'spanned'
picture-options='scaled'
# Specify the left or top color when drawing gradients or the solid color
primary-color='000000'
# Specify the right or bottom color when drawing gradients
secondary-color='FFFFFF'
```

2. Optionally, if you want a user to not be able to change the default background, override the user's setting in the **/etc/dconf/db/local.d/locks/background** file:

```
# List the keys used to configure the desktop background
/org/gnome/desktop/background/picture-uri
/org/gnome/desktop/background/picture-options
/org/gnome/desktop/background/primary-color
/org/gnome/desktop/background/secondary-color
```

3. Update the system databases:

```
# dconf update
```

4. Users must log out and back in again before the system-wide settings take effect.

8.1.2. Adding extra backgrounds

You can make extra backgrounds available to users on your system.

Procedure

1. Use the **org.gnome.desktop.background** schemas to create a file in the **xml** format specifying your extra background's appearance.

Table 8.1. Frequently used org.gnome.desktop.background schemas GSettings Keys

Key Name	Possible Values	Description
picture-options	"none", "wallpaper", "centered", "scaled", "stretched", "zoom", "spanned"	Determines how the image set by wallpaper_filename is rendered.
color-shading-type	"horizontal", "vertical", and "solid"	Determines shade the background color.
primary-color	default: #023c88	Left or Top color when drawing gradients, or the solid color.
secondary-color	default: #5789ca	Right or Bottom color when drawing gradients, not used for solid color.

The full range of options can be found in the **dconf-editor** GUI or the **gsettings** command-line utility. For more information, see [Section 6.3, "Displaying GSettings values for desktop applications"](#).

2. Store the *.xml file under the **/usr/share/gnome-background-properties/** directory.

When a user clicks their name in the top right corner, chooses **Settings**, and in the **Personal** section of the table selects **Background**, they will see the new background available.

Example implementation of org.gnome.desktop.background GSettings keys

An example extra backgrounds file with one <wallpaper> element

```
<?xml version="1.0" encoding="UTF-8"?>
<!DOCTYPE wallpapers SYSTEM "gnome-wp-list.dtd">
<wallpapers>
  <wallpaper deleted="false">
    <name>Company Background</name>
    <name xml:lang="de">Firmenhintergrund</name>
    <filename>/usr/local/share/backgrounds/company-wallpaper.jpg</filename>
    <options>zoom</options>
    <shade_type>solid</shade_type>
    <pcolor>#ffffff</pcolor>
    <scolor>#000000</scolor>
  </wallpaper>
</wallpapers>
```

In one configuration file, you can specify multiple **<wallpaper>** elements to add more backgrounds as shown in the following example with two **<wallpaper>** elements, adding two different backgrounds.

An example extra backgrounds file with two **<wallpaper>** elements

```
<?xml version="1.0" encoding="UTF-8"?>
<!DOCTYPE wallpapers SYSTEM "gnome-wp-list.dtd">
<wallpapers>
  <wallpaper deleted="false">
    <name>Company Background</name>
    <name xml:lang="de">Firmenhintergrund</name>
    <filename>/usr/local/share/backgrounds/company-wallpaper.jpg</filename>
    <options>zoom</options>
    <shade_type>solid</shade_type>
    <pcolor>#ffffff</pcolor>
    <scolor>#000000</scolor>
  </wallpaper>
  <wallpaper deleted="false">
    <name>Company Background 2</name>
    <name xml:lang="de">Firmenhintergrund 2</name>
    <filename>/usr/local/share/backgrounds/company-wallpaper-2.jpg</filename>
    <options>zoom</options>
    <shade_type>solid</shade_type>
    <pcolor>#ff0000</pcolor>
    <scolor>#00ffff</scolor>
  </wallpaper>
</wallpapers>
```

8.1.3. Setting the screen shield

Screen shield is the screen that quickly slides down when the system is locked. It is controlled by the **org.gnome.desktop.screensaver.picture-uri** GSettings key. GDM uses its own dconf profile, so you can set the default background by changing the settings in that profile.

For more information on **GSettings** and **dconf**, see [Section 6.1, "Introduction to configuring GNOME"](#).

Procedure

1. Create a gdm database for machine-wide settings in **/etc/dconf/db/gdm.d/01-screensaver**:

```
[org/gnome/desktop/screensaver]
picture-uri='file:///opt/corp/background.jpg'
```

Replace **/opt/corp/background.jpg** with the path to the image file you want to use as the screen shield. Supported formats are PNG, JPG, JPEG, and TGA. Note that the image will be scaled if necessary to fit the screen.

2. Update the system databases:

```
# dconf update
```

3. Users must log out and back in again before the system-wide settings take effect.

Troubleshooting

If the screen shield does not update, you can:

1. Make sure that you have updated the system databases by running the **dconf update** command as the **root** user.
2. Try restarting GDM.

8.2. USING GNOME SHELL EXTENSIONS TO CUSTOMIZE DESKTOP ENVIRONMENT

GNOME Shell extensions allow for the customization of the default GNOME Shell interface and its parts, such as window management and application launching.



IMPORTANT

Before deploying third-party GNOME Shell extensions on Red Hat Enterprise Linux, make sure to read the following document to learn about the Red Hat support policy for third-party software: [How does Red Hat Global Support Services handle third-party software, drivers, and/or uncertified hardware/hypervisors?](#)

8.2.1. Overview of GNOME Shell extensions

This section provides an overview of GNOME Shell extensions available on RHEL 8, including the name of the package providing a particular extension, and the description of what each extension does.

Table 8.2. Overview of available GNOME Shell extensions

Package name	Extension name	Description
gnome-shell-extension-apps-menu	apps-menu	Applications menu for GNOME Shell
gnome-shell-extension-top-icons	Top Icons	Show legacy icons on top
gnome-shell-extension-user-theme	user-theme	Support for custom themes in GNOME Shell
gnome-shell-extension-drive-menu	drive-menu	Drive status menu for GNOME Shell
gnome-shell-extension-window-list	window-list	Display a window list at the bottom of the screen in GNOME Shell
gnome-shell-extension-dash-to-dock	Dash to Dock	Dock for the Gnome Shell by micxgx.gmail.com
gnome-shell-extension-desktop-icons	Desktop Icons	Desktop icons support for the GNOME Classic experience
gnome-shell-extension-no-hot-corner	nohotcorner	Disable the hot corner in GNOME Shell

Package name	Extension name	Description
gnome-shell-extension-systemMonitor	systemMonitor	System Monitor for GNOME Shell
gnome-shell-extension-updates-dialog	Updates Dialog	Show a modal dialog when there are software updates
gnome-shell-extension-window-grouper	window-grouper	Keep windows that belong to the same process on the same workspace
gnome-shell-extension-panel-favorites	panel-favorites	Favorite launchers in GNOME Shell's top bar
gnome-shell-extension-windowsNavigator	windowNavigator	Support for keyboard selection of windows and workspaces in GNOME shell
gnome-shell-extension-auto-move-windows	Autom Move Windows	Assign specific workspaces to applications in GNOME Shell
gnome-shell-extension-launch-new-instance	launch-new-instance	Always launch a new application instance for GNOME Shell
gnome-shell-extension-workspace-indicator	workspace-indicator	Workspace indicator for GNOME Shell
gnome-shell-extension-disable-screenshield	Disable Screen Shield	Disable GNOME Shell screen shield if lock is disabled
gnome-shell-extension-native-window-placement	native-window-placement	Native window placement for GNOME Shell
gnome-shell-extension-screenshot-window-sizer	screenshot-window-sizer	Screenshot window sizer for GNOME Shell
gnome-shell-extension-horizontal-workspaces	horizontal-workspaces	Desktop icons support for the GNOME Classic experience
gnome-shell-extension-places-menu	places-menu	Places status menu for GNOME Shell
gnome-classic-session	–	GNOME Classic mode session

8.2.2. Enabling machine-wide extensions

Prerequisites

To make extensions available to all users on the system, install them in the **/usr/share/gnome-shell/extensions** directory.

Procedure

1. Create a local database file for machine-wide settings in **/etc/dconf/db/local.d/00-extensions**:

```
[org/gnome/shell]
# List all extensions that you want to have enabled for all users
enabled-extensions=['myextension1@myname.example.com',
'myextension2@myname.example.com']
```

The **enabled-extensions** key specifies the enabled extensions using the extensions' uuid (**myextension1@myname.example.com** and **myextension2@myname.example.com**).

2. Update the system databases:

```
# dconf update
```

3. Users must log out and back in again before the system-wide settings take effect.



NOTE

There is currently no way to enable additional extensions for users who have already logged in. This does not apply for existing users who have installed and enabled their own GNOME extensions.

8.2.3. Locking down enabled extensions

You can prevent the user from enabling or disabling extensions by locking down the **org.gnome.shell.enabled-extensions** key.

Procedure

1. Create a local database file for machine-wide settings in **/etc/dconf/db/local.d/00-extensions**:

```
[org/gnome/shell]
# List all extensions that you want to have enabled for all users
enabled-extensions=['myextension1@myname.example.com',
'myextension2@myname.example.com']
```

The **enabled-extensions** key specifies the enabled extensions using the extensions' uuid (**myextension1@myname.example.com** and **myextension2@myname.example.com**).

2. Override the user's setting and prevent the user from changing it in **/etc/dconf/db/local.d/locks/extensions**:

```
# Lock the list of mandatory extensions
/org/gnome/shell/enabled-extensions
```

3. Update the system databases:

```
# dconf update
```

4. Users must log out and back in again before the system-wide settings take effect.

After locking down the **org.gnome.shell.enabled-extensions**, any extensions installed in **~/.local/share/gnome-shell/extensions** or **/usr/share/gnome-shell/extensions** that are not listed in the **org.gnome.shell.enabled-extensions** key will not be loaded by GNOME Shell, thus preventing the user from using them.

8.2.4. Setting up mandatory extensions

In GNOME Shell, you can provide a set of extensions that the user has to use.

Prerequisites

The extensions must be installed under the **/usr/share/gnome-shell/extensions** directory.

Procedure

1. Create a local database file for machine-wide settings in **/etc/dconf/db/local.d/00-extensions-mandatory**:

```
[org/gnome/shell]
# List all mandatory extensions
enabled-extensions=['myextension1@myname.example.com',
'myextension2@myname.example.com']
```

The **enabled-extensions** key specifies the enabled extensions using the extensions' uuid (**myextension1@myname.example.com** and **myextension2@myname.example.com**).

2. Override the user's setting and prevent the user from changing it in **/etc/dconf/db/local.d/locks/extensions-mandatory**:

```
# Lock the list of mandatory extensions
/org/gnome/shell/enabled-extensions
```

3. Update the system databases:

```
# dconf update
```

4. Users must log out and back in again before the system-wide settings take effect.

CHAPTER 9. CUSTOMIZING GNOME DESKTOP FEATURES

9.1. CHANGING THE LANGUAGE USING DESKTOP GUI


This section describes how to change the system language using the desktop GUI.

Prerequisites


- Required language packages are installed on your system

Procedure


1. Open the **GNOME Control Center** from the **System menu** by clicking on its icon.




2. In the **GNOME Control Center**, choose **Region & Language** from the left vertical bar.
3. Click the **Language** menu.




4. Select the required region and language from the menu.



If your region and language are not listed, scroll down, and click **More** to select from available regions and languages.



5. Click **Done**.
6. Click **Restart** for changes to take effect.



NOTE

Some applications do not support certain languages. The text of an application that cannot be translated into the selected language remains in US English.

Additional resources

- [Launching applications in GNOME](#)

9.2. ENABLING THE CTRL+ALT+BACKSPACE SHORTCUT

The **Ctrl+Alt+Backspace** shortcut key combination is used for terminating the **X.Org** display server.

You might want to terminate **X.Org** especially when:

- A program caused **X.Org** to stop working.
- You need to switch from your logged-in session quickly.
- You have launched a program that failed.
- You cannot operate in the current session.
- Your screen freezes.

To enable the **Ctrl+Alt+Backspace** shortcut to forcibly terminate **X.Org** by default for all users, you need to set the **org.gnome.desktop.input-sources.xkb-options** GSettings key.

Procedure

1. Create a local database for machine-wide settings in **/etc/dconf/db/local.d/00-input-sources**:

```
[org/gnome/desktop/input-sources]
# Enable Ctrl-Alt-Backspace for all users
xkb-options=["terminate:ctrl_alt_bksp"]
```

2. Override the user's setting, and prevent the user from changing it in **/etc/dconf/db/local.d/locks/input-sources**:

```
# Lock the list of enabled XKB options
/org/gnome/desktop/input-sources/xkb-options
```

3. Update the system databases for the changes to take effect:

```
# dconf update
```


4. Users must log out and back in again before the system-wide settings take effect.

If the **Ctrl+Alt+Backspace** key combination is enabled, all users can terminate **X.Org**, which brings them back to the login prompt.

9.3. DISABLING COMMAND-LINE ACCESS

To disable command-line access for a desktop user, you need to make configuration changes in a number of different contexts:

- [Section 9.3.1, “Setting the org.gnome.desktop.lockdown.disable-command-line Key”](#)
- [Section 9.3.2, “Disabling virtual terminal switching on X.Org”](#)
- Remove **Terminal** and any other application that provides access to the terminal from the **Applications menu** and **Activities Overview** in GNOME Shell. This is done by removing menu items for those applications.



NOTE

The following steps do not remove the desktop user’s permissions to access a command line, but rather remove the ways that the desktop user could access command line.

9.3.1. Setting the org.gnome.desktop.lockdown.disable-command-line Key

This approach prevents the user from:

- Accessing the terminal
- Specifying a command line to be executed by using the **Alt+F2** command prompt

Procedure

1. Create a local database for machine-wide settings in **/etc/dconf/db/local.d/00-lockdown**:

```
[org/gnome/desktop/lockdown]
# Disable command-line access
disable-command-line=true
```

2. Override the user’s setting and prevent the user from changing it in **/etc/dconf/db/local.d/locks/lockdown**:

```
# Lock the disabled command-line access
/org/gnome/desktop/lockdown
```

3. Update the system databases:

```
# dconf update
```

4. Users must log out and back in again before the system-wide settings take effect.

9.3.2. Disabling virtual terminal switching on X.Org

With the **X.Org** display server, users can normally use the **Ctrl+Alt+function** key shortcuts to switch from the GNOME Desktop and **X.Org** to a virtual terminal. You can disable access to all virtual terminals by modifying the **X.Org** configuration. The **X.Org** configuration should be modified by adding the **DontVTSwitch** option to the **Serverflags** section of an X configuration file in the **/etc/X11/xorg.conf.d/** directory, as shown by the following procedure.



IMPORTANT

You cannot apply the procedure if **GNOME Shell on Wayland** is used as the display server.

Procedure

1. Create or edit an X configuration file in the **/etc/X11/xorg.conf.d/** directory:



NOTE

By convention, these host-specific configuration file names start with two digits and a hyphen and always have the **.conf** extension. Thus, the following file name can be **/etc/X11/xorg.conf.d/10-xorg.conf**.

```
Section "Serverflags"
```

```
Option "DontVTSwitch" "yes"
```

```
EndSection
```

2. Restart the **X.Org** display server for the changes to take effect.

9.4. PREVENTING THE COMPUTER FROM SUSPENDING WHEN CLOSING THE LID

When closing the lid of your laptop, the computer by default suspends in order to save power. You can prevent the computer from suspending when closing the lid by changing the setting for that behavior.



WARNING

Some laptops can overheat if they are left running with the lid closed, especially if they are in a confined place. Therefore, consider whether changing the default setting from suspend to an other option is beneficial in your case.

Procedure

1. Open the **/etc/systemd/logind.conf** file for editing.

- Find the **HandleLidSwitch=suspend** line in the file.
If it is quoted out with the **#** character at the start, unquote it by removing **#**.

If the line is not present in the file, add it.

- Replace the default **suspend** parameter with:

- **lock** for the screen to lock
- **ignore** for nothing to happen
- **poweroff** for the computer to switch off

For example:

```
[Login]
HandleLidSwitch=lock
```

- Save your changes, and close the editor.
- Run the following command so that your changes preserve the next restart of the system:

```
# systemctl restart systemd-logind.service
```



WARNING

Restarting the service forcibly interrupts any currently running GNOME session of any desktop user who is logged in. This can result in users losing unsaved data.

For more information on the **/etc/systemd/logind.conf** file, see the **logind.conf** man page.

9.5. CHANGING BEHAVIOR WHEN PRESSING THE POWER BUTTON IN GRAPHICAL TARGET MODE

When the machine is booted to a graphical login screen or user session, hitting the **power** button makes the machine suspend by default. This happens both in cases when the user presses the **power** button physically or when pressing a virtual **power** button from a remote console. To achieve a different behavior when pressing the **power** button, set the function of this button with **dconf**.

For example, if you want the system to shutdown after pressing the **power** button, use the following procedure:

Procedure

- Create a local database for system-wide settings in the **/etc/dconf/db/local.d/01-power** file:

```
[org/gnome/settings-daemon/plugins/power]
power-button-action='interactive'
```

2. Override the user's setting, and prevent the user from changing it in the **/etc/dconf/db/local.d/locks/01-power** file:

```
/org/gnome/settings-daemon/plugins/power/power-button-action
```

3. Update the system databases:

```
# dconf update
```

4. Log out and back in again before the system-wide settings take effect.


This configuration initiates a system shutdown after pressing the **power** button. To configure the system differently, you can set the behavior of particular buttons.

Options for particular buttons:

- nothing
does nothing
- suspend
suspends the system
- hibernate
hibernates the system
- interactive
shows a pop-up query asking the user what to do

With interactive mode, the system powers off automatically after 60 seconds when hitting the power button. However, you can choose a different behavior from the pop-up query as shown in the figure below.

Pop-up query for interactive mode



CHAPTER 10. ENABLING CHINESE, JAPANESE, OR KOREAN TEXT INPUT

If you write with Chinese, Japanese, or Korean characters, you can configure RHEL to input text in your language.

10.1. INPUT METHODS

Certain scripts, such as Chinese, Japanese, or Korean, require keyboard input to go through an Input Method Engine (IME) to enter native text.

An input method is a set of conversion rules between the text input and the selected script. An IME is a software that performs the input conversion specified by the input method.

To input text in these scripts, you must set up an IME. If you installed the system in your native language and selected your language at the **GNOME Initial Setup** screen, the input method for your language is enabled by default.

10.2. AVAILABLE INPUT METHOD ENGINES

The following input method engines (IMEs) are available on RHEL from the listed packages:

Table 10.1. Available input method engines

Languages	Scripts	IME name	Package
Chinese	Simplified Chinese	Intelligent Pinyin	ibus-libpinyin
Chinese	Traditional Chinese	New Zhuyin	ibus-libzhuyin
Japanese	Kanji, Hiragana, Katakana	Kana Kanji	ibus-kkc
Korean	Hangul	Hangul	ibus-hangul
Other	Various	M17N	ibus-m17n

10.3. INSTALLING INPUT METHOD ENGINES

This procedure installs input method engines (IMEs) that you can use to input Chinese, Japanese, and Korean text.

Procedure

- Install all available input method packages:

```
# yum install @input-methods
```

10.4. SWITCHING THE INPUT METHOD IN GNOME


This procedure sets up the input method for your script, such as for Chinese, Japanese, or Korean scripts.

Prerequisites


- The input method packages are installed.

Procedure


1. Go to the **system menu**, which is accessible from the top-right screen corner, and click the **Settings** icon.
2. Select the **Region & Language** section.
3. In the **Input Sources** list, review the currently enabled input methods.



4. If your input method is missing:
 - a. Click the **+** button under the **Input Sources** list.




- b. Select your language.


**NOTE**

If you cannot find your language in the menu, click the three dots icon (**More...**) at the end of the menu.

- c. Select the input method that you want to use. A cog wheel icon marks all input methods to distinguish them from simple keyboard layouts.



- d. Confirm your selection by clicking **Add**.
5. Switch the active input method using one of the following ways:
 - Click the input method indicator on the right side of the top panel and select your input method.



- Switch between the enabled input methods using the **Super+Space** keyboard shortcut.

Verification

1. Open a text editor.
2. Type text in your language.
3. Verify that the text appears in your native script.

CHAPTER 11. INPUTTING UNCOMMON CHARACTERS USING THE COMPOSE KEY

The Compose key is a feature that enables you to type special symbols or characters which are missing on your keyboard. In GNOME Desktop, you can define one of the existing keys on your keyboard as the Compose key. You can use the Compose key in combination with other keys, known as Compose key sequences, to enter special characters you type frequently.

11.1. ENABLING THE COMPOSE KEY

You can enable the Compose key either for an individual user or for all users.

11.1.1. Enabling the Compose key for an individual user with the Tweaks application

To enable the Compose key for an individual user by Tweaks application follow these steps.


Prerequisites

- The **Tweaks** application is installed on your system.

```
# yum install gnome-tweaks
```

Procedure

1. Open the **Tweaks** application.
2. Navigate into **Keyboard & Mouse - Compose Key** and enable it.
3. Choose which key will be used as the Compose key from the listed keys.



11.1.2. Enabling the Compose key for an individual user using GSettings

To enable the Compose key for an individual user by **gsettings** command follow these steps.

Procedure

- Enable the Compose key and set the compose character to right **alt**.

```
$ gsettings set org.gnome.desktop.input-sources xkb-options "['compose:ralt']"
```

If you want to set a different key than right **alt**, replace *ralt* with the name of the key as specified in the **man xkeyboard-config(7)**.

11.1.3. Enabling the Compose key for all users

To enable the Compose key for all users follow these steps.

Procedure

1. Create a **local** database for machine-wide settings and enter the following:

```
# vim /etc/dconf/db/local.d/00-input-sources
```

```
[org/gnome/desktop/input-sources]
# Set the Right Alt key as the Compose key and enable it
xkb-options=['compose:ralt']
```

If you want to set a different key than right **alt**, replace *ralt* with the name of the key as specified in the **man xkeyboard-config(7)**.

2. To override the user's settings and prevent the user from changing it, create a file **/etc/dconf/db/local.d/locks/input-sources** and enter the following:

```
# vim /etc/dconf/db/local.d/locks/input-sources
```

```
# Lock the list of enabled XKB options
/org/gnome/desktop/input-sources/xkb-options
```

3. Update the system databases for changes to take effect:

```
# dconf update
```

4. Users must log out and back in again before the system-wide settings take effect.

11.2. USING THE COMPOSE KEY TO INPUT CHARACTERS

This procedure shows how to use the Compose key.

Prerequisites

- The Compose key is enabled on your system.

Procedure

Procedure

1. Press and release the Compose key.
2. Type the key combination to get the specific symbol. For example, type **A E** (in capitals) to get **Æ**, or in lowercase to get **æ**.

11.3. THE COMPOSE KEY SEQUENCES

This section shows some of the Compose key sequences.

Table 11.1. Common sequences

First key	Second key	Third key	Result
o	c		©
d	h		ð
,	a		ą
s	s		ß
<	<		«
?	?		¿
-	-	-	—
^	-	a	ä
=	c		€
1	4		¼

Additional resources

For more sequences refer to the [X.Org](#) webpage.

CHAPTER 12. MANAGING STORAGE VOLUMES IN GNOME

This section describes how you can manage storage volumes in GNOME with a virtual file system. GNOME Virtual File System (GVFS) is an extension of the virtual file system interface provided by the libraries the GNOME desktop is built on.

12.1. THE GVFS SYSTEM

The GVFS provides complete virtual file system infrastructure and handles storage in the GNOME desktop. It uses addresses for full identification based on the URI (Uniform Resource Identifier) standard, syntactically similar to URL addresses in web browsers. These addresses in the form of **schema://user@server/path** are the key information determining the kind of service.

The GVFS helps to mount the resources. These mounts are shared between multiple applications. Resources are tracked globally within the running desktop session, which means that even if you quit an application that triggered the mount, it continues to be available for any other application. Multiple applications can access the mount at the same time unless it is limited by a back end. Some protocols by design permit only a single channel.

GVFS mounts removable media in the **/run/media/** directory.

12.2. THE FORMAT OF THE GVFS URI STRING

You must form a URI string to use back end services. This string is a basic identifier used in GVFS, which carries all necessary information needed for unique identification, such as type of service, back end ID, absolute path, or user name if required. You can see this information in the **Files** address bar and GTK+ open or save file dialog.

The following example is a very basic form of the URI string and points to a root directory (/) of the FTP (File Transfer Protocol) server running at *ftp.myserver.net* domain:

Example: URI string pointing to the root FTP directory

```
ftp://ftp.myserver.net/
```

Example: URI string pointing to a text file

```
ssh://joe@ftp.myserver.net/home/joe/todo.txt
```

12.3. MOUNTING A STORAGE VOLUME IN GNOME

In virtual file systems, particular resources are set to be mounted automatically, but the most common way is to trigger mounts manually.

Procedure

1. Open the **Files** application.
2. Press **Ctrl+L** to view the location bar.
3. Enter a well-formed URI string.
Alternatively, **Files** provides the **Connect to server** dialog, which you can find in **Other locations** → **Connect to server**.

4. When asked for login credentials, enter your name and password into the relevant entry boxes.
5. When the mounting process finishes, you can start working with the storage volume.

12.4. UNMOUNTING A STORAGE VOLUME IN GNOME

You can eject or unmount resources using the following procedure.

Procedure

1. Click the **Eject** icon on the chosen mount.
2. Wait until the mount disappears or notification about the safe removal appears.

12.5. OVERVIEW OF FUSE DAEMON IN GVFS

Applications built with the GIO library can access GVFS mounts. In addition, GVFS provides a FUSE daemon which exposes active GVFS mounts. Any application can access active GVFS mounts using the standard POSIX APIs as though mounts were regular file systems.

In certain applications, additional library dependency and new virtual file system (VFS) subsystem specifics might be unsuitable or too complicated. For such reasons and to boost compatibility, GVFS provides a File System in Userspace (FUSE) daemon, which exposes active mounts through its mount for standard Portable Operating System Interface (POSIX) access. This daemon transparently translates incoming requests to imitate a local file system for applications.



IMPORTANT

You might experience difficulties with certain combinations of applications and GVFS back ends.

The FUSE daemon starts automatically with the main **gvfs** daemon and places its mount either in the **/run/user/UID/gvfs/** or **~/.gvfs/** files as a fallback. Manual browsing shows individual directories for each GVFS mount. The system passes the transformed path as an argument when you are opening documents from GVFS locations with non-native applications. Note that native GIO applications automatically translate this path back to a native URI.

12.6. GIO TOOLS AND XDG-UTILS IN GNOME


GIO provides several commands that might be useful for scripting or testing. Here is a set of POSIX commands counterparts as follows:

Commands	Description
gio cat	Displays the content of a file.
gio mkdir	Creates a new directory.
gio rename	Renames a file.

gio mount	Provides access to various aspects of the gio mounting functionality.
gio set	Sets a file attribute on a file.
gio copy	Makes a copy of a file.
gio list	Lists directory contents.
gio move	Moves a file from one location to another.
gio remove	Removes a file.
gio trash	Sends files or directories to the Trashcan . This can be a different folder depending on where the file is located, and not all file systems support this concept. In the common case that the file lives inside a user's home directory, the trash folder is \$XDG_DATA_HOME/Trash .
gio info	Displays information of the given locations.
gio save	Reads from standard input and saves the data to the given location.
gio tree	Lists the contents of the given locations recursively, in a tree-like format. If no location is given, it defaults to the current directory.

Following additional commands provide more control of GIO specifics:

gio monitor	Monitors files or directories for changes, such as creation, deletion, content and attribute changes, and mount and unmount operations affecting the monitored locations.
gio mime	Lists the registered and recommended applications for the mimetype if no handler is given, else, it is set as the default handler for the mimetype.
gio open	Opens files with the default application that is registered to handle files of this type.



NOTE

For user convenience, **bash** completion is provided as a part of the package.

All these commands are native GIO clients, there is no need for the fallback FUSE daemon to be

running. Their purpose is not to be drop-in replacements for POSIX commands, in fact, a very little range of switches is supported. In their basic form, these commands take an URI string as an argument instead of a local path.

This all allows GNOME to be well-supported within **xdg-tools**, a freedesktop.org interoperability project. For example, the **xdg-open** utility calls **gio open** when a running GNOME session is detected, and reads the file type associations from the correct location.

Additional resources

- The **gio(1)** man page.

12.7. EXECUTING THE GIO COMMANDS

The following are a few examples of the GIO commands usage:

- To lists all files in /tmp on a local file system, run:

```
$ gio list file:///tmp
```

- To list contents of a text file from a remote machine:

```
$ gio cat ssh://joe@ftp.myserver.net/home/joe/todo.txt
```

- To copy the referenced text file to a local /tmp directory, run:

```
$ gio copy ssh://joe@ftp.myserver.net/home/joe/todo.txt /tmp/
```

Additional resources

- The **gio** man page.

12.8. OVERVIEW OF GVFS METADATA

The GVFS metadata storage is implemented as a set of key-and-value pairs that bind information to a particular file. Thus, there is a tool for a user or application to save small data designed for runtime information such as icon position, last-played location, position in a document, emblems, notes, and so on.

Whenever you move a file or directory, GVFS moves the metadata accordingly so that metadata stays connected to the respective file. The GVFS stores all metadata privately, so metadata is available only on the machine. However, GVFS tracks mounts and removable media as well.



NOTE

GVFS mounts removable media in the **/run/media/** directory.

To view and manipulate with metadata, you can use:

- the **gio info** command,
- the **gio set** command, or

- any other native GIO way of working with attributes.

Additional resources

- The **gio** man page.

12.9. SETTING CUSTOM GIO METADATA ATTRIBUTE

This procedure describes how to set a custom metadata attribute.

Notice the differences between particular **gio info** calls and data persistence after a move or rename (note the **gio info** command output):

Procedure

1. Create an empty file.

```
$ touch /tmp/myfile
```

2. View the metadata of this file.

```
$ gio info -a 'metadata:*' /tmp/myfile
uri: file:///tmp/myfile
attributes:
```

3. Set a string to this file.

```
$ gio set -t string /tmp/myfile 'metadata::mynote' 'Please remember to delete this file!'
```

4. View the metadata.

```
$ gio info -a 'metadata:*' /tmp/myfile
uri: file:///tmp/myfile
attributes:
  metadata::mynote: Please remember to delete this file!
```

5. Move this file to a new location.

```
$ gio move /tmp/myfile /tmp/newfile
```

6. View the metadata.

```
$ gio info -a 'metadata:*' /tmp/newfile
uri: file:///tmp/newfile
attributes:
  metadata::mynote: Please remember to delete this file!
```

The metadata persists when you move the file using the GIO API.

Additional resources

- The **gio** man page.

12.10. PASSWORD MANAGEMENT OF GVFS MOUNTS

A typical GVFS mount authenticates on its activation unless the resource allows anonymous authentication or does not require any authentication at all. In a standard GTK+ dialog, you can choose to store or not to store the password.

When you select the persistent storage, the password is stored in the user **keyring**. **GNOME Keyring** is a central place for secrets storage. The password is encrypted and automatically unlocked on desktop session start using the password provided on login. For protecting it by a different password, you can set the password at the first use.

The **Passwords and Keys** application helps to manage the stored password and **GNOME Keyring**. It allows removing individual records or changing passwords.

Additional resources

- For more information on **Passwords and Keys**, see the help manual for **Passwords and Keys** embedded directly in the desktop.

12.11. ACCESSING GVFS MOUNTS THAT REQUIRE AUTHENTICATION

This procedure describes how you can access GVFS mounts using authentication.

Procedure

1. Open **Files**
2. Activate the address bar by pressing **Ctrl+L**
3. Enter a well-formed URI string of a service that needs authentication (for example, **sftp://localhost/**).
The credentials dialog appears asking for a user name, password, and password storage options.
4. Fill in the credentials and confirm.

12.12. GVFS BACK ENDS

Back ends in GVFS provide access to a specific type of resource. The following is a list of available GVFS back ends and their specifications:



NOTE

Some back ends are packaged separately and not installed by default. For installing additional back ends, use the **yum** package manager.

Table 12.1. Available back ends

Back end	Description
afc	Similar to MTP (Media Transfer Protocol), exposes files on your Apple iDevice (connected through USB).

Back end	Description
afp	Apple Filing Protocol (AFP) client to access file services of macOS X and original Mac operation system.
archive	Handles various archiving files (ZIP, TAR) in read-only way.
admin	Provides admin access to the local file system.
burn	A virtual back end that burning applications use as a temporary storage for new CD, DVD, or BD medium contents.
cdda	Exposes Audio CD through separate Waveform Audio File Format (WAV) files.
computer	Virtual back end consolidating active mounts and physical volumes. Acts similarly to a signpost. Previously used by Nautilus for its Computer view.
dav, davs	WebDAV client, including secure variant. Authentication is possible only during mount. The back end does not support later re-authentication on per-folder basis.
dns-sd	DNS Service Discovery – Avahi client, used during network browsing, forms persistent URIs to discovered services.
ftp	A fully featured File Transfer Protocol (FTP) client. Supports passive transfers by default. Also, handles secure mode over ftps (explicit mode) and ftpis (implicit mode) schemes.
gphoto2	A Picture Transfer Protocol (PTP) client to access your camera attached by USB or FireWire.
google	Provides access to Google Drive. The Google Drive account needs to be configured over Gnome online accounts.
http	Handles all HTTP requests; useful for easy downloading files from web in client applications.
locatest	Simple testing back end that proxies the file:/// URI . The back end supports error injection.

Back end	Description
mtp	Media Transfer Protocol back end for accessing media player and smart phone memory.
network	Allows you to browse Window Network and show shares discovered over Avahi.
recent	A back end used in the file chooser dialog to list recent files used by GNOME applications.
sftp	A fully-featured SSH File Transfer Protocol (SFTP) client.
smb	Access Samba and Windows shares.
trash	A trash back end which allows to restore deleted files.

12.13. TROUBLESHOOTING VOLUME MANAGEMENT IN GNOME

Following are some common errors of volume management in GNOME and ways to resolve them.

12.13.1. Troubleshooting access to GVFS locations from non-GIO clients

If you have problems accessing GVFS locations from your application, it might mean that it is not native GIO client. Native GIO clients are typically all GNOME applications using GNOME libraries (**glib**, **gio**). The **gvfs-fuse** service is provided as a fallback for non-GIO clients.

Prerequisite

- You have **gvfs-fuse** package installed.

```
$ dnf install gvfs-fuse
```

Procedure

1. Ensure that **gvfs-fuse** is running.

```
$ ps ax | grep gvfsd-fuse
```

Since **gvfs-fuse** runs automatically and it is not recommended to start it by yourself, try logging out and logging in, if **gvfs-fuse** is not running.

2. Find the system user ID (UID) for the **/run/user/UID/gvfs/** path by running the **id** command, the **gvfsd-fuse** daemon requires a path it is supposed to expose its services at, or, when the **/run/user/UID/gvfs/** path is unavailable, **gvfsd-fuse** uses a **.gvfs** path in your home directory.

```
$ id -u
```


3. If **gvfsd-fuse** is still not running, start the **gvfsd-fuse** daemon:

```
$ /usr/libexec/gvfsd-fuse -f /run/user/UID/gvfs
```

Now, the FUSE mount is available, and you can manually browse for the path in your application.

4. Find the GVFS mounts under the `/run/user/UID/gvfs/` or `.gvfs` locations.

12.13.2. Troubleshooting an invisible connected USB disk

Under certain circumstances, when you connect a flash drive, the GNOME Desktop might not display it. If your flash drive is not visible in **Files**, but you can see it in **Disks** application, you can attempt to set the **Show in user interface** flag in **Disks**.

Procedure

1. Open the **Disks** application.
2. Go to the **Additional partition option** actions menu clicking the **cogwheel** icon and click **Edit Mount Options...**
3. Click **Show in user interface** and confirm by clicking **OK**.
4. If the flash drive is still not visible, you can try to physically remove the drive and try connecting it again.

12.13.3. Troubleshooting unknown or unwanted partitions listed in Files

Sometimes, you might see unknown or unwanted partitions when you plug a disk in. For example, when you plug in a flash disk, it is automatically mounted and its volumes are shown in the sidebar. Some devices have a special partition with backups, or help files which you might not want to see each time you plug in the device.

Procedure

1. Open the **Disks** application.
2. Go to the **Additional partition option** actions menu clicking the **cogwheel** icon and click **Edit Mount Options...**
3. Uncheck **Show in user interface**
4. Confirm by clicking **OK**.

12.13.4. Troubleshooting if a connection to the remote GVFS file system is unavailable

There are number of situations in which the client is unexpectedly and unwillingly disconnected from a virtual file system or a remote disk mount and is not reconnected automatically. You might see the error messages in such situations. Several causes trigger such situations:

- The connection is interrupted. For example, your laptop is disconnected from the Wi-Fi.
- The user is inactive for some time and is disconnected by the server (idle timeout).

- The computer is resumed from sleep mode.

Procedure

1. Unmount file system.
2. Mount it again.
3. If the connection is getting disabled more often, check the settings in the **Network** panel in the GNOME **Settings**.

12.13.5. Troubleshooting a busy disk in GNOME

If you receive a notification about your disk being busy, determine the programs that are accessing the disk. Then, you can end the programs that are running. You can also use the **System Monitor** to kill the programs forcefully.

Prerequisites

- You have **iotop** installed. You can install it by running as a root user:

```
# yum install iotop
```

Procedure

1. Examine the list of open files.
 - Run the **lsdf** command to get the list of open files.
 - If **lsdf** is not available, run the **ps ax** command.
 - You can use the **System Monitor** application to display the running processes in a GUI.
2. When you have determined the programs, end or kill them as follows:
 - On the command line, execute the **kill** command.
 - In the **System Monitor**, right-click the line with the program process name, and click **End** or **Kill** from the context menu.

Additional resources

- The **kill** man page.

CHAPTER 13. MANAGING BOOKMARKS IN GNOME

In GNOME, you can edit the bookmarks that are displayed in applications and dialogs that manage files.

13.1. BOOKMARKS IN GNOME


Bookmarks integrate into GTK+ and in the GNOME desktop. Every application that presents a standard GTK+ **Open** and **Save** dialog (**GtkFileChooser**) lists bookmarks in the left panel of the dialog. Also, **Files** and its clones present bookmarks in a sidebar.

Besides bookmarks, **GtkFileChooser** lists all other available GVFS volumes and mounts in the sidebar.

While activating a bookmark for the first time, the GVFS subsystem looks for existing mounts and tries to mount the location if the mount does not exist yet. This way, you can authenticate even within the **Open** or **Save** dialog.

Bookmarks are located in the `~/.config/gtk-3.0/bookmarks` file. In the following example, the bookmarked locations are `~/Music`, `~/Pictures`, `~/Videos`, `~/Downloads`, and `~/bin`, so the content of the `~/.config/gtk-3.0/bookmarks` file looks as follows:

```
file:///home/username/Music
file:///home/username/Pictures
file:///home/username/Videos
file:///home/username/Downloads
file:///home/username/bin
```



NOTE

Replace username with the user name you are logged in.

You can use this file to edit bookmarks based on your requirements.

13.2. ADDING A BOOKMARK IN FILES

You can save a reference to a location by bookmarking it.

Procedure

1. Select the folder or file you want to bookmark.
2. Do one of the following:
 - Press **Ctrl+D** or
 - Drag and drop the file or folder to the sidebar.

13.3. BOOKMARKS FOR ALL GNOME USERS

System administrators can set a group of bookmarks for all users at once by allowing access to file shares for the users. **GNOME** stores a list of file-sharing servers in the `~/.config/gtk-3.0/servers` file in the XBEL format. XML Bookmark Exchange Language (XBEL) is an XML standard that allows you share URIs (Uniform Resource Identifiers). It is possible to add the list of file-sharing servers to that file to make file-shares easily accessible to multiple users.

In GNOME, XBEL is used to share desktop bookmarks in applications like **Files**. Here is an example of creating a bookmark titled **GNOME FTP** with the URI <ftp://ftp.gnome.org/> in the `~/.config/gtk-3.0/servers` file.

```
<?xml version="1.0" encoding="UTF-8"?>
<xbel version="1.0"
  xmlns:bookmark="http://www.freedesktop.org/standards/desktop-bookmarks"
  xmlns:mime="http://www.freedesktop.org/standards/shared-mime-info">
  <bookmark href="ftp://ftp.gnome.org/">
    <title>GNOME FTP</title>
  </bookmark>
</xbel>
```

CHAPTER 14. CUSTOMIZING DEFAULT FAVORITE APPLICATIONS

You can customize frequently used applications as your favorite applications. You can see these favorite applications on the GNOME Shell *dash* in the Activities overview. You can use **dconf** to set the favorite applications for an individual user or for all users.

14.1. SETTING DIFFERENT FAVORITE APPLICATIONS FOR INDIVIDUAL USERS

You can set the default favorite applications for individual users. You can add applications into your favorite list easily using any of the methods mentioned below.

- Open the Activities overview and click Activities at the top left of the screen.
- Click the grid button to find the application you want and right-click the application icon and select Add to Favorites.
- Click-and-drag the icon into the dash.

Run the following command to view all the applications that exists in the favorite list:

```
dconf read /org/gnome/shell/favorite-apps
```



NOTE

If you want to lock down the above settings to prevent users from changing them. See [Chapter 16, Locking down selected tasks](#) for more information.

14.2. SETTING THE SAME FAVORITE APPLICATIONS FOR ALL USERS

You can modify system database files using **dconf** keyfiles to set the same favorites for all users. The following steps edit the **dconf** profile and then create a keyfile to set default favorite applications for all users in the local configuration database.

Procedure

1. Create the key file **/etc/dconf/db/local.d/00-favorite-apps** to provide information for the local database. **/etc/dconf/db/local.d/00-favorite-apps** contents:

```
# Snippet sets gedit, terminal and nautilus as default favorites for all users
[org/gnome/shell]
favorite-apps = ['gedit.desktop', 'gnome-terminal.desktop', 'nautilus.desktop']
```

2. To prevent users from overriding these settings, create the file **/etc/dconf/db/local.d/locks/favorite-apps** with the following content:

```
# Lock default favorite applications
/org/gnome/shell/favorite-apps
```

3. Run the **dconf update** command to incorporate your changes into the system databases.

4. Logout and login again for system-wide changes to take effect.

CHAPTER 15. AUTHENTICATING THE USER IN THE DESKTOP ENVIRONMENT

You can perform the following operations:

- Configure enterprise login options in GNOME,
- Enable smart card authentication, and
- Enable fingerprint authentication.

15.1. USING ENTERPRISE CREDENTIALS TO AUTHENTICATE IN GNOME

You can use your enterprise domain credentials to access your system. This section explains how to log in using enterprise credentials in GNOME, configure enterprise credentials at the GNOME welcome screen, and add an authenticated user with enterprise credentials in GNOME.

15.1.1. Logging in with Enterprise Credentials in GNOME

You can use your domain credentials to login to GNOME if your network has an Active Directory or Identity Management domain available, and you have a domain account.

Prerequisites

- System is configured to use enterprise domain accounts
For more information, see [Joining the RHEL 8 system to the IdM domain using the web console](#)

Procedure

- While logging in, enter the domain user name followed by an @ sign, and then your domain name. For example, if your domain name is **example.com** and the user name is **User**, enter:

```
User@example.com
```



NOTE

If the machine is already configured for domain accounts, you should see a helpful hint describing the login format.

15.1.2. Configuring enterprise credentials at the GNOME welcome screen

Perform the following steps to configure workstation for enterprise credentials using the welcome screen that belongs to the **GNOME Initial Setup** program.

The initial setup runs only when you create a new user and log into that account for the first time.

Procedure

1. At the login welcome screen, choose **Use Enterprise Login**.
2. Enter your domain name into the **Domain** field.

3. Enter your domain account user name and password.
4. Click **Next**.
5. Depending on the domain configuration, a pop up prompts for the domain administrator's credentials.

15.1.3. Adding an authenticated user with enterprise credentials in GNOME

This procedure helps to create a new user through the **GNOME Settings** application. The user is authenticated using enterprise credentials.

Prerequisites

- Configured enterprise credentials at the GNOME welcome screen. For more information, see [Section 15.1.2, "Configuring enterprise credentials at the GNOME welcome screen"](#).

Procedure

1. Open the **Settings** window clicking icons in the top right corner of the screen.
2. From the list of items, select **Details > Users**.
3. Click **Unlock** and enter the administrator's password.
4. Click **Add user...**
5. Click **Enterprise Login**.
6. Fill out the **Domain**, **Username**, and **Password** fields for your enterprise account.
7. Click **Add**.
8. Depending on the domain configuration, a pop up prompts for the domain administrator's credentials.

15.1.4. Troubleshooting enterprise login in GNOME

You can use the realm utility and its various sub-commands to troubleshoot the enterprise login configuration.

Procedure

- To see whether the machine is configured for enterprise logins, run the following command:

```
$ realm list
```



NOTE

Network administrators can configure and pre-join workstations to the relevant domains using the kickstart **realm join** command, or running **realm join** in an automated fashion from a script.

Additional resources

- The **realm** man page.

15.2. ENABLING SMART CARD AUTHENTICATION

You can enable workstations to authenticate using smart cards. In order to do so, you must configure GDM to allow prompting for smart cards and configure operating system to log in using a smart card.

You can use two ways to configure the GDM to allow prompting for smart card authentication with GUI or using the command line.

15.2.1. Configuring smart card authentication in GDM using the GUI

You can enable smart card authentication using **dconf** editor GUI. The **dconf** Editor application helps to update the configuration-related values on a dconf database.

Prerequisites

- Install the dconf-editor package:

```
# yum install dconf-editor
```

Procedure

1. Open the dconf-Editor application and navigate to **/org/gnome/login-screen**.
2. Turn on the **enable-password-authentication** option.
3. Turn on the **enable-smartcard-authentication** option.

Additional resources

- The **dconf-editor** man page.
- The **dconf** man page.

15.2.2. Configuring smart card authentication in GDM using the command line

You can use the **dconf** command-line utility to enable the GDM login screen to recognize smart card authentication.

Procedure

1. Create a keyfile for the GDM database in **/etc/dconf/db/gdm.d/login-screen**, which contains the following content:

```
[org/gnome/login-screen]
enable-password-authentication='false'
enable-smartcard-authentication='true'
```

2. Update the system **dconf** databases:

```
# dconf update
```

Additional resources

- The **dconf** man page.

15.2.3. Enabling the smart card authentication method in the system

For smart card authentication you can use the **system-config-authentication** tool to configure the system to allow you to use smart cards. Thus, you can avail GDM as a valid authentication method for the graphical environment. The tool is provided by the **authconfig-gtk** package.

Prerequisites

- Install **authconfig-gtk** package
- Configure GDM for smart card authentication

Additional resources

- For details about configuring system to allow smart card authentication and the system-config-authentication tool, see [Configuring smart cards using authselect](#)

15.3. FINGERPRINT AUTHENTICATION

You can use the **system-config-authentication** tool to enable fingerprint authentication to allow users to login using their enrolled fingerprints. The tool is provided by the **authconfig-gtk** package.

Additional resources

- For more information about fingerprint authentication and the **system-config-authentication** tool, see the [Configuring user authentication using authselect](#).

CHAPTER 16. LOCKING DOWN SELECTED TASKS

This section describes how to lock down for users the following tasks:

- Printing
- File saving on disk
- Repartitioning
- User logout and user switching

16.1. LOCKING DOWN PRINTING

You can disable the print dialog from being shown to users. This can be useful if you are giving temporary access to a user or you do not want the user to print to network printers.



IMPORTANT

The feature only works in applications which support it. Not all GNOME and third party applications have this feature enabled. The changes do not have effect on applications which do not support this feature.

To prevent applications from printing, lock down the **org.gnome.desktop.lockdown.disable-printing** key:

Procedure

1. Create the user profile in **/etc/dconf/profile/user** unless it already exists:

```
user-db:user
system-db:local
```

2. Create a local database for machine-wide settings in the **etc/dconf/db/local.d/00-lockdown** file:

```
[org/gnome/desktop/lockdown]

# Prevent applications from printing
disable-printing=true
```

3. Override the user's setting and prevent the user from changing it in the **/etc/dconf/db/local.d/locks/lockdown** file:

```
# List the keys used to configure lockdown
/org/gnome/desktop/lockdown/disable-printing
```


4. Update the system databases:

```
# dconf update
```

Having followed these steps, applications supporting this lockdown key, such as **Evolution**, **Evince**, or **Gedit**, will disable printing.

16.2. LOCKING FILE SAVING ON DISK

You can disable the **Save** and **Save As** dialogs. This can be useful if you are giving temporary access to a user or you do not want the user to save files to the computer.



IMPORTANT

The feature only works in applications which support it. Not all GNOME and third party applications have this feature enabled. The changes will have no effect on applications which do not support this feature.

To prevent applications from file saving, lock down the **org.gnome.desktop.lockdown.disable-save-to-disk** key:

Procedure

1. Create the user profile in **/etc/dconf/profile/user** unless it already exists:

```
user-db:user
system-db:local
```

2. Create a local database for machine-wide settings in the **/etc/dconf/db/local.d/00-lockdown** file:

```
[org/gnome/desktop/lockdown]

# Prevent the user from saving files on disk
disable-save-to-disk=true
```

3. Override the user's setting and prevent the user from changing it in the **/etc/dconf/db/local.d/locks/lockdown** file:

```
# Lock this key to disable saving files on disk
/org/gnome/desktop/lockdown/disable-save-to-disk
```

4. Update the system databases:

```
# dconf update
```

Having followed these steps, applications supporting this lockdown key, for example **Videos**, **Image Viewer**, **Evolution**, **Document Viewer**, or **GNOME Shell**, will disable their **Save As** dialogs.

16.3. LOCKING REPARTITIONING

polkit enables you to set permissions for individual operations. For **udisks2**, the utility for disk management services, the configuration is located at **/usr/share/polkit-1/actions/org.freedesktop.udisks2.policy**. This file contains a set of actions and default values, which can be overridden by system administrator.



IMPORTANT

polkit configuration stored in **/etc** overrides the configuration shipped by packages in **/usr/share/**.

Procedure

1. Create a file with the same content as in **/usr/share/polkit-1/actions/org.freedesktop.udisks2.policy**:

```
cp /usr/share/polkit-1/actions/org.freedesktop.udisks2.policy /etc/share/polkit-1/actions/org.freedesktop.udisks2.policy
```

Do not change the **/usr/share/polkit-1/actions/org.freedesktop.udisks2.policy** file, your changes will be overwritten by the next package update.

2. Delete the action you do not need, and add the following lines to the **/etc/polkit-1/actions/org.freedesktop.udisks2.policy** file:

```
<action id="org.freedesktop.udisks2.modify-device">
  <message>Authentication is required to modify the disks settings</message>
  <defaults>
    <allow_any>no</allow_any>
    <allow_inactive>no</allow_inactive>
    <allow_active>yes</allow_active>
  </defaults>
</action>
```

Replace **no** by **auth_admin** if you want to ensure only the **root** user is able to perform the action.

3. Save the changes.

When the user tries to change the disks settings, the following message is returned:

```
Authentication is required to modify the disks settings.
```

16.4. LOCKING DOWN USER LOGOUT AND USER SWITCHING

To prevent the user from logging out, use the following procedure.

Procedure

1. Create the **/etc/dconf/profile/user** profile, which contains the following lines:

```
user-db:user
system-db:local
```

where **local** is the name of a dconf database

2. Create the **/etc/dconf/db/local.d/** directory if it does not already exist.
3. Create the **/etc/dconf/db/local.d/00-logout** key file to provide information for the local database:

```
[org/gnome/desktop/lockdown]
# Prevent the user from user switching
disable-log-out=true
```

4. Override the user's setting, and prevent the user from changing it in the **/etc/dconf/db/local.d/locks/lockdown** file:

```
# Lock this key to disable user logout
/org/gnome/desktop/lockdown/disable-log-out
```

5. Update the system databases:

```
# dconf update
```

6. Users must log out and back in again before the system-wide settings take effect.



IMPORTANT

Users can evade the logout lockdown by switching to a different user. To prevent such scenario, lock down user switching as well.

To lock down user switching, use the following procedure:

Procedure

1. Create the **/etc/dconf/profile/user** profile, which contains the following lines:

```
user-db:user
system-db:local
```

where **local** is the name of a dconf database

2. Create the **/etc/dconf/db/local.d/** directory if it does not already exist.
3. Create the **/etc/dconf/db/local.d/00-user-switching** key file to provide information for the local database:

```
# Prevent the user from user switching
[org/gnome/desktop/lockdown]
disable-user-switching=true

[org/gnome/desktop/screensaver]
user-switch-enabled=false
```

4. Override the user's setting, and prevent the user from changing it in the **/etc/dconf/db/local.d/locks/lockdown** file:

```
# Lock this key to disable user switching
/org/gnome/desktop/lockdown/disable-user-switching
/org/gnome/desktop/screensaver/user-switch-enabled
```

5. Update the system databases:

| # dconf update

6. Users must log out and back in again before the system-wide settings take effect.

CHAPTER 17. RESTRICTING THE SESSION TO A SINGLE APPLICATION

You can start the GNOME session in single-application mode, also known as kiosk mode. In this session, GNOME displays only a full-screen window of the application that you have selected.

17.1. SINGLE-APPLICATION MODE

Single-application mode is a modified GNOME session that reconfigures the Mutter window manager into an interactive kiosk. This session locks down certain behavior to make the standard desktop more restrictive. The user can interact only with a single application selected by the administrator.

You can set up single-application mode in a number of fields, from communication to entertainment or education, and use it as a self-serve machine, an event manager, a registration point, and so on.

The single-application mode configuration is available from the **gnome-session-kiosk-session** package.

17.2. ENABLING SINGLE-APPLICATION MODE

This procedure installs and enables single-application mode, which restricts the GNOME session to a single application.

Procedure

1. Install the **gnome-session-kiosk-session** package:

```
# yum install gnome-session-kiosk-session
```

2. As the user that will open the single-application session, create the **/home/user/.local/bin/redhat-kiosk** file:

```
[user]$ mkdir -p ~/.local/bin
```

```
[user]$ touch ~/.local/bin/redhat-kiosk
```

3. Edit the **/home/user/.local/bin/redhat-kiosk** file and enter the executable name of the application that you want to launch in single-application mode.
For example, to launch the **Firefox** browser in single-application mode, enter the following content:

```
#!/bin/sh

while true; do
    firefox --kiosk https://example.org
done
```

The **while true** loop ensures that the application restarts if it terminates for any reason.

4. Make the file executable:

```
[user]$ chmod +x ~/.local/bin/redhat-kiosk
```


5. If you created the file or its containing directories as a different user than the single-application user, such as **root**, ensure that the file has the correct permissions:

```
# chown -R user.group ~user/.local
```

6. At the GNOME login screen, select the **Kiosk** session from the cogwheel button menu and log in as the single-application user.

CHAPTER 18. MANAGING USER SESSIONS

18.1. WHAT GDM IS

The GNOME Display Manager (GDM) is a graphical login program running in the background that runs and manages the **X.Org** display servers for both local and remote logins.

GDM is a replacement for XDM, the X Display Manager. However, GDM is not derived from XDM and does not contain any original XDM code. In addition, there is no support for a graphical configuration tool in GDM, so editing the **/etc/gdm/custom.conf** configuration file is necessary to change the GDM settings.

18.2. RESTARTING GDM

When you make changes to the system configuration such as setting up the login screen banner message, login screen logo, or login screen background, restart GDM for your changes to take effect.



WARNING

Restarting the service forcibly interrupts any currently running GNOME session of any desktop user who is logged in. This can result in users losing unsaved data.

Procedure

- To restart the GDM service, run the following command:

```
# systemctl restart gdm.service
```

Procedure

- To display results of the GDM configuration, run the following command:

```
$ DCONF_PROFILE=gdm gsettings list-recursively org.gnome.login-screen
```

18.3. ADDING AN AUTOSTART APPLICATION FOR ALL USERS

You can set application to start automatically when any user logs into the GNOME environment.

Procedure

1. Create a **.desktop** file in the **/etc/xdg/autostart/** directory, such as **/etc/xdg/autostart/nautilus.desktop**. Enter the following content in the file:

```
[Desktop Entry]
Type=Application
Name=Files
```

```
Exec=/usr/bin/nautilus -n
OnlyShowIn=GNOME;
X-GNOME-Autostart-enabled=true
```

- Replace **Files** with the name of the application.
 - Replace **/usr/bin/nautilus -n** with the command that starts the application. Use the full file path.
2. Optionally, configure the application to start only when a selected GSettings key is enabled. GNOME then runs the application automatically if the key's value is true. If the key's value changes in the running session, GNOME starts or stops the application to match the new value. Add the following line in the **.desktop** file:

```
AutostartCondition=GSettings org.gnome.desktop.background show-desktop-icons
```

- Replace **org.gnome.desktop.background show-desktop-icons** with the GSettings schema and key that the automatic start depends on.

Additional resources

- You can also configure an autostart application for a specific user. Use the **Tweaks** application, which is available from the **gnome-tweaks** package.

18.4. CONFIGURING AUTOMATIC LOGIN

As an administrator, you can enable automatic login from the **Users** panel in **GNOME Settings**, or you can set up automatic login manually in the GDM custom configuration file, as follows.

Run the following procedure to set up automatic login for a user **john**.

Procedure

- Edit the **/etc/gdm/custom.conf** file, and make sure that the **[daemon]** section in the file specifies the following:

```
[daemon]
AutomaticLoginEnable=True
AutomaticLogin=john
```

Replace **john** with the user that you want to be automatically logged in.

18.5. CONFIGURING AUTOMATIC LOGOUT

User sessions that have been idle for a specific period of time can be ended automatically. You can set different behavior based on whether the machine is running from a battery or from mains power by setting the corresponding GSettings key, then locking it.

**WARNING**

Users can potentially lose unsaved data if an idle session is automatically ended.

To set automatic logout for a mains powered machine:

Procedure

1. Create a local database for machine-wide settings in the **/etc/dconf/db/local.d/00-autologout** file:

```
[org/gnome/settings-daemon/plugins/power]
# Set the timeout to 900 seconds when on mains power
sleep-inactive-ac-timeout=900
# Set action after timeout to be logout when on mains power
sleep-inactive-ac-type='logout'
```

2. Override the user's setting, and prevent the user from changing it in the **/etc/dconf/db/local.d/locks/autologout** file:

```
# Lock automatic logout settings
/org/gnome/settings-daemon/plugins/power/sleep-inactive-ac-timeout
/org/gnome/settings-daemon/plugins/power/sleep-inactive-ac-type
```

3. Update the system databases:

```
# dconf update
```

4. Users must log out and back in again before the system-wide settings take effect.

The following GSettings keys are of interest:

- `org.gnome.settings-daemon.plugins.power.sleep-inactive-ac-timeout`
The number of seconds that the computer needs to be inactive before it goes to sleep if it is running from AC power.
- `org.gnome.settings-daemon.plugins.power.sleep-inactive-ac-type`
What should happen when the timeout has passed if the computer is running from AC power.
- `org.gnome.settings-daemon.plugins.power.sleep-inactive-battery-timeout`
The number of seconds that the computer needs to be inactive before it goes to sleep if it is running from power.
- `org.gnome.settings-daemon.plugins.power.sleep-inactive-battery-type`
What should happen when the timeout has passed if the computer is running from battery power.

If you want to list available values for a key, use the following procedure:

Procedure

- Run the **gsettings range** command on the required key. For example:

```
$ gsettings range org.gnome.settings-daemon.plugins.power sleep-inactive-ac-type
enum
'blank'
'suspend'
'shutdown'
'hibernate'
'interactive'
'nothing'
'logout'
```

18.6. SETTING SCREEN BRIGHTNESS AND IDLE TIME

This section describes how to:

- Configure the drop in the brightness level
- Set brightness level
- Set idle time

Configuring the drop in the brightness level

To set the drop in the brightness level when the device has been idle for some time:

Procedure

1. Create a local database for machine-wide settings in the **/etc/dconf/db/local.d/00-power** file including these lines:

```
[org/gnome/settings-daemon/plugins/power]
idle-dim=true
```

2. Update the system databases:

```
# dconf update
```

3. Users must log out and back in again before the system-wide settings take effect.

Setting brightness level

To set brightness level:

Procedure

1. Create a local database for machine-wide settings in the **/etc/dconf/db/local.d/00-power** file, as in the following example:

```
[org/gnome/settings-daemon/plugins/power]
idle-brightness=30
```

Replace **30** with the integer value you want to use.

2. Update the system databases:

■

```
# dconf update
```

3. Users must log out and back in again before the system-wide settings take effect.

Setting idle time

To set idle time after which the screen is blanked and the default screensaver is displayed:

Procedure

1. Create a local database for machine-wide settings in **/etc/dconf/db/local.d/00-session**, as in the following example:

```
[org/gnome/desktop/session]
idle-delay=uint32 900
```

Replace **900** with the integer value you want to use.

You must include the **uint32** along with the integer value as shown.

2. Update the system databases:

```
# dconf update
```

3. Users must log out and back in again before the system-wide settings take effect.

18.7. LOCKING THE SCREEN WHEN THE USER IS IDLE

To enable the screensaver and make the screen lock automatically when the user is idle, follow this procedure:

Procedure

1. Create a local database for system-wide settings in the **etc/dconf/db/local.d/00-screensaver** file:

```
[org/gnome/desktop/session]
# Set the lock time out to 180 seconds before the session is considered idle
idle-delay=uint32 180
[org/gnome/desktop/screensaver]
# Set this to true to lock the screen when the screensaver activates
lock-enabled=true
# Set the lock timeout to 180 seconds after the screensaver has been activated
lock-delay=uint32 180
```

You must include the **uint32** along with the integer key values as shown.

2. Override the user's setting, and prevent the user from changing it in the **/etc/dconf/db/local.d/locks/screensaver** file:

```
# Lock desktop screensaver settings
/org/gnome/desktop/session/idle-delay
/org/gnome/desktop/screensaver/lock-enabled
/org/gnome/desktop/screensaver/lock-delay
```

3. Update the system databases:

```
# dconf update
```

4. Users must log out and back in again before the system-wide settings take effect.

18.8. SCREENCAST RECORDING

GNOME Shell features a built-in screencast recorder. The recorder allows users to record desktop or application activity during their session and distribute the recordings as high-resolution video files in the **webm** format.

To make a screencast:

Procedure

1. To start the recording, press the **Ctrl+Alt+Shift+R** shortcut.
When the recorder is capturing the screen activity, it displays a red circle in the top-right corner of the screen.
2. To stop the recording, press the **Ctrl+Alt+Shift+R** shortcut.
The red circle in the top-right corner of the screen disappears.
3. Navigate to the **~/Videos** directory where you can find the recorded video with a file name that starts with *Screencast* and includes the date and time of the recording.



NOTE

The built-in recorder always captures the entire screen, including all monitors in multi-monitor setups.

CHAPTER 19. CONFIGURING THE DESKTOP ENVIRONMENT FOR ACCESSIBILITY

As a system administrator, you can configure a system with the desktop environment to support users with a visual impairment.

Accessibility in Red Hat Enterprise Linux 8 desktop for the blind users is ensured by the **Orca** screen reader, which is included in the default installation of the operating system.

Orca reads information from the screen and communicates it to the user using:

- Speech synthesizer – provides a speech output
- Braille display – provides a tactile output

For more information on Orca settings, see [Orca's help page](#).

For Orca's communication outputs to function properly, the system administrator must:

- Configure the **brltty** service
- Switch on the **Always Show Universal Access Menu** option
- Enable the **Festival** speech synthesizer

19.1. CONFIGURING THE BRLTTY SERVICE

The Braille display is a device that uses the **brltty** service to provide tactile output for visually impaired users.

In order that a Braille display works correctly, system administrators must:

- [Enable the brltty service](#)
- [Authorize users of a Braille display device](#)
- [Set the driver for a Braille display device](#)
- [Configure a Braille display device](#)

19.1.1. Enabling the brltty service

The Braille display cannot work unless the **brltty** service is running. By default, **brltty** is disabled.

To enable **brltty** to be started on boot, use the following procedure.

Procedure

- To enable the **brltty** service on boot, run:

```
# systemctl enable --now brltty
```

Verification steps

1. Reboot the system.
2. Make sure that the **brltty** service is running:

```
# systemctl status brltty
• brltty.service - Braille display driver for Linux/Unix
  Loaded: loaded (/usr/lib/systemd/system/brltty.service; enabled; vendor pres>
  Active: active (running) since Tue 2019-09-10 14:13:02 CEST; 39s ago
  Process: 905 ExecStart=/usr/bin/brltty (code=exited, status=0/SUCCESS)
  Main PID: 914 (brltty)
    Tasks: 3 (limit: 11360)
   Memory: 4.6M
   CGroup: /system.slice/brltty.service
           └─914 /usr/bin/brltty
```

19.1.2. Authorizing users of a Braille display device

To set the users who are authorized to use a Braille display device, you can choose one of the following methods, which have an equal effect:

- [Authorizing users of a Braille display device with brltty.conf](#)
- [Authorizing users of a Braille display device with brlapi.key](#)

Authorization using the **/etc/brlapi.key** file is suitable only for the file systems where users or groups can be assigned to a file.

Authorization using the **/etc/brltty.conf** file is suitable even for the file systems where users or groups cannot be assigned to a file.

19.1.2.1. Authorizing users of a Braille display device with brltty.conf

Procedure

1. Open the **/etc/brltty.conf** file, and find the section called **Application Programming Interface Parameters**.
2. Specify the users.
 - To specify one or more individual users, list the users on the following line:

```
api-parameters Auth=user:user_1, user_2, ... # Allow some local user
```

- To specify a user group, enter its name on the following line:

```
api-parameters Auth=group:group # Allow some local group
```

19.1.2.2. Authorizing users of a Braille display device with brlapi.key

Authorization using the **/etc/brlapi.key** file is suitable only for the file systems where users or groups can be assigned to a file.

Prerequisites

- Your system must use a file system where users or groups can be assigned to a file.

Procedure

1. Create the **/etc/brlapi.key** file.

```
# mcookie > /etc/brlapi.key
```

2. Change ownership of the **/etc/brlapi.key** to particular user or group.

- To specify an individual user:

```
# chown user_1 /etc/brlapi.key
```

- To specify a group:

```
# chown group_1 /etc/brlapi.key
```

3. Adjust the content of **/etc/brltty.conf** by including the following line:

```
api-parameters Auth=keyfile:/etc/brlapi.key
```

19.1.3. Setting the driver for a Braille display device

The **braille-driver** directive in **/etc/brltty.conf** file specifies a two-letter driver identification code of the driver for the Braille display device.

Procedure

- Decide whether you want to use the autodetection for finding the appropriate driver for your Braille display device.
 - To use autodetection, use the default option as follows:

```
braille-driver auto # autodetect
```



WARNING

Autodetection tries all drivers. Therefore, it might take a long time or even fail. For this reason, setting up a particular driver is recommended.

- If you do not want to use the autodetection, specify the identification code of the required driver in the **braille-driver** directive. Choose the identification code of required driver from the list provided in **/etc/brltty.conf**, for example:

```
braille-driver xw # XWindow
```

You can also set multiple drivers, separated by commas, and autodetection is then performed among them.

19.1.4. Configuring a Braille display device

The **braille-device** directive in the `/etc/brltty.conf` file specifies the device to which the Braille display device is connected.

19.1.4.1. Supported types of Braille display device

This section describes which types of Braille display devices are supported.

Table 19.1. Braille display device types and the corresponding syntax

Braille device type	Syntax of the type
Serial device	serial:path [a]
USB device	[serial-number] [b]
Bluetooth device	bluetooth:address

[a] Relative paths are at **/dev**.

[b] The brackets ([]) here indicate optionality.

Example settings for particular Braille display devices:

```
braille-device serial:/dev/ttyS0      # First serial device
braille-device usb:                  # First USB device matching braille driver
braille-device usb:nnnnn             # Specific USB device by serial number
braille-device bluetooth:xx:xx:xx:xx:xx:xx # Specific Bluetooth device by address
```

You can also set multiple devices, separated by commas, and each of them will be probed in turn.



IMPORTANT

If the device is connected by a serial-to-USB adapter, setting **braille-device** to **usb:** does not work. In this case, identify the virtual serial device that the kernel has created for the adapter. The virtual serial device can look like this:

```
serial:/dev/ttyUSB0
```

You can find the actual device name in the kernel messages on the device plug with the following command:

```
# dmesg | fgrep ttyUSB0
```

19.1.4.2. Setting specific parameters for Braille display devices

To set specific parameters for particular Braille display devices, use the **braille-parameters** directive in **/etc/brltty.conf** file. The **braille-parameters** directive passes non-generic parameters through to the braille driver. Choose the required parameters from the list in **/etc/brltty.conf**.

19.1.4.2.1. Setting the text table

The **text-table** directive in **/etc/brltty.conf** specifies which text table is used to encode the symbols. Relative paths to text tables are stored within the **/etc/brltty/Text/** directory.

Procedure

1. Decide whether you want to use the autoselection for finding the appropriate text table.
2. If you want to use the autoselection, leave **text-table** specified to **auto**, which is the default option.

```
text-table auto # locale-based autoselection
```

This ensures that local-based autoselection with fallback to **en-nabcc** is performed.

For example, to use the text table for American English:

```
text-table en_US # English (United States)
```

19.1.4.2.2. Setting the contraction table

The **contraction-table** directive in the **/etc/brltty.conf** file specifies which table is used to encode the abbreviations. Relative paths to particular contraction tables are stored within the **/etc/brltty/Contraction/** directory.

Procedure

- Choose the required contraction-table from the list in **/etc/brltty.conf**.
For example, to use the contraction table for American English, grade 2:

```
contraction-table en-us-g2 # English (US, grade 2)
```



WARNING

If not specified, no contraction table is used.


19.2. SWITCHING ON THE ALWAYS SHOW UNIVERSAL ACCESS MENU

To activate the **Orca** screen reader, switch on **Always Show Universal Access Menu** as described in the following procedure.

Procedure

1. Open the **Gnome Settings** menu, and click **Universal Access**.
2. Switch on **Always Show Universal Access Menu**

Switching on the Always Show Universal Access Menu in GNOME Settings



Verification steps

- Optionally, verify that the **Universal Access Menu** icon is displayed on the top bar even if all options from this menu are switched off.



Alternatively, you can switch the **Orca** screen reader on by pressing the **Super+Alt+S** key combination. As a result, the **Universal Access Menu** icon is displayed on the top bar.



WARNING

If you activate **Orca** by pressing **Super+Alt+S**, the icon disappears in case that the user switches off all of the provided options from the **Universal Access Menu**. Missing icon can cause difficulties to users with a visual impairment. System administrators can prevent the inaccessibility of the icon by switching on the **Always Show Universal Access Menu** as described in the above procedure. When the **Always Show Universal Access Menu** is switched on, the icon is displayed on the top bar even in the situation when all options from this menu are switched off.

19.3. ENABLING THE FESTIVAL SPEECH SYNTHESIS SYSTEM

By default, **Orca** uses the **eSpeak** speech synthesizer, but it also supports the **Festival** speech synthesis system. Both **eSpeak** and **Festival** synthesize voice differently. Some users might prefer **Festival** to the default **eSpeak** synthesizer.

19.3.1. Enabling Festival

To enable **Festival** to be automatically started on boot, follow this procedure.

Prerequisites

- All packages that are necessary for the **Festival** stack are installed on the system:

```
# yum install festival festival-freebsoft-utils
```

Procedure

1. Create a new systemd unit file in the **/etc/systemd/system/** directory, and make the file executable:

```
# touch /etc/systemd/system/festival.service
# chmod 664 /etc/systemd/system/festival.service
```

2. Ensure that the script in the **/usr/bin/festival_server** file is used to run **Festival** by adding the following content to the **/etc/systemd/system/festival.service** file:

```
[Unit]
Description=Festival speech synthesis server
[Service]
ExecStart=/usr/bin/festival_server
Type=simple
```

3. Notify systemd that a new **festival.service** file exists:

```
# systemctl daemon-reload
```

4. Start and enable the **festival** service:

■

```
# systemctl enable --now festival
```

19.3.2. Enabling the required voice

Festival offers multiples voices provided in these packages:

- **festvox-awb-arctic-hts**
- **festvox-bdl-arctic-hts**
- **festvox-clb-arctic-hts**
- **festvox-kal-diphone**
- **festvox-rms-arctic-hts**
- **festvox-slt-arctic-hts**
- **hispavoces-pal-diphone**
- **hispavoces-sfl-diphone**

To make a particular voice or voices that users require available, follow this procedure.

Prerequisites

- You know which voices are available and which voices the users of the system prefer. For detailed information about a particular voice, run:

```
# yum info package_name
```

Procedure

1. To make the required voice available, install the package with this voice:

```
# yum install package_name
```

2. Reboot the system to apply changes:


```
# reboot
```

CHAPTER 20. TABLETS


To manage Wacom tablets connected to your system, use the following tools:

- The **gnome-settings-daemon** service
- The **Wacom Tablet** settings panel in the GNOME environment

The Wacom Tablet settings panel for a tablet



The Wacom Tablet settings panel for a grip pen



Both these tools, as well as the **libinput** stack, use the **libwacom** tablet client library, which stores the data about Wacom tablets.

If you want to add support for a new tablet into the **libwacom** library, you must ensure that a definition file for this new tablet exists.

20.1. PREPARING A TABLET DEFINITION FILE

The **libwacom** tablet client library needs a definition file for the tablet that you want to add.

To ensure that the tablet definition file exists, follow this procedure.

Prerequisites

Prerequisites

- List all local devices recognized by **libwacom**:

```
$ libwacom-list-local-devices
```

Make sure that your device is recognized in the output.

If your device is not listed, the device is missing from the **libwacom** database. However, the device might still be visible as an event device in the kernel under **/proc/bus/input/devices**, and if you use the **X.Org** display server, in the **X11** session on the **xinput** list.

Procedure

1. Install the package that provides tablet definition files:

```
# yum install libwacom-data
```

The package installs tablet definitions in the **/usr/share/libwacom/** directory.

2. Check whether the definition file is available in the **/usr/share/libwacom/** directory.
To use the screen mapping correctly, support for your tablet must be included in the **libwacom** database and in the **udev** rules file.



IMPORTANT

A common indicator that a device is not supported by **libwacom** is that it works normally in a GNOME session, but the device is not correctly mapped to the screen.

3. If the definition file for your device is not available in **/usr/share/libwacom/**, you have these options:
 - The required definition file may already be available in the [linuxwacom/libwacom](#) upstream repository. You can try to find the definition file there. If you find your tablet model in the list, copy the file to the local machine.
 - You can create a new tablet definition file. Use the **data/wacom.example** file below, and edit particular lines based on the characteristics of your device.

Example 20.1. Example model file description for a tablet

```
[Device]

# The product is the product name announced by the kernel
Product=Intuos 4 WL 6x9

# Vendor name of this tablet
Vendor=Wacom

# DeviceMatch includes the bus (usb, serial), the vendor ID and the actual
# product ID
DeviceMatch=usb:056a:00bc

# Class of the tablet. Valid classes include Intuos3, Intuos4, Graphire, Bamboo, Cintiq
Class=Intuos4
```

```

# Exact model of the tablet, not including the size.
Model=Intuos 4 Wireless

# Width in inches, as advertised by the manufacturer
Width=9

# Height in inches, as advertised by the manufacturer
Height=6

# Optional features that this tablet supports
# Some features are dependent on the actual tool used, e.g. not all styli
# have an eraser and some styli have additional custom axes (e.g. the
# airbrush pen). These features describe those available on the tablet.
#
# Features not set in a file default to false/0

[Features]
# This tablet supports styli (and erasers, if present on the actual stylus)
Stylus=true

# This tablet supports touch.
Touch=false

# This tablet has a touch ring (Intuos4 and Cintiq 24HD)
Ring=true
# This tablet has a second touch ring (Cintiq 24HD)
Ring2=false

# This tablet has a vertical/horizontal scroll strip
VStrip=false
HStrip=false

# Number of buttons on the tablet
Buttons=9

# This tablet is built-in (most serial tablets, Cintiqs)
BuiltIn=false

```

20.2. ADDING SUPPORT FOR A NEW TABLET

To add support for a new tablet into the **libwacom** tablet information client library, follow this procedure.

Prerequisites

- The definition file for the tablet that you want to add exists.
For more information on ensuring that the definition file exists, see [Section 20.1, “Preparing a tablet definition file”](#).

Procedure

1. Add and install the definition file with the **.tablet** suffix:

■

```
# cp the-new-file.tablet /usr/share/libwacom/
```

Once installed, the tablet is part of the **libwacom** database. The tablet is then available through **libwacom-list-local-devices**.

2. Create a new **/etc/udev/rules/99-libwacom-override.rules** file with the following content so that your settings are not overwritten:

```
ACTION!="add|change", GOTO="libwacom_end"
KERNEL!="event[0-9]*", GOTO="libwacom_end"

[new tablet match entries go here]

LABEL="libwacom_end"
```

3. Reboot your system.

20.3. WHERE IS THE WACOM TABLET CONFIGURATION STORED

Configuration for your Wacom tablet is stored in GSettings in the **/org/gnome/settings-daemon/peripherals/wacom/machine-id-device-id** key, where **machine-id** is a D-Bus machine ID, and **device-id** is a tablet device ID.

The configuration schema for the tablet is **org.gnome.settings-daemon.peripherals.wacom**.

Stylus configuration is stored in the **/org/gnome/settings-daemon/peripherals/wacom/device-id/tool-id** key, where **tool-id** is the identifier for the stylus used for professional ranges. For the consumer ranges with no support for **tool-id**, a generic identifier is used instead.

The configuration schema for the stylus is **org.gnome.settings-daemon.peripherals.wacom.stylus**. The configuration schema for the eraser is **org.gnome.settings-daemon.peripherals.wacom.eraser**.

20.4. LISTING AVAILABLE WACOM TABLET CONFIGURATION PATHS

To get the full list of tablet configuration paths used on a particular machine, use the **gsd-list-wacom** tool, which is provided by the **gnome-settings-daemon** package.

Prerequisites

- Make sure that the **gnome-settings-daemon** package is installed on your system.

```
# yum install gnome-settings-daemon
```

Procedure

- To get the full list of tablet configuration paths used on your machine, run the following command:

```
$ /usr/libexec/gsd-list-wacom
```



IMPORTANT

Using **machine-id**, **device-id**, and **tool-id** in configuration paths allows for shared home directories with independent tablet configuration per machine. However, when sharing home directories between Machines, the Wacom settings apply only to one machine.

This is because the **machine-id** for your Wacom tablet is included in the configuration path of the **/org/gnome/settings-daemon/peripherals/wacom/machine-id-device-id GSettings** key, which stores your tablet settings.

CHAPTER 21. INSTALLING APPLICATIONS USING FLATPAK

You can install certain applications using the Flatpak package manager. The following sections describe how to search for, install, launch, and update Flatpak applications on the command line and in the graphical interface.

21.1. THE FLATPAK TECHNOLOGY

Flatpak provides a sandbox environment for application building, deployment, distribution, and installation.

Applications that you launch using Flatpak have minimum access to the host system, which protects the system installation against third-party applications. Flatpak provides application stability regardless of the versions of libraries installed on the host system.

Flatpak applications are distributed from repositories called remotes. Red Hat provides a remote with RHEL applications. Additionally, third-party remotes are available as well. Red Hat does not support applications from third-party remotes.

21.2. SETTING UP FLATPAK

This procedure installs the Flatpak package manager.

Procedure

- Install the **flatpak** package:

```
# yum install flatpak
```

21.3. ENABLING THE RED HAT FLATPAK REMOTE

This procedure configures the Red Hat Container Catalog as a Flatpak remote on your system.

Prerequisites

- You have an account on the Red Hat Customer Portal.



NOTE

For large-scale deployments where the users do not have Customer Portal accounts, Red Hat recommends using registry service accounts. For details, see [Registry Service Accounts](#).

Procedure

1. Enable the **rhel** Flatpak remote:

```
$ flatpak remote-add \
  --if-not-exists \
  rhel \
  https://flatpaks.redhat.io/rhel.flatpakrepo
```

2. Log into the Red Hat Container Catalog:

```
$ podman login registry.redhat.io
```

Username: *your-user-name*

Password: *your-password*

Provide the credentials to your Red Hat Customer Portal account or your registry service account tokens.

By default, Podman saves the credentials only until you log out.

3. Optional: Save your credentials permanently. Use one of the following options:

- Save the credentials for the current user:

```
$ cp $XDG_RUNTIME_DIR/containers/auth.json \  
$HOME/.config/flatpak/oci-auth.json
```

- Save the credentials system-wide:

```
# cp $XDG_RUNTIME_DIR/containers/auth.json \  
/etc/flatpak/oci-auth.json
```

For best practices, Red Hat recommends that you log into the Red Hat Container Catalog using registry account tokens when installing credentials system-wide.

Verification

- List the enabled Flatpak remotes:

```
$ flatpak remotes
```

Name	Options
rhel	system,oci,no-gpg-verify

21.4. SEARCHING FOR FLATPAK APPLICATIONS

This procedure searches for an application in the enabled Flatpak remotes on the command line. The search uses the application name and description.

Prerequisites

- Flatpak is installed.
- The Red Hat Flatpak repository is enabled.

Procedure

- Search for an application by name:

```
$ flatpak search application-name
```

For example, to search for the **LibreOffice** application, use:

```
$ flatpak search LibreOffice
```

The search results include the ID of the application:

Application ID	Version	Branch	Remotes	Description
org.libreoffice.LibreOffice		stable	rhel	The LibreOffice productivity suite

21.5. INSTALLING FLATPAK APPLICATIONS

This procedure installs a selected application from the enabled Flatpak remotes on the command line.

Prerequisites

- Flatpak is installed.
- The Red Hat Flatpak remote is enabled.

Procedure

- Install an application from the **rhel** remote:

```
$ flatpak install rhel application-id
```

Replace *application-id* with the ID of the application. For example:

```
$ flatpak install rhel org.libreoffice.LibreOffice
```

21.6. LAUNCHING FLATPAK APPLICATIONS

This procedure launches an installed Flatpak application from the command line.

Prerequisites

- Flatpak is installed.
- The selected Flatpak application is installed.

Procedure

- Launch the application:

```
$ flatpak run application-id
```

Replace *application-id* with the ID of the application. For example:

```
$ flatpak run org.libreoffice.LibreOffice
```

21.7. UPDATING FLATPAK APPLICATIONS

This procedure updates one or more installed Flatpak applications to the most recent version in the corresponding Flatpak remote.

Prerequisites

- Flatpak is installed.
- A Flatpak remote is enabled.

Procedure

- Update one or more Flatpak applications:
 - To update a specific Flatpak application, specify the application ID:

```
$ flatpak update application-id
```

- To update all Flatpak applications, specify no IDs:

```
$ flatpak update
```

21.8. INSTALLING FLATPAK APPLICATIONS IN THE GRAPHICAL INTERFACE

This procedure searches for Flatpak applications using the **Software** application.

Prerequisites

- Flatpak is installed.
- The Red Hat Flatpak remote is enabled.

Procedure

1. Open the **Software** application.
2. Make sure that the **Explore** tab is active.
3. Click the search button in the top-left corner of the window.
4. In the input box, type the name of the application that you want to install, such as **LibreOffice**.
5. Select the correct application in the search results.
If the application is listed several times, select the version where the **Source** field in the **Details** section reports **flatpaks.redhat.io**.
6. Click the **Install** button.
7. If **Software** asks you to log in, enter your Customer Portal credentials or your registry service account tokens.
8. Wait for the installation process to complete.
9. Optional: Click the **Launch** button to launch the application.

21.9. UPDATING FLATPAK APPLICATIONS IN THE GRAPHICAL INTERFACE

This procedure updates one or more installed Flatpak applications using the **Software** application.

Prerequisites

- Flatpak is installed.
- A Flatpak remote is enabled.

Procedure

1. Open the **Software** application.
2. Select the **Updates** tab.
3. In the **Application Updates** section, you can find all available updates to Flatpak applications.
4. Update one or more applications:
 - To apply all available updates, click the **Update All** button.
 - To update only a specific application, click the **Update** button next to the application item.
5. Optional: Enable automatic application updates.
 - a. Click the menu button in the top right corner of the window.
 - b. Select **Update Preferences**.
 - c. Enable **Automatic Updates**.
Flatpak applications now update automatically.