

Generalised Extreme Value (GEV) distribution

Parametrisation

The GEV distribution is defined through the cummulative distribution function

$$F(y; \eta, \tau, \xi) = \exp \left(- \left[1 + \xi \sqrt{\tau w} (y - \eta) \right]^{-1/\xi} \right)$$

for

$$1 + \xi \sqrt{\tau w} (y - \eta) > 0$$

and for a continuously response y where

η : is the linear predictor

τ : is the “precision”

w : is a fixed weight, $w > 0$.

Link-function

The linear predictor is given in the parameterisation of the GEV distribution.

Hyperparameters

The GEV-models has two hyperparameters. The “precision” is represented as

$$\theta_1 = \log \tau$$

and the prior is defined on θ_1 . The shape parameter ξ is represented as

$$\xi = s\theta_2$$

where $s > 0$ is a chosen fixed scaling, and the prior is defined on θ_2 .

Specification

- family = **gev**
- Required arguments: y and w (keyword **weights**)
- The scaling s is given by the argument **scale.xi.gev** and is default set to 0.01, and provides an more appropriate scale for θ_2 .

The weights has default value 1.

Example

In the following example, we estimate the parameters of the GEV distribution on some simulated data.

```
rgev = function(n=1, xi = 0, mu = 0.0, sd = 1.0) {  
  u = runif(n)  
  if (xi == 0) {  
    x = -log(-log(u))  
  } else {  
    x = ((-log(u))^-xi - 1.0)/xi  
  }  
}
```

```

    }
    return (x*sd + mu)
}

n = 100
z = rnorm(n)
sd.y = 0.5
xi = 0
y = 1+z + rgev(n, xi=xi, sd = sd.y)

formula = y ~ 1 + f(inla.group(z), model="rw1")
data = data.frame(y,z)

r = inla(formula, data = data, family = "gev",
        control.data = list(scale.xi.gev = 0.01))

```

Notes

None.