

# Appendix

## Interactive Mode

### Error Handling

When an error occurs, the interpreter prints an error message and a stack trace. In interactive mode, it then returns to the primary prompt; when input came from a file, it exits with a nonzero exit status after printing the stack trace. (Exceptions handled by an `keyword:'except'` clause in a `keyword:'try'` statement are not errors in this context.) Some errors are unconditionally fatal and cause an exit with a nonzero exit; this applies to internal inconsistencies and some cases of running out of memory. All error messages are written to the standard error stream; normal output from executed commands is written to standard output.

**System Message: ERROR/3** (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\tutorial\[cpython-main] [Doc] [tutorial]appendix.rst, line 18); [backlink](#)

Unknown interpreted text role "keyword".

**System Message: ERROR/3** (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\tutorial\[cpython-main] [Doc] [tutorial]appendix.rst, line 18); [backlink](#)

Unknown interpreted text role "keyword".

Typing the interrupt character (usually `kbd:'Control-C'` or `kbd:'Delete'`) to the primary or secondary prompt cancels the input and returns to the primary prompt. [1] Typing an interrupt while a command is executing raises the `exc:'KeyboardInterrupt'` exception, which may be handled by a `keyword:'try'` statement.

**System Message: ERROR/3** (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\tutorial\[cpython-main] [Doc] [tutorial]appendix.rst, line 28); [backlink](#)

Unknown interpreted text role "kbd".

**System Message: ERROR/3** (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\tutorial\[cpython-main] [Doc] [tutorial]appendix.rst, line 28); [backlink](#)

Unknown interpreted text role "kbd".

**System Message: ERROR/3** (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\tutorial\[cpython-main] [Doc] [tutorial]appendix.rst, line 28); [backlink](#)

Unknown interpreted text role "exc".

**System Message: ERROR/3** (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\tutorial\[cpython-main] [Doc] [tutorial]appendix.rst, line 28); [backlink](#)

Unknown interpreted text role "keyword".

### Executable Python Scripts

On BSD'ish Unix systems, Python scripts can be made directly executable, like shell scripts, by putting the line

```
#!/usr/bin/env python3.5
```

(assuming that the interpreter is on the user's `envvar:'PATH'`) at the beginning of the script and giving the file an executable mode. The `#!` must be the first two characters of the file. On some platforms, this first line must end with a Unix-style line ending (`'\n'`), not a Windows (`'\r\n'`) line ending. Note that the hash, or pound, character, `'#'`, is used to start a comment in Python.

**System Message: ERROR/3** (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\tutorial\[cpython-main] [Doc] [tutorial]appendix.rst, line 45); [backlink](#)

Unknown interpreted text role "envvar".

The script can be given an executable mode, or permission, using the `program:'chmod'` command.

**System Message: ERROR/3** (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\tutorial\[cpython-main] [Doc] [tutorial]appendix.rst, line 52); [backlink](#)

Unknown interpreted text role "program".

```
$ chmod +x myscript.py
```

On Windows systems, there is no notion of an "executable mode". The Python installer automatically associates `.py` files with `python.exe` so that a double-click on a Python file will run it as a script. The extension can also be `.pyw`, in that case, the console window that normally appears is suppressed.

## The Interactive Startup File

When you use Python interactively, it is frequently handy to have some standard commands executed every time the interpreter is started. You can do this by setting an environment variable named `:envvar:PYTHONSTARTUP` to the name of a file containing your start-up commands. This is similar to the `:file:.profile` feature of the Unix shells.

**System Message: ERROR/3** (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\tutorial\[cpython-main] [Doc] [tutorial]appendix.rst, line 71); [backlink](#)

Unknown interpreted text role "envvar".

**System Message: ERROR/3** (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\tutorial\[cpython-main] [Doc] [tutorial]appendix.rst, line 71); [backlink](#)

Unknown interpreted text role "file".

This file is only read in interactive sessions, not when Python reads commands from a script, and not when `:file:/dev/tty` is given as the explicit source of commands (which otherwise behaves like an interactive session). It is executed in the same namespace where interactive commands are executed, so that objects that it defines or imports can be used without qualification in the interactive session. You can also change the prompts `sys.ps1` and `sys.ps2` in this file.

**System Message: ERROR/3** (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\tutorial\[cpython-main] [Doc] [tutorial]appendix.rst, line 77); [backlink](#)

Unknown interpreted text role "file".

If you want to read an additional start-up file from the current directory, you can program this in the global start-up file using code like `if os.path.isfile('.pythonrc.py'): exec(open('.pythonrc.py').read())`. If you want to use the startup file in a script, you must do this explicitly in the script:

```
import os
filename = os.environ.get('PYTHONSTARTUP')
if filename and os.path.isfile(filename):
    with open(filename) as fobj:
        startup_file = fobj.read()
    exec(startup_file)
```

## The Customization Modules

Python provides two hooks to let you customize it: `:mod:sitecustomize` and `:mod:usercustomize`. To see how it works, you need first to find the location of your user site-packages directory. Start Python and run this code:

**System Message: ERROR/3** (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\tutorial\[cpython-main] [Doc] [tutorial]appendix.rst, line 104); [backlink](#)

Unknown interpreted text role "mod".

**System Message: ERROR/3** (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\tutorial\[cpython-main] [Doc] [tutorial]appendix.rst, line 104); [backlink](#)

Unknown interpreted text role "mod".

```
>>> import site
>>> site.getusersitepackages()
'/home/user/.local/lib/python3.5/site-packages'
```

Now you can create a file named `:file:usercustomize.py` in that directory and put anything you want in it. It will affect every

invocation of Python, unless it is started with the `:option:`-s`` option to disable the automatic import.

**System Message: ERROR/3** (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\tutorial\[cpython-main] [Doc] [tutorial]appendix.rst, line 112); [backlink](#)

Unknown interpreted text role "file".

**System Message: ERROR/3** (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\tutorial\[cpython-main] [Doc] [tutorial]appendix.rst, line 112); [backlink](#)

Unknown interpreted text role "option".

`:mod:`sitecustomize`` works in the same way, but is typically created by an administrator of the computer in the global site-packages directory, and is imported before `:mod:`usercustomize``. See the documentation of the `:mod:`site`` module for more details.

**System Message: ERROR/3** (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\tutorial\[cpython-main] [Doc] [tutorial]appendix.rst, line 116); [backlink](#)

Unknown interpreted text role "mod".

**System Message: ERROR/3** (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\tutorial\[cpython-main] [Doc] [tutorial]appendix.rst, line 116); [backlink](#)

Unknown interpreted text role "mod".

**System Message: ERROR/3** (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\tutorial\[cpython-main] [Doc] [tutorial]appendix.rst, line 116); [backlink](#)

Unknown interpreted text role "mod".

## Footnotes

[1] A problem with the GNU Readline package may prevent this.