

# VMCOREINFO

## What is it?

VMCOREINFO is a special ELF note section. It contains various information from the kernel like structure size, page size, symbol values, field offsets, etc. These data are packed into an ELF note section and used by user-space tools like crash and makedumpfile to analyze a kernel's memory layout.

## Common variables

### **init\_uts\_ns.name.release**

The version of the Linux kernel. Used to find the corresponding source code from which the kernel has been built. For example, crash uses it to find the corresponding vmlinux in order to process vmcore.

### **PAGE\_SIZE**

The size of a page. It is the smallest unit of data used by the memory management facilities. It is usually 4096 bytes of size and a page is aligned on 4096 bytes. Used for computing page addresses.

### **init\_uts\_ns**

The UTS namespace which is used to isolate two specific elements of the system that relate to the `uname(2)` system call. It is named after the data structure used to store information returned by the `uname(2)` system call.

User-space tools can get the kernel name, host name, kernel release number, kernel version, architecture name and OS type from it.

### **(uts\_namespace, name)**

Offset of the name's member. Crash Utility and Makedumpfile get the start address of the `init_uts_ns.name` from this.

### **node\_online\_map**

An array `node_states[N_ONLINE]` which represents the set of online nodes in a system, one bit position per node number. Used to keep track of which nodes are in the system and online.

### **swapper\_pg\_dir**

The global page directory pointer of the kernel. Used to translate virtual to physical addresses.

### **\_stext**

Defines the beginning of the text section. In general, `_stext` indicates the kernel start address. Used to convert a virtual address from the direct kernel map to a physical address.

### **vmap\_area\_list**

Stores the virtual area list. makedumpfile gets the `vmalloc` start value from this variable and its value is necessary for `vmalloc` translation.

### **mem\_map**

Physical addresses are translated to struct pages by treating them as an index into the `mem_map` array. Right-shifting a physical address `PAGE_SHIFT` bits converts it into a page frame number which is an index into that `mem_map` array.

Used to map an address to the corresponding struct page.

### **contig\_page\_data**

Makedumpfile gets the `pglist_data` structure from this symbol, which is used to describe the memory layout.

User-space tools use this to exclude free pages when dumping memory.

### **mem\_section|(mem\_section, NR\_SECTION\_ROOTS)|(mem\_section, section\_mem\_map)**

The address of the `mem_section` array, its length, structure size, and the `section_mem_map` offset.

It exists in the sparse memory mapping model, and it is also somewhat similar to the `mem_map` variable, both of them are used to translate an address.

### **MAX\_PHYSMEM\_BITS**

Defines the maximum supported physical address space memory.

### **page**

The size of a page structure. struct page is an important data structure and it is widely used to compute contiguous memory.

### **pglist\_data**

The size of a `pglist_data` structure. This value is used to check if the `pglist_data` structure is valid. It is also used for checking the

memory type.

### **zone**

The size of a zone structure. This value is used to check if the zone structure has been found. It is also used for excluding free pages.

### **free\_area**

The size of a free\_area structure. It indicates whether the free\_area structure is valid or not. Useful when excluding free pages.

### **list\_head**

The size of a list\_head structure. Used when iterating lists in a post-mortem analysis session.

### **nodemask\_t**

The size of a nodemask\_t type. Used to compute the number of online nodes.

### **(page, flags[\_refcount|mapping|lru|\_mapcount|private|compound\_dtor|compound\_order|compound\_head])**

User-space tools compute their values based on the offset of these variables. The variables are used when excluding unnecessary pages.

### **(pglist\_data, node\_zones|nr\_zones|node\_mem\_map|node\_start\_pfn|node\_spanned\_pages|node\_id)**

On NUMA machines, each NUMA node has a pg\_data\_t to describe its memory layout. On UMA machines there is a single pglist\_data which describes the whole memory.

These values are used to check the memory type and to compute the virtual address for memory map.

### **(zone, free\_area|vm\_stat|spanned\_pages)**

Each node is divided into a number of blocks called zones which represent ranges within memory. A zone is described by a structure zone.

User-space tools compute required values based on the offset of these variables.

### **(free\_area, free\_list)**

Offset of the free\_list's member. This value is used to compute the number of free pages.

Each zone has a free\_area structure array called free\_area[MAX\_ORDER]. The free\_list represents a linked list of free page blocks.

### **(list\_head, next|prev)**

Offsets of the list\_head's members. list\_head is used to define a circular linked list. User-space tools need these in order to traverse lists.

### **(vmap\_area, va\_start|list)**

Offsets of the vmap\_area's members. They carry vmalloc-specific information. Makedumpfile gets the start address of the vmalloc region from this.

### **(zone.free\_area, MAX\_ORDER)**

Free areas descriptor. User-space tools use this value to iterate the free\_area ranges. MAX\_ORDER is used by the zone buddy allocator.

### **prb**

A pointer to the printk ringbuffer (struct printk\_ringbuffer). This may be pointing to the static boot ringbuffer or the dynamically allocated ringbuffer, depending on when the the core dump occurred. Used by user-space tools to read the active kernel log buffer.

### **printk\_rb\_static**

A pointer to the static boot printk ringbuffer. If @prb has a different value, this is useful for viewing the initial boot messages, which may have been overwritten in the dynamically allocated ringbuffer.

### **clear\_seq**

The sequence number of the printk() record after the last clear command. It indicates the first record after the last SYSLOG\_ACTION\_CLEAR, like issued by 'dmesg -c'. Used by user-space tools to dump a subset of the dmesg log.

### **printk\_ringbuffer**

The size of a printk\_ringbuffer structure. This structure contains all information required for accessing the various components of the kernel log buffer.

### **(printk\_ringbuffer, desc\_ring|text\_data\_ring|dict\_data\_ring|fail)**

Offsets for the various components of the printk ringbuffer. Used by user-space tools to view the kernel log buffer without requiring the declaration of the structure.

## **prb\_desc\_ring**

The size of the prb\_desc\_ring structure. This structure contains information about the set of record descriptors.

### **(prb\_desc\_ring, count\_bits|descs|head\_id|tail\_id)**

Offsets for the fields describing the set of record descriptors. Used by user-space tools to be able to traverse the descriptors without requiring the declaration of the structure.

## **prb\_desc**

The size of the prb\_desc structure. This structure contains information about a single record descriptor.

### **(prb\_desc, info|state\_var|text\_blk\_lpos|dict\_blk\_lpos)**

Offsets for the fields describing a record descriptors. Used by user-space tools to be able to read descriptors without requiring the declaration of the structure.

## **prb\_data\_blk\_lpos**

The size of the prb\_data\_blk\_lpos structure. This structure contains information about where the text or dictionary data (data block) is located within the respective data ring.

### **(prb\_data\_blk\_lpos, begin|next)**

Offsets for the fields describing the location of a data block. Used by user-space tools to be able to locate data blocks without requiring the declaration of the structure.

## **printk\_info**

The size of the printk\_info structure. This structure contains all the meta-data for a record.

### **(printk\_info, seq|ts\_nsec|text\_len|dict\_len|caller\_id)**

Offsets for the fields providing the meta-data for a record. Used by user-space tools to be able to read the information without requiring the declaration of the structure.

## **prb\_data\_ring**

The size of the prb\_data\_ring structure. This structure contains information about a set of data blocks.

### **(prb\_data\_ring, size\_bits|data|head\_lpos|tail\_lpos)**

Offsets for the fields describing a set of data blocks. Used by user-space tools to be able to access the data blocks without requiring the declaration of the structure.

## **atomic\_long\_t**

The size of the atomic\_long\_t structure. Used by user-space tools to be able to copy the full structure, regardless of its architecture-specific implementation.

### **(atomic\_long\_t, counter)**

Offset for the long value of an atomic\_long\_t variable. Used by user-space tools to access the long value without requiring the architecture-specific declaration.

### **(free\_area.free\_list, MIGRATE\_TYPES)**

The number of migrate types for pages. The free\_list is described by the array. Used by tools to compute the number of free pages.

## **NR\_FREE\_PAGES**

On linux-2.6.21 or later, the number of free pages is in vm\_stat[NR\_FREE\_PAGES]. Used to get the number of free pages.

### **PG\_lru|PG\_private|PG\_swapcache|PG\_swapbacked|PG\_slab|PG\_hwpoison|PG\_head\_mask**

Page attributes. These flags are used to filter various unnecessary for dumping pages.

### **PAGE\_BUDDY\_MAPCOUNT\_VALUE(~PG\_buddy)|PAGE\_OFFLINE\_MAPCOUNT\_VALUE(~PG\_offline)**

More page attributes. These flags are used to filter various unnecessary for dumping pages.

## **HUGETLB\_PAGE\_DTOR**

The HUGETLB\_PAGE\_DTOR flag denotes hugetlbfs pages. Makedumpfile excludes these pages.

## **x86\_64**

## **phys\_base**

Used to convert the virtual address of an exported kernel symbol to its corresponding physical address.

## **init\_top\_pgt**

Used to walk through the whole page table and convert virtual addresses to physical addresses. The `init_top_pgt` is somewhat similar to `swapper_pg_dir`, but it is only used in `x86_64`.

### **pgtable\_l5\_enabled**

User-space tools need to know whether the crash kernel was in 5-level paging mode.

### **node\_data**

This is a struct `pglist_data` array and stores all NUMA nodes information. Makedumpfile gets the `pglist_data` structure from it.

### **(node\_data, MAX\_NUMNODES)**

The maximum number of nodes in system.

### **KERNELOFFSET**

The kernel randomization offset. Used to compute the page offset. If KASLR is disabled, this value is zero.

### **KERNEL\_IMAGE\_SIZE**

Currently unused by Makedumpfile. Used to compute the module virtual address by Crash.

### **sme\_mask**

AMD-specific with SME support: it indicates the secure memory encryption mask. Makedumpfile tools need to know whether the crash kernel was encrypted. If SME is enabled in the first kernel, the crash kernel's page table entries (pgd/pud/pmd/pte) contain the memory encryption mask. This is used to remove the SME mask and obtain the true physical address.

Currently, `sme_mask` stores the value of the C-bit position. If needed, additional SME-relevant info can be placed in that variable.

For example:

```
[ misc                ][ enc bit  ][ other misc SME info      ]
0000_0000_0000_0000_1000_0000_0000_0000_0000_0000_..._0000
63   59   55   51   47   43   39   35   31   27   ... 3
```

### **x86\_32**

### **X86\_PAE**

Denotes whether physical address extensions are enabled. It has the cost of a higher page table lookup overhead, and also consumes more page table space per process. Used to check whether PAE was enabled in the crash kernel when converting virtual addresses to physical addresses.

### **ia64**

### **pgdat\_list(pgdat\_list, MAX\_NUMNODES)**

`pg_data_t` array storing all NUMA nodes information. `MAX_NUMNODES` indicates the number of the nodes.

### **node\_memblk(node\_memblk, NR\_NODE\_MEMBLKS)**

List of node memory chunks. Filled when parsing the SRAT table to obtain information about memory nodes. `NR_NODE_MEMBLKS` indicates the number of node memory chunks.

These values are used to compute the number of nodes the crashed kernel used.

### **node\_memblk\_s(node\_memblk\_s, start\_paddr)(node\_memblk\_s, size)**

The size of a struct `node_memblk_s` and the offsets of the `node_memblk_s`'s members. Used to compute the number of nodes.

### **PGTABLE\_3|PGTABLE\_4**

User-space tools need to know whether the crash kernel was in 3-level or 4-level paging mode. Used to distinguish the page table.

### **ARM64**

### **VA\_BITS**

The maximum number of bits for virtual addresses. Used to compute the virtual memory ranges.

### **kimage\_voffset**

The offset between the kernel virtual and physical mappings. Used to translate virtual to physical addresses.

### **PHYS\_OFFSET**

Indicates the physical address of the start of memory. Similar to `kimage_voffset`, which is used to translate virtual to physical addresses.

### **KERNELOFFSET**

The kernel randomization offset. Used to compute the page offset. If KASLR is disabled, this value is zero.

## **KERNELPACMASK**

The mask to extract the Pointer Authentication Code from a kernel virtual address.

## **TCR\_EL1.T1SZ**

Indicates the size offset of the memory region addressed by TTBR1\_EL1. The region size is  $2^{(64-T1SZ)}$  bytes.

TTBR1\_EL1 is the table base address register specified by ARMv8-A architecture which is used to lookup the page-tables for the Virtual addresses in the higher VA range (refer to ARMv8 ARM document for more details).

## **MODULES\_VADDR|MODULES\_END|VMALLOC\_START|VMALLOC\_END|VMEMMAP\_START|VMEMMAP\_END**

Used to get the correct ranges:

MODULES\_VADDR ~ MODULES\_END-1 : Kernel module space. VMALLOC\_START ~ VMALLOC\_END-1 : vmalloc() / ioremap() space. VMEMMAP\_START ~ VMEMMAP\_END-1 : vmemmap region, used for struct page array.

## **arm**

### **ARM\_LPAE**

It indicates whether the crash kernel supports large physical address extensions. Used to translate virtual to physical addresses.

## **s390**

### **lowcore\_ptr**

An array with a pointer to the lowcore of every CPU. Used to print the psw and all registers information.

### **high\_memory**

Used to get the vmalloc\_start address from the high\_memory symbol.

### **(lowcore\_ptr, NR\_CPUS)**

The maximum number of CPUs.

## **powerpc**

### **node\_data|(node\_data, MAX\_NUMNODES)**

See above.

### **contig\_page\_data**

See above.

### **vmemmap\_list**

The vmemmap\_list maintains the entire vmemmap physical mapping. Used to get vmemmap list count and populated vmemmap regions info. If the vmemmap address translation information is stored in the crash kernel, it is used to translate vmemmap kernel virtual addresses.

### **mmu\_vmemmap\_psize**

The size of a page. Used to translate virtual to physical addresses.

### **mmu\_psize\_defs**

Page size definitions, i.e. 4k, 64k, or 16M.

Used to make vtop translations.

### **vmemmap\_backing|(vmemmap\_backing, list)|(vmemmap\_backing, phys)|(vmemmap\_backing, virt\_addr)**

The vmemmap virtual address space management does not have a traditional page table to track which virtual struct pages are backed by a physical mapping. The virtual to physical mappings are tracked in a simple linked list format.

User-space tools need to know the offset of list, phys and virt\_addr when computing the count of vmemmap regions.

### **mmu\_psize\_def|(mmu\_psize\_def, shift)**

The size of a struct mmu\_psize\_def and the offset of mmu\_psize\_def's member.

Used in vtop translations.

## **sh**

**node\_data**(**node\_data**, **MAX\_NUMNODES**)

See above.

### **X2TLB**

Indicates whether the crashed kernel enabled SH extended mode.