

Video Output Overlay Interface

Also known as **On-Screen Display (OSD)**

Some video output devices can overlay a framebuffer image onto the outgoing video signal. Applications can set up such an overlay using this interface, which borrows structures and ioctls of the [ref:Video Overlay <overlay>](#) interface.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v4l\ (linux-master) (Documentation) (userspace-api) (media) (v4l) dev-osd.rst, line 11); [backlink](#)

Unknown interpreted text role "ref".

The OSD function is accessible through the same character special file as the [ref:Video Output <capture>](#) function.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v4l\ (linux-master) (Documentation) (userspace-api) (media) (v4l) dev-osd.rst, line 16); [backlink](#)

Unknown interpreted text role "ref".

Note

The default function of such a `/dev/video` device is video capturing or output. The OSD function is only available after calling the [ref:VIDIOC_S_FMT <VIDIOC_G_FMT>](#) ioctl.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v4l\ (linux-master) (Documentation) (userspace-api) (media) (v4l) dev-osd.rst, line 21); [backlink](#)

Unknown interpreted text role "ref".

Querying Capabilities

Devices supporting the *Video Output Overlay* interface set the `V4L2_CAP_VIDEO_OUTPUT_OVERLAY` flag in the capabilities field of struct [c:type:v4l2_capability](#) returned by the [ref:VIDIOC_QUERYCAP](#) ioctl.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v4l\ (linux-master) (Documentation) (userspace-api) (media) (v4l) dev-osd.rst, line 29); [backlink](#)

Unknown interpreted text role "c:type".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v4l\ (linux-master) (Documentation) (userspace-api) (media) (v4l) dev-osd.rst, line 29); [backlink](#)

Unknown interpreted text role "ref".

Framebuffer

Contrary to the *Video Overlay* interface the framebuffer is normally implemented on the TV card and not the graphics card. On Linux it is accessible as a framebuffer device (`/dev/fbN`). Given a V4L2 device, applications can find the corresponding framebuffer device by calling the [ref:VIDIOC_G_FBUF <VIDIOC_G_FBUF>](#) ioctl. It returns, amongst other information, the physical address of the framebuffer in the `base` field of struct [c:type:v4l2_framebuffer](#). The framebuffer device ioctl

`FBIOGET_FSCREENINFO` returns the same address in the `smem_start` field of struct [c:type:fb_fix_screeninfo](#). The `FBIOGET_FSCREENINFO` ioctl and struct [c:type:fb_fix_screeninfo](#) are defined in the `linux/fb.h` header file.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v4l\ (linux-master) (Documentation) (userspace-api) (media) (v4l) dev-osd.rst, line 38); [backlink](#)

Unknown interpreted text role "ref".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v4l\linux-master) (Documentation) (userspace-api) (media) (v4l) dev-osd.rst, line 38); [backlink](#)

Unknown interpreted text role "c:type".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v4l\linux-master) (Documentation) (userspace-api) (media) (v4l) dev-osd.rst, line 38); [backlink](#)

Unknown interpreted text role "c:type".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v4l\linux-master) (Documentation) (userspace-api) (media) (v4l) dev-osd.rst, line 38); [backlink](#)

Unknown interpreted text role "c:type".

The width and height of the framebuffer depends on the current video standard. A V4L2 driver may reject attempts to change the video standard (or any other ioctl which would imply a framebuffer size change) with an `EBUSY` error code until all applications closed the framebuffer device.

Example: Finding a framebuffer device for OSD

```
#include <linux/fb.h>

struct v4l2_framebuffer fbuf;
unsigned int i;
int fb_fd;

if (-1 == ioctl(fd, VIDIOC_G_FBUF, &fbuf)) {
    perror("VIDIOC_G_FBUF");
    exit(EXIT_FAILURE);
}

for (i = 0; i < 30; i++) {
    char dev_name[16];
    struct fb_fix_screeninfo si;

    snprintf(dev_name, sizeof(dev_name), "/dev/fb%u", i);

    fb_fd = open(dev_name, O_RDWR);
    if (-1 == fb_fd) {
        switch (errno) {
            case ENOENT: /* no such file */
            case ENXIO: /* no driver */
                continue;

            default:
                perror("open");
                exit(EXIT_FAILURE);
        }
    }

    if (0 == ioctl(fb_fd, FBIOGET_FSCREENINFO, &si)) {
        if (si.smem_start == (unsigned long) fbuf.base)
            break;
    } else {
        /* Apparently not a framebuffer device. */
    }

    close(fb_fd);
    fb_fd = -1;
}

/* fb_fd is the file descriptor of the framebuffer device
   for the video output overlay, or -1 if no device was found. */
```

Overlay Window and Scaling

The overlay is controlled by source and target rectangles. The source rectangle selects a subsection of the framebuffer image to be overlaid, the target rectangle an area in the outgoing video signal where the image will appear. Drivers may or may not support

scaling, and arbitrary sizes and positions of these rectangles. Further drivers may support any (or none) of the clipping/blending methods defined for the [ref: Video Overlay <overlay>](#) interface.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v4l\ (linux-master) (Documentation) (userspace-api) (media) (v4l) dev-osd.rst, line 109); [backlink](#)

Unknown interpreted text role "ref".

A struct `:c.type:'v4l2_window'` defines the size of the source rectangle, its position in the framebuffer and the clipping/blending method to be used for the overlay. To get the current parameters applications set the `type` field of a struct `:c.type:'v4l2_format'` to `V4L2_BUF_TYPE_VIDEO_OUTPUT_OVERLAY` and call the [ref:VIDIOC_G_FMT <VIDIOC_G_FMT>](#) ioctl. The driver fills the struct `:c.type:'v4l2_window'` substructure named `win`. It is not possible to retrieve a previously programmed clipping list or bitmap.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v4l\ (linux-master) (Documentation) (userspace-api) (media) (v4l) dev-osd.rst, line 117); [backlink](#)

Unknown interpreted text role "c:type".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v4l\ (linux-master) (Documentation) (userspace-api) (media) (v4l) dev-osd.rst, line 117); [backlink](#)

Unknown interpreted text role "c:type".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v4l\ (linux-master) (Documentation) (userspace-api) (media) (v4l) dev-osd.rst, line 117); [backlink](#)

Unknown interpreted text role "ref".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v4l\ (linux-master) (Documentation) (userspace-api) (media) (v4l) dev-osd.rst, line 117); [backlink](#)

Unknown interpreted text role "c:type".

To program the source rectangle applications set the `type` field of a struct `:c.type:'v4l2_format'` to `V4L2_BUF_TYPE_VIDEO_OUTPUT_OVERLAY`, initialize the `win` substructure and call the [ref:VIDIOC_S_FMT <VIDIOC_S_FMT>](#) ioctl. The driver adjusts the parameters against hardware limits and returns the actual parameters as [ref:VIDIOC_G_FMT <VIDIOC_G_FMT>](#) does. Like [ref:VIDIOC_S_FMT <VIDIOC_S_FMT>](#), the [ref:VIDIOC_TRY_FMT <VIDIOC_G_FMT>](#) ioctl can be used to learn about driver capabilities without actually changing driver state. Unlike [ref:VIDIOC_S_FMT <VIDIOC_G_FMT>](#) this also works after the overlay has been enabled.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v4l\ (linux-master) (Documentation) (userspace-api) (media) (v4l) dev-osd.rst, line 127); [backlink](#)

Unknown interpreted text role "c:type".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v4l\ (linux-master) (Documentation) (userspace-api) (media) (v4l) dev-osd.rst, line 127); [backlink](#)

Unknown interpreted text role "ref".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v4l\ (linux-master) (Documentation) (userspace-api) (media) (v4l) dev-osd.rst, line 127); [backlink](#)

Unknown interpreted text role "ref".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-

master\Documentation\userspace-api\media\v4l\ (linux-master) (Documentation) (userspace-api) (media) (v4l) dev-osd.rst, line 127); [backlink](#)

Unknown interpreted text role "ref".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v4l\ (linux-master) (Documentation) (userspace-api) (media) (v4l) dev-osd.rst, line 127); [backlink](#)

Unknown interpreted text role "ref".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v4l\ (linux-master) (Documentation) (userspace-api) (media) (v4l) dev-osd.rst, line 127); [backlink](#)

Unknown interpreted text role "ref".

A struct `:c:type:`v4l2_crop`` defines the size and position of the target rectangle. The scaling factor of the overlay is implied by the width and height given in struct `:c:type:`v4l2_window`` and struct `:c:type:`v4l2_crop``. The cropping API applies to *Video Output* and *Video Output Overlay* devices in the same way as to *Video Capture* and *Video Overlay* devices, merely reversing the direction of the data flow. For more information see `:ref:`crop``.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v4l\ (linux-master) (Documentation) (userspace-api) (media) (v4l) dev-osd.rst, line 137); [backlink](#)

Unknown interpreted text role "c:type".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v4l\ (linux-master) (Documentation) (userspace-api) (media) (v4l) dev-osd.rst, line 137); [backlink](#)

Unknown interpreted text role "c:type".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v4l\ (linux-master) (Documentation) (userspace-api) (media) (v4l) dev-osd.rst, line 137); [backlink](#)

Unknown interpreted text role "c:type".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v4l\ (linux-master) (Documentation) (userspace-api) (media) (v4l) dev-osd.rst, line 137); [backlink](#)

Unknown interpreted text role "ref".

Enabling Overlay

There is no V4L2 ioctl to enable or disable the overlay, however the framebuffer interface of the driver may support the `FBIOBLANK` ioctl.