

USB Anchors

What is anchor?

A USB driver needs to support some callbacks requiring a driver to cease all IO to an interface. To do so, a driver has to keep track of the URBs it has submitted to know they've all completed or to call `usb_kill_urb` for them. The anchor is a data structure takes care of keeping track of URBs and provides methods to deal with multiple URBs.

Allocation and Initialisation

There's no API to allocate an anchor. It is simply declared as `struct usb_anchor`. `:c:func:'init_usb_anchor'` must be called to initialise the data structure.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\driver-api\usb\ (linux-master) (Documentation) (driver-api) (usb) anchors.rst, line 18); [backlink](#)

Unknown interpreted text role "c:func".

Deallocation

Once it has no more URBs associated with it, the anchor can be freed with normal memory management operations.

Association and disassociation of URBs with anchors

An association of URBs to an anchor is made by an explicit call to `:c:func:'usb_anchor_urb'`. The association is maintained until an URB is finished by (successful) completion. Thus disassociation is automatic. A function is provided to forcibly finish (kill) all URBs associated with an anchor. Furthermore, disassociation can be made with `:c:func:'usb_unanchor_urb'`

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\driver-api\usb\ (linux-master) (Documentation) (driver-api) (usb) anchors.rst, line 31); [backlink](#)

Unknown interpreted text role "c:func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\driver-api\usb\ (linux-master) (Documentation) (driver-api) (usb) anchors.rst, line 31); [backlink](#)

Unknown interpreted text role "c:func".

Operations on multitudes of URBs

`:c:func:'usb_kill_anchored_urbs'`

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\driver-api\usb\ (linux-master) (Documentation) (driver-api) (usb) anchors.rst, line 41); [backlink](#)

Unknown interpreted text role "c:func".

This function kills all URBs associated with an anchor. The URBs are called in the reverse temporal order they were submitted. This way no data can be reordered.

`:c:func:'usb_unlink_anchored_urbs'`

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\driver-api\usb\ (linux-master) (Documentation) (driver-api) (usb) anchors.rst, line 48); [backlink](#)

Unknown interpreted text role "c:func".

This function unlinks all URBs associated with an anchor. The URBs are processed in the reverse temporal order they were submitted. This is similar to `:c:func:'usb_kill_anchored_urbs'`, but it will not sleep. Therefore no guarantee is made that the URBs have been unlinked when the call returns. They may be unlinked later but will be unlinked in finite time.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\driver-api\usb\ (linux-master) (Documentation) (driver-api) (usb) anchors.rst, line 52); [backlink](#)

Unknown interpreted text role "c:func".

`:c:func:'usb_scuttle_anchored_urbs'`

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\driver-api\usb\ (linux-master) (Documentation) (driver-api) (usb) anchors.rst, line 59); [backlink](#)

Unknown interpreted text role "c:func".

All URBs of an anchor are unanchored en masse.

`:c:func:'usb_wait_anchor_empty_timeout'`

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\driver-api\usb\ (linux-master) (Documentation) (driver-api) (usb) anchors.rst, line 64); [backlink](#)

Unknown interpreted text role "c:func".

This function waits for all URBs associated with an anchor to finish or a timeout, whichever comes first. Its return value will tell you whether the timeout was reached.

`:c:func:'usb_anchor_empty'`

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\driver-api\usb\ (linux-master) (Documentation) (driver-api) (usb) anchors.rst, line 71); [backlink](#)

Unknown interpreted text role "c:func".

Returns true if no URBs are associated with an anchor. Locking is the caller's responsibility.

`:c:func:'usb_get_from_anchor'`

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\driver-api\usb\ (linux-master) (Documentation) (driver-api) (usb) anchors.rst, line 77); [backlink](#)

Unknown interpreted text role "c:func".

Returns the oldest anchored URB of an anchor. The URB is unanchored and returned with a reference. As you may mix URBs to several destinations in one anchor you have no guarantee the chronologically first submitted URB is returned.