



Vive Input Utility Developer Guide

vivesoftware@htc.com

Abstract

Vive Input Utility is a tool based on the SteamVR plugin that allows developers to access Vive device status in handy way.

We also introduce a mouse pointer solution that works in 3D space and is compatible with the Unity Event System.

By importing this utility, developers can save lots of time in writing redundant code to manage Vive devices.

Motivation

The SteamVR plugin provides a C# interface to let Unity developers interact with Vive devices.

But getting the controller input status or device pose causes lots of redundant code:

- You must continuously get the correct device index, which is determined by `SteamVR_ControllerManager` whenever a controller is connected.
- Locating `SteamVR_ControllerManager` also causes more effort.

So our main goal is to provide handy interface and reduce the redundancy.

Main Features

- Using static function to retrieve device input:
 - Button's event
 - Tracking pose.
- Using ViveRaycaster component to achieve 3D-space-pointer that compatible with Unity Event System.

Static Interface

- Get button's event

Instead of finding device through SteamVR scripts...

```
using UnityEngine;
using Valve.VR;

public class GetPressDown_SteamVR : MonoBehaviour
{
    public SteamVR_ControllerManager manager;

    private void Update()
    {
        // get trigger
        SteamVR_TrackedObject trackedObj = manager.right.GetComponent<SteamVR_TrackedObject>();
        SteamVR_Controller.Device rightDevice = SteamVR_Controller.Input((int)trackedObj.index);
        if (rightDevice.GetPressDown(EVRButtonId.k_EButton_SteamVR_Trigger))
        {
            // ...
        }
    }
}
```

Static class ViveInput provides a simpler API to achieve that.

```
using UnityEngine;
using HTC.UnityPlugin.Vive;

public class GetPressDown_ViveInput : MonoBehaviour
{
    private void Update()
    {
        // get trigger
        if (ViveInput.GetPressDown(HandRole.RightHand, ControllerButton.Trigger))
        {
            // ...
        }
    }
}
```

- Listen to button's event

ViveInput also provides callback style listener.

```
using UnityEngine;
using HTC.UnityPlugin.Vive;

public class GetPressDown_ViveInputHandler : MonoBehaviour
{
    private void Awake()
    {
        ViveInput.AddPressDown(HandRole.LeftHand, ControllerButton.Trigger, OnTrigger);
    }

    private void OnDestroy()
    {
        ViveInput.RemovePressDown(HandRole.LeftHand, ControllerButton.Trigger, OnTrigger);
    }

    private void OnTrigger()
    {
        // ...
    }
}
```

- Get tracking pose

Static class VivePose provides an API to get a device pose.

It is easy to identify device role by static class DeviceRole.

```
using UnityEngine;
using HTC.UnityPlugin.Vive;
using HTC.UnityPlugin.PoseTracker;

public class GetPose_VivePose : MonoBehaviour
{
    public Transform deviceOrigin;


    public void ToMidPoint()
    {
        Pose rightHandPose = VivePose.GetPose(HandRole.RightHand);
        Pose leftHandPose = VivePose.GetPose(HandRole.LeftHand);

        Pose.SetPose(transform, Pose.Lerp(rightHandPose, leftHandPose, 0.5f), deviceOrigin);
    }
}
```

Helper Components

- Vive Pose Tracker

It works like SteamVR_TrackedObject, but targets device by using ViveRole.DeviceRole instead of device index.




- Pose Modifier


It is a tracking effect script applied to a pose tracker.

Implement abstract class PoseTracker.BasePoseModifier to write custom tracking effect.

Without pose modifier




With pose modifier



<https://vimeo.com/171724218>




<https://vimeo.com/171724270>



Multiple modifiers are allowed. Priority determines the pose modified order.

- **Pose Stabilizer**
If controller moves within the threshold, the object stays. Otherwise, the object keeps the offset and follows.
- **Pose Easer**
Let the object follows controller using easing curve.
- **Pose Freezer**
It constrains the object following movement by setting axis flags.



Vive Input Utility Developer Guide

- Vive Raycaster & Raycast Method

Custom Pointer3DRaycaster implement for Vive controller to achieve 3D-space-pointer that compatible with Unity Event System.


Vive Raycaster is an event raycaster script that sends Vive button's event from its transform.

That means your controller can act like a 3D mouse by combining Vive Pose Tracker and Vive Raycaster.

A Vive Raycaster must works with Raycast Method to raycast against different types of objects.

| Raycast Method | Against Type |
|---------------------------|---|
| Physics Raycast Method | Collider |
| Physics 2D Raycast Method | Collider2D |
| Graphic Raycast Method | Graphic in target Canvas |
| Canvas Raycast Method | Graphic in all Canvas with CanvasRaycastTarget component |

For example, you can arrange them like this to interact with UGUI menu:



More examples:

<https://vimeo.com/169824408>



<https://vimeo.com/169824438>



- Raycaster Event Handler

You must implement an Event System Handler to catch an event sent by an event raycaster.

- Add a component that implements event handler interfaces that are supported by the built-in Input Module on an object. See <https://docs.unity3d.com/Manual/SupportedEvents.html> to learn more about built-in event handlers.
- Add event receiver (Collider/Collider2D/Graphic) to the object or child of the object.

```
using UnityEngine;
using UnityEngine.EventSystems;
using System.Collections.Generic;
using HTC.UnityPlugin.Vive;

public class MyPointerEventHandler : MonoBehaviour
{
    , IPointerEnterHandler
    , IPointerExitHandler
    , IPointerClickHandler
{
    private HashSet<PointerEventData> hovers = new HashSet<PointerEventData>();

    public void OnPointerEnter(PointerEventData eventData)
    {
        if (hovers.Add(eventData) && hovers.Count == 1)
        {
            // turn to highlight state
        }
    }

    public void OnPointerExit(PointerEventData eventData)
    {
        if (hovers.Remove(eventData) && hovers.Count == 0)
        {
            // turn to normal state
        }
    }

    public void OnPointerClick(PointerEventData eventData)
    {
        if (eventData.IsViveButton(ControllerButton.Trigger))
        {
            // Vive button triggered!
        }
        else if (eventData.button == PointerEventData.InputButton.Left)
        {
            // Standalone button triggered!
        }
    }
}
```

- Vive Collider Event Caster



Like Vive Raycaster, Vive Collider Event Caster is also an extension of Unity Event System.

But the Collider Event Caster isn't driven by any input module, so they can work together at the same time if needed.

Instead of using raycast, Collider Event Caster uses 3D physics triggers to "point at" other 3D physics colliders and sends them button events.

As a result, when setting up Collider Event Caster, remember to set child colliders as a trigger.

To setup Vive Collider Event Caster in short cut, follow the tutorial document, and replace VivePointers with ViveColliders prefab in step 2.



- Collider Event Handler

Because Collider Event System works based on trigger message, the event receiver can only be colliders that able to send trigger message. (Box/Sphere/Capsule/Mesh colliders)

Collider Event doesn't supports built-in event handlers, only the followings:

- [IColliderEventHoverEnterHandler](#)
Called when a controller enters the object.
- [IColliderEventHoverExitHandler](#)
Called when a controller exits the object.
- [IColliderEventPressDownHandler](#)
Called when a controller button is pressed on the object.
- [IColliderEventPressUpHandler](#)
Called when a controller button is released on the object.
- [IColliderEventPressEnterHandler](#)
Called when a controller enters the object with pressed button or when a controller button is pressed on the object.

- [IColliderEventPressExitHandler](#)
Called when a controller exits the object with pressed button or when a controller button is released on the object.
- [IColliderEventClickHandler](#)
Called when a controller is pressed and released on the same object without leaving it.
- [IColliderEventDragStartHandler](#)
Called on the drag object when dragging is about to begin.
- [IColliderEventDragFixedUpdateHandler](#)
Called on the drag object when a drag is happening in that fixed frame (called on the original drag start object).
- [IColliderEventDragUpdateHandler](#)
Called on the drag object when a drag is happening in that frame (called on the original drag start object).
- [IColliderEventDragEndHandler](#)
Called on the drag object when a drag finishes (called on the original drag start object).
- [IColliderEventDropEndHandler](#)
Called on the object where a drag finishes.
- [IColliderEventAxisChangedHandler](#)
Called when the touch pad scrolls or trigger button moves on the object.

- Collider Event Data

There are three kinds of event data sent to the event handler, each of them delivered with different properties and status, except eventCaster, the owner of the event data.

- [ColliderHoverEventData](#)
An empty event data without any properties except eventCaster.
- [ColliderButtonEventData](#)
Represents a button on a controller. You can get button status from its properties like isPressed, isDragging, pressPosition and pressRotation.
- [ColliderAxisEventData](#)
Stored with scroll delta values.

Prefabs

- Vive Pointers

Combination of stabilized VivePoseTracker and ViveRaycaster to achieve 3D mouse pointer to interact with built-in UGUI elements or physics colliders.

- Vive Colliders

Combination of VivePoseTracker and ViveColliderEventCaster to interact with physics colliders like grabbing things.

- Vive Rig

Combination of [CameraRig], VivePointers, ViveColliders and custom model to demonstrate a way to control all these features, see ControllerManagerSample component to learn how it works.

API Reference

- **uint** `ViveRole.GetDeviceIndex(DeviceRole role)`
Returns device index of the device identified by the role. Returns `OpenVR.k_unTrackedDeviceIndexInvalid` if the role doesn't assign to any device.
- **bool** `VivePose.HasFocus()`
Returns true if input focus captured by current process. Usually the process losses focus when player switch to deshboard by clicking Steam button.
- **bool** `VivePose.IsConnected(DeviceRole role)`
Returns true if the device identified by role is connected.
- **bool** `VivePose.HasTracking(DeviceRole role)`
Returns true if tracking data of the device identified by role has valid value.
- **Pose** `VivePose.GetPose(DeviceRole role, Transform origin = null)`
Returns tracking pose of the device identified by role.
- **void** `VivePose.SetPose(Transform target, DeviceRole role, Transform origin = null)`
Set target pose to tracking pose of the device identified by role relative to the origin.
- **bool** `ViveInput.GetPress(HandRole role, ControllerButton button)`
Returns true while the button on the controller identified by role is held down.
- **bool** `ViveInput.GetPressDown(HandRole role, ControllerButton button)`
Returns true during the frame the user pressed down the button on the controller identified by role.
- **bool** `ViveInput.GetPressUp(HandRole role, ControllerButton button)`
Returns true during the frame the user releases the button on the role.
- **float** `ViveInput.GetTriggerValue(HandRole role)`
Returns raw analog value of the trigger button on the controller identified by role.
- **Vector2** `ViveInput.GetPadAxis(HandRole role)`
Returns raw analog value of the touch pad on the controller identified by role.
- **int** `ViveInput.ClickCount(HandRole role, ControllerButton button)`
Return amount of clicks in a row for the button on the controller identified by role. Set `ViveInput.clickInterval` to configure click interval.

- **float ViveInput.LastPressDownTime**(**HandRole** role, **ControllerButton** button)
Returns time of the last frame that user pressed down the button on the controller identified by role.
- **void ViveInput.AddPress**(**HandRole** role, **ControllerButton** button, **Action** callback)
Add press handler for the button on the controller identified by role.
- **void ViveInput.AddPressDown**(**HandRole** role, **ControllerButton** button, **Action** callback)
Add press down handler for the button on the controller identified by role.
- **void ViveInput.AddPressUp**(**HandRole** role, **ControllerButton** button, **Action** callback)
Add press up handler for the button on the controller identified by role.
- **void ViveInput.AddClick**(**HandRole** role, **ControllerButton** button, **Action** callback)
Add click handler for the button on the controller identified by role. Use ViveInput.ClickCount to get click count.
- **void ViveInput.RemovePress**(**HandRole** role, **ControllerButton** button, **Action** callback)
Remove press handler for the button on the controller identified by role.
- **void ViveInput.RemovePressDown**(**HandRole** role, **ControllerButton** button, **Action** callback)
Remove press down handler for the button on the controller identified by role.
- **void ViveInput.RemovePressUp**(**HandRole** role, **ControllerButton** button, **Action** callback)
Remove press up handler for the button on the controller identified by role.
- **void ViveInput.RemoveClick**(**HandRole** role, **ControllerButton** button, **Action** callback)
Remove click handler for the button on the controller identified by role.
- **void ViveInput.TriggerHapticPulse**(**HandRole** role, **ushort** intensity = 500)
Trigger vibration of the controller identified by role.