

# Install and Configure

## Samba Server on Ubuntu

### 22.04/20.04 for File Sharing

 Last Updated: June 27th, 2022  Guoan Xiao (Admin)  45  
Comments  Ubuntu

In this tutorial, we're going to learn how to install and configure a **Samba** server on Ubuntu 22.04/20.04 to share files on the local network. Samba is a free and open-source SMB/CIFS protocol implementation for Unix and Linux that allows for file and print sharing between Unix/Linux, Windows, and macOS machines in a local area network.

Samba is usually installed and run on Linux. It comprises several programs that serve different but related purposes, the most important two of which are:

- **smbd**: provides SMB/CIFS service (file sharing and printing), can also act as a Windows domain controller.
- **nmdb**: This daemon provides NetBIOS name service, listens for name-server requests. It also allows the Samba server to be found by other computers on the network.

## How to Install Samba Server on Ubuntu

Samba is included in most Linux distributions. To install Samba on Ubuntu, simply run the following command in terminal.

```
sudo apt install samba samba-common-b  
in
```

The latest stable version available is 4.12.0, released on March 03, 2019. To check your Samba version, run

```
smbd --version
```

Sample output:

```
Version 4.7.6-Ubuntu
```

To check if Samba service is running, issue the following command.

```
systemctl status smbd nmbd
```

To start these two services, issue the following command:

```
sudo systemctl start smbd nmbd
```

Once started, smbd will be listening on TCP port 139 and 445. nmbd will be listening on UDP port 137 and 138.

- TCP 139: used for file and printer sharing and other operations.
- TCP 445: the NetBIOS-less CIFS port.
- UDP 137: used for NetBIOS network browsing.
- UDP 138: used for NetBIOS name service.

If you have enabled the [UFW firewall](#) on Ubuntu, then you need to open the above ports in the firewall with the following command.

```
sudo ufw allow samba
```

## Create a Private Samba Share

In this section, we will see how to create a private Samba share that requires the client to enter username and password

in order to gain access. The main Samba configuration file is located at: `/etc/samba/smb.conf`. You can edit it in terminal with a command line text editor like `nano`.


```
sudo nano /etc/samba/smb.conf
```

In the `[global]` section, make sure the value of `workgroup` is the same with the workgroup settings of Windows computers.

```
workgroup = WORKGROUP
```

```
#===== Global Settings =====  
[global]  
## Browsing/Identification ###  
# Change this to the workgroup/NT-domain name your Samba server will part of  
workgroup = WORKGROUP  
# server string is the equivalent of the NT Description field  
server string = %h server (Samba, Ubuntu)
```

You can find the setting on your Windows computer by going to Control Panel > System and Security > System.



Then scroll down to the bottom of the file. (In nano text editor, you can achieve that by pressing `CTRL+W` then `CTRL+V`.) Add a new section like below.

```
[Private]
```

```
comment = needs username and password
```

```
to access
path = /srv/samba/private/
browseable = yes
guest ok = no
writable = yes
valid users = @samba
```

Explanation:

- **Private** is the folder name that will be displayed on the Windows network.
- The comment is a description for the shared folder.
- The path parameter specifies the path to the shared folder. I use `/srv/samba/private/` as an example. You can also use a folder in your home directory.
- **browseable = yes**: Allow other computers in the network to see the Samba server and Samba share. If set to no, users have to know the name of the Samba server and then manually enter a path in the file manager to access the shared folder.
- **guest ok = no**: Disable guest access. In other words, you need to enter username and password on the client computer to access the shared folder.
- **writable = yes**: Grants both read and write permission to clients.
- **valid users = @samba**: Only users in the samba group are allowed to access this Samba share.

Save and close the file. (To save the file in nano text editor, press `Ctrl+O`, then press `Enter` to confirm the file name to write. To close the file, press `Ctrl+X`.) Now we need to create a Samba user. First, we need to create a standard Linux user account with the following command. Replace **username** with your desired username.

```
sudo adduser username
```

You will be prompted to set an Unix password. After that, you also need to set a separate Samba password for the new user with the following command:

```
sudo smbpasswd -a username
```

Create the samba group.

```
sudo groupadd samba
```

And add this user to the samba group.

```
sudo gpasswd -a username samba
```

Create the private share folder.

```
sudo mkdir -p /srv/samba/private/
```

The samba group needs to have read, write and execute permission on the shared folder. You can grant these permissions by executing the following command. (If your system doesn't have the `setfacl` command, you need to install the `acl` package with `sudo apt install acl`.)

```
sudo setfacl -R -m "g:samba:rwx" /srv/samba/private/
```

Next, run the following command to check if there's syntactic errors.

```
testparm
```

Now all left to do is to restart `smbd` and `nmbd` daemon.

```
sudo systemctl restart smbd nmbd
```

# How to Create a Samba Public Share

## Without Authentication

To create a public share without requiring username and password, the following conditions must be met.

- Set `security = user` in the global section of Samba configuration file. Although you can create a public share with the `security = share` mode, but this security mode is deprecated. It is strongly suggested that you avoid `share` mode.
- Set `map to guest = bad user` in the global section of Samba configuration file. This will cause `smbd` to use a guest account to authenticate clients who don't have registered account on the Samba server. Since it's a guest account, Samba clients don't need to enter password.
- Set `guest ok = yes` in the share definition to allow guest access.
- Grant read, write and execute permission of the public folder to the `nobody` account, which is the default guest account.

As a matter of fact, the first two conditions are already met as Samba by default uses these two settings.

Here's a step-by-step guide to create a public share. First, open and edit the Samba configuration file.

```
sudo nano /etc/samba/smb.conf
```

In the `[global]` section, make sure the value of `workgroup` is the same with the `workgroup` settings of Windows computers.

```
workgroup = WORKGROUP
```

```

#===== Global Settings =====
[global]


## Browsing/Identification ##

# Change this to the workgroup/NT-domain name your Samba server will part of
workgroup = WORKGROUP

# server string is the equivalent of the NT Description field
server string = %h server (Samba, Ubuntu)

```

You can find the setting on your Windows computer by going to Control Panel > System and Security > System.



Then scroll down to the bottom of the file and paste the following lines.

```

[public]

comment = public share, no need to en
ter username and password
path = /srv/samba/public/
browseable = yes
writable = yes
guest ok = yes

```

Save and close the file. Next, create the /srv/samba/public/ folder.

```
sudo mkdir -p /srv/samba/public
```

Then make sure the nobody account has read, write and execute permission on the public folder by executing the

following command. (If your system doesn't have the `setfacl` command, you need to install the `acl` package with `sudo apt install acl`.)

```
sudo setfacl -R -m "u:nobody:rwx" /srv/samba/public/
```

Restart `smbd` and `nmbd`.

```
sudo systemctl restart smbd nmbd
```


## Accessing Samba Shared Folder From Windows

On a Windows computer that is in the same network, open File Explorer and click **Network** on the left pane. If you see the following message, then you need to click on the message and turn on network discovery and file sharing.

File sharing is turned off. Some network computers and devices might not be visible.


Next, enter `\\` followed by the IP address of Samba server in the address bar of File Explorer, like this:

`\\192.168.0.102`. You will see a list of shared resources on the Samba server.





Then double-click the shared folder. To access the private share, you need to enter the samba username and password. You don't need to do so to access public share.



Once connected, you can read, write and delete files in the Samba shared folder.

## Connecting Error

If you get the following error:

```
You do not have permission to access
\\hostname\share-name. Contact your n
etwork administrator to request acces
s.
```

You can try connecting to the Samba share from the command prompt. Open up a command prompt, then run the following command to close current Samba session.

```
net use \\samba-server-ip\share-name
/delete
```


Next, connect to the Samba share with the following command:

```
net use \\samba-server-ip\share-name
/user:samba-username password
```

Once the above command completed successfully, go to the Network tab in File Explorer and now you should be able to access the Samba share.

## Drive Mapping on Windows

One feature of the Windows operating system is the capability to map a drive letter (such as S:) to a remote directory. To map the drive letter S : to the Samba share, right-click the Samba shared folder and select **Map network drive**. Then choose a drive letter and click Finish.




Once the drive mapping is established, applications can access the files in the Samba share through the drive letter S : . And this Samba share will be automatically mounted when you log in to your Windows computer.


## Accessing Samba Share Folder in Nautilus File Manager on Linux

If you are using Nautilus file manager, then click Other Locations on the left pane. On the bottom, you will see an option to **connect to server**. To access your Samba share, type in `smb : //` followed by the IP address of the Samba server and press Enter. For example:


- `smb://192.168.0.102`



You will see a list of shared resources on the Samba server.




If you click the private shared folder, then you will need to enter the Samba username and password. If you click the public shared folder, then choose to connect as Anonymous.



If you see the following error message,

failed to retrieve share list from server



You can try fixing this error by mounting the Samba share from the command line, which is discussed below.

## Automatically Mount Samba Share From Command Line on Linux

**Note:** Automatically mounting the Samba share is done on clients. These commands should be run on a Samba client, if the Samba client runs Linux. You should not do it on the Samba server itself.

If you need to automatically mount the Samba share at boot time, you can use the command line to mount and then add an entry in the `/etc/fstab` file. In order to do that, you need to install the `cifs-utils` package.

CentOS/RHEL

```
sudo dnf install cifs-utils
```

Debian/Ubuntu

```
sudo apt install cifs-utils
```

Then create a mount point for the Samba share.

```
sudo mkdir /mnt/samba-private
```

Now you can use the following command to mount a private shared folder.

```
sudo mount -t cifs -o username=your_samba_username //192.168.0.102/private  
/mnt/samba-private/
```

It will ask you to enter the Samba password. After that, it will be mounted at `/mnt/samba-private/` directory.

To automatically mount the Samba share, edit `/etc/fstab` file.

```
sudo nano /etc/fstab
```

Add the following line in the file.

```
//192.168.0.102/private /mnt/samba-private cifs x-systemd.automount,  
_netdev,credentials=/etc/samba-credential.conf,uid=1000,gid=1000,x-gvfs-show 0 0
```

Where:

- **//192.168.0.102/private**: the IP address of Samba server and the share name.
- **/mnt/samba-private**: mount point for the Samba share.
- **cifs**: filesystem type
- **x-systemd.automount**: This option tells systemd to create an automount unit for the file system. We use this because it ensures the remote filesystem is mounted only after there's network access.
- **\_netdev**: This specifies that the mount requires network.
- **credentials=**: Linux should look for credentials in the `/etc/samba-credential.conf` file.
- **uid=1000,gid=1000**: By default the mounted filesystem would be owned by the root user. We use **uid** and **gid** to change the ownership of the filesystem.

Normally you use your own **uid** and **gid**, which are both 1000 by default.

- **x-gvfs-show**: If you are using GNOME desktop environment or its derivatives, you can use this option to show the mounted file system in the file manager.

Save and close the file. Then create the credential file.

```
sudo nano /etc/samba-credential.conf
```

Add the following lines in the file.

```
username=your_samba_username  
password=samba_password  
domain=WORKGROUP
```

Save and close the file. Make sure only the root user can read this file.

```
sudo chmod 600 /etc/samba-credential.  
conf
```

If you restart your Linux computer now, the Samba share will be automatically mounted. You can also run the following command to mount the Samba share without restart.

```
sudo mount -a
```

If you see the permission denied error and you can find the following line by running the `sudo dmesg` command,

```
VFS: cifs_mount failed w/return code  
= -13
```

it's probably because you have a typo in the `/etc/samba-credential` file.

**Further reading:** [How to Automount File Systems on Linux.](#)

## Can't Write to the Samba Share?

The CIFS mount described above allows you to write to the Samba share. If you see the following error while creating a file:

```
Read-only file system
```

Check that you set `writable = yes` in the Samba configuration file. Sometimes, the Samba shared folder is on an external hard drive, then make sure you mount the external hard drive in read-write mode on the Samba server. For example, I mounted my `btrfs` hard drive with the following line in `/etc/fstab`.

```
LABEL=5TB    /mnt/5TB    btrfs    default  
ts    0    0
```

It turns out that the `defaults` option doesn't allow write operation. To make it writable, add `rw` option.

```
LABEL=5TB    /mnt/5TB    btrfs    default  
ts,rw    0    0
```

Then unmount the hard drive. You need to use your own mount point.

```
sudo umount /mnt/5TB
```

And mount it again.

```
sudo mount -a
```

## Troubleshooting Tip

If your Samba server is not working as expected, you can check the log files under `/var/log/samba/` directory. You can add the following line in the `[global]` section of `/etc/samba/smb.conf` file to increase the log level if you want to log more information.

```
log level = 2
```

## A Simple Trick to Boost Samba Performance

You can enable the TCP BBR algorithm to boost server network performance.

- [Easily Boost Ubuntu Network Performance by Enabling TCP BBR](#)

## Wrapping Up

That's it! I hope this tutorial helped you set up Samba server on Ubuntu. As always, if you found this post useful, then [subscribe to our free newsletter](#). And you may also want to read the following article to share printer on the local network.

- [Set Up CUPS Print Server on Ubuntu \(Bonjour, IPP, Samba, AirPrint\)](#)

Want to run Samba over the Internet? You need to set up **WireGuard VPN** to encrypt the SMB/CIFS protocol. Since WireGuard uses peer-to-peer public-key authentication, it also allows you to remove password authentication in Samba, provided that you configure the firewall to allow Samba for VPN clients only and forbid all other IP addresses.



- [Set Up Your Own WireGuard VPN Server on Ubuntu 22.04/20.04/18.04](#)

Want better performance? You can use NFS (Network File System) instead of Samba.

- [How to Set Up NFS Share on Ubuntu 20.04, 18.04](#)

Rate this tutorial

■ ■ ■ [Total: 102 Average: 4.2]

You may also like:

WHY IS RELATED  
CONTENT NOT  
SHOWING UP?

**Why is Related Content not showing up?**

🔖 Samba

🔖 Samba Server

🔖 Ubuntu 16.04