

Photon Voice

v2.20.1

Generated by Doxygen 1.8.17

1 Main Page	1
2 Namespace Documentation	3
2.1 Photon Namespace Reference	3
2.2 Photon.Voice Namespace Reference	3
2.2.1 Enumeration Type Documentation	5
2.2.1.1 AudioSampleType	5
2.2.1.2 Codec	5
2.3 Photon.Voice.IOS Namespace Reference	6
2.3.1 Enumeration Type Documentation	6
2.3.1.1 AudioSessionCategory	6
2.3.1.2 AudioSessionCategoryOption	7
2.3.1.3 AudioSessionMode	8
2.4 Photon.Voice.PUN Namespace Reference	9
2.5 Photon.Voice.Unity Namespace Reference	9
2.6 Photon.Voice.Unity.UtilityScripts Namespace Reference	10
2.7 POpusCodec Namespace Reference	10
2.8 POpusCodec.Enums Namespace Reference	10
2.8.1 Enumeration Type Documentation	10
2.8.1.1 Bandwidth	10
2.8.1.2 Channels	11
2.8.1.3 Delay	11
2.8.1.4 OpusApplicationType	11
2.8.1.5 SignalHint	12
3 Class Documentation	13
3.1 AudioClipWrapper Class Reference	13
3.2 AudioDesc Class Reference	13
3.3 AudioInChangeNotifier Class Reference	14
3.4 AudioInEnumerator Class Reference	14
3.4.1 Detailed Description	14
3.5 AudioOutCapture Class Reference	15
3.6 AudioSessionParameters Struct Reference	15
3.7 AudioSessionParametersPresets Class Reference	15
3.7.1 Member Data Documentation	15
3.7.1.1 Game	15
3.7.1.2 VoIP	16
3.8 AudioSyncBuffer< T > Class Template Reference	16
3.9 AudioUtil Class Reference	16
3.9.1 Detailed Description	18
3.9.2 Member Function Documentation	18
3.9.2.1 Convert() [1/2]	18
3.9.2.2 Convert() [2/2]	18

3.9.2.3 ForceToStereo< T >()	18
3.9.2.4 Resample< T >()	19
3.9.2.5 ResampleAndConvert() [1/2]	19
3.9.2.6 ResampleAndConvert() [2/2]	20
3.10 BufferReaderPushAdapter< T > Class Template Reference	20
3.10.1 Detailed Description	21
3.10.2 Constructor & Destructor Documentation	21
3.10.2.1 BufferReaderPushAdapter()	21
3.10.3 Member Function Documentation	21
3.10.3.1 Service()	21
3.11 BufferReaderPushAdapterAsyncPool< T > Class Template Reference	21
3.11.1 Detailed Description	22
3.11.2 Constructor & Destructor Documentation	22
3.11.2.1 BufferReaderPushAdapterAsyncPool()	22
3.11.3 Member Function Documentation	22
3.11.3.1 Service()	22
3.12 BufferReaderPushAdapterAsyncPoolCopy< T > Class Template Reference	23
3.12.1 Detailed Description	23
3.12.2 Constructor & Destructor Documentation	23
3.12.2.1 BufferReaderPushAdapterAsyncPoolCopy()	23
3.12.3 Member Function Documentation	24
3.12.3.1 Service()	24
3.13 BufferReaderPushAdapterAsyncPoolFloatToShort Class Reference	24
3.13.1 Detailed Description	24
3.13.2 Constructor & Destructor Documentation	25
3.13.2.1 BufferReaderPushAdapterAsyncPoolFloatToShort()	25
3.13.3 Member Function Documentation	25
3.13.3.1 Service()	25
3.14 BufferReaderPushAdapterAsyncPoolShortToFloat Class Reference	25
3.14.1 Detailed Description	26
3.14.2 Constructor & Destructor Documentation	26
3.14.2.1 BufferReaderPushAdapterAsyncPoolShortToFloat()	26
3.14.3 Member Function Documentation	26
3.14.3.1 Service()	26
3.15 BufferReaderPushAdapterBase< T > Class Template Reference	27
3.15.1 Detailed Description	27
3.15.2 Constructor & Destructor Documentation	27
3.15.2.1 BufferReaderPushAdapterBase()	27
3.15.3 Member Function Documentation	27
3.15.3.1 Dispose()	28
3.15.3.2 Service()	28
3.16 ConnectAndJoin Class Reference	28

3.17 RawCodec.Decoder< T > Class Template Reference	29
3.17.1 Member Function Documentation	29
3.17.1.1 Input()	29
3.17.1.2 Open()	29
3.18 OpusCodec.Decoder< T > Class Template Reference	30
3.18.1 Member Function Documentation	30
3.18.1.1 Input()	30
3.18.1.2 Open()	30
3.19 OpusCodec.DecoderFactory Class Reference	31
3.20 OpusCodec.Encoder< T > Class Template Reference	31
3.21 RawCodec.Encoder< T > Class Template Reference	31
3.22 OpusCodec.EncoderFloat Class Reference	32
3.23 OpusCodec.EncoderShort Class Reference	32
3.24 OpusCodec.Factory Class Reference	32
3.25 FactoryPrimitiveArrayPool< T > Class Template Reference	32
3.25.1 Detailed Description	33
3.26 FactoryReusableArray< T > Class Template Reference	33
3.26.1 Detailed Description	33
3.27 FrameOut< T > Class Template Reference	34
3.28 Framer< T > Class Template Reference	34
3.28.1 Detailed Description	34
3.28.2 Constructor & Destructor Documentation	34
3.28.2.1 Framer()	34
3.28.3 Member Function Documentation	35
3.28.3.1 Count()	35
3.28.3.2 Frame()	35
3.29 IAudioDesc Interface Reference	35
3.29.1 Detailed Description	36
3.29.2 Property Documentation	36
3.29.2.1 Channels	36
3.29.2.2 Error	36
3.29.2.3 SamplingRate	36
3.30 IAudioOut< T > Interface Template Reference	36
3.31 IAudioPusher< T > Interface Template Reference	37
3.31.1 Detailed Description	37
3.31.2 Member Function Documentation	37
3.31.2.1 SetCallback()	37
3.32 IAudioReader< T > Interface Template Reference	38
3.32.1 Detailed Description	38
3.33 IDataReader< T > Interface Template Reference	38
3.33.1 Detailed Description	38
3.33.2 Member Function Documentation	38

3.33.2.1 Read()	38
3.34 IDecoder Interface Reference	39
3.34.1 Detailed Description	39
3.34.2 Member Function Documentation	39
3.34.2.1 Input()	39
3.34.2.2 Open()	39
3.34.3 Property Documentation	40
3.34.3.1 Error	40
3.35 IDecoderQueuedOutputImageNative Interface Reference	40
3.36 IEncoder Interface Reference	40
3.36.1 Detailed Description	41
3.36.2 Member Function Documentation	41
3.36.2.1 DequeueOutput()	41
3.36.2.2 EndOfStream()	41
3.36.3 Property Documentation	41
3.36.3.1 Error	41
3.36.3.2 Info	42
3.36.3.3 Output	42
3.37 IEncoderDirect< B > Interface Template Reference	42
3.37.1 Detailed Description	42
3.37.2 Member Function Documentation	42
3.37.2.1 Input()	42
3.38 AudioUtil.ILevelMeter Interface Reference	43
3.38.1 Detailed Description	43
3.38.2 Member Function Documentation	43
3.38.2.1 ResetAccumAvgPeakAmp()	43
3.38.3 Property Documentation	43
3.38.3.1 AccumAvgPeakAmp	44
3.38.3.2 CurrentAvgAmp	44
3.38.3.3 CurrentPeakAmp	44
3.39 ILocalVoiceAudio Interface Reference	44
3.39.1 Detailed Description	44
3.39.2 Member Function Documentation	45
3.39.2.1 VoiceDetectorCalibrate()	45
3.39.3 Property Documentation	45
3.39.3.1 LevelMeter	45
3.39.3.2 VoiceDetector	45
3.39.3.3 VoiceDetectorCalibrating	45
3.40 ILoggable Interface Reference	46
3.41 ILoggableDependent Interface Reference	46
3.42 ILogger Interface Reference	46
3.43 ImageBufferInfo Class Reference	46

3.44 ImageBufferNative Class Reference	47
3.45 ImageBufferNativeAlloc Class Reference	47
3.46 ImageBufferNativeGCHandleSinglePlane Class Reference	47
3.47 ImageBufferNativePool< T > Class Template Reference	47
3.48 ImageInputBuf Struct Reference	48
3.49 ImageOutputBuf Struct Reference	48
3.50 IOSAudioForceToSpeaker Class Reference	48
3.51 IProcessor< T > Interface Template Reference	48
3.51.1 Detailed Description	49
3.51.2 Member Function Documentation	49
3.51.2.1 Process()	49
3.52 IServiceable Interface Reference	49
3.52.1 Detailed Description	49
3.52.2 Member Function Documentation	50
3.52.2.1 Service()	50
3.53 AudioUtil.IVoiceDetector Interface Reference	50
3.53.1 Detailed Description	50
3.53.2 Property Documentation	50
3.53.2.1 ActivityDelayMs	51
3.53.2.2 Detected	51
3.53.2.3 DetectedTime	51
3.53.2.4 On	51
3.53.2.5 Threshold	51
3.53.3 Event Documentation	51
3.53.3.1 OnDetected	51
3.54 IVoiceTransport Interface Reference	52
3.55 AudioUtil.LevelMeter< T > Class Template Reference	52
3.55.1 Detailed Description	53
3.55.2 Member Function Documentation	53
3.55.2.1 Process()	53
3.55.2.2 ResetAccumAvgPeakAmp()	53
3.56 AudioUtil.LevelMeterDummy Class Reference	53
3.56.1 Detailed Description	54
3.56.2 Member Function Documentation	54
3.56.2.1 ResetAccumAvgPeakAmp()	54
3.57 AudioUtil.LevelMeterFloat Class Reference	54
3.57.1 Detailed Description	54
3.57.2 Constructor & Destructor Documentation	54
3.57.2.1 LevelMeterFloat()	54
3.58 AudioUtil.LevelMeterShort Class Reference	55
3.58.1 Detailed Description	55
3.58.2 Constructor & Destructor Documentation	55

3.58.2.1 LevelMeterShort()	55
3.59 LoadBalancingFrontend Class Reference	56
3.60 LoadBalancingTransport Class Reference	56
3.60.1 Detailed Description	57
3.60.2 Constructor & Destructor Documentation	57
3.60.2.1 LoadBalancingTransport()	57
3.60.3 Member Function Documentation	57
3.60.3.1 Dispose()	57
3.60.3.2 Service()	58
3.60.4 Property Documentation	58
3.60.4.1 GlobalInterestGroup	58
3.60.4.2 VoiceClient	58
3.61 LoadBalancingTransport2 Class Reference	58
3.61.1 Detailed Description	59
3.62 LocalVoice Class Reference	59
3.62.1 Detailed Description	60
3.62.2 Member Function Documentation	60
3.62.2.1 RemoveSelf()	60
3.62.3 Property Documentation	60
3.62.3.1 DebugEchoMode	61
3.62.3.2 Encrypt	61
3.62.3.3 FramesSent	61
3.62.3.4 FramesSentBytes	61
3.62.3.5 Info	61
3.62.3.6 InterestGroup	61
3.62.3.7 IsCurrentlyTransmitting	62
3.62.3.8 LocalUserServiceable	62
3.62.3.9 Reliable	62
3.62.3.10 TransmitEnabled	62
3.63 LocalVoiceAudio< T > Class Template Reference	62
3.63.1 Detailed Description	63
3.63.2 Member Function Documentation	63
3.63.2.1 Create()	63
3.63.2.2 VoiceDetectorCalibrate()	64
3.63.3 Property Documentation	64
3.63.3.1 VoiceDetectorCalibrating	64
3.64 LocalVoiceAudioDummy Class Reference	64
3.64.1 Detailed Description	65
3.64.2 Member Function Documentation	65
3.64.2.1 VoiceDetectorCalibrate()	65
3.64.3 Member Data Documentation	65
3.64.3.1 Dummy	66

3.65 LocalVoiceAudioFloat Class Reference	66
3.65.1 Detailed Description	66
3.66 LocalVoiceAudioShort Class Reference	66
3.66.1 Detailed Description	66
3.67 LocalVoiceFramed< T > Class Template Reference	66
3.67.1 Detailed Description	67
3.67.2 Member Function Documentation	68
3.67.2.1 AddPostProcessor()	68
3.67.2.2 AddPreProcessor()	68
3.67.2.3 ClearProcessors()	68
3.67.2.4 Dispose()	68
3.67.2.5 PushData()	69
3.67.2.6 PushDataAsync()	69
3.67.3 Property Documentation	69
3.67.3.1 PushDataAsyncReady	69
3.68 LocalVoiceFramedBase Class Reference	69
3.68.1 Detailed Description	69
3.68.2 Property Documentation	70
3.68.2.1 FrameSize	70
3.69 Logger Class Reference	70
3.70 MicAmplifier Class Reference	70
3.71 MicAmplifierFloat Class Reference	70
3.72 MicAmplifierShort Class Reference	71
3.73 MicWrapper Class Reference	71
3.74 MicWrapperPusher Class Reference	71
3.75 NativeAndroidMicrophoneSettings Class Reference	72
3.76 ObjectFactory< TType, TInfo > Interface Template Reference	72
3.76.1 Detailed Description	72
3.77 ObjectPool< TType, TInfo > Class Template Reference	73
3.77.1 Detailed Description	73
3.77.2 Constructor & Destructor Documentation	74
3.77.2.1 ObjectPool() [1/2]	74
3.77.2.2 ObjectPool() [2/2]	74
3.77.3 Member Function Documentation	74
3.77.3.1 AcquireOrCreate() [1/2]	75
3.77.3.2 AcquireOrCreate() [2/2]	75
3.77.3.3 Dispose()	75
3.77.3.4 Init()	75
3.77.3.5 Release() [1/2]	75
3.77.3.6 Release() [2/2]	76
3.77.4 Property Documentation	76
3.77.4.1 Info	76

3.78 OpusCodec Class Reference	76
3.79 OpusDecoder< T > Class Template Reference	77
3.80 OpusEncoder Class Reference	77
3.80.1 Property Documentation	78
3.80.1.1 EncoderDelay	78
3.81 OpusException Class Reference	78
3.82 OpusLib Class Reference	78
3.83 PhotonVoiceCreatedParams Class Reference	79
3.84 Recorder.PhotonVoiceCreatedParams Class Reference	79
3.85 PhotonVoiceLagSimulationGui Class Reference	79
3.86 PhotonVoiceNetwork Class Reference	79
3.86.1 Detailed Description	80
3.86.2 Member Function Documentation	80
3.86.2.1 ConnectAndJoinRoom()	80
3.86.2.2 Disconnect()	81
3.86.3 Member Data Documentation	81
3.86.3.1 AutoConnectAndJoin	81
3.86.3.2 AutoLeaveAndDisconnect	81
3.86.3.3 VoiceRoomNameSuffix	81
3.86.3.4 WorkInOfflineMode	81
3.86.4 Property Documentation	81
3.86.4.1 Instance	82
3.87 PhotonVoiceStatsGui Class Reference	82
3.87.1 Detailed Description	82
3.88 PhotonVoiceView Class Reference	82
3.88.1 Detailed Description	83
3.88.2 Member Function Documentation	83
3.88.2.1 Init()	83
3.88.3 Member Data Documentation	83
3.88.3.1 AutoCreateRecorderIfNotFound	84
3.88.3.2 SetupDebugSpeaker	84
3.88.3.3 UsePrimaryRecorder	84
3.88.4 Property Documentation	84
3.88.4.1 IsPhotonViewReady	84
3.88.4.2 IsRecorder	84
3.88.4.3 IsRecording	84
3.88.4.4 IsSetup	85
3.88.4.5 IsSpeaker	85
3.88.4.6 IsSpeakerLinked	85
3.88.4.7 IsSpeaking	85
3.88.4.8 RecorderInUse	85
3.88.4.9 SpeakerInUse	85

3.89 PrimitiveArrayPool< T > Class Template Reference	86
3.89.1 Detailed Description	86
3.90 RawCodec Class Reference	86
3.91 Recorder Class Reference	86
3.91.1 Detailed Description	89
3.91.2 Member Function Documentation	89
3.91.2.1 Init() [1/2]	89
3.91.2.2 Init() [2/2]	90
3.91.2.3 RestartRecording()	90
3.91.2.4 StartRecording()	90
3.91.2.5 StopRecording()	90
3.91.2.6 VoiceDetectorCalibrate()	91
3.91.3 Property Documentation	91
3.91.3.1 AudioClip	91
3.91.3.2 AudioGroup	91
3.91.3.3 AutoStart	91
3.91.3.4 Bitrate	91
3.91.3.5 DebugEchoMode	92
3.91.3.6 Encrypt	92
3.91.3.7 FrameDuration	92
3.91.3.8 InputFactory	92
3.91.3.9 InterestGroup	92
3.91.3.10 IsCurrentlyTransmitting	92
3.91.3.11 IsInitialized	93
3.91.3.12 IsRecording	93
3.91.3.13 LevelMeter	93
3.91.3.14 LoopAudioClip	93
3.91.3.15 MicrophoneType	93
3.91.3.16 PhotonMicrophoneDeviceId	93
3.91.3.17 PhotonMicrophoneEnumerator	94
3.91.3.18 ReactOnSystemChanges	94
3.91.3.19 RecordOnlyWhenEnabled	94
3.91.3.20 ReliableMode	94
3.91.3.21 RequiresRestart	94
3.91.3.22 SamplingRate	94
3.91.3.23 SkipDeviceChangeChecks	95
3.91.3.24 SourceType	95
3.91.3.25 StopRecordingWhenPaused	95
3.91.3.26 TransmitEnabled	95
3.91.3.27 TrySamplingRateMatch	95
3.91.3.28 TypeConvert	95
3.91.3.29 UnityMicrophoneDevice	96

3.91.3.30 UseOnAudioFilterRead	96
3.91.3.31 UserData	96
3.91.3.32 VoiceDetection	96
3.91.3.33 VoiceDetectionDelayMs	96
3.91.3.34 VoiceDetectionThreshold	96
3.91.3.35 VoiceDetector	97
3.91.3.36 VoiceDetectorCalibrating	97
3.92 RemoteVoiceInfo Class Reference	97
3.92.1 Detailed Description	97
3.92.2 Property Documentation	97
3.92.2.1 ChannelId	97
3.92.2.2 Info	98
3.92.2.3 PlayerId	98
3.92.2.4 VoiceId	98
3.93 RemoteVoiceLink Class Reference	98
3.94 RemoteVoiceOptions Struct Reference	98
3.94.1 Detailed Description	99
3.94.2 Member Function Documentation	99
3.94.2.1 SetOutput()	99
3.94.3 Property Documentation	99
3.94.3.1 Decoder	99
3.94.3.2 OnRemoteVoiceRemoveAction	100
3.95 AudioUtil.Resampler< T > Class Template Reference	100
3.95.1 Detailed Description	100
3.95.2 Constructor & Destructor Documentation	100
3.95.2.1 Resampler()	100
3.95.3 Member Function Documentation	101
3.95.3.1 Process()	101
3.96 Speaker Class Reference	101
3.96.1 Detailed Description	102
3.96.2 Member Function Documentation	102
3.96.2.1 RestartPlayback()	102
3.96.2.2 StartPlayback()	102
3.96.2.3 StopPlayback()	102
3.96.3 Property Documentation	102
3.96.3.1 Actor	103
3.96.3.2 IsLinked	103
3.96.3.3 IsPlaying	103
3.96.3.4 Lag	103
3.96.3.5 OnRemoteVoiceRemoveAction	103
3.96.3.6 PlaybackOnlyWhenEnabled	103
3.96.3.7 PlaybackStarted	104

3.97 TestTone Class Reference	104
3.98 AudioUtil.ToneAudioPusher< T > Class Template Reference	104
3.98.1 Detailed Description	104
3.98.2 Constructor & Destructor Documentation	104
3.98.2.1 ToneAudioPusher()	104
3.98.3 Member Function Documentation	105
3.98.3.1 SetCallback()	105
3.99 AudioUtil.ToneAudioReader< T > Class Template Reference	105
3.99.1 Detailed Description	106
3.99.2 Constructor & Destructor Documentation	106
3.99.2.1 ToneAudioReader()	106
3.99.3 Member Function Documentation	106
3.99.3.1 Read()	106
3.99.4 Property Documentation	107
3.99.4.1 Channels	107
3.99.4.2 Error	107
3.99.4.3 SamplingRate	107
3.100 ToneAudioReader Class Reference	107
3.101 UnityAndroidAudioInAEC Class Reference	108
3.102 UnityAudioOut Class Reference	108
3.103 UnityMicrophone Class Reference	108
3.103.1 Detailed Description	109
3.104 UnsupportedCodecException Class Reference	109
3.104.1 Detailed Description	109
3.104.2 Constructor & Destructor Documentation	109
3.104.2.1 UnsupportedCodecException()	109
3.105 UnsupportedSampleTypeException Class Reference	110
3.105.1 Detailed Description	110
3.105.2 Constructor & Destructor Documentation	110
3.105.2.1 UnsupportedSampleTypeException()	110
3.106 OpusCodec.Util Class Reference	111
3.107 VoiceClient Class Reference	111
3.107.1 Detailed Description	112
3.107.2 Member Function Documentation	112
3.107.2.1 CreateLocalVoice()	112
3.107.2.2 CreateLocalVoiceAudio< T >()	113
3.107.2.3 CreateLocalVoiceAudioFromSource()	113
3.107.2.4 CreateLocalVoiceFramed< T >()	114
3.107.2.5 LocalVoicesInChannel()	114
3.107.2.6 RemoteVoiceInfoDelegate()	115
3.107.2.7 RemoveLocalVoice()	115
3.107.2.8 Service()	115

3.107.3 Property Documentation	115
3.107.3.1 DebugLostPercent	115
3.107.3.2 FramesLost	116
3.107.3.3 FramesReceived	116
3.107.3.4 FramesSent	116
3.107.3.5 FramesSentBytes	116
3.107.3.6 LocalVoices	116
3.107.3.7 OnRemoteVoiceInfoAction	116
3.107.3.8 RemoteVoiceInfos	117
3.107.3.9 RoundTripTime	117
3.107.3.10 RoundTripTimeVariance	117
3.107.3.11 SuppressInfoDuplicateWarning	117
3.108 VoiceComponent Class Reference	117
3.109 VoiceConnection Class Reference	118
3.109.1 Detailed Description	119
3.109.2 Member Function Documentation	119
3.109.2.1 ConnectUsingSettings()	119
3.109.2.2 Dispatch()	120
3.109.2.3 InitRecorder()	120
3.109.3 Member Data Documentation	120
3.109.3.1 AutoCreateSpeakerIfNotFound	120
3.109.3.2 MinimalTimeScaleToDispatchInFixedUpdate	121
3.109.3.3 Settings	121
3.109.3.4 SpeakerFactory	121
3.109.4 Property Documentation	121
3.109.4.1 BestRegionSummaryInPreferences	121
3.109.4.2 ClientState	121
3.109.4.3 FramesLostPercent	122
3.109.4.4 FramesLostPerSecond	122
3.109.4.5 FramesReceivedPerSecond	122
3.109.4.6 Logger	122
3.109.4.7 LogLevel	122
3.109.4.8 PrimaryRecorder	122
3.109.4.9 SpeakerPrefab	123
3.109.4.10 VoiceClient	123
3.109.5 Event Documentation	123
3.109.5.1 RemoteVoiceAdded	123
3.109.5.2 SpeakerLinked	123
3.110 AudioUtil.VoiceDetector< T > Class Template Reference	123
3.110.1 Detailed Description	124
3.110.2 Member Function Documentation	124
3.110.2.1 Process()	124

3.110.3 Property Documentation	125
3.110.3.1 ActivityDelayMs	125
3.110.3.2 Detected	125
3.110.3.3 DetectedTime	125
3.110.3.4 On	125
3.110.3.5 Threshold	125
3.110.4 Event Documentation	126
3.110.4.1 OnDetected	126
3.111 AudioUtil.VoiceDetectorCalibration< T > Class Template Reference	126
3.111.1 Detailed Description	126
3.111.2 Constructor & Destructor Documentation	126
3.111.2.1 VoiceDetectorCalibration()	126
3.111.3 Member Function Documentation	127
3.111.3.1 Calibrate()	127
3.111.3.2 Process()	127
3.112 AudioUtil.VoiceDetectorDummy Class Reference	127
3.112.1 Detailed Description	128
3.113 AudioUtil.VoiceDetectorFloat Class Reference	128
3.113.1 Detailed Description	128
3.113.2 Constructor & Destructor Documentation	128
3.113.2.1 VoiceDetectorFloat()	128
3.114 AudioUtil.VoiceDetectorShort Class Reference	129
3.114.1 Detailed Description	129
3.114.2 Constructor & Destructor Documentation	129
3.114.2.1 VoiceDetectorShort()	129
3.115 VoiceEvent Class Reference	130
3.115.1 Member Data Documentation	130
3.115.1.1 Code	130
3.116 VoiceInfo Struct Reference	130
3.116.1 Detailed Description	131
3.116.2 Member Function Documentation	131
3.116.2.1 CreateAudio()	131
3.116.2.2 CreateAudioOpus()	132
3.116.3 Property Documentation	132
3.116.3.1 Bitrate	132
3.116.3.2 Channels	132
3.116.3.3 FrameDurationSamples	133
3.116.3.4 FrameDurationUs	133
3.116.3.5 FrameSize	133
3.116.3.6 Height	133
3.116.3.7 SamplingRate	133
3.116.3.8 UserData	133

3.116.3.9 Width	134
3.117 AudioUtil.VoiceLevelDetectCalibrate< T > Class Template Reference	134
3.117.1 Detailed Description	134
3.117.2 Constructor & Destructor Documentation	134
3.117.2.1 VoiceLevelDetectCalibrate()	134
3.117.3 Member Function Documentation	135
3.117.3.1 Calibrate()	135
3.117.3.2 Process()	135
3.117.4 Property Documentation	135
3.117.4.1 LevelMeter	136
3.117.4.2 VoiceDetector	136
3.118 VoiceLogger Class Reference	136
3.119 WebRtcAudioDsp Class Reference	136
3.119.1 Member Function Documentation	137
3.119.1.1 SetOrSwitchAudioListener()	137
3.119.1.2 SetOrSwitchAudioOutCapture()	137
3.120 WebRTCAudioLib Class Reference	138
3.121 WebRTCAudioProcessor Class Reference	138
Index	141

Chapter 1

Main Page

Photon Voice 2 has three key classes:

- `Photon.Voice.Unity.VoiceConnection` (extends `Photon.Realtime.LoadBalancingClient`)
- `Photon.Voice.Unity.Recorder`
- `Photon.Voice.Unity.Speaker`

If you also use the integration with PUN 2, we added two components for ease-of-use and more convenience:

- `Photon.Voice.PUN.PhotonVoiceNetwork`
- `Photon.Voice.PUN.PhotonVoiceView`

Photon Voice 2 also comes with a WebRTC based DSP (`Photon.Voice.Unity.WebRtcAudioDsp` using `Photon.Voice.WebRTCAudioProcessor`).

Read more in the official documentation [here](#).

You can download Photon Voice 2 [here](#).

Chapter 2

Namespace Documentation

2.1 Photon Namespace Reference

2.2 Photon.Voice Namespace Reference

Classes

- class [AudioDesc](#)
- class [AudioInChangeNotifier](#)
- class [AudioInEnumerator](#)
Enumerates microphones available on device.
- class [AudioSyncBuffer](#)
- class [AudioUtil](#)
Collection of Audio Utility functions and classes.
- class [BufferReaderPushAdapter](#)
Simple [BufferReaderPushAdapterBase](#) implementation using a single buffer, using synchronous [LocalVoice.PushData](#)
- class [BufferReaderPushAdapterAsyncPool](#)
[BufferReaderPushAdapter](#) implementation using asynchronous [LocalVoice.PushDataAsync](#).
- class [BufferReaderPushAdapterAsyncPoolCopy](#)
[BufferReaderPushAdapter](#) implementation using asynchronous [LocalVoice.PushDataAsync](#) and data copy.
- class [BufferReaderPushAdapterAsyncPoolFloatToShort](#)
[BufferReaderPushAdapter](#) implementation using asynchronous [LocalVoice.PushDataAsync](#), converting float samples to short.
- class [BufferReaderPushAdapterAsyncPoolShortToFloat](#)
[BufferReaderPushAdapter](#) implementation using asynchronous [LocalVoice.PushDataAsync](#), converting short samples to float.
- class [BufferReaderPushAdapterBase](#)
Adapter base class to move data by reading from [IDataReader.Read](#) and pushing to [LocalVoice](#).
- class [FactoryPrimitiveArrayPool](#)
[PrimitiveArrayPool<T>](#) as wrapped in object factory interface.
- class [FactoryReusableArray](#)
Array factory returnig the same array instance as long as it requested with the same array length. If length changes, new array instance created.
- class [FrameOut](#)
- class [Framer](#)

- Utility class to re-frame audio packets.*
- interface [IAudioDesc](#)
 - Audio Source interface.*
- interface [IAudioOut](#)
- interface [IAudioPusher](#)
 - Audio Pusher interface.*
- interface [IAudioReader](#)
 - Audio Reader interface.*
- interface [IDataReader](#)
 - Interface for pulling data, in case this is more appropriate than pushing it.*
- interface [IDecoder](#)
 - Generic decoder interface.*
- interface [IDecoderQueuedOutputImageNative](#)
- interface [IEncoder](#)
 - Generic encoder interface.*
- interface [IEncoderDirect](#)
 - Interface for an encoder which consumes input data via explicit call.*
- interface [ILocalVoiceAudio](#)
 - Interface for an outgoing audio stream.*
- interface [ILogger](#)
- class [ImageBufferInfo](#)
- class [ImageBufferNative](#)
- class [ImageBufferNativeAlloc](#)
- class [ImageBufferNativeGCHandleSinglePlane](#)
- class [ImageBufferNativePool](#)
- struct [ImageInputBuf](#)
- struct [ImageOutputBuf](#)
- interface [IProcessor](#)
 - Audio Processor interface.*
- interface [IServiceable](#)
 - Interface for classes that want their [Service\(\)](#) function to be called regularly in the context of a [LocalVoice](#).*
- interface [IVoiceTransport](#)
- class [LoadBalancingFrontend](#)
- class [LoadBalancingTransport](#)
 - Extends [LoadBalancingClient](#) with audio streaming functionality.*
- class [LoadBalancingTransport2](#)
 - Variant of [LoadBalancingTransport](#). Aims to be non-alloc at the cost of breaking compatibility with older clients.*
- class [LocalVoice](#)
 - Represents outgoing data stream.*
- class [LocalVoiceAudio](#)
 - Outgoing audio stream.*
- class [LocalVoiceAudioDummy](#)
 - Dummy [LocalVoiceAudio](#)*
- class [LocalVoiceAudioFloat](#)
 - Specialization of [LocalVoiceAudio](#) for float audio*
- class [LocalVoiceAudioShort](#)
 - Specialization of [LocalVoiceAudio](#) for short audio*
- class [LocalVoiceFramed](#)
 - Typed re-framing [LocalVoice](#)*
- class [LocalVoiceFramedBase](#)
 - Typed re-framing [LocalVoice](#)*
- interface [ObjectFactory](#)

- Uniform interface to `ObjectPool<TType, TInfo>` and single reusable object.*
- class [ObjectPool](#)
 - Generic Pool to re-use objects of a certain type (`TType`) that optionally match a certain property or set of properties (`TInfo`).*
- class [OpusCodec](#)
- class **PhotonTransportProtocol**
- class [PrimitiveArrayPool](#)
 - Pool of Arrays with components of type `T`, with [ObjectPool](#) info being the array's size.*
- class [RawCodec](#)
- class **RemoteVoice**
- class [RemoteVoiceInfo](#)
 - Information about a remote voice (incoming stream).*
- struct [RemoteVoiceOptions](#)
 - Event Actions and other options for a remote voice (incoming stream).*
- class **SpacingProfile**
- class [UnsupportedCodecException](#)
 - Exception thrown if an unsupported codec is encountered.*
- class [UnsupportedSampleTypeException](#)
 - Exception thrown if an unsupported audio sample type is encountered.*
- class [VoiceClient](#)
 - [Voice](#) client interact with other clients on network via [IVoiceTransport](#).*
- class [VoiceEvent](#)
- struct [VoiceInfo](#)
 - Describes stream properties.*
- class [WebRTCAudioLib](#)
- class [WebRTCAudioProcessor](#)

Enumerations

- enum [AudioSampleType](#)
 - The type of samples used for audio processing.*
- enum **FrameFlags** : byte
- enum [Codec](#)
 - Enum for Media Codecs supported by PhotonVoice.*
- enum **ImageFormat**
- enum **Rotation**
- enum **Flip**

2.2.1 Enumeration Type Documentation

2.2.1.1 AudioSampleType

```
enum AudioSampleType [strong]
```

The type of samples used for audio processing.

2.2.1.2 Codec

```
enum Codec [strong]
```

Enum for Media Codecs supported by PhotonVoice.

Transmitted in [VoiceInfo](#). Do not change the values of this Enum!

Enumerator

AudioOpus	OPUS audio
-----------	------------

2.3 Photon.Voice.IOS Namespace Reference

Classes

- struct [AudioSessionParameters](#)
- class [AudioSessionParametersPresets](#)

Enumerations

- enum [AudioSessionCategory](#)
- enum [AudioSessionMode](#)
- enum [AudioSessionCategoryOption](#)

2.3.1 Enumeration Type Documentation

2.3.1.1 AudioSessionCategory

```
enum AudioSessionCategory [strong]
```

Enumerator

Ambient	Use this category for background sounds such as rain, car engine noise, etc. Mixes with other music. <code>API_AVAILABLE(ios(3.0), watchos(2.0), tvos(9.0))</code> <code>API_UNAVAILABLE(macos);</code>
SoloAmbient	Use this category for background sounds. Other music will stop playing. <code>API_AVAILABLE(ios(3.0), watchos(2.0), tvos(9.0))</code> <code>API_UNAVAILABLE(macos);</code>
Playback	Use this category for music tracks. <code>API_AVAILABLE(ios(3.0), watchos(2.0), tvos(9.0))</code> <code>API_UNAVAILABLE(macos);</code>
Record	Use this category when recording audio. <code>API_AVAILABLE(ios(3.0), watchos(2.0), tvos(9.0))</code> <code>API_UNAVAILABLE(macos);</code>
PlayAndRecord	Use this category when recording and playing back audio. <code>API_AVAILABLE(ios(3.0), watchos(2.0), tvos(9.0))</code> <code>API_UNAVAILABLE(macos);</code>
AudioProcessing	Use this category when using a hardware codec or signal processor while not playing or recording audio. <code>API_DEPRECATED("No longer supported", ios(3.0, 10.0))</code> <code>API_UNAVAILABLE(watchos, tvos)</code> <code>API_UNAVAILABLE(macos);</code>

Enumerator

MultiRoute	<p>Use this category to customize the usage of available audio accessories and built-in audio hardware. For example, this category provides an application with the ability to use an available USB output and headphone output simultaneously for separate, distinct streams of audio data. Use of this category by an application requires a more detailed knowledge of, and interaction with, the capabilities of the available audio routes. May be used for input, output, or both. Note that not all output types and output combinations are eligible for multi-route. Input is limited to the last-in input port. Eligible inputs consist of the following: AVAudioSessionPortUSBAudio, AVAudioSessionPortHeadsetMic, and AVAudioSessionPortBuiltInMic.</p> <p>Eligible outputs consist of the following: AVAudioSessionPortUSBAudio, AVAudioSessionPortLineOut, AVAudioSessionPortHeadphones, AVAudioSessionPortHDMI, and AVAudioSessionPortBuiltInSpeaker.</p> <p>Note that AVAudioSessionPortBuiltInSpeaker is only allowed to be used when there are no other outputs connected. API_AVAILABLE(ios(6.0), watchos(2.0), tvos(9.0)) API_UNAVAILABLE(macos);</p>
------------	---

2.3.1.2 AudioSessionCategoryOption

```
enum AudioSessionCategoryOption [strong]
```

Enumerator

MixWithOthers	<p>This allows an application to set whether or not other active audio apps will be interrupted or mixed with when your app's audio session goes active. The typical cases are: (1) AVAudioSessionCategoryPlayAndRecord or AVAudioSessionCategoryMultiRoute this will default to false, but can be set to true. This would allow other applications to play in the background while an app had both audio input and output enabled (2) AVAudioSessionCategoryPlayback this will default to false, but can be set to true. This would allow other applications to play in the background, but an app will still be able to play regardless of the setting of the ringer switch (3) Other categories this defaults to false and cannot be changed (that is, the mix with others setting of these categories cannot be overridden. An application must be prepared for setting this property to fail as behaviour may change in future releases. If an application changes their category, they should reassert the option (it is not sticky across category changes). MixWithOthers is only valid with AVAudioSessionCategoryPlayAndRecord, AVAudioSessionCategoryPlayback, and AVAudioSessionCategoryMultiRoute</p>
DuckOthers	<p>This allows an application to set whether or not other active audio apps will be ducked when when your app's audio session goes active. An example of this is the Nike app, which provides periodic updates to its user (it reduces the volume of any music currently being played while it provides its status). This defaults to off. Note that the other audio will be ducked for as long as the current session is active. You will need to deactivate your audio session when you want full volume playback of the other audio. If your category is AVAudioSessionCategoryPlayback, AVAudioSessionCategoryPlayAndRecord, or AVAudioSessionCategoryMultiRoute, by default the audio session will be non-mixable and non-ducking. Setting this option will also make your category mixable with others (AVAudioSessionCategoryOptionMixWithOthers will be set). DuckOthers is only valid with AVAudioSessionCategoryAmbient, AVAudioSessionCategoryPlayAndRecord, AVAudioSessionCategoryPlayback, and AVAudioSessionCategoryMultiRoute</p>

Enumerator

AllowBluetooth	<p>This allows an application to change the default behaviour of some audio session categories with regards to showing bluetooth Hands-Free Profile (HFP) devices as available routes. The current category behavior is: (1) AVAudioSessionCategoryPlayAndRecord this will default to false, but can be set to true. This will allow a paired bluetooth HFP device to show up as an available route for input, while playing through the category-appropriate output (2) AVAudioSessionCategoryRecord this will default to false, but can be set to true. This will allow a paired bluetooth HFP device to show up as an available route for input (3) Other categories this defaults to false and cannot be changed (that is, enabling bluetooth for input in these categories is not allowed) An application must be prepared for setting this option to fail as behaviour may change in future releases. If an application changes their category or mode, they should reassert the override (it is not sticky across category and mode changes). AllowBluetooth is only valid with AVAudioSessionCategoryRecord and AVAudioSessionCategoryPlayAndRecord</p>
DefaultToSpeaker	<p>This allows an application to change the default behaviour of some audio session categories with regards to the audio route. The current category behavior is: (1) AVAudioSessionCategoryPlayAndRecord category this will default to false, but can be set to true. this will route to Speaker (instead of Receiver) when no other audio route is connected. (2) Other categories this defaults to false and cannot be changed (that is, the default to speaker setting of these categories cannot be overridden An application must be prepared for setting this property to fail as behaviour may change in future releases. If an application changes their category, they should reassert the override (it is not sticky across category and mode changes). DefaultToSpeaker is only valid with AVAudioSessionCategoryPlayAndRecord</p>

2.3.1.3 AudioSessionMode

```
enum AudioSessionMode [strong]
```

Enumerator

Default	Modes modify the audio category in order to introduce behavior that is tailored to the specific use of audio within an application. Available in iOS 5.0 and greater. The default mode API_AVAILABLE(ios(5.0), watchos(2.0), tvos(9.0)) API_UNAVAILABLE(macos);
VoiceChat	Only valid with AVAudioSessionCategoryPlayAndRecord. Appropriate for Voice over IP (VoIP) applications. Reduces the number of allowable audio routes to be only those that are appropriate for VoIP applications and may engage appropriate system-supplied signal processing. Has the side effect of setting AVAudioSessionCategoryOptionAllowBluetooth API_AVAILABLE(ios(5.0), watchos(2.0), tvos(9.0)) API_UNAVAILABLE(macos);
VideoRecording	Only valid with AVAudioSessionCategoryPlayAndRecord or AVAudioSessionCategoryRecord. Modifies the audio routing options and may engage appropriate system-supplied signal processing. API_AVAILABLE(ios(5.0), watchos(2.0), tvos(9.0)) API_UNAVAILABLE(macos);
Measurement	Appropriate for applications that wish to minimize the effect of system-supplied signal processing for input and/or output audio signals. API_AVAILABLE(ios(5.0), watchos(2.0), tvos(9.0)) API_UNAVAILABLE(macos);
MoviePlayback	Engages appropriate output signal processing for movie playback scenarios. Currently only applied during playback over built-in speaker. API_AVAILABLE(ios(6.0), watchos(2.0), tvos(9.0)) API_UNAVAILABLE(macos);

Enumerator

VideoChat	Only valid with <code>kAudioSessionCategory_PlayAndRecord</code> . Reduces the number of allowable audio routes to be only those that are appropriate for video chat applications. May engage appropriate system-supplied signal processing. Has the side effect of setting <code>AVAudioSessionCategoryOptionAllowBluetooth</code> and <code>AVAudioSessionCategoryOptionDefaultToSpeaker</code> . <code>API_AVAILABLE(ios(7.0), watchos(2.0), tvos(9.0)) API_UNAVAILABLE(macos);</code>
-----------	---

2.4 Photon.Voice.PUN Namespace Reference

Classes

- class [PhotonVoiceNetwork](#)

This class can be used to automatically sync client states between [PUN](#) and [Voice](#). It also sets a custom [PUN Speaker](#) factory to find the [Speaker](#) component for a character's voice. For this to work attach a [PhotonVoiceView](#) next to the [PhotonView](#) of your player's prefab.

- class [PhotonVoiceView](#)

Component that should be attached to a networked [PUN](#) prefab that has [PhotonView](#). It will bind remote [Recorder](#) with local [Speaker](#) of the same networked prefab. This component makes automatic voice stream routing easy for players' characters/avatars.

2.5 Photon.Voice.Unity Namespace Reference

Classes

- class [AudioClipWrapper](#)
- class [AudioOutCapture](#)
- interface [ILoggable](#)
- interface [ILoggableDependent](#)
- class [IOSAudioForceToSpeaker](#)
- class [Logger](#)
- class [MicWrapper](#)
- class [MicWrapperPusher](#)
- class [NativeAndroidMicrophoneSettings](#)
- class [PhotonVoiceCreatedParams](#)
- class [Recorder](#)

Component representing outgoing audio stream in scene.

- class [RemoteVoiceLink](#)
- class [Speaker](#)

Component representing remote audio stream in local scene.

- class [UnityAndroidAudioInAEC](#)
- class [UnityAudioOut](#)
- class [UnityMicrophone](#)

A wrapper around [UnityEngine.Microphone](#) to be able to safely use [Microphone](#) and compile for WebGL.

- class [VoiceComponent](#)
- class [VoiceConnection](#)

Component that represents a client voice connection to [Photon](#) Servers.

- class [VoiceLogger](#)
- class [WebRtcAudioDsp](#)

2.6 Photon.Voice.Unity.UtilityScripts Namespace Reference

Classes

- class [ConnectAndJoin](#)
- class [MicAmplifier](#)
- class [MicAmplifierFloat](#)
- class [MicAmplifierShort](#)
- class [PhotonVoiceLagSimulationGui](#)
- class [PhotonVoiceStatsGui](#)

Basic GUI to show traffic and health statistics of the connection to [Photon](#), toggled by shift+tab.

- class [TestTone](#)
- class [ToneAudioReader](#)

2.7 POpusCodec Namespace Reference

Classes

- class [OpusDecoder](#)
- class [OpusEncoder](#)
- class [OpusException](#)
- class [OpusLib](#)
- class [Wrapper](#)

2.8 POpusCodec.Enums Namespace Reference

Enumerations

- enum [Bandwidth](#) : int
- enum [Channels](#) : int
- enum **Complexity** : int
- enum [Delay](#)

Using a duration of less than 10 ms will prevent the encoder from using the LPC or hybrid modes.

- enum **ForceChannels** : int
- enum [OpusApplicationType](#) : int
- enum **OpusStatusCode** : int
- enum **SamplingRate** : int
- enum [SignalHint](#) : int

2.8.1 Enumeration Type Documentation

2.8.1.1 Bandwidth

```
enum Bandwidth : int [strong]
```

Enumerator

Narrowband	Up to 4Khz
Mediumband	Up to 6Khz
Wideband	Up to 8Khz
SuperWideband	Up to 12Khz
Fullband	Up to 20Khz (High Definition)

2.8.1.2 Channels

```
enum Channels : int [strong]
```

Enumerator

Mono	1 Channel
Stereo	2 Channels

2.8.1.3 Delay

```
enum Delay [strong]
```

Using a duration of less than 10 ms will prevent the encoder from using the LPC or hybrid modes.

Enumerator

Delay2dot5ms	2.5ms
Delay5ms	5ms
Delay10ms	10ms
Delay20ms	20ms
Delay40ms	40ms
Delay60ms	60ms

2.8.1.4 OpusApplicationType

```
enum OpusApplicationType : int [strong]
```

Enumerator

Voip	Gives best quality at a given bitrate for voice signals. It enhances the input signal by high-pass filtering and emphasizing formants and harmonics. Optionally it includes in-band forward error correction to protect against packet loss. Use this mode for typical VoIP applications. Because of the enhancement, even at high bitrates the output may sound different from the input.
Audio	Gives best quality at a given bitrate for most non-voice signals like music. Use this mode for music and mixed (music/voice) content, broadcast, and applications requiring less than 15 ms of coding delay.
RestrictedLowDelay	Configures low-delay mode that disables the speech-optimized mode in exchange for slightly reduced delay.

2.8.1.5 SignalHint

```
enum SignalHint : int [strong]
```

Enumerator

Auto	(default)
Voice	Bias thresholds towards choosing LPC or Hybrid modes
Music	Bias thresholds towards choosing MDCT modes.

Chapter 3

Class Documentation

3.1 AudioClipWrapper Class Reference

Inherits [IAudioReader< float >](#).

Public Member Functions

- **AudioClipWrapper** (AudioClip audioClip)
- bool **Read** (float[] buffer)
- void **Dispose** ()

Properties

- bool **Loop** [get, set]
- int **SamplingRate** [get]
- int **Channels** [get]
- string **Error** [get]

3.2 AudioDesc Class Reference

Inherits [IAudioDesc](#).

Public Member Functions

- **AudioDesc** (int samplingRate, int channels, string error)
- void **Dispose** ()

Properties

- int **SamplingRate** [get]
- int **Channels** [get]
- string **Error** [get]

3.3 **AudiInChangeNotifier** Class Reference

Inherits IDisposable.

Public Member Functions

- **AudiInChangeNotifier** (Action callback, [ILogger](#) logger)
- void **Dispose** ()

Public Attributes

- readonly bool **IsSupported** = false

Properties

- string **Error** [get]

3.4 **AudiInEnumerator** Class Reference

Enumerates microphones available on device.

Inherits IDisposable.

Public Member Functions

- **AudiInEnumerator** ([ILogger](#) logger)
- void **Refresh** ()
- string **NameAtIndex** (int i)
- int **IDAtIndex** (int i)
- bool **IDIsValid** (int id)
- void **Dispose** ()

Public Attributes

- readonly bool **IsSupported** = false

Properties

- string **Error** [get]
- int **Count** [get]

3.4.1 Detailed Description

Enumerates microphones available on device.

3.5 AudioOutCapture Class Reference

Inherits MonoBehaviour.

Events

- Action< float[], int > **OnAudioFrame**

3.6 AudioSessionParameters Struct Reference

Public Member Functions

- int **CategoryOptionsToInt** ()
- override string **ToString** ()

Public Attributes

- [AudioSessionCategory](#) **Category**
- [AudioSessionMode](#) **Mode**
- [AudioSessionCategoryOption](#)[] **CategoryOptions**

3.7 AudioSessionParametersPresets Class Reference

Static Public Attributes

- static [AudioSessionParameters](#) **Game**
- static [AudioSessionParameters](#) **VoIP**

3.7.1 Member Data Documentation

3.7.1.1 Game

```
AudioSessionParameters Game [static]
```

Initial value:

```
= new AudioSessionParameters()  
{  
    Category = AudioSessionCategory.PlayAndRecord,  
    Mode = AudioSessionMode.Default,  
    CategoryOptions = new AudioSessionCategoryOption[] {  
        AudioSessionCategoryOption.DefaultToSpeaker, AudioSessionCategoryOption.AllowBluetooth }  
}
```

3.7.1.2 VoIP

```
AudioSessionParameters VoIP [static]
```

Initial value:

```
= new AudioSessionParameters()  
{  
    Category = AudioSessionCategory.PlayAndRecord,  
    Mode = AudioSessionMode.VoiceChat,  
  
    CategoryOptions = new AudioSessionCategoryOption[] { AudioSessionCategoryOption.AllowBluetooth }  
}
```

3.8 AudioSyncBuffer< T > Class Template Reference

Inherits [IAudioOut< T >](#).

Public Member Functions

- **AudioSyncBuffer** ([ILogger](#) logger, string logPrefix, bool debugInfo)
- void **Start** (int sampleRate, int channels, int frameSamples, int playDelayMs)
- void **Service** ()
- void **Read** (T[] outBuf, int outChannels, int outSampleRate)
- void **Push** (T[] frame)
- void **Flush** ()
- void **Stop** ()

Static Public Attributes

- const int **FRAME_POOL_CAPACITY** = 50

Properties

- int **Lag** [get]
- bool **IsPlaying** [get]

3.9 AudioUtil Class Reference

Collection of Audio Utility functions and classes.

Classes

- interface [ILevelMeter](#)
Audio Level Metering interface.
- interface [IVoiceDetector](#)
Voice Activity Detector interface.
- class [LevelMeter](#)
Audio Level Meter.
- class [LevelMeterDummy](#)
Dummy Audio Level Meter that doesn't actually do anything.
- class [LevelMeterFloat](#)
LevelMeter specialization for float audio.
- class [LevelMeterShort](#)
LevelMeter specialization for short audio.
- class [Resampler](#)
Sample-rate conversion Audio Processor.
- class [ToneAudioPusher](#)
IAudioPusher that provides a constant tone signal.
- class [ToneAudioReader](#)
IAudioReader that provides a constant tone signal.
- class [VoiceDetector](#)
Simple voice activity detector triggered by signal level.
- class [VoiceDetectorCalibration](#)
Calibration Utility for Voice Detector
- class [VoiceDetectorDummy](#)
Dummy VoiceDetector that doesn't actually do anything.
- class [VoiceDetectorFloat](#)
VoiceDetector specialization for float audio.
- class [VoiceDetectorShort](#)
VoiceDetector specialization for float audio.
- class [VoiceLevelDetectCalibrate](#)
Utility Audio Processor Voice Detection Calibration.

Static Public Member Functions

- static void [Resample](#)< T > (T[] src, T[] dst, int dstCount, int channels)
Resample audio data so that the complete src buffer fits into dstCount samples in the dst buffer.
- static void **Resample**< T > (T[] src, int srcOffset, int srcCount, T[] dst, int dstOffset, int dstCount, int channels)
- static void **Resample**< T > (T[] src, int srcOffset, int srcCount, int srcChannels, T[] dst, int dstOffset, int dstCount, int dstChannels)
- static void [ResampleAndConvert](#) (short[] src, float[] dst, int dstCount, int channels)
Resample audio data so that the complete src buffer fits into dstCount samples in the dst buffer, and convert short to float samples along the way.
- static void [ResampleAndConvert](#) (float[] src, short[] dst, int dstCount, int channels)
Resample audio data so that the complete src buffer fits into dstCount samples in the dst buffer, and convert float to short samples along the way.
- static void [Convert](#) (float[] src, short[] dst, int dstCount)
Convert audio buffer from float to short samples.
- static void [Convert](#) (short[] src, float[] dst, int dstCount)
Convert audio buffer from short to float samples.
- static void [ForceToStereo](#)< T > (T[] src, T[] dst, int srcChannels)
Convert audio buffer with arbitrary number of channels to stereo.

3.9.1 Detailed Description

Collection of Audio Utility functions and classes.

3.9.2 Member Function Documentation

3.9.2.1 Convert() [1/2]

```
static void Convert (
    float[] src,
    short[] dst,
    int dstCount ) [static]
```

Convert audio buffer from float to short samples.

Parameters

<i>src</i>	Source buffer.
<i>dst</i>	Destination buffer.
<i>dstCount</i>	Size of destination buffer (in total samples), source buffer must be of same length or longer.

3.9.2.2 Convert() [2/2]

```
static void Convert (
    short[] src,
    float[] dst,
    int dstCount ) [static]
```

Convert audio buffer from short to float samples.

Parameters

<i>src</i>	Source buffer.
<i>dst</i>	Destination buffer.
<i>dstCount</i>	Size of destination buffer (in total samples), source buffer must be of same length or longer.

3.9.2.3 ForceToStereo< T >()

```
static void ForceToStereo< T > (
    T[] src,
```

```
T[] dst,
int srcChannels ) [static]
```

Convert audio buffer with arbitrary number of channels to stereo.

For mono sources (`srcChannels==1`), the signal will be copied to both Left and Right stereo channels. For all others, the first two available channels will be used, any other channels will be discarded.

Parameters

<i>src</i>	Source buffer.
<i>dst</i>	Destination buffer.
<i>srcChannels</i>	Number of (interleaved) channels in src.

3.9.2.4 Resample< T >()

```
static void Resample< T > (
    T[] src,
    T[] dst,
    int dstCount,
    int channels ) [static]
```

Resample audio data so that the complete src buffer fits into dstCount samples in the dst buffer.

This implements a primitive nearest-neighbor resampling algorithm for an arbitrary number of channels.

Parameters

<i>src</i>	Source buffer.
<i>dst</i>	Destination buffer.
<i>dstCount</i>	Target size of destination buffer (in samples per channel).
<i>channels</i>	Number of channels in the signal (1=mono, 2=stereo). Must be > 0.

3.9.2.5 ResampleAndConvert() [1/2]

```
static void ResampleAndConvert (
    float[] src,
    short[] dst,
    int dstCount,
    int channels ) [static]
```

Resample audio data so that the complete src buffer fits into dstCount samples in the dst buffer, and convert float to short samples along the way.

This implements a primitive nearest-neighbor resampling algorithm for an arbitrary number of channels.

Parameters

<i>src</i>	Source buffer.
<i>dst</i>	Destination buffer.
<i>dstCount</i>	Target size of destination buffer (in samples per channel).
<i>channels</i>	Number of channels in the signal (1=mono, 2=stereo). Must be > 0.

3.9.2.6 ResampleAndConvert() [2/2]

```
static void ResampleAndConvert (
    short[] src,
    float[] dst,
    int dstCount,
    int channels ) [static]
```

Resample audio data so that the complete src buffer fits into dstCount samples in the dst buffer, and convert short to float samples along the way.

This implements a primitive nearest-neighbor resampling algorithm for an arbitrary number of channels.

Parameters

<i>src</i>	Source buffer.
<i>dst</i>	Destination buffer.
<i>dstCount</i>	Target size of destination buffer (in samples per channel).
<i>channels</i>	Number of channels in the signal (1=mono, 2=stereo). Must be > 0.

3.10 BufferReaderPushAdapter< T > Class Template Reference

Simple [BufferReaderPushAdapterBase](#) implementation using a single buffer, using synchronous [LocalVoice.PushData](#)

Inherits [BufferReaderPushAdapterBase< T >](#).

Public Member Functions

- [BufferReaderPushAdapter](#) ([LocalVoice](#) localVoice, [IDataReader< T >](#) reader)
Create a new [BufferReaderPushAdapter](#) instance
- override void [Service](#) ([LocalVoice](#) localVoice)
Do the actual data read/push.

Protected Attributes

- [T\[\]](#) **buffer**

3.10.1 Detailed Description

Simple `BufferedReaderPushAdapterBase` implementation using a single buffer, using synchronous `LocalVoice.PushData`

3.10.2 Constructor & Destructor Documentation

3.10.2.1 `BufferedReaderPushAdapter()`

```
BufferedReaderPushAdapter (
    LocalVoice localVoice,
    IDataReader< T > reader )
```

Create a new `BufferedReaderPushAdapter` instance

Parameters

<i>localVoice</i>	<code>LocalVoice</code> instance to push data to.
<i>reader</i>	<code>IDataReader</code> to read from.

3.10.3 Member Function Documentation

3.10.3.1 `Service()`

```
override void Service (
    LocalVoice localVoice ) [virtual]
```

Do the actual data read/push.

Parameters

<i>localVoice</i>	<code>LocalVoice</code> instance to push data to.
-------------------	---

Implements `BufferedReaderPushAdapterBase< T >`.

3.11 `BufferedReaderPushAdapterAsyncPool< T >` Class Template Reference

`BufferedReaderPushAdapter` implementation using asynchronous `LocalVoice.PushDataAsync`.

Inherits `BufferedReaderPushAdapterBase< T >`.

Public Member Functions

- [BufferReaderPushAdapterAsyncPool](#) ([LocalVoice](#) localVoice, [IDataReader](#)< T > reader)
Create a new [BufferReaderPushAdapter](#) instance
- override void [Service](#) ([LocalVoice](#) localVoice)
Do the actual data read/push.

Additional Inherited Members

3.11.1 Detailed Description

[BufferReaderPushAdapter](#) implementation using asynchronous [LocalVoice.PushDataAsync](#).

Acquires a buffer from pool before each Read, releases buffer after last Read (brings Acquire/Release overhead).

Expects localVoice to be a [LocalVoiceFramed](#)<T> of same T.

3.11.2 Constructor & Destructor Documentation

3.11.2.1 [BufferReaderPushAdapterAsyncPool](#)()

```
BufferReaderPushAdapterAsyncPool (
    LocalVoice localVoice,
    IDataReader< T > reader )
```

Create a new [BufferReaderPushAdapter](#) instance

Parameters

<i>localVoice</i>	LocalVoice instance to push data to.
<i>reader</i>	DataReader to read from.

3.11.3 Member Function Documentation

3.11.3.1 [Service](#)()

```
override void Service (
    LocalVoice localVoice ) [virtual]
```

Do the actual data read/push.

Parameters

<i>localVoice</i>	LocalVoice instance to push data to. Must be a LocalVoiceFramed<T> of same T.
-------------------	---

Implements [BufferReaderPushAdapterBase< T >](#).

3.12 BufferReaderPushAdapterAsyncPoolCopy< T > Class Template Reference

[BufferReaderPushAdapter](#) implementation using asynchronous [LocalVoice.PushDataAsync](#) and data copy.

Inherits [BufferReaderPushAdapterBase< T >](#).

Public Member Functions

- [BufferReaderPushAdapterAsyncPoolCopy](#) ([LocalVoice](#) localVoice, [IDataReader< T >](#) reader)
Create a new [BufferReaderPushAdapter](#) instance
- override void [Service](#) ([LocalVoice](#) localVoice)
Do the actual data read/push.

Protected Attributes

- `T[] buffer`

3.12.1 Detailed Description

[BufferReaderPushAdapter](#) implementation using asynchronous [LocalVoice.PushDataAsync](#) and data copy.

Reads data to preallocated buffer, copies it to buffer from pool before pushing. Compared with [, this avoids one pool Acquire/Release](#)

3.12.2 Constructor & Destructor Documentation

3.12.2.1 BufferReaderPushAdapterAsyncPoolCopy()

```
BufferReaderPushAdapterAsyncPoolCopy (
    LocalVoice localVoice,
    IDataReader< T > reader )
```

Create a new [BufferReaderPushAdapter](#) instance

Parameters

<i>localVoice</i>	LocalVoice instance to push data to.
<i>reader</i>	DataReader to read from.

3.12.3 Member Function Documentation

3.12.3.1 Service()

```
override void Service (
    LocalVoice localVoice ) [virtual]
```

Do the actual data read/push.

Parameters

<i>localVoice</i>	LocalVoice instance to push data to. Must be a LocalVoiceFramed<T> of same T.
-------------------	---

Implements [BufferReaderPushAdapterBase< T >](#).

3.13 BufferReaderPushAdapterAsyncPoolFloatToShort Class Reference

[BufferReaderPushAdapter](#) implementation using asynchronous [LocalVoice.PushDataAsync](#), converting float samples to short.

Inherits [BufferReaderPushAdapterBase< float >](#).

Public Member Functions

- [BufferReaderPushAdapterAsyncPoolFloatToShort](#) ([LocalVoice](#) localVoice, [IDataReader](#)< float > reader)
Create a new [BufferReaderPushAdapter](#) instance
- override void [Service](#) ([LocalVoice](#) localVoice)
Do the actual data read/push.

Additional Inherited Members

3.13.1 Detailed Description

[BufferReaderPushAdapter](#) implementation using asynchronous [LocalVoice.PushDataAsync](#), converting float samples to short.

This adapter works exactly like [BufferReaderPushAdapterAsyncPool](#), but it converts float samples to short. Acquires a buffer from pool before each Read, releases buffer after last Read.

Expects localVoice to be a [LocalVoiceFramed<T>](#) of same T.

3.13.2 Constructor & Destructor Documentation

3.13.2.1 BufferReaderPushAdapterAsyncPoolFloatToShort()

```
BufferReaderPushAdapterAsyncPoolFloatToShort (
    LocalVoice localVoice,
    IDataReader< float > reader )
```

Create a new [BufferReaderPushAdapter](#) instance

Parameters

<i>localVoice</i>	LocalVoice instance to push data to.
<i>reader</i>	IDataReader to read from.

3.13.3 Member Function Documentation

3.13.3.1 Service()

```
override void Service (
    LocalVoice localVoice ) [virtual]
```

Do the actual data read/push.

Parameters

<i>localVoice</i>	LocalVoice instance to push data to. Must be a LocalVoiceFramed<T> of same T.
-------------------	---

Implements [BufferReaderPushAdapterBase< float >](#).

3.14 BufferReaderPushAdapterAsyncPoolShortToFloat Class Reference

[BufferReaderPushAdapter](#) implementation using asynchronous [LocalVoice.PushDataAsync](#), converting short samples to float.

Inherits [BufferReaderPushAdapterBase< short >](#).

Public Member Functions

- [BufferReaderPushAdapterAsyncPoolShortToFloat](#) ([LocalVoice](#) localVoice, [IDataReader< short >](#) reader)
Create a new [BufferReaderPushAdapter](#) instance
- override void [Service](#) ([LocalVoice](#) localVoice)
Do the actual data read/push.

Additional Inherited Members

3.14.1 Detailed Description

[BufferReaderPushAdapter](#) implementation using asynchronous [LocalVoice.PushDataAsync](#), converting short samples to float.

This adapter works exactly like [BufferReaderPushAdapterAsyncPool](#), but it converts short samples to float. Acquires a buffer from pool before each Read, releases buffer after last Read.

Expects localVoice to be a [LocalVoiceFramed<T>](#) of same T.

3.14.2 Constructor & Destructor Documentation

3.14.2.1 [BufferReaderPushAdapterAsyncPoolShortToFloat\(\)](#)

```
BufferReaderPushAdapterAsyncPoolShortToFloat (
    LocalVoice localVoice,
    IDataReader< short > reader )
```

Create a new [BufferReaderPushAdapter](#) instance

Parameters

<i>localVoice</i>	LocalVoice instance to push data to.
<i>reader</i>	DataReader to read from.

3.14.3 Member Function Documentation

3.14.3.1 [Service\(\)](#)

```
override void Service (
    LocalVoice localVoice ) [virtual]
```

Do the actual data read/push.

Parameters

<i>localVoice</i>	LocalVoice instance to push data to. Must be a LocalVoiceFramed<T> of same T.
-------------------	---

Implements [BufferReaderPushAdapterBase< short >](#).

3.15 `BufferedReaderPushAdapterBase< T >` Class Template Reference

Adapter base class to move data by reading from `IDataReader.Read` and pushing to `LocalVoice`.

Inherits `IServiceable`.

Inherited by `BufferedReaderPushAdapter< T >`, `BufferedReaderPushAdapterAsyncPool< T >`, and `BufferedReaderPushAdapterAsyncPool`.

Public Member Functions

- abstract void `Service` (`LocalVoice` localVoice)
Do the actual data read/push.
- `BufferedReaderPushAdapterBase` (`IDataReader< T >` reader)
Create a new `BufferedReaderPushAdapterBase` instance
- void `Dispose` ()
Release resources associated with this instance.

Protected Attributes

- `IDataReader< T >` `reader`

3.15.1 Detailed Description

Adapter base class to move data by reading from `IDataReader.Read` and pushing to `LocalVoice`.

Use this with a `LocalVoice` of same T type.

3.15.2 Constructor & Destructor Documentation

3.15.2.1 `BufferedReaderPushAdapterBase()`

```
BufferedReaderPushAdapterBase (
    IDataReader< T > reader )
```

Create a new `BufferedReaderPushAdapterBase` instance

Parameters

<code>reader</code>	DataReader to read from.
---------------------	--------------------------

3.15.3 Member Function Documentation

3.15.3.1 Dispose()

```
void Dispose ( )
```

Release resources associated with this instance.

3.15.3.2 Service()

```
abstract void Service (
    LocalVoice localVoice ) [pure virtual]
```

Do the actual data read/push.

Parameters

<i>localVoice</i>	LocalVoice instance to push data to.
-------------------	--

Implements [IServiceable](#).

Implemented in [BufferedReaderPushAdapterAsyncPoolShortToFloat](#), [BufferedReaderPushAdapterAsyncPoolFloatToShort](#), [BufferedReaderPushAdapterAsyncPoolCopy< T >](#), [BufferedReaderPushAdapterAsyncPool< T >](#), and [BufferedReaderPushAdapter< T >](#).

3.16 ConnectAndJoin Class Reference

Inherits [MonoBehaviour](#), [IConnectionCallbacks](#), and [IMatchmakingCallbacks](#).

Public Member Functions

- void **ConnectNow** ()
- void **OnCreatedRoom** ()
- void **OnCreateRoomFailed** (short returnCode, string message)
- void **OnFriendListUpdate** (List< FriendInfo > friendList)
- void **OnJoinedRoom** ()
- void **OnJoinRandomFailed** (short returnCode, string message)
- void **OnJoinRoomFailed** (short returnCode, string message)
- void **OnLeftRoom** ()
- void **OnConnected** ()
- void **OnConnectedToMaster** ()
- void **OnDisconnected** (DisconnectCause cause)
- void **OnRegionListReceived** (RegionHandler regionHandler)
- void **OnCustomAuthenticationResponse** (Dictionary< string, object > data)
- void **OnCustomAuthenticationFailed** (string debugMessage)

Public Attributes

- bool **RandomRoom** = true
- string **RoomName**

Properties

- bool **IsConnected** [get]

3.17 RawCodec.Decoder< T > Class Template Reference

Inherits [IDecoder](#).

Public Member Functions

- **Decoder** (Action< [FrameOut](#)< T >> output)
- void **Open** ([VoiceInfo](#) info)
Open (initialize) the decoder.
- void **Input** (byte[] buf, FrameFlags flags)
Consumes the given encoded data.
- void **Dispose** ()

Properties

- string **Error** [get]

3.17.1 Member Function Documentation

3.17.1.1 Input()

```
void Input (
    byte[] buf,
    FrameFlags flags )
```

Consumes the given encoded data.

Implements [IDecoder](#).

3.17.1.2 Open()

```
void Open (
    VoiceInfo info )
```

Open (initialize) the decoder.

Parameters

<i>info</i>	Properties of the data stream to decode.
-------------	--

Implements [IDecoder](#).

3.18 OpusCodec.Decoder< T > Class Template Reference

Inherits [IDecoder](#).

Public Member Functions

- **Decoder** (Action< [FrameOut](#)< T >> output, [ILogger](#) logger)
- void **Open** ([VoiceInfo](#) i)
Open (initialize) the decoder.
- void **Dispose** ()
- void **Input** (byte[] buf, FrameFlags flags)
Consumes the given encoded data.

Protected Attributes

- [OpusDecoder](#)< T > **decoder**

Properties

- string **Error** [get]
- [VoiceInfo](#) **Info** [get]

3.18.1 Member Function Documentation

3.18.1.1 Input()

```
void Input (
    byte[] buf,
    FrameFlags flags )
```

Consumes the given encoded data.

Implements [IDecoder](#).

3.18.1.2 Open()

```
void Open (
    VoiceInfo info )
```

Open (initialize) the decoder.

Parameters

<i>info</i>	Properties of the data stream to decode.
-------------	--

Implements [IDecoder](#).

3.19 OpusCodec.DecoderFactory Class Reference

Static Public Member Functions

- static [IEncoder](#) **Create**< T > ([VoiceInfo](#) i, [ILogger](#) logger)

3.20 OpusCodec.Encoder< T > Class Template Reference

Inherits [IEncoderDirect< T\[\]>](#).

Public Member Functions

- void **Input** (T[] buf)
- void **EndOfStream** ()
- [ArraySegment< byte >](#) **DequeueOutput** (out [FrameFlags](#) flags)
- void **Dispose** ()

Protected Member Functions

- **Encoder** ([VoiceInfo](#) i, [ILogger](#) logger)
- abstract [ArraySegment< byte >](#) **encodeTyped** (T[] buf)

Protected Attributes

- [OpusEncoder](#) **encoder**
- bool **disposed**

Properties

- string **Error** [get]
- [Action< ArraySegment< byte >, FrameFlags >](#) **Output** [get, set]
- [VoiceInfo](#) **Info** [get]

3.21 RawCodec.Encoder< T > Class Template Reference

Inherits [IEncoderDirect< T\[\]>](#).

Public Member Functions

- `ArraySegment< byte > DequeueOutput` (out `FrameFlags` flags)
- `void EndOfStream` ()
- `void Dispose` ()
- `void Input` (`T[]` buf)

Properties

- `string Error` [get]
- `Action< ArraySegment< byte >, FrameFlags > Output` [get, set]
- `VoicelInfo Info` [get]

3.22 OpusCodec.EncoderFloat Class Reference

Inherits [OpusCodec.Encoder< float >](#).

Protected Member Functions

- override `ArraySegment< byte > encodeTyped` (`float[]` buf)

Additional Inherited Members

3.23 OpusCodec.EncoderShort Class Reference

Inherits [OpusCodec.Encoder< short >](#).

Protected Member Functions

- override `ArraySegment< byte > encodeTyped` (`short[]` buf)

Additional Inherited Members

3.24 OpusCodec.Factory Class Reference

Static Public Member Functions

- static `IEncoder CreateEncoder< B >` (`VoicelInfo` i, `ILogger` logger)

3.25 FactoryPrimitiveArrayPool< T > Class Template Reference

`PrimitiveArrayPool<T>` as wrapped in object factory interface.

Inherits [ObjectFactory< T\[\], int >](#).

Public Member Functions

- **FactoryPrimitiveArrayPool** (int capacity, string name)
- **FactoryPrimitiveArrayPool** (int capacity, string name, int info)
- **T[] New** ()
- **T[] New** (int size)
- void **Free** (T[] obj)
- void **Free** (T[] obj, int info)
- void **Dispose** ()

Properties

- int **Info** [get]

3.25.1 Detailed Description

PrimitiveArrayPool<T> as wrapped in object factory interface.

Template Parameters

<i>T</i>	Array element type.
----------	---------------------

3.26 FactoryReusableArray< T > Class Template Reference

Array factory returnig the same array instance as long as it requested with the same array length. If length changes, new array instance created.

Inherits [ObjectFactory< T\[\], int >](#).

Public Member Functions

- **FactoryReusableArray** (int size)
- **T[] New** ()
- **T[] New** (int size)
- void **Free** (T[] obj)
- void **Free** (T[] obj, int info)
- void **Dispose** ()

Properties

- int **Info** [get]

3.26.1 Detailed Description

Array factory returnig the same array instance as long as it requested with the same array length. If length changes, new array instance created.

Template Parameters

<i>T</i>	Array element type.
----------	---------------------

3.27 FrameOut< T > Class Template Reference

Public Member Functions

- **FrameOut** (T[] buf, bool endOfStream)
- [FrameOut](#)< T > **Set** (T[] buf, bool endOfStream)

Properties

- T[] **Buf** [get]
- bool **EndOfStream** [get]

3.28 Framer< T > Class Template Reference

Utility class to re-frame audio packets.

Public Member Functions

- [Framer](#) (int frameSize)
Create new [Framer](#) instance.
- int [Count](#) (int bufLen)
Get the number of frames available after adding bufLen samples.
- IEnumerable< T[] > [Frame](#) (T[] buf)
Append arbitrary-sized buffer and return available full frames.

3.28.1 Detailed Description

Utility class to re-frame audio packets.

3.28.2 Constructor & Destructor Documentation

3.28.2.1 Framer()

```
Framer (
    int frameSize )
```

Create new [Framer](#) instance.

3.28.3 Member Function Documentation

3.28.3.1 Count()

```
int Count (
    int bufLen )
```

Get the number of frames available after adding bufLen samples.

Parameters

<i>bufLen</i>	Number of samples that would be added.
---------------	--

Returns

Number of full frames available when adding bufLen samples.

3.28.3.2 Frame()

```
IEnumerable<T[]> Frame (
    T[] buf )
```

Append arbitrary-sized buffer and return available full frames.

Parameters

<i>buf</i>	Array of samples to add.
------------	--------------------------

Returns

Enumerator of full frames (might be none).

3.29 IAudioDesc Interface Reference

Audio Source interface.

Inherits IDisposable.

Inherited by [AudioDesc](#), [IAudioPusher< T >](#), and [IAudioReader< T >](#).

Properties

- int [SamplingRate](#) [get]
Sampling rate of the audio signal (in Hz).
- int [Channels](#) [get]
Number of channels in the audio signal.
- string [Error](#) [get]
If not null, audio object is in invalid state.

3.29.1 Detailed Description

Audio Source interface.

3.29.2 Property Documentation

3.29.2.1 Channels

```
int Channels [get]
```

Number of channels in the audio signal.

3.29.2.2 Error

```
string Error [get]
```

If not null, audio object is in invalid state.

3.29.2.3 SamplingRate

```
int SamplingRate [get]
```

Sampling rate of the audio signal (in Hz).

3.30 IAudioOut< T > Interface Template Reference

Inherited by [AudioSyncBuffer< T >](#).

Public Member Functions

- void **Start** (int frequency, int channels, int frameSamplesPerChannel, int playDelayMs)
- void **Flush** ()
- void **Stop** ()
- void **Push** (T[] frame)
- void **Service** ()

Properties

- bool **IsPlaying** [get]
- int **Lag** [get]

3.31 `IAudioPusher< T >` Interface Template Reference

Audio Pusher interface.

Inherits [IAudioDesc](#).

Inherited by [AudioUtil.ToneAudioPusher< T >](#).

Public Member Functions

- void [SetCallback](#) (Action< T[]> callback, [ObjectFactory](#)< T[], int > bufferFactory)
Set the callback function used for pushing data.

Additional Inherited Members

3.31.1 Detailed Description

Audio Pusher interface.

Opposed to an [IAudioReader](#) (which will deliver audio data when it is "pulled"), an [IAudioPusher](#) will push its audio data whenever it is ready,

3.31.2 Member Function Documentation

3.31.2.1 `SetCallback()`

```
void SetCallback (
    Action< T[]> callback,
    ObjectFactory< T[], int > bufferFactory )
```

Set the callback function used for pushing data.

Parameters

<i>callback</i>	Callback function to use.
<i>localVoice</i>	Outgoing audio stream, for context.

Implemented in [AudioUtil.ToneAudioPusher< T >](#).

3.32 IAudioReader< T > Interface Template Reference

Audio Reader interface.

Inherits [IDataReader< T >](#), and [IAudioDesc](#).

Inherited by [AudioUtil.ToneAudioReader< T >](#).

Additional Inherited Members

3.32.1 Detailed Description

Audio Reader interface.

Opposed to an [IAudioPusher](#) (which will push its audio data whenever it is ready), an [IAudioReader](#) will deliver audio data when it is "pulled" (it's Read function is called).

3.33 IDataReader< T > Interface Template Reference

Interface for pulling data, in case this is more appropriate than pushing it.

Inherits [IDisposable](#).

Inherited by [IAudioReader< T >](#).

Public Member Functions

- bool [Read](#) (T[] buffer)

Fill full given frame buffer with source uncompressed data or return false if not enough such data.

3.33.1 Detailed Description

Interface for pulling data, in case this is more appropriate than pushing it.

3.33.2 Member Function Documentation

3.33.2.1 Read()

```
bool Read (
    T[] buffer )
```

Fill full given frame buffer with source uncompressed data or return false if not enough such data.

Parameters

<i>buffer</i>	Buffer to fill.
---------------	-----------------

Returns

True if buffer was filled successfully, false otherwise.

Implemented in [AudioUtil.ToneAudioReader< T >](#).

3.34 IDecoder Interface Reference

Generic decoder interface.

Inherits [IDisposable](#).

Inherited by [IDecoderQueuedOutputImageNative](#), [OpusCodec.Decoder< T >](#), and [RawCodec.Decoder< T >](#).

Public Member Functions

- void [Open](#) ([VoiceInfo](#) info)
Open (initialize) the decoder.
- void [Input](#) (byte[] buf, [FrameFlags](#) flags)
Consumes the given encoded data.

Properties

- string [Error](#) [get]
If not null, the object is in invalid state.

3.34.1 Detailed Description

Generic decoder interface.

3.34.2 Member Function Documentation

3.34.2.1 Input()

```
void Input (
    byte[] buf,
    FrameFlags flags )
```

Consumes the given encoded data.

Implemented in [OpusCodec.Decoder< T >](#), and [RawCodec.Decoder< T >](#).

3.34.2.2 Open()

```
void Open (
    VoiceInfo info )
```

Open (initialize) the decoder.

Parameters

<i>info</i>	Properties of the data stream to decode.
-------------	--

Implemented in [RawCodec.Decoder< T >](#), and [OpusCodec.Decoder< T >](#).

3.34.3 Property Documentation

3.34.3.1 Error

`string Error [get]`

If not null, the object is in invalid state.

3.35 IDecoderQueuedOutputImageNative Interface Reference

Inherits [IDecoder](#).

Properties

- ImageFormat **OutputImageFormat** [get, set]
- Flip **OutputImageFlip** [get, set]
- Func< int, int, IntPtr > **OutputImageBufferGetter** [get, set]

Additional Inherited Members

3.36 IEncoder Interface Reference

Generic encoder interface.

Inherits [IDisposable](#).

Inherited by [IEncoderDirect< B >](#).

Public Member Functions

- ArraySegment< byte > [DequeueOutput](#) (out FrameFlags flags)
Returns next encoded data frame (if such output supported).
- void [EndOfStream](#) ()
Forces an encoder to flush and produce frame with EndOfStream flag (in output queue).

Properties

- string [Error](#) [get]
If not null, the object is in invalid state.
- Action< ArraySegment< byte >, FrameFlags > [Output](#) [set]
Set callback encoder calls on each encoded data frame (if such output supported).
- [VoicelInfo Info](#) [get]
Codec may override some settings like video resolution after creation.

3.36.1 Detailed Description

Generic encoder interface.

Depending on implementation, encoder should either call [Output](#) on eaach data frame or return next data frame in [DequeueOutput\(\)](#) call.

3.36.2 Member Function Documentation

3.36.2.1 DequeueOutput()

```
ArraySegment<byte> DequeueOutput (
    out FrameFlags flags )
```

Returns next encoded data frame (if such output supported).

3.36.2.2 EndOfStream()

```
void EndOfStream ( )
```

Forces an encoder to flush and produce frame with EndOfStream flag (in output queue).

3.36.3 Property Documentation

3.36.3.1 Error

```
string Error [get]
```

If not null, the object is in invalid state.

3.36.3.2 Info

`VoiceInfo` Info [get]

Codec may override some settings like video resolution after creation.

3.36.3.3 Output

`Action<ArraySegment<byte>, FrameFlags>` Output [set]

Set callback encoder calls on each encoded data frame (if such output supported).

3.37 IEncoderDirect< B > Interface Template Reference

Interface for an encoder which consumes input data via explicit call.

Inherits [IEncoder](#).

Public Member Functions

- void [Input](#) (B buf)
Consumes the given raw data.

Additional Inherited Members

3.37.1 Detailed Description

Interface for an encoder which consumes input data via explicit call.

3.37.2 Member Function Documentation

3.37.2.1 Input()

```
void Input (  
    B buf )
```

Consumes the given raw data.

Parameters

<i>buf</i>	Array containing raw data (e.g. audio samples).
------------	---

3.38 AudioUtil.ILevelMeter Interface Reference

Audio Level Metering interface.

Inherited by [AudioUtil.LevelMeter< T >](#), and [AudioUtil.LevelMeterDummy](#).

Public Member Functions

- void [ResetAccumAvgPeakAmp](#) ()
Reset [AccumAvgPeakAmp](#).

Properties

- float [CurrentAvgAmp](#) [get]
Average amplitude value over last half second.
- float [CurrentPeakAmp](#) [get]
Maximum amplitude value over last half second sec.
- float [AccumAvgPeakAmp](#) [get]
Average of CurrentPeakAmps since last reset.

3.38.1 Detailed Description

Audio Level Metering interface.

3.38.2 Member Function Documentation

3.38.2.1 ResetAccumAvgPeakAmp()

```
void ResetAccumAvgPeakAmp ( )
```

Reset [AccumAvgPeakAmp](#).

Implemented in [AudioUtil.LevelMeter< T >](#), and [AudioUtil.LevelMeterDummy](#).

3.38.3 Property Documentation

3.38.3.1 AccumAvgPeakAmp

```
float AccumAvgPeakAmp [get]
```

Average of CurrentPeakAmps since last reset.

3.38.3.2 CurrentAvgAmp

```
float CurrentAvgAmp [get]
```

Average amplitude value over last half second.

3.38.3.3 CurrentPeakAmp

```
float CurrentPeakAmp [get]
```

Maximum amplitude value over last half second sec.

3.39 ILocalVoiceAudio Interface Reference

Interface for an outgoing audio stream.

Inherited by [LocalVoiceAudio< T >](#), and [LocalVoiceAudioDummy](#).

Public Member Functions

- void [VoiceDetectorCalibrate](#) (int durationMs, Action< float > onCalibrated=null)
Trigger voice detector calibration process.

Properties

- [AudioUtil.IVoiceDetector VoiceDetector](#) [get]
The VoiceDetector in use.
- [AudioUtil.ILevelMeter LevelMeter](#) [get]
The LevelMeter utility in use.
- bool [VoiceDetectorCalibrating](#) [get]
If true, voice detector calibration is in progress.

3.39.1 Detailed Description

Interface for an outgoing audio stream.

A [LocalVoice](#) always brings a LevelMeter and a VoiceDetector, which you can access using this interface.

3.39.2 Member Function Documentation

3.39.2.1 VoiceDetectorCalibrate()

```
void VoiceDetectorCalibrate (
    int durationMs,
    Action< float > onCalibrated = null )
```

Trigger voice detector calibration process.

While calibrating, keep silence. [Voice](#) detector sets threshold based on measured background noise level.

Parameters

<i>durationMs</i>	Duration of calibration (in milliseconds).
<i>onCalibrated</i>	Called when calibration is complete. Parameter is new threshold value.

Implemented in [LocalVoiceAudioDummy](#), and [LocalVoiceAudio< T >](#).

3.39.3 Property Documentation

3.39.3.1 LevelMeter

```
AudioUtil.ILevelMeter LevelMeter [get]
```

The LevelMeter utility in use.

3.39.3.2 VoiceDetector

```
AudioUtil.IVoiceDetector VoiceDetector [get]
```

The VoiceDetector in use.

Use it to enable or disable voice detector and set its parameters.

3.39.3.3 VoiceDetectorCalibrating

```
bool VoiceDetectorCalibrating [get]
```

If true, voice detector calibration is in progress.

3.40 ILoggable Interface Reference

Inherited by [ILoggableDependent](#), and [VoiceConnection](#).

Properties

- DebugLevel **LogLevel** [get, set]
- [VoiceLogger](#) **Logger** [get]

3.41 ILoggableDependent Interface Reference

Inherits [ILoggable](#).

Inherited by [VoiceComponent](#).

Properties

- bool **IgnoreGlobalLogLevel** [get, set]

3.42 ILogger Interface Reference

Inherited by [IVoiceTransport](#), [Logger](#), and [VoiceLogger](#).

Public Member Functions

- void **LogError** (string fmt, params object[] args)
- void **LogWarning** (string fmt, params object[] args)
- void **LogInfo** (string fmt, params object[] args)
- void **LogDebug** (string fmt, params object[] args)

3.43 ImageBufferInfo Class Reference

Public Member Functions

- **ImageBufferInfo** (int width, int height, int[] stride, ImageFormat format)

Properties

- int **Width** [get]
- int **Height** [get]
- int[] **Stride** [get]
- ImageFormat **Format** [get]
- Rotation **Rotation** [get, set]
- Flip **Flip** [get, set]

3.44 ImageBufferNative Class Reference

Inherited by [ImageBufferNativeAlloc](#), and [ImageBufferNativeGCHandleSinglePlane](#).

Public Member Functions

- **ImageBufferNative** ([ImageBufferInfo](#) info)
- virtual void **Release** ()
- virtual void **Dispose** ()

Properties

- [ImageBufferInfo](#) **Info** [get, protected set]
- IntPtr[] **Planes** [get, protected set]

3.45 ImageBufferNativeAlloc Class Reference

Inherits [ImageBufferNative](#), and [IDisposable](#).

Public Member Functions

- **ImageBufferNativeAlloc** ([ImageBufferNativePool](#)< [ImageBufferNativeAlloc](#) > pool, [ImageBufferInfo](#) info)
- override void **Release** ()
- override void **Dispose** ()

Additional Inherited Members

3.46 ImageBufferNativeGCHandleSinglePlane Class Reference

Inherits [ImageBufferNative](#), and [IDisposable](#).

Public Member Functions

- **ImageBufferNativeGCHandleSinglePlane** ([ImageBufferNativePool](#)< [ImageBufferNativeGCHandleSinglePlane](#) > pool, [ImageBufferInfo](#) info)
- void **PinPlane** (byte[] plane)
- override void **Release** ()
- override void **Dispose** ()

Additional Inherited Members

3.47 ImageBufferNativePool< T > Class Template Reference

Inherits [ObjectPool](#)< [T](#), [ImageBufferInfo](#) >.

Public Member Functions

- delegate T **Factory** ([ImageBufferNativePool](#)< T > pool, [ImageBufferInfo](#) info)
- **ImageBufferNativePool** (int capacity, Factory factory, string name)
- **ImageBufferNativePool** (int capacity, Factory factory, string name, [ImageBufferInfo](#) info)

Protected Member Functions

- override T **createObject** ([ImageBufferInfo](#) info)
- override void **destroyObject** (T obj)
- override bool **infosMatch** ([ImageBufferInfo](#) i0, [ImageBufferInfo](#) i1)

Additional Inherited Members

3.48 ImageInputBuf Struct Reference

Public Attributes

- [IntPtr](#)[] **Buf**
- int **Width**
- int **Height**
- int[] **Stride**
- ImageFormat **ImageFormat**
- Rotation **Rotation**
- Flip **Flip**

3.49 ImageOutputBuf Struct Reference

Public Attributes

- [IntPtr](#) **Buf**
- int **Width**
- int **Height**
- int **Stride**

3.50 IOSAudioForceToSpeaker Class Reference

Inherits [MonoBehaviour](#).

3.51 IProcessor< T > Interface Template Reference

Audio Processor interface.

Inherits [IDisposable](#).

Inherited by [AudioUtil.LevelMeter](#)< T >, [AudioUtil.Resampler](#)< T >, [AudioUtil.VoiceDetector](#)< T >, [AudioUtil.VoiceDetectorCalibration](#) and [AudioUtil.VoiceLevelDetectCalibrate](#)< T >.

Public Member Functions

- `T[] Process (T[] buf)`
Process a frame of audio data.

3.51.1 Detailed Description

Audio Processor interface.

3.51.2 Member Function Documentation

3.51.2.1 Process()

```
T [ ] Process (
    T [ ] buf )
```

Process a frame of audio data.

Parameters

<i>buf</i>	Buffer containing input audio data
------------	------------------------------------

Returns

Buffer containing output audio data or null if frame has been discarded (VAD)

Implemented in [AudioUtil.VoiceLevelDetectCalibrate< T >](#), [AudioUtil.VoiceDetector< T >](#), [AudioUtil.VoiceDetectorCalibration< T >](#), [AudioUtil.LevelMeter< T >](#), and [AudioUtil.Resampler< T >](#).

3.52 IServiceable Interface Reference

Interface for classes that want their [Service\(\)](#) function to be called regularly in the context of a [LocalVoice](#).

Inherited by [BufferReaderPushAdapterBase< T >](#).

Public Member Functions

- `void Service (LocalVoice localVoice)`
Service function that should be called regularly.

3.52.1 Detailed Description

Interface for classes that want their [Service\(\)](#) function to be called regularly in the context of a [LocalVoice](#).

3.52.2 Member Function Documentation

3.52.2.1 Service()

```
void Service (
    LocalVoice localVoice )
```

Service function that should be called regularly.

Implemented in [BufferReaderPushAdapterAsyncPoolCopy< T >](#), [BufferReaderPushAdapterAsyncPool< T >](#), [BufferReaderPushAdapter< T >](#), and [BufferReaderPushAdapterBase< T >](#).

3.53 AudioUtil.IVoiceDetector Interface Reference

[Voice](#) Activity Detector interface.

Inherited by [AudioUtil.VoiceDetector< T >](#), and [AudioUtil.VoiceDetectorDummy](#).

Properties

- bool [On](#) [get, set]
If true, voice detection enabled.
- float [Threshold](#) [get, set]
Voice detected as soon as signal level exceeds threshold.
- bool [Detected](#) [get]
If true, voice detected.
- DateTime [DetectedTime](#) [get]
Last time when switched to detected state.
- int [ActivityDelayMs](#) [get, set]
Keep detected state during this time after signal level dropped below threshold.

Events

- Action [OnDetected](#)
Called when switched to detected state.

3.53.1 Detailed Description

[Voice](#) Activity Detector interface.

3.53.2 Property Documentation

3.53.2.1 ActivityDelayMs

```
int ActivityDelayMs [get], [set]
```

Keep detected state during this time after signal level dropped below threshold.

3.53.2.2 Detected

```
bool Detected [get]
```

If true, voice detected.

3.53.2.3 DetectedTime

```
DateTime DetectedTime [get]
```

Last time when switched to detected state.

3.53.2.4 On

```
bool On [get], [set]
```

If true, voice detection enabled.

3.53.2.5 Threshold

```
float Threshold [get], [set]
```

[Voice](#) detected as soon as signal level exceeds threshold.

3.53.3 Event Documentation

3.53.3.1 OnDetected

```
Action OnDetected
```

Called when switched to detected state.

3.54 IVoiceTransport Interface Reference

Inherits [ILogger](#).

Inherited by [LoadBalancingTransport](#).

Public Member Functions

- bool **IsChannelJoined** (int channelId)
- void **SendVoicesInfo** (IEnumerable< [LocalVoice](#) > voices, int channelId, int targetPlayerId)
- void **SendVoiceRemove** ([LocalVoice](#) voice, int channelId, int targetPlayerId)
- void **SendFrame** (ArraySegment< byte > data, FrameFlags flags, byte evNumber, byte voiceId, int channelId, int targetPlayerId, bool reliable, [LocalVoice](#) localVoice)
- string **ChannelIdStr** (int channelId)
- string **PlayerIdStr** (int playerId)

3.55 AudioUtil.LevelMeter< T > Class Template Reference

Audio Level Meter.

Inherits [IProcessor< T >](#), and [AudioUtil.ILevelMeter](#).

Public Member Functions

- void [ResetAccumAvgPeakAmp](#) ()
Reset AccumAvgPeakAmp.
- abstract T[] [Process](#) (T[] buf)
Process a frame of audio data.
- void **Dispose** ()

Protected Attributes

- float **ampSum**
- float **ampPeak**
- int **bufferSize**
- float[] **prevValues**
- int **prevValuesHead**
- float **accumAvgPeakAmpSum**
- int **accumAvgPeakAmpCount**
- float **currentPeakAmp**
- float **norm**

Properties

- float **CurrentAvgAmp** [get]
- float **CurrentPeakAmp** [get, protected set]
- float? **AccumAvgPeakAmp** [get]

3.55.1 Detailed Description

Audio Level Meter.

3.55.2 Member Function Documentation

3.55.2.1 Process()

```
abstract T [ ] Process (
    T [ ] buf ) [pure virtual]
```

Process a frame of audio data.

Parameters

<i>buf</i>	Buffer containing input audio data
------------	------------------------------------

Returns

Buffer containing output audio data or null if frame has been discarded (VAD)

Implements [IProcessor< T >](#).

3.55.2.2 ResetAccumAvgPeakAmp()

```
void ResetAccumAvgPeakAmp ( )
```

Reset AccumAvgPeakAmp.

Implements [AudioUtil.LevelMeter](#).

3.56 AudioUtil.LevelMeterDummy Class Reference

Dummy Audio Level Meter that doesn't actually do anything.

Inherits [AudioUtil.LevelMeter](#).

Public Member Functions

- void [ResetAccumAvgPeakAmp](#) ()
Reset AccumAvgPeakAmp.

Properties

- float **CurrentAvgAmp** [get]
- float **CurrentPeakAmp** [get]
- float **AccumAvgPeakAmp** [get]

3.56.1 Detailed Description

Dummy Audio Level Meter that doesn't actually do anything.

3.56.2 Member Function Documentation

3.56.2.1 ResetAccumAvgPeakAmp()

```
void ResetAccumAvgPeakAmp ( )
```

Reset AccumAvgPeakAmp.

Implements [AudioUtil.LevelMeter](#).

3.57 AudioUtil.LevelMeterFloat Class Reference

[LevelMeter](#) specialization for float audio.

Inherits [AudioUtil.LevelMeter< float >](#).

Public Member Functions

- [LevelMeterFloat](#) (int samplingRate, int numChannels)
Create new [LevelMeterFloat](#) instance.
- override float[] **Process** (float[] buf)

Additional Inherited Members

3.57.1 Detailed Description

[LevelMeter](#) specialization for float audio.

3.57.2 Constructor & Destructor Documentation

3.57.2.1 LevelMeterFloat()

```
LevelMeterFloat (
    int samplingRate,
    int numChannels )
```

Create new [LevelMeterFloat](#) instance.

Parameters

<i>samplingRate</i>	Sampling rate of the audio signal (in Hz).
<i>numChannels</i>	Number of channels in the audio signal.

3.58 AudioUtil.LevelMeterShort Class Reference

[LevelMeter](#) specialization for short audio.

Inherits [AudioUtil.LevelMeter< short >](#).

Public Member Functions

- [LevelMeterShort](#) (int samplingRate, int numChannels)
Create new [LevelMeterShort](#) instance.
- override short[] **Process** (short[] buf)

Additional Inherited Members

3.58.1 Detailed Description

[LevelMeter](#) specialization for short audio.

3.58.2 Constructor & Destructor Documentation

3.58.2.1 LevelMeterShort()

```
LevelMeterShort (
    int samplingRate,
    int numChannels )
```

Create new [LevelMeterShort](#) instance.

Parameters

<i>samplingRate</i>	Sampling rate of the audio signal (in Hz).
<i>numChannels</i>	Number of channels in the audio signal.

3.59 LoadBalancingFrontend Class Reference

Inherits [LoadBalancingTransport](#).

Additional Inherited Members

3.60 LoadBalancingTransport Class Reference

Extends [LoadBalancingClient](#) with audio streaming functionality.

Inherits [LoadBalancingClient](#), [IVoiceTransport](#), and [IDisposable](#).

Inherited by [LoadBalancingFrontend](#), and [LoadBalancingTransport2](#).

Public Member Functions

- void **LogError** (string fmt, params object[] args)
- void **LogWarning** (string fmt, params object[] args)
- void **LogInfo** (string fmt, params object[] args)
- void **LogDebug** (string fmt, params object[] args)
- bool **IsChannelJoined** (int channelId)
- [LoadBalancingTransport](#) (ConnectionProtocol connectionProtocol=ConnectionProtocol.Udp)
Initializes a new [LoadBalancingTransport](#).
- new void [Service](#) ()
This method dispatches all available incoming commands and then sends this client's outgoing commands. Call this method regularly (2 to 20 times a second).
- virtual bool **ChangeAudioGroups** (byte[] groupsToRemove, byte[] groupsToAdd)
- void **SendVoicesInfo** (IEnumerable< [LocalVoice](#) > voices, int channelId, int targetPlayerId)
- void **SendVoiceRemove** ([LocalVoice](#) voice, int channelId, int targetPlayerId)
- virtual void **SendFrame** (ArraySegment< byte > data, FrameFlags flags, byte evNumber, byte voiceId, int channelId, int targetPlayerId, bool reliable, [LocalVoice](#) localVoice)
- string **ChannelIdStr** (int channelId)
- string **PlayerIdStr** (int playerId)
- void [Dispose](#) ()
Releases all resources used by the [LoadBalancingTransport](#) instance.

Protected Member Functions

- virtual void **onEventActionVoiceClient** (EventData ev)

Protected Attributes

- [VoiceClient](#) **voiceClient**

Properties

- [VoiceClient](#) [VoiceClient](#) [get]

The [VoiceClient](#) implementation associated with this [LoadBalancingTransport](#).

- byte [GlobalAudioGroup](#) [get, set]
- byte [GlobalInterestGroup](#) [get, set]

Set global audio group for this client. This call sets [InterestGroup](#) for existing local voices and for created later to given value. Client set as listening to this group only until [LoadBalancingPeer.OpChangeGroups\(\)](#) called. This method can be called any time.

3.60.1 Detailed Description

Extends [LoadBalancingClient](#) with audio streaming functionality.

Use your normal [LoadBalancing](#) workflow to join a [Voice](#) room. All standard [LoadBalancing](#) features are available.

To work with audio:

- Create outgoing audio streams with [Client.CreateLocalVoice](#).
- Handle new incoming audio streams info with [OnRemoteVoiceInfoAction](#) .
- Handle incoming audio streams data with [OnAudioFrameAction](#) .
- Handle closing of incoming audio streams with .

3.60.2 Constructor & Destructor Documentation

3.60.2.1 LoadBalancingTransport()

```
LoadBalancingTransport (
    ConnectionProtocol connectionProtocol = ConnectionProtocol.Udp )
```

Initializes a new [LoadBalancingTransport](#).

Parameters

<i>connectionProtocol</i>	Connection protocol (UDP or TCP). ConnectionProtocol
---------------------------	--

3.60.3 Member Function Documentation

3.60.3.1 Dispose()

```
void Dispose ( )
```

Releases all resources used by the [LoadBalancingTransport](#) instance.

3.60.3.2 Service()

```
new void Service ( )
```

This method dispatches all available incoming commands and then sends this client's outgoing commands. Call this method regularly (2 to 20 times a second).

3.60.4 Property Documentation

3.60.4.1 GlobalInterestGroup

```
byte GlobalInterestGroup [get], [set]
```

Set global audio group for this client. This call sets InterestGroup for existing local voices and for created later to given value. Client set as listening to this group only until LoadBalancingPeer.OpChangeGroups() called. This method can be called any time.

[LocalVoice.InterestGroup](#) LoadBalancingPeer.OpChangeGroups(byte[], byte[])

3.60.4.2 VoiceClient

```
VoiceClient VoiceClient [get]
```

The [VoiceClient](#) implementation associated with this [LoadBalancingTransport](#).

3.61 LoadBalancingTransport2 Class Reference

Variant of [LoadBalancingTransport](#). Aims to be non-alloc at the cost of breaking compatibility with older clients.

Inherits [LoadBalancingTransport](#).

Public Member Functions

- **LoadBalancingTransport2** (ConnectionProtocol connectionProtocol=ConnectionProtocol.Udp)
- override void **SendFrame** (ArraySegment< byte > data, FrameFlags flags, byte evNumber, byte voiceId, int channelId, int targetPlayerId, bool reliable, [LocalVoice](#) localVoice)

Protected Member Functions

- override void **onEventActionVoiceClient** (EventData ev)

Additional Inherited Members

3.61.1 Detailed Description

Variant of [LoadBalancingTransport](#). Aims to be non-alloc at the cost of breaking compatibility with older clients.

3.62 LocalVoice Class Reference

Represents outgoing data stream.

Inherits [IDisposable](#).

Inherited by [LocalVoiceAudioDummy](#), and [LocalVoiceFramedBase](#).

Public Member Functions

- virtual [IEncoder](#) **CreateDefaultEncoder** ([VoiceInfo](#) info)
- void **RemoveSelf** ()
Remove this voice from it's [VoiceClient](#) (using [VoiceClient.RemoveLocalVoice](#)
- virtual void **Dispose** ()

Static Public Attributes

- const int **DATA_POOL_CAPACITY** = 50

Protected Member Functions

- void **resetNoTransmitCnt** ()

Protected Attributes

- [VoiceInfo](#) info
- [IEncoder](#) encoder
- [VoiceClient](#) voiceClient
- [ArraySegment](#)< byte > **configFrame**
- volatile bool **disposed**
- object **disposeLock** = new object()

Properties

- byte **Group** [get, set]
- byte **InterestGroup** [get, set]
If InterestGroup != 0, voice's data is sent only to clients listening to this group (if supported by transport).
- **VoiceInfo Info** [get]
Returns Info structure assigned on local voice cration.
- bool **TransmitEnabled** [get, set]
If true, stream data broadcasted.
- bool **IsCurrentlyTransmitting** [get, protected set]
Returns true if stream broadcasts.
- int **FramesSent** [get]
Sent frames counter.
- int **FramesSentBytes** [get]
Sent frames bytes counter.
- bool **Reliable** [get, set]
Send data reliable.
- bool **Encrypt** [get, set]
Send data encrypted.
- **IServiceable LocalUserServiceable** [get, set]
Optional user object attached to [LocalVoice](#). its Service() will be called at each [VoiceClient.Service\(\)](#) call.
- bool **DebugEchoMode** [get, set]
If true, outgoing stream routed back to client via server same way as for remote client's streams. Can be swithed any time. OnRemoteVoiceInfoAction and OnRemoteVoiceRemoveAction are triggered if required. This functionality availability depends on transport.

3.62.1 Detailed Description

Represents outgoing data stream.

3.62.2 Member Function Documentation

3.62.2.1 RemoveSelf()

```
void RemoveSelf ( )
```

Remove this voice from it's [VoiceClient](#) (using [VoiceClient.RemoveLocalVoice](#)

.

3.62.3 Property Documentation

3.62.3.1 DebugEchoMode

```
bool DebugEchoMode [get], [set]
```

If true, outgoing stream routed back to client via server same way as for remote client's streams. Can be swithed any time. OnRemoteVoiceInfoAction and OnRemoteVoiceRemoveAction are triggered if required. This functionality availability depends on transport.

3.62.3.2 Encrypt

```
bool Encrypt [get], [set]
```

Send data encrypted.

3.62.3.3 FramesSent

```
int FramesSent [get]
```

Sent frames counter.

3.62.3.4 FramesSentBytes

```
int FramesSentBytes [get]
```

Sent frames bytes counter.

3.62.3.5 Info

```
VoiceInfo Info [get]
```

Returns Info structure assigned on local voice cration.

3.62.3.6 InterestGroup

```
byte InterestGroup [get], [set]
```

If InterestGroup != 0, voice's data is sent only to clients listening to this group (if supported by transport).

3.62.3.7 IsCurrentlyTransmitting

```
bool IsCurrentlyTransmitting [get], [protected set]
```

Returns true if stream broadcasts.

3.62.3.8 LocalUserServiceable

```
IServiceable LocalUserServiceable [get], [set]
```

Optional user object attached to [LocalVoice](#). its Service() will be called at each [VoiceClient.Service\(\)](#) call.

3.62.3.9 Reliable

```
bool Reliable [get], [set]
```

Send data reliable.

3.62.3.10 TransmitEnabled

```
bool TransmitEnabled [get], [set]
```

If true, stream data broadcasted.

3.63 LocalVoiceAudio< T > Class Template Reference

Outgoing audio stream.

Inherits [LocalVoiceFramed< T >](#), and [ILocalVoiceAudio](#).

Public Member Functions

- override [IEncoder](#) **CreateDefaultEncoder** ([VoiceInfo](#) info)
- void [VoiceDetectorCalibrate](#) (int durationMs, Action< float > onCalibrated=null)
Trigger voice detector calibration process.

Static Public Member Functions

- static [LocalVoiceAudio< T >](#) **Create** ([VoiceClient](#) voiceClient, byte voiceId, [IEncoder](#) encoder, [VoiceInfo](#) voiceInfo, [IAudioDesc](#) audioSourceDesc, int channelId)
Create a new LocalVoiceAudio< T > instance.

Protected Member Functions

- void **initBuiltinProcessors** ()

Protected Attributes

- [AudioUtil.VoiceDetector< T >](#) **voiceDetector**
- [AudioUtil.VoiceDetectorCalibration< T >](#) **voiceDetectorCalibration**
- [AudioUtil.LevelMeter< T >](#) **levelMeter**
- int **channels**
- bool **resampleSource**

Properties

- virtual [AudioUtil.IVoiceDetector](#) **VoiceDetector** [get]
- virtual [AudioUtil.ILevelMeter](#) **LevelMeter** [get]
- bool [VoiceDetectorCalibrating](#) [get]

True if the VoiceDetector is currently calibrating.

Additional Inherited Members

3.63.1 Detailed Description

Outgoing audio stream.

3.63.2 Member Function Documentation

3.63.2.1 Create()

```
static LocalVoiceAudio<T> Create (
    VoiceClient voiceClient,
    byte voiceId,
    IEncoder encoder,
    VoiceInfo voiceInfo,
    IAudioDesc audioSourceDesc,
    int channelId ) [static]
```

Create a new LocalVoiceAudio<T> instance.

Parameters

<i>voiceClient</i>	The VoiceClient to use for this outgoing stream.
<i>voiceId</i>	Numeric ID for this voice.
<i>encoder</i>	Encoder to use for this voice.
<i>channelId</i>	Voice transport channel ID to use for this voice.

Returns

The new `LocalVoiceAudio<T>` instance.

3.63.2.2 VoiceDetectorCalibrate()

```
void VoiceDetectorCalibrate (
    int durationMs,
    Action< float > onCalibrated = null )
```

Trigger voice detector calibration process.

While calibrating, keep silence. [Voice](#) detector sets threshold basing on measured background noise level.

Parameters

<i>durationMs</i>	Duration of calibration in milliseconds.
<i>onCalibrated</i>	Called when calibration is complete. Parameter is new threshold value.

Implements [ILocalVoiceAudio](#).

3.63.3 Property Documentation**3.63.3.1 VoiceDetectorCalibrating**

```
bool VoiceDetectorCalibrating [get]
```

True if the `VoiceDetector` is currently calibrating.

3.64 LocalVoiceAudioDummy Class Reference

Dummy [LocalVoiceAudio](#)

Inherits [LocalVoice](#), and [ILocalVoiceAudio](#).

Public Member Functions

- void [VoiceDetectorCalibrate](#) (int durationMs, Action< float > onCalibrated=null)
Trigger voice detector calibration process.

Static Public Attributes

- static [LocalVoiceAudioDummy Dummy](#) = new [LocalVoiceAudioDummy\(\)](#)
A Dummy [LocalVoiceAudio](#) instance.

Properties

- [AudioUtil.IVoiceDetector VoiceDetector](#) [get]
- [AudioUtil.ILevelMeter LevelMeter](#) [get]
- bool [VoiceDetectorCalibrating](#) [get]

Additional Inherited Members

3.64.1 Detailed Description

Dummy [LocalVoiceAudio](#)

For testing, this [LocalVoiceAudio](#) implementation features a [AudioUtil.VoiceDetectorDummy](#) and a [AudioUtil.LevelMeterDummy](#)

3.64.2 Member Function Documentation

3.64.2.1 VoiceDetectorCalibrate()

```
void VoiceDetectorCalibrate (
    int durationMs,
    Action< float > onCalibrated = null )
```

Trigger voice detector calibration process.

While calibrating, keep silence. [Voice](#) detector sets threshold based on measured background noise level.

Parameters

<i>durationMs</i>	Duration of calibration (in milliseconds).
<i>onCalibrated</i>	Called when calibration is complete. Parameter is new threshold value.

Implements [ILocalVoiceAudio](#).

3.64.3 Member Data Documentation

3.64.3.1 Dummy

```
LocalVoiceAudioDummy Dummy = new LocalVoiceAudioDummy() [static]
```

A Dummy [LocalVoiceAudio](#) instance.

3.65 LocalVoiceAudioFloat Class Reference

Specialization of [LocalVoiceAudio](#) for float audio

Inherits [LocalVoiceAudio< float >](#).

Additional Inherited Members

3.65.1 Detailed Description

Specialization of [LocalVoiceAudio](#) for float audio

3.66 LocalVoiceAudioShort Class Reference

Specialization of [LocalVoiceAudio](#) for short audio

Inherits [LocalVoiceAudio< short >](#).

Additional Inherited Members

3.66.1 Detailed Description

Specialization of [LocalVoiceAudio](#) for short audio

3.67 LocalVoiceFramed< T > Class Template Reference

Typed re-framing [LocalVoice](#)

Inherits [LocalVoiceFramedBase](#).

Inherited by [LocalVoiceAudio< T >](#).

Public Member Functions

- void [AddPostProcessor](#) (params [IProcessor](#)< T >[] processors)
Adds processors after any built-in processors and everything added with AddPreProcessor.
- void [AddPreProcessor](#) (params [IProcessor](#)< T >[] processors)
Adds processors before built-in processors and everything added with AddPostProcessor.
- void [ClearProcessors](#) ()
Clears all processors in pipeline including built-in resampling. User should add at least resampler processor after call.
- void [PushDataAsync](#) (T[] buf)
Asynchronously push data into this stream.
- void [PushData](#) (T[] buf)
Synchronously push data into this stream.
- override void [Dispose](#) ()
Releases resources used by the VoiceFramed instance. Buffers used for asynchronous push will be disposed in encoder thread's 'finally'.

Protected Member Functions

- T[] [processFrame](#) (T[] buf)

Properties

- [FactoryPrimitiveArrayPool](#)< T > **BufferFactory** [get]
- bool [PushDataAsyncReady](#) [get]
Whether this [LocalVoiceFramed](#) has capacity for more data buffers to be pushed asynchronously.

Additional Inherited Members

3.67.1 Detailed Description

Typed re-framing [LocalVoice](#)

Consumes data in array buffers of arbitrary length. Repacks them in frames of constant length for further processing and encoding.

Parameters

<i>voiceInfo</i>	Outgoing stream parameters. Set applicable fields to read them by encoder and by receiving client when voice created.
<i>channelId</i>	Transport channel specific to transport.
<i>encoder</i>	Encoder producing the stream.

Returns

Outgoing stream handler.

3.67.2 Member Function Documentation

3.67.2.1 AddPostProcessor()

```
void AddPostProcessor (
    params IProcessor< T >[] processors )
```

Adds processors after any built-in processors and everything added with AddPreProcessor.

Parameters

<i>processors</i>	
-------------------	--

3.67.2.2 AddPreProcessor()

```
void AddPreProcessor (
    params IProcessor< T >[] processors )
```

Adds processors before built-in processors and everything added with AddPostProcessor.

Parameters

<i>processors</i>	
-------------------	--

3.67.2.3 ClearProcessors()

```
void ClearProcessors ( )
```

Clears all processors in pipeline including built-in resampling. User should add at least resampler processor after call.

3.67.2.4 Dispose()

```
override void Dispose ( ) [virtual]
```

Releases resources used by the VoiceFramed instance. Buffers used for asynchronous push will be disposed in encoder thread's 'finally'.

Reimplemented from [LocalVoice](#).

3.67.2.5 PushData()

```
void PushData (
    T[] buf )
```

Synchronously push data into this stream.

3.67.2.6 PushDataAsync()

```
void PushDataAsync (
    T[] buf )
```

Asynchronously push data into this stream.

3.67.3 Property Documentation

3.67.3.1 PushDataAsyncReady

```
bool PushDataAsyncReady [get]
```

Whether this [LocalVoiceFramed](#) has capacity for more data buffers to be pushed asynchronously.

3.68 LocalVoiceFramedBase Class Reference

Typed re-framing [LocalVoice](#)

Inherits [LocalVoice](#).

Inherited by [LocalVoiceFramed< T >](#).

Properties

- int [FrameSize](#) [get]

Data flow will be repacked to frames of this size. May differ from input voiceInfo.FrameSize. Processors should resample in this case.

Additional Inherited Members

3.68.1 Detailed Description

Typed re-framing [LocalVoice](#)

Base class for typed re-framing [LocalVoice](#) implementation ([LocalVoiceFramedBase<T>](#))

3.68.2 Property Documentation

3.68.2.1 FrameSize

`int FrameSize [get]`

Data flow will be repacked to frames of this size. May differ from input `voiceInfo.FrameSize`. Processors should resample in this case.

3.69 Logger Class Reference

Inherits [ILogger](#).

Public Member Functions

- void **LogError** (string fmt, params object[] args)
- void **LogWarning** (string fmt, params object[] args)
- void **LogInfo** (string fmt, params object[] args)
- void **LogDebug** (string fmt, params object[] args)

3.70 MicAmplifier Class Reference

Inherits [VoiceComponent](#).

Properties

- float **AmplificationFactor** [get, set]
- float **BoostValue** [get, set]

Additional Inherited Members

3.71 MicAmplifierFloat Class Reference

Inherits [IProcessor< float >](#).

Public Member Functions

- **MicAmplifierFloat** (float amplificationFactor, float boostValue)
- float[] **Process** (float[] buf)
- void **Dispose** ()

Properties

- float **AmplificationFactor** [get, set]
- float **BoostValue** [get, set]
- float **MaxBefore** [get]
- float **MaxAfter** [get]
- bool **Disabled** [get, set]

3.72 MicAmplifierShort Class Reference

Inherits [IProcessor< short >](#).

Public Member Functions

- **MicAmplifierShort** (short amplificationFactor, short boostValue)
- short[] **Process** (short[] buf)
- void **Dispose** ()

Properties

- short **AmplificationFactor** [get, set]
- short **BoostValue** [get, set]
- short **MaxBefore** [get]
- short **MaxAfter** [get]
- bool **Disabled** [get, set]

3.73 MicWrapper Class Reference

Inherits [IAudioReader< float >](#).

Public Member Functions

- **MicWrapper** (string device, int suggestedFrequency, [ILogger](#) logger)
- void **Dispose** ()
- bool **Read** (float[] buffer)

Properties

- int? **SamplingRate** [get]
- int? **Channels** [get]
- string **Error** [get]

3.74 MicWrapperPusher Class Reference

Inherits [IAudioPusher< float >](#).

Public Member Functions

- **MicWrapperPusher** (string device, AudioSource aS, int suggestedFrequency, [ILogger](#) lg, bool destroyOnStop=true)
- **MicWrapperPusher** (string device, GameObject gO, int suggestedFrequency, [ILogger](#) lg, bool destroyOnStop=true)
- **MicWrapperPusher** (string device, Transform parentTransform, int suggestedFrequency, [ILogger](#) lg, bool destroyOnStop=true)
- void **SetCallback** (Action< float[]> callback, [ObjectFactory](#)< float[], int > bufferFactory)
- void **Dispose** ()

Properties

- int? **SamplingRate** [get]
- int? **Channels** [get]
- string **Error** [get]

3.75 NativeAndroidMicrophoneSettings Class Reference

Public Attributes

- bool **AcousticEchoCancellation**
- bool **AutomaticGainControl**
- bool **NoiseSuppression**

3.76 ObjectFactory< TType, TInfo > Interface Template Reference

Uniform interface to [ObjectPool<TType, TInfo>](#) and single reusable object.

Inherits [IDisposable](#).

Public Member Functions

- TType **New** ()
- TType **New** (TInfo info)
- void **Free** (TType obj)
- void **Free** (TType obj, TInfo info)

Properties

- TInfo **Info** [get]

3.76.1 Detailed Description

Uniform interface to [ObjectPool<TType, TInfo>](#) and single reusable object.

Template Parameters

<i>TType</i>	Object type.
<i>TInfo</i>	Type of property used to check 2 objects identity (like integral length of array).

3.77 ObjectPool< TType, TInfo > Class Template Reference

Generic Pool to re-use objects of a certain type (TType) that optionally match a certain property or set of properties (TInfo).

Inherits IDisposable.

Public Member Functions

- [ObjectPool](#) (int capacity, string name)
Create a new [ObjectPool](#) instance. Does not call [Init\(\)](#).
- [ObjectPool](#) (int capacity, string name, TInfo info)
Create a new [ObjectPool](#) instance with the given info structure. Calls [Init\(\)](#).
- void [Init](#) (TInfo info)
(Re-)Initializes this [ObjectPool](#).
- TType [AcquireOrCreate](#) ()
Acquire an existing object, or create a new one if none are available.
- TType [AcquireOrCreate](#) (TInfo info)
Acquire an existing object (if info matches), or create a new one from the passed info.
- virtual bool [Release](#) (TType obj, TInfo objInfo)
Returns object to pool.
- virtual bool [Release](#) (TType obj)
Returns object to pool, or destroys it if the pool is full.
- void [Dispose](#) ()
Free resources associated with this [ObjectPool](#)

Protected Member Functions

- abstract TType **createObject** (TInfo info)
- abstract void **destroyObject** (TType obj)
- abstract bool **infosMatch** (TInfo i0, TInfo i1)

Protected Attributes

- int **capacity**
- TInfo **info**
- int **pos**
- string **name**

Properties

- TInfo [Info](#) [get]
The property (info) that objects in this Pool must match.

3.77.1 Detailed Description

Generic Pool to re-use objects of a certain type (TType) that optionally match a certain property or set of properties (TInfo).

Template Parameters

<i>TType</i>	Object type.
<i>TInfo</i>	Type of parameter used to check 2 objects identity (like integral length of array).

3.77.2 Constructor & Destructor Documentation

3.77.2.1 `ObjectPool()` [1/2]

```
ObjectPool (
    int capacity,
    string name )
```

Create a new `ObjectPool` instance. Does not call `Init()`.

Parameters

<i>capacity</i>	Capacity (size) of the object pool.
<i>name</i>	Name of the object pool.

3.77.2.2 `ObjectPool()` [2/2]

```
ObjectPool (
    int capacity,
    string name,
    TInfo info )
```

Create a new `ObjectPool` instance with the given info structure. Calls `Init()`.

Parameters

<i>capacity</i>	Capacity (size) of the object pool.
<i>name</i>	Name of the object pool.
<i>info</i>	Info about this Pool's objects.

3.77.3 Member Function Documentation

3.77.3.1 AcquireOrCreate() [1/2]

```
TType AcquireOrCreate ( )
```

Acquire an existing object, or create a new one if none are available.

If it fails to get one from the pool, this will create from the info given in this pool's constructor.

3.77.3.2 AcquireOrCreate() [2/2]

```
TType AcquireOrCreate (
    TInfo info )
```

Acquire an existing object (if info matches), or create a new one from the passed info.

Parameters

<i>info</i>	Info structure to match, or create a new object with.
-------------	---

3.77.3.3 Dispose()

```
void Dispose ( )
```

Free resources assoicated with this [ObjectPool](#)

3.77.3.4 Init()

```
void Init (
    TInfo info )
```

(Re-)Initializes this [ObjectPool](#).

If there are objects available in this Pool, they will be destroyed. Allocates (Capacity) new Objects.

Parameters

<i>info</i>	Info about this Pool's objects.
-------------	---------------------------------

3.77.3.5 Release() [1/2]

```
virtual bool Release (
    TType obj ) [virtual]
```

Returns object to pool, or destroys it if the pool is full.

Parameters

<i>obj</i>	The object to return to the pool.
------------	-----------------------------------

3.77.3.6 Release() [2/2]

```
virtual bool Release (
    TType obj,
    TInfo objInfo ) [virtual]
```

Returns object to pool.

Parameters

<i>obj</i>	The object to return to the pool.
<i>objInfo</i>	The info structure about obj.

obj is returned to the pool only if *objInfo* matches this pool's info. Else, it is destroyed.

3.77.4 Property Documentation

3.77.4.1 Info

```
TInfo Info [get]
```

The property (info) that objects in this Pool must match.

3.78 OpusCodec Class Reference

Classes

- class [Decoder](#)
- class [DecoderFactory](#)
- class [Encoder](#)
- class [EncoderFloat](#)
- class [EncoderShort](#)
- class [Factory](#)
- class [Util](#)

Public Types

- enum **FrameDuration**

Properties

- static string **Version** [get]

3.79 OpusDecoder< T > Class Template Reference

Inherits IDisposable.

Public Member Functions

- **OpusDecoder** (SamplingRate outputSamplingRateHz, [Channels](#) numChannels)
- T[] **DecodePacket** (byte[] packetData)
- T[] **DecodeEndOfStream** ()
- void **Dispose** ()

Properties

- [Bandwidth](#)? **PreviousPacketBandwidth** [get]

3.80 OpusEncoder Class Reference

Inherits IDisposable.

Public Member Functions

- **OpusEncoder** (SamplingRate inputSamplingRateHz, [Channels](#) numChannels, int bitrate, [OpusApplicationType](#) applicationType, [Delay](#) encoderDelay)
- ArraySegment< byte > **Encode** (float[] pcmSamples)
- ArraySegment< byte > **Encode** (short[] pcmSamples)
- void **Dispose** ()

Static Public Attributes

- const int **BitrateMax** = -1

Properties

- SamplingRate **InputSamplingRate** [get]
- Channels **InputChannels** [get]
- Delay **EncoderDelay** [get, set]

Using a duration of less than 10 ms will prevent the encoder from using the LPC or hybrid modes.
- int **FrameSizePerChannel** [get]
- int **Bitrate** [get, set]
- Bandwidth **MaxBandwidth** [get, set]
- Complexity **Complexity** [get, set]
- int **ExpectedPacketLossPercentage** [get, set]
- SignalHint **SignalHint** [get, set]
- ForceChannels **ForceChannels** [get, set]
- bool? **UseInbandFEC** [get, set]
- int **PacketLossPercentage** [get, set]
- bool? **UseUnconstrainedVBR** [get, set]
- bool? **DtxEnabled** [get, set]

3.80.1 Property Documentation

3.80.1.1 EncoderDelay

Delay **EncoderDelay** [get], [set]

Using a duration of less than 10 ms will prevent the encoder from using the LPC or hybrid modes.

3.81 OpusException Class Reference

Inherits Exception.

Public Member Functions

- **OpusException** (OpusStatusCode statusCode, string message)

Properties

- OpusStatusCode **StatusCode** [get]

3.82 OpusLib Class Reference

Properties

- static string **Version** [get]

3.83 PhotonVoiceCreatedParams Class Reference

Inherited by [Recorder.PhotonVoiceCreatedParams](#).

Properties

- [Voice.LocalVoice](#) **Voice** [get, set]
- [Voice.IAudioDesc](#) **AudioDesc** [get, set]

3.84 Recorder.PhotonVoiceCreatedParams Class Reference

Inherits [PhotonVoiceCreatedParams](#).

Additional Inherited Members

3.85 PhotonVoiceLagSimulationGui Class Reference

Inherits [MonoBehaviour](#).

Public Member Functions

- void **OnEnable** ()

3.86 PhotonVoiceNetwork Class Reference

This class can be used to automatically sync client states between [PUN](#) and [Voice](#). It also sets a custom [PUN](#) Speaker factory to find the Speaker component for a character's voice. For this to work attach a [PhotonVoiceView](#) next to the PhotonView of your player's prefab.

Inherits [VoiceConnection](#).

Public Member Functions

- bool [ConnectAndJoinRoom](#) ()
Connect voice client to [Photon](#) servers and join a [Voice](#) room
- void [Disconnect](#) ()
Disconnect voice client from all [Photon](#) servers

Public Attributes

- bool [AutoConnectAndJoin](#) = true
Auto connect voice client and join a voice room when [PUN](#) client is joined to a [PUN](#) room
- bool [AutoLeaveAndDisconnect](#) = true
Auto disconnect voice client when [PUN](#) client is not joined to a [PUN](#) room
- bool [WorkInOfflineMode](#) = true
Whether or not [Photon Voice](#) client should follow [PUN](#) client if the latter is in offline mode.

Static Public Attributes

- const string [VoiceRoomNameSuffix](#) = "_voice_"
Suffix for voice room names appended to [PUN](#) room names.

Protected Member Functions

- override void **Awake** ()
- override void **OnDisable** ()
- override void **OnDestroy** ()
- override void **OnVoiceStateChanged** ([ClientState](#) fromState, [ClientState](#) toState)
- override [Speaker SimpleSpeakerFactory](#) (int playerId, byte voiceId, object userData)

Properties

- static [PhotonVoiceNetwork Instance](#) [get, set]
Singleton instance for [PhotonVoiceNetwork](#)

Additional Inherited Members

3.86.1 Detailed Description

This class can be used to automatically sync client states between [PUN](#) and [Voice](#). It also sets a custom [PUN](#) Speaker factory to find the Speaker component for a character's voice. For this to work attach a [PhotonVoiceView](#) next to the PhotonView of your player's prefab.

3.86.2 Member Function Documentation

3.86.2.1 ConnectAndJoinRoom()

```
bool ConnectAndJoinRoom ( )
```

Connect voice client to [Photon](#) servers and join a [Voice](#) room

Returns

If true, connection command send from client

3.86.2.2 Disconnect()

```
void Disconnect ( )
```

Disconnect voice client from all [Photon](#) servers

3.86.3 Member Data Documentation

3.86.3.1 AutoConnectAndJoin

```
bool AutoConnectAndJoin = true
```

Auto connect voice client and join a voice room when [PUN](#) client is joined to a [PUN](#) room

3.86.3.2 AutoLeaveAndDisconnect

```
bool AutoLeaveAndDisconnect = true
```

Auto disconnect voice client when [PUN](#) client is not joined to a [PUN](#) room

3.86.3.3 VoiceRoomNameSuffix

```
const string VoiceRoomNameSuffix = "_voice_" [static]
```

Suffix for voice room names appended to [PUN](#) room names.

3.86.3.4 WorkInOfflineMode

```
bool WorkInOfflineMode = true
```

Whether or not [Photon Voice](#) client should follow [PUN](#) client if the latter is in offline mode.

3.86.4 Property Documentation

3.86.4.1 Instance

`PhotonVoiceNetwork` Instance [static], [get], [set]

Singleton instance for [PhotonVoiceNetwork](#)

3.87 PhotonVoiceStatsGui Class Reference

Basic GUI to show traffic and health statistics of the connection to [Photon](#), toggled by shift+tab.

Inherits [MonoBehaviour](#).

3.87.1 Detailed Description

Basic GUI to show traffic and health statistics of the connection to [Photon](#), toggled by shift+tab.

The shown health values can help identify problems with connection losses or performance. Example: If the time delta between two consecutive `SendOutgoingCommands` calls is a second or more, chances rise for a disconnect being caused by this (because acknowledgments to the server need to be sent in due time).

3.88 PhotonVoiceView Class Reference

Component that should be attached to a networked [PUN](#) prefab that has [PhotonView](#). It will bind remote [Recorder](#) with local [Speaker](#) of the same networked prefab. This component makes automatic voice stream routing easy for players' characters/avatars.

Inherits [VoiceComponent](#).

Public Member Functions

- void [Init](#) ()
Initializes this [PhotonVoiceView](#) for [Voice](#) usage based on the [PhotonView](#), [Recorder](#) and [Speaker](#) components.

Public Attributes

- bool [AutoCreateRecorderIfNotFound](#)
If true, a [Recorder](#) component will be added to the same [GameObject](#) if not found already.
- bool [UsePrimaryRecorder](#)
If true, [PhotonVoiceNetwork.PrimaryRecorder](#) will be used by this [PhotonVoiceView](#)
- bool [SetupDebugSpeaker](#)
If true, a [Speaker](#) component will be setup to be used for the [DebugEcho](#) mode

Protected Member Functions

- override void [Awake](#) ()

Properties

- [Recorder RecorderInUse](#) [get, set]
The Recorder component currently used by this [PhotonVoiceView](#)
- [Speaker SpeakerInUse](#) [get, set]
The Speaker component currently used by this [PhotonVoiceView](#)
- bool [IsSetup](#) [get]
If true, this [PhotonVoiceView](#) is setup and ready to be used
- bool [IsSpeaker](#) [get]
If true, this [PhotonVoiceView](#) has a Speaker setup for playback of received audio frames from remote audio source
- bool [IsSpeaking](#) [get]
If true, this [PhotonVoiceView](#) has a Speaker that is currently playing received audio frames from remote audio source
- bool [IsRecorder](#) [get]
If true, this [PhotonVoiceView](#) has a Recorder setup for transmission of audio stream from local audio source
- bool [IsRecording](#) [get]
If true, this [PhotonVoiceView](#) has a Recorder that is currently transmitting audio stream from local audio source
- bool [IsSpeakerLinked](#) [get]
If true, the [SpeakerInUse](#) is linked to the remote voice stream
- bool [IsPhotonViewReady](#) [get]
If true, the [PhotonView](#) attached to the same [GameObject](#) has a valid [ViewID](#) > 0

Additional Inherited Members

3.88.1 Detailed Description

Component that should be attached to a networked [PUN](#) prefab that has [PhotonView](#). It will bind remote Recorder with local Speaker of the same networked prefab. This component makes automatic voice stream routing easy for players' characters/avatars.

3.88.2 Member Function Documentation

3.88.2.1 Init()

```
void Init ( )
```

Initializes this [PhotonVoiceView](#) for [Voice](#) usage based on the [PhotonView](#), [Recorder](#) and [Speaker](#) components.

The initialization should happen automatically. Call this method explicitly if this does not succeed. The initialization is a two steps operation: step one is the setup of Recorder and Speaker to be used. Step two is the late-linking -if needed- of the [SpeakerInUse](#) and corresponding remote voice info -if any- via [ViewID](#).

3.88.3 Member Data Documentation

3.88.3.1 AutoCreateRecorderIfNotFound

```
bool AutoCreateRecorderIfNotFound
```

If true, a Recorder component will be added to the same GameObject if not found already.

3.88.3.2 SetupDebugSpeaker

```
bool SetupDebugSpeaker
```

If true, a Speaker component will be setup to be used for the DebugEcho mode

3.88.3.3 UsePrimaryRecorder

```
bool UsePrimaryRecorder
```

If true, [PhotonVoiceNetwork.PrimaryRecorder](#) will be used by this [PhotonVoiceView](#)

3.88.4 Property Documentation

3.88.4.1 IsPhotonViewReady

```
bool IsPhotonViewReady [get]
```

If true, the PhotonView attached to the same GameObject has a valid ViewID > 0

3.88.4.2 IsRecorder

```
bool IsRecorder [get]
```

If true, this [PhotonVoiceView](#) has a Recorder setup for transmission of audio stream from local audio source

3.88.4.3 IsRecording

```
bool IsRecording [get]
```

If true, this [PhotonVoiceView](#) has a Recorder that is currently transmitting audio stream from local audio source

3.88.4.4 IsSetup

```
bool IsSetup [get]
```

If true, this [PhotonVoiceView](#) is setup and ready to be used

3.88.4.5 IsSpeaker

```
bool IsSpeaker [get]
```

If true, this [PhotonVoiceView](#) has a Speaker setup for playback of received audio frames from remote audio source

3.88.4.6 IsSpeakerLinked

```
bool IsSpeakerLinked [get]
```

If true, the SpeakerInUse is linked to the remote voice stream

3.88.4.7 IsSpeaking

```
bool IsSpeaking [get]
```

If true, this [PhotonVoiceView](#) has a Speaker that is currently playing received audio frames from remote audio source

3.88.4.8 RecorderInUse

```
Recorder RecorderInUse [get], [set]
```

The Recorder component currently used by this [PhotonVoiceView](#)

3.88.4.9 SpeakerInUse

```
Speaker SpeakerInUse [get], [set]
```

The Speaker component currently used by this [PhotonVoiceView](#)

3.89 `PrimitiveArrayPool< T >` Class Template Reference

Pool of Arrays with components of type T, with [ObjectPool](#) info being the array's size.

Inherits [ObjectPool< T\[\], int >](#).

Public Member Functions

- **PrimitiveArrayPool** (int capacity, string name)
- **PrimitiveArrayPool** (int capacity, string name, int info)

Protected Member Functions

- override T[] **createObject** (int info)
- override void **destroyObject** (T[] obj)
- override bool **infosMatch** (int i0, int i1)

Additional Inherited Members

3.89.1 Detailed Description

Pool of Arrays with components of type T, with [ObjectPool](#) info being the array's size.

Template Parameters

<i>T</i>	Array element type.
----------	---------------------

3.90 `RawCodec` Class Reference

Classes

- class [Decoder](#)
- class [Encoder](#)

3.91 `Recorder` Class Reference

Component representing outgoing audio stream in scene.

Inherits [VoiceComponent](#).

Classes

- class [PhotonVoiceCreatedParams](#)

Public Types

- enum **InputSourceType**
- enum **MicType**
- enum **SampleTypeConv**

Public Member Functions

- void **Init** ([VoiceClient](#) voiceClient, object customObj=null)
Initializes the [Recorder](#) component to be able to transmit audio.
- void **Init** ([VoiceConnection](#) voiceConnection)
Initializes the [Recorder](#) component to be able to transmit audio.
- void **Relnit** ()
- void **RestartRecording** (bool force=false)
Restarts recording if something has changed that requires this.
- void **VoiceDetectorCalibrate** (int durationMs, Action< float > detectionEndedCallback=null)
Trigger voice detector calibration process. While calibrating, keep silence. [Voice](#) detector sets threshold basing on measured background noise level.
- void **StartRecording** ()
Starts recording.
- void **StopRecording** ()
Stops recording.

Static Public Member Functions

- static bool **CompareUnityMicNames** (string mic1, string mic2)
- static bool **IsDefaultUnityMic** (string mic)

Static Public Attributes

- const int **MIN_OPUS_BITRATE** = 6000
- const int **MAX_OPUS_BITRATE** = 510000

Protected Member Functions

- virtual void **SendPhotonVoiceCreatedMessage** ()

Properties

- static [AudioInEnumerator PhotonMicrophoneEnumerator](#) [get]
Enumerator for the available microphone devices gathered by the [Photon](#) plugin.
- bool [IsInitialized](#) [get]
If true, this [Recorder](#) has been initialized and is ready to transmit to remote clients. Otherwise call [Init\(VoiceConnection\)](#).
- bool [RequiresInit](#) [get]
- bool [RequiresRestart](#) [get, protected set]
Returns true if something has changed in the [Recorder](#) while recording that won't take effect unless recording is restarted using [RestartRecording](#).
- bool [TransmitEnabled](#) [get, set]
If true, audio transmission is enabled.
- bool [Encrypt](#) [get, set]
If true, voice stream is sent encrypted.
- bool [DebugEchoMode](#) [get, set]
If true, outgoing stream routed back to client via server same way as for remote client's streams.
- bool [ReliableMode](#) [get, set]
If true, stream data sent in reliable mode.
- bool [VoiceDetection](#) [get, set]
If true, voice detection enabled.
- float [VoiceDetectionThreshold](#) [get, set]
Voice detection threshold (0..1, where 1 is full amplitude).
- int [VoiceDetectionDelayMs](#) [get, set]
Keep detected state during this time after signal level dropped below threshold. Default is 500ms
- object [UserData](#) [get, set]
Custom user object to be sent in the voice stream info event.
- Func< [IAudioDesc](#) > [InputFactory](#) [get, set]
Set the method returning new [Voice.IAudioDesc](#) instance to be assigned to a new voice created with Source set to Factory
- [AudioUtil.IVoiceDetector?](#) [VoiceDetector](#) [get]
Returns voice activity detector for recorder's audio stream.
- string [UnityMicrophoneDevice](#) [get, set]
Set or get [Unity](#) microphone device used for streaming.
- int [PhotonMicrophoneDeviceId](#) [get, set]
Set or get photon microphone device used for streaming.
- byte [AudioGroup](#) [get, set]
Target interest group that will receive transmitted audio.
- byte [InterestGroup](#) [get, set]
Target interest group that will receive transmitted audio.
- bool [IsCurrentlyTransmitting](#) [get]
Returns true if audio stream broadcasts.
- [AudioUtil.ILevelMeter?](#) [LevelMeter](#) [get]
Level meter utility.
- bool [VoiceDetectorCalibrating](#) [get]
If true, voice detector calibration is in progress.
- [ILocalVoiceAudio](#) **voiceAudio** [get]
- InputSourceType [SourceType](#) [get, set]
Audio data source.
- MicType [MicrophoneType](#) [get, set]
Which microphone API to use when the Source is set to Microphone.
- SampleTypeConv [TypeConvert](#) [get, set]

- *Force creation of 'short' pipeline and convert audio data to short for 'float' audio sources.*
- `AudioClip AudioClip` [get, set]
Source audio clip.
- `bool LoopAudioClip` [get, set]
Loop playback for audio clip sources.
- `SamplingRate SamplingRate` [get, set]
Outgoing audio stream sampling rate.
- `OpusCodec.FrameDuration FrameDuration` [get, set]
Outgoing audio stream encoder delay.
- `int Bitrate` [get, set]
Outgoing audio stream bitrate.
- `bool IsRecording` [get, set]
Gets or sets whether this Recorder is actively recording audio to be transmitted.
- `bool ReactOnSystemChanges` [get, set]
If true, the Recorder will automatically restart recording to recover from audio device changes.
- `bool AutoStart` [get, set]
If true, automatically start recording when initialized.
- `bool RecordOnlyWhenEnabled` [get, set]
If true, component will work only when enabled and active in hierarchy.
- `bool SkipDeviceChangeChecks` [get, set]
If true, restarts recording without checking if audio config/device changes affected recording.
- `bool StopRecordingWhenPaused` [get, set]
If true, stop recording when paused resume/restart when un-paused.
- `bool UseOnAudioFilterRead` [get, set]
If true, recording will make use of Unity's OnAudioFilterRead callback from a muted local AudioSource.
- `bool TrySamplingRateMatch` [get, set]
If true, Recorder will try to match sampling rates of microphone device and Opus encoder to avoid re sampling of audio input.

Additional Inherited Members

3.91.1 Detailed Description

Component representing outgoing audio stream in scene.

3.91.2 Member Function Documentation

3.91.2.1 Init() [1/2]

```
void Init (
    VoiceClient voiceClient,
    object customObj = null )
```

Initializes the Recorder component to be able to transmit audio.

Parameters

<i>voiceClient</i>	The VoiceClient to be used with this Recorder .
<i>customObj</i>	Optional user data object to be transmitted with the voice stream info

3.91.2.2 Init() [2/2]

```
void Init (
    VoiceConnection voiceConnection )
```

Initializes the [Recorder](#) component to be able to transmit audio.

Parameters

<i>voiceConnection</i>	The VoiceConnection to be used with this Recorder .
------------------------	---

3.91.2.3 RestartRecording()

```
void RestartRecording (
    bool force = false )
```

Restarts recording if something has changed that requires this.

Parameters

<i>force</i>	Set to true if you want to restart even if this is not required (RequiresRestart = false)
--------------	---

3.91.2.4 StartRecording()

```
void StartRecording ( )
```

Starts recording.

3.91.2.5 StopRecording()

```
void StopRecording ( )
```

Stops recording.

3.91.2.6 VoiceDetectorCalibrate()

```
void VoiceDetectorCalibrate (
    int durationMs,
    Action< float > detectionEndedCallback = null )
```

Trigger voice detector calibration process. While calibrating, keep silence. [Voice](#) detector sets threshold basing on measured background noise level.

Parameters

<i>durationMs</i>	Duration of calibration in milliseconds.
<i>detectionEndedCallback</i>	Callback when VAD calibration ends.

3.91.3 Property Documentation

3.91.3.1 AudioClip

```
AudioClip AudioClip [get], [set]
```

Source audio clip.

3.91.3.2 AudioGroup

```
byte AudioGroup [get], [set]
```

Target interest group that will receive transmitted audio.

If AudioGroup != 0, recorder's audio data is sent only to clients listening to this group.

3.91.3.3 AutoStart

```
bool AutoStart [get], [set]
```

If true, automatically start recording when initialized.

3.91.3.4 Bitrate

```
int Bitrate [get], [set]
```

Outgoing audio stream bitrate.

3.91.3.5 DebugEchoMode

```
bool DebugEchoMode [get], [set]
```

If true, outgoing stream routed back to client via server same way as for remote client's streams.

3.91.3.6 Encrypt

```
bool Encrypt [get], [set]
```

If true, voice stream is sent encrypted.

3.91.3.7 FrameDuration

```
OpusCodec.FrameDuration FrameDuration [get], [set]
```

Outgoing audio stream encoder delay.

3.91.3.8 InputFactory

```
Func<IAudioDesc> InputFactory [get], [set]
```

Set the method returning new [Voice.IAudioDesc](#) instance to be assigned to a new voice created with Source set to Factory

3.91.3.9 InterestGroup

```
byte InterestGroup [get], [set]
```

Target interest group that will receive transmitted audio.

If InterestGroup != 0, recorder's audio data is sent only to clients listening to this group.

3.91.3.10 IsCurrentlyTransmitting

```
bool IsCurrentlyTransmitting [get]
```

Returns true if audio stream broadcasts.

3.91.3.11 IsInitialized

```
bool IsInitialized [get]
```

If true, this [Recorder](#) has been initialized and is ready to transmit to remote clients. Otherwise call [Init\(VoiceConnection\)](#).

3.91.3.12 IsRecording

```
bool IsRecording [get], [set]
```

Gets or sets whether this [Recorder](#) is actively recording audio to be transmitted.

3.91.3.13 LevelMeter

```
AudioUtil.ILevelMeter? LevelMeter [get]
```

Level meter utility.

3.91.3.14 LoopAudioClip

```
bool LoopAudioClip [get], [set]
```

Loop playback for audio clip sources.

3.91.3.15 MicrophoneType

```
MicType MicrophoneType [get], [set]
```

Which microphone API to use when the Source is set to Microphone.

3.91.3.16 PhotonMicrophoneDeviceId

```
int PhotonMicrophoneDeviceId [get], [set]
```

Set or get photon microphone device used for streaming.

3.91.3.17 PhotonMicrophoneEnumerator

`AudioInEnumerator PhotonMicrophoneEnumerator [static], [get]`

Enumerator for the available microphone devices gathered by the [Photon](#) plugin.

3.91.3.18 ReactOnSystemChanges

`bool ReactOnSystemChanges [get], [set]`

If true, the [Recorder](#) will automatically restart recording to recover from audio device changes.

By default, the [Recorder](#) will restart recording only when the [Recorder.SourceType](#) is `InputSourceType.Microphone` and the device being used is no longer available or valid, in some cases you may need to force restarts even if the device in use did not change. To enable this set [Recorder.SkipDeviceChangeChecks](#) to true.

3.91.3.19 RecordOnlyWhenEnabled

`bool RecordOnlyWhenEnabled [get], [set]`

If true, component will work only when enabled and active in hierarchy.

3.91.3.20 ReliableMode

`bool ReliableMode [get], [set]`

If true, stream data sent in reliable mode.

3.91.3.21 RequiresRestart

`bool RequiresRestart [get], [protected set]`

Returns true if something has changed in the [Recorder](#) while recording that won't take effect unless recording is restarted using [RestartRecording](#).

Think of this as a "isDirty" flag.

3.91.3.22 SamplingRate

`SamplingRate SamplingRate [get], [set]`

Outgoing audio stream sampling rate.

3.91.3.23 SkipDeviceChangeChecks

```
bool SkipDeviceChangeChecks [get], [set]
```

If true, restarts recording without checking if audio config/device changes affected recording.

To be used when [Recorder.ReactOnSystemChanges](#) is true.

3.91.3.24 SourceType

```
InputSourceType SourceType [get], [set]
```

Audio data source.

3.91.3.25 StopRecordingWhenPaused

```
bool StopRecordingWhenPaused [get], [set]
```

If true, stop recording when paused resume/restart when un-paused.

3.91.3.26 TransmitEnabled

```
bool TransmitEnabled [get], [set]
```

If true, audio transmission is enabled.

3.91.3.27 TrySamplingRateMatch

```
bool TrySamplingRateMatch [get], [set]
```

If true, [Recorder](#) will try to match sampling rates of microphone device and Opus encoder to avoid re sampling of audio input.

3.91.3.28 TypeConvert

```
SampleTypeConv TypeConvert [get], [set]
```

Force creation of 'short' pipeline and convert audio data to short for 'float' audio sources.

3.91.3.29 UnityMicrophoneDevice

```
string UnityMicrophoneDevice [get], [set]
```

Set or get [Unity](#) microphone device used for streaming.

3.91.3.30 UseOnAudioFilterRead

```
bool UseOnAudioFilterRead [get], [set]
```

If true, recording will make use of [Unity](#)'s OnAudioFiltlerRead callback from a muted local AudioSource.

If enabled, 3D sounds and voice positioning can be lost.

3.91.3.31 UserData

```
object UserData [get], [set]
```

Custom user object to be sent in the voice stream info event.

3.91.3.32 VoiceDetection

```
bool VoiceDetection [get], [set]
```

If true, voice detection enabled.

3.91.3.33 VoiceDetectionDelayMs

```
int VoiceDetectionDelayMs [get], [set]
```

Keep detected state during this time after signal level dropped below threshold. Default is 500ms

3.91.3.34 VoiceDetectionThreshold

```
float VoiceDetectionThreshold [get], [set]
```

[Voice](#) detection threshold (0..1, where 1 is full amplitude).

3.91.3.35 VoiceDetector

`AudioUtil.IVoiceDetector? VoiceDetector [get]`

Returns voice activity detector for recorder's audio stream.

3.91.3.36 VoiceDetectorCalibrating

`bool VoiceDetectorCalibrating [get]`

If true, voice detector calibration is in progress.

3.92 RemoteVoiceInfo Class Reference

Information about a remote voice (incoming stream).

Properties

- `VoiceInfo Info [get]`
Remote voice info.
- `int ChannelId [get]`
ID of channel used for transmission.
- `int PlayerId [get]`
Player ID of voice owner.
- `byte VoiceId [get]`
Voice ID (unique in the room).

3.92.1 Detailed Description

Information about a remote voice (incoming stream).

3.92.2 Property Documentation

3.92.2.1 ChannelId

`int ChannelId [get]`

ID of channel used for transmission.

3.92.2.2 Info

`VoiceInfo` Info [get]

Remote voice info.

3.92.2.3 PlayerId

`int` `PlayerId` [get]

Player ID of voice owner.

3.92.2.4 VoiceId

`byte` `VoiceId` [get]

`Voice` ID (unique in the room).

3.93 RemoteVoiceLink Class Reference

Public Member Functions

- **RemoteVoiceLink** (`VoiceInfo` info, int playerId, int voiceId, int channelId, ref `RemoteVoiceOptions` options)

Properties

- `VoiceInfo` **Info** [get]
- int **PlayerId** [get]
- int **VoiceId** [get]
- int **ChannelId** [get]

Events

- Action< `FrameOut`< float > > **FloatFrameDecoded**
- Action **RemoteVoiceRemoved**

3.94 RemoteVoiceOptions Struct Reference

Event Actions and other options for a remote voice (incoming stream).

Public Member Functions

- void **SetOutput** (Action< [FrameOut](#)< float >> output)
Register a method to be called when new data frame received..
- void **SetOutput** (Action< [FrameOut](#)< short >> output)
- void **SetOutput** (Action< [ImageOutputBuf](#) > output)

Properties

- Action [OnRemoteVoiceRemoveAction](#) [get, set]
Register a method to be called when the remote voice is removed.
- [IDecoder](#) [Decoder](#) [get, set]
Remote voice data decoder. Use to set decoder options or override it with user decoder.
- ImageFormat **OutputImageFormat** [get, set]
- Flip **OutputImageFlip** [get, set]

3.94.1 Detailed Description

Event Actions and other options for a remote voice (incoming stream).

3.94.2 Member Function Documentation

3.94.2.1 SetOutput()

```
void SetOutput (
    Action< FrameOut< float >> output )
```

Register a method to be called when new data frame received..

3.94.3 Property Documentation

3.94.3.1 Decoder

```
IDecoder Decoder [get], [set]
```

Remote voice data decoder. Use to set decoder options or override it with user decoder.

3.94.3.2 OnRemoteVoiceRemoveAction

Action OnRemoteVoiceRemoveAction [get], [set]

Register a method to be called when the remote voice is removed.

3.95 AudioUtil.Resampler< T > Class Template Reference

Sample-rate conversion Audio Processor.

Inherits [IProcessor< T >](#).

Public Member Functions

- [Resampler](#) (int dstSize, int channels)
Create a new [Resampler](#) instance.
- T[] [Process](#) (T[] buf)
Process a frame of audio data.
- void **Dispose** ()

Protected Attributes

- T[] **frameResampled**

3.95.1 Detailed Description

Sample-rate conversion Audio Processor.

This processor converts the sample-rate of the source stream. Internally, it uses AudioUtil.Resample.

3.95.2 Constructor & Destructor Documentation

3.95.2.1 Resampler()

```
Resampler (
    int dstSize,
    int channels )
```

Create a new [Resampler](#) instance.

Parameters

<i>dstSize</i>	Frame size of a destination frame. Determines output rate.
<i>channels</i>	Number of audio channels expected in both in- and output.

3.95.3 Member Function Documentation

3.95.3.1 Process()

```
T [ ] Process (
    T [ ] buf )
```

Process a frame of audio data.

Parameters

<i>buf</i>	Buffer containing input audio data
------------	------------------------------------

Returns

Buffer containing output audio data or null if frame has been discarded (VAD)

Implements [IProcessor< T >](#).

3.96 Speaker Class Reference

Component representing remote audio stream in local scene.

Inherits [VoiceComponent](#).

Public Member Functions

- bool [StartPlayback](#) ()
Starts the audio playback of the linked incoming remote audio stream via AudioSource component.
- bool [StopPlayback](#) ()
Stops the audio playback of the linked incoming remote audio stream via AudioSource component.
- bool [RestartPlayback](#) ()
Restarts the audio playback of the linked incoming remote audio stream via AudioSource component.

Properties

- int **PlayDelayMs** [get, set]
- bool [IsPlaying](#) [get]
Is the speaker playing right now.
- int? [Lag](#) [get]
Smoothed difference between (jittering) stream and (clock-driven) audioOutput.
- Action< [Speaker](#) > [OnRemoteVoiceRemoveAction](#) [get, set]
Register a method to be called when remote voice removed.
- Realtime.Player [Actor](#) [get, set]
Per room, the connected users/players are represented with a Realtime.Player, also known as Actor.
- bool [IsLinked](#) [get]
Whether or not this [Speaker](#) has been linked to a remote voice stream.
- bool [PlaybackOnlyWhenEnabled](#) [get, set]
If true, component will work only when enabled and active in hierarchy.
- bool [PlaybackStarted](#) [get]
Returns if the playback is on.

Additional Inherited Members

3.96.1 Detailed Description

Component representing remote audio stream in local scene.

3.96.2 Member Function Documentation

3.96.2.1 RestartPlayback()

```
bool RestartPlayback ( )
```

Restarts the audio playback of the linked incoming remote audio stream via AudioSource component.

Returns

True if playback is successfully restarted.

3.96.2.2 StartPlayback()

```
bool StartPlayback ( )
```

Starts the audio playback of the linked incoming remote audio stream via AudioSource component.

Returns

True if playback is successfully started.

3.96.2.3 StopPlayback()

```
bool StopPlayback ( )
```

Stops the audio playback of the linked incoming remote audio stream via AudioSource component.

Returns

True if playback is successfully stopped.

3.96.3 Property Documentation

3.96.3.1 Actor

```
Realtime.Player Actor [get], [set]
```

Per room, the connected users/players are represented with a `Realtime.Player`, also known as Actor.

[Photon Voice](#) calls this Actor, to avoid a name-clash with the Player class in [Voice](#).

3.96.3.2 IsLinked

```
bool IsLinked [get]
```

Whether or not this [Speaker](#) has been linked to a remote voice stream.

3.96.3.3 IsPlaying

```
bool IsPlaying [get]
```

Is the speaker playing right now.

3.96.3.4 Lag

```
int? Lag [get]
```

Smoothed difference between (jittering) stream and (clock-driven) audioOutput.

3.96.3.5 OnRemoteVoiceRemoveAction

```
Action<Speaker> OnRemoteVoiceRemoveAction [get], [set]
```

Register a method to be called when remote voice removed.

3.96.3.6 PlaybackOnlyWhenEnabled

```
bool PlaybackOnlyWhenEnabled [get], [set]
```

If true, component will work only when enabled and active in hierarchy.

3.96.3.7 PlaybackStarted

`bool PlaybackStarted [get]`

Returns if the playback is on.

3.97 TestTone Class Reference

Inherits `MonoBehaviour`.

3.98 AudioUtil.ToneAudioPusher< T > Class Template Reference

[IAudioPusher](#) that provides a constant tone signal.

Inherits [IAudioPusher< T >](#).

Public Member Functions

- [ToneAudioPusher](#) (int frequency=440, int bufSizeMs=100, int samplingRate=441000, int channels=2)
Create a new [ToneAudioReader](#) instance
- void [SetCallback](#) (Action< T[]> callback, [ObjectFactory](#)< T[], int > bufferFactory)
Set the callback function used for pushing data
- void **Dispose** ()

Properties

- int **Channels** [get]
- int **SamplingRate** [get]
- string **Error** [get]

3.98.1 Detailed Description

[IAudioPusher](#) that provides a constant tone signal.

3.98.2 Constructor & Destructor Documentation

3.98.2.1 ToneAudioPusher()

```
ToneAudioPusher (
    int frequency = 440,
    int bufSizeMs = 100,
    int samplingRate = 441000,
    int channels = 2 )
```

Create a new [ToneAudioReader](#) instance

Parameters

<i>frequency</i>	Frequency of the generated tone (in Hz).
<i>bufSizeMs</i>	Size of buffers to push (in milliseconds).
<i>samplingRate</i>	Sampling rate of the audio signal (in Hz).
<i>channels</i>	Number of channels in the audio signal.

3.98.3 Member Function Documentation

3.98.3.1 SetCallback()

```
void SetCallback (
    Action< T[] > callback,
    ObjectFactory< T[], int > bufferFactory )
```

Set the callback function used for pushing data

Parameters

<i>callback</i>	Callback function to use
<i>localVoice</i>	Outgoing audio stream, for context

Implements [IAudioPusher< T >](#).

3.99 AudioUtil.ToneAudioReader< T > Class Template Reference

[IAudioReader](#) that provides a constant tone signal.

Inherits [IAudioReader< T >](#).

Public Member Functions

- [ToneAudioReader](#) (Func< double > clockSec=null, double frequency=440, int samplingRate=441000, int channels=2)
Create a new [ToneAudioReader](#) instance
- void **Dispose** ()
- bool [Read](#) (T[] buf)
Fill full given frame buffer with source uncompressed data or return false if not enough such data.

Properties

- int [Channels](#) [get]
Number of channels in the audio signal.
- int [SamplingRate](#) [get]
Sampling rate of the audio signal (in Hz).
- string [Error](#) [get]
If not null, audio object is in invalid state.

3.99.1 Detailed Description

[IAudioReader](#) that provides a constant tone signal.

See also [MicWrapper](#) and [AudioClipWrapper](#) Because of current resampling algorithm, the tone is distorted if `SamplingRate` does not equal encoder sampling rate.

3.99.2 Constructor & Destructor Documentation

3.99.2.1 ToneAudioReader()

```
ToneAudioReader (
    Func< double > clockSec = null,
    double frequency = 440,
    int samplingRate = 441000,
    int channels = 2 )
```

Create a new [ToneAudioReader](#) instance

Parameters

<i>clockSec</i>	Function to get current time in seconds. In Unity , pass in '()' => <code>AudioSettings.dspTime</code> for better results.
<i>frequency</i>	Frequency of the generated tone (in Hz).
<i>samplingRate</i>	Sampling rate of the audio signal (in Hz).
<i>channels</i>	Number of channels in the audio signal.

3.99.3 Member Function Documentation

3.99.3.1 Read()

```
bool Read (
    T[] buffer )
```

Fill full given frame buffer with source uncompressed data or return false if not enough such data.

Parameters

<i>buffer</i>	Buffer to fill.
---------------	-----------------

Returns

True if buffer was filled successfully, false otherwise.

Implements [IDataReader< T >](#).

3.99.4 Property Documentation

3.99.4.1 Channels

```
int Channels [get]
```

Number of channels in the audio signal.

3.99.4.2 Error

```
string Error [get]
```

If not null, audio object is in invalid state.

3.99.4.3 SamplingRate

```
int SamplingRate [get]
```

Sampling rate of the audio signal (in Hz).

3.100 ToneAudioReader Class Reference

Inherits [IAudioReader< float >](#).

Public Member Functions

- void **Dispose** ()
- bool **Read** (float[] buf)

Properties

- int **Channels** [get]
- int **SamplingRate** [get]
- string **Error** [get]

3.101 UnityAndroidAudioInAEC Class Reference

Inherits [IAudioPusher< short >](#).

Public Member Functions

- **UnityAndroidAudioInAEC** ([Voice.ILogger](#) logger, bool enableAEC=false, bool enableAGC=false, bool enableNS=false)
- void **SetCallback** (Action< short[]> callback, [ObjectFactory](#)< short[], int > bufferFactory)
- void **Dispose** ()

Properties

- int **Channels** [get]
- int **SamplingRate** [get]
- string **Error** [get]

3.102 UnityAudioOut Class Reference

Inherits [IAudioOut< float >](#).

Public Member Functions

- **UnityAudioOut** (AudioSource audioSource, [ILogger](#) logger, string logPrefix, bool debugInfo)
- void **Start** (int frequency, int channels, int frameSamples, int playDelayMs)
- void **Service** ()
- void **Push** (float[] frame)
- void **Flush** ()
- void **Stop** ()

Static Public Attributes

- const int **FRAME_POOL_CAPACITY** = 50

Properties

- int? **Lag** [get]
- bool **IsPlaying** [get]

3.103 UnityMicrophone Class Reference

A wrapper around UnityEngine.Microphone to be able to safely use Microphone and compile for WebGL.

Static Public Member Functions

- static void **End** (string deviceName)
- static void **GetDeviceCaps** (string deviceName, out int minFreq, out int maxFreq)
- static int **GetPosition** (string deviceName)
- static bool **IsRecording** (string deviceName)
- static AudioClip **Start** (string deviceName, bool loop, int lengthSec, int frequency)

Properties

- static string[] **devices** [get]

3.103.1 Detailed Description

A wrapper around UnityEngine.Microphone to be able to safely use Microphone and compile for WebGL.

3.104 UnsupportedCodecException Class Reference

Exception thrown if an unsupported codec is encountered.

Inherits Exception.

Public Member Functions

- [UnsupportedCodecException](#) (string info, [Codec](#) codec, [ILogger](#) logger)
Create a new [UnsupportedCodecException](#).

3.104.1 Detailed Description

Exception thrown if an unsupported codec is encountered.

PhotonVoice currently only supports one Codec, [Codec.AudioOpus](#).

3.104.2 Constructor & Destructor Documentation

3.104.2.1 UnsupportedCodecException()

```
UnsupportedCodecException (  
    string info,  
    Codec codec,  
    ILogger logger )
```

Create a new [UnsupportedCodecException](#).

Parameters

<i>info</i>	The info prepending standard message.
<i>codec</i>	The codec actually encountered.
<i>logger</i>	Logger.

3.105 UnsupportedSampleTypeException Class Reference

Exception thrown if an unsupported audio sample type is encountered.

Inherits Exception.

Public Member Functions

- [UnsupportedSampleTypeException](#) (Type t)
Create a new [UnsupportedSampleTypeException](#).

3.105.1 Detailed Description

Exception thrown if an unsupported audio sample type is encountered.

PhotonVoice generally supports 32-bit floating point ("float") or 16-bit signed integer ("short") audio, but it usually won't be converted automatically due to the high CPU overhead (and potential loss of precision) involved.

3.105.2 Constructor & Destructor Documentation

3.105.2.1 UnsupportedSampleTypeException()

```
UnsupportedSampleTypeException (  
    Type t )
```

Create a new [UnsupportedSampleTypeException](#).

Parameters

<i>t</i>	The sample type actually encountered.
----------	---------------------------------------

3.106 OpusCodec.Util Class Reference

3.107 VoiceClient Class Reference

Voice client interact with other clients on network via [IVoiceTransport](#).

Inherits [IDisposable](#).

Public Member Functions

- delegate void [RemoteVoiceInfoDelegate](#) (int channelId, int playerId, byte voiceId, [VoiceInfo](#) voiceInfo, ref [RemoteVoiceOptions](#) options)
Remote voice info event delegate.
- [IEnumerable](#)< [LocalVoice](#) > [LocalVoicesInChannel](#) (int channelId)
Iterates through copy of all local voices list of given channel.
- void **LogRemoteVoiceStates** ()
- void [Service](#) ()
This method dispatches all available incoming commands and then sends this client's outgoing commands. Call this method regularly (2..20 times a second).
- [LocalVoice](#) [CreateLocalVoice](#) ([VoiceInfo](#) voiceInfo, int channelId=0, [IEncoder](#) encoder=null)
Creates basic outgoing stream w/o data processing support. Provided encoder should generate output data stream.
- [LocalVoiceFramed](#)< T > [CreateLocalVoiceFramed](#)< T > ([VoiceInfo](#) voiceInfo, int frameSize, int channelId=0, [IEncoder](#) encoder=null)
Creates outgoing stream consuming sequence of values passed in array buffers of arbitrary length which repacked in frames of constant length for further processing and encoding.
- [LocalVoiceAudio](#)< T > [CreateLocalVoiceAudio](#)< T > ([VoiceInfo](#) voiceInfo, [IAudioDesc](#) audioSourceDesc, int channelId=0, [IEncoder](#) encoder=null)
Creates outgoing audio stream. Adds audio specific features (e.g. resampling, level meter) to processing pipeline and to returning stream handler.
- [LocalVoice](#) [CreateLocalVoiceAudioFromSource](#) ([VoiceInfo](#) voiceInfo, [IAudioDesc](#) source, [AudioSampleType](#) sampleType, int channelId=0, [IEncoder](#) encoder=null)
Creates outgoing audio stream of type automatically assigned and adds procedures (callback or serviceable) for consuming given audio source data. Adds audio specific features (e.g. resampling, level meter) to processing pipeline and to returning stream handler.
- void [RemoveLocalVoice](#) ([LocalVoice](#) voice)
Removes local voice (outgoing data stream).

Parameters

voice	Handler of outgoing stream to be removed.
-------	---

- void **Dispose** ()

Properties

- int [FramesLost](#) [get, set]
Lost frames counter.
- int [FramesReceived](#) [get]
Received frames counter.
- int [FramesSent](#) [get]

- Sent frames counter.*
 - int [FramesSentBytes](#) [get]
- Sent frames bytes counter.*
 - int [RoundTripTime](#) [get]
- Average time required voice packet to return to sender.*
 - int [RoundTripTimeVariance](#) [get]
- Average round trip time variation.*
 - bool [SuppressInfoDuplicateWarning](#) [get, set]
- Do not log warning when duplicate info received.*
 - [RemoteVoiceInfoDelegate OnRemoteVoiceInfoAction](#) [get, set]
- Register a method to be called when remote voice info arrived (after join or new new remote voice creation). Metod parameters: (int channelId, int playerId, byte voiceId, [VoiceInfo](#) voiceInfo, ref [RemoteVoiceOptions](#) options);*
 - int [DebugLostPercent](#) [get, set]
- Lost frames simulation ratio.*
 - IEnumerable< [LocalVoice](#) > [LocalVoices](#) [get]
- Iterates through copy of all local voices list.*
 - IEnumerable< [RemoteVoiceInfo](#) > [RemoteVoiceInfos](#) [get]
- Iterates through all remote voices infos.*

3.107.1 Detailed Description

[Voice](#) client interact with other clients on network via [IVoiceTransport](#).

3.107.2 Member Function Documentation

3.107.2.1 CreateLocalVoice()

```
LocalVoice CreateLocalVoice (
    VoiceInfo voiceInfo,
    int channelId = 0,
    IEncoder encoder = null )
```

Creates basic outgoing stream w/o data processing support. Provided encoder should generate output data stream.

Parameters

<i>voiceInfo</i>	Outgoing stream parameters. Set applicable fields to read them by encoder and by receiving client when voice created.
<i>channelId</i>	Transport channel specific to transport.
<i>encoder</i>	Encoder producing the stream.

Returns

Outgoing stream handler.

3.107.2.2 CreateLocalVoiceAudio< T >()

```
LocalVoiceAudio<T> CreateLocalVoiceAudio< T > (
    VoiceInfo voiceInfo,
    IAudioDesc audioSourceDesc,
    int channelId = 0,
    IEncoder encoder = null )
```

Creates outgoing audio stream. Adds audio specific features (e.g. resampling, level meter) to processing pipeline and to returning stream handler.

Template Parameters

<i>T</i>	Element type of audio array buffers.
----------	--------------------------------------

Parameters

<i>voiceInfo</i>	Outgoing audio stream parameters. Set applicable fields to read them by encoder and by receiving client when voice created.
<i>channelId</i>	Transport channel specific to transport.
<i>encoder</i>	Audio encoder. Set to null to use default Opus encoder.

Returns

Outgoing stream handler.

audioSourceDesc.SamplingRate and voiceInfo.SamplingRate may do not match. Automatic resampling will occur in this case.

3.107.2.3 CreateLocalVoiceAudioFromSource()

```
LocalVoice CreateLocalVoiceAudioFromSource (
    VoiceInfo voiceInfo,
    IAudioDesc source,
    AudioSampleType sampleType,
    int channelId = 0,
    IEncoder encoder = null )
```

Creates outgoing audio stream of type automatically assigned and adds procedures (callback or serviceable) for consuming given audio source data. Adds audio specific features (e.g. resampling, level meter) to processing pipeline and to returning stream handler.

Parameters

<i>voiceInfo</i>	Outgoing audio stream parameters. Set applicable fields to read them by encoder and by receiving client when voice created.
<i>source</i>	Streaming audio source.
<i>sampleType</i>	Voice 's audio sample type. If does not match source audio sample type, conversion will occur.
<i>channelId</i>	Transport channel specific to transport.
<i>encoder</i>	Audio encoder. Set to null to use default Opus encoder.

Returns

Outgoing stream handler.

audioSourceDesc.SamplingRate and voiceInfo.SamplingRate may do not match. Automatic resampling will occur in this case.

3.107.2.4 CreateLocalVoiceFramed< T >()

```
LocalVoiceFramed<T> CreateLocalVoiceFramed< T > (
    VoiceInfo voiceInfo,
    int frameSize,
    int channelId = 0,
    IEncoder encoder = null )
```

Creates outgoing stream consuming sequence of values passed in array buffers of arbitrary length which repacked in frames of constant length for further processing and encoding.

Template Parameters

<i>T</i>	Type of data consumed by outgoing stream (element type of array buffers).
----------	---

Parameters

<i>voiceInfo</i>	Outgoing stream parameters. Set applicable fields to read them by encoder and by receiving client when voice created.
<i>frameSize</i>	Size of buffer LocalVoiceFramed repacks input data stream to.
<i>channelId</i>	Transport channel specific to transport.
<i>encoder</i>	Encoder compressing data stream in pipeline.

Returns

Outgoing stream handler.

3.107.2.5 LocalVoicesInChannel()

```
IEnumerable<LocalVoice> LocalVoicesInChannel (
    int channelId )
```

Iterates through copy of all local voices list of given channel.

3.107.2.6 RemoteVoiceInfoDelegate()

```
delegate void RemoteVoiceInfoDelegate (
    int channelId,
    int playerId,
    byte voiceId,
    VoiceInfo voiceInfo,
    ref RemoteVoiceOptions options )
```

Remote voice info event delegate.

3.107.2.7 RemoveLocalVoice()

```
void RemoveLocalVoice (
    LocalVoice voice )
```

Removes local voice (outgoing data stream).

Parameters

<i>voice</i>	Handler of outgoing stream to be removed.
--------------	---

3.107.2.8 Service()

```
void Service ( )
```

This method dispatches all available incoming commands and then sends this client's outgoing commands. Call this method regularly (2..20 times a second).

3.107.3 Property Documentation

3.107.3.1 DebugLostPercent

```
int DebugLostPercent [get], [set]
```

Lost frames simulation ratio.

3.107.3.2 FramesLost

```
int FramesLost [get], [set]
```

Lost frames counter.

3.107.3.3 FramesReceived

```
int FramesReceived [get]
```

Received frames counter.

3.107.3.4 FramesSent

```
int FramesSent [get]
```

Sent frames counter.

3.107.3.5 FramesSentBytes

```
int FramesSentBytes [get]
```

Sent frames bytes counter.

3.107.3.6 LocalVoices

```
IEnumerable<LocalVoice> LocalVoices [get]
```

Iterates through copy of all local voices list.

3.107.3.7 OnRemoteVoiceInfoAction

```
RemoteVoiceInfoDelegate OnRemoteVoiceInfoAction [get], [set]
```

Register a method to be called when remote voice info arrived (after join or new new remote voice creation). Metod parameters: (int channelId, int playerId, byte voiceId, [VoiceInfo](#) voiceInfo, ref [RemoteVoiceOptions](#) options);

3.107.3.8 RemoteVoiceInfos

```
IEnumerable<RemoteVoiceInfo> RemoteVoiceInfos [get]
```

Iterates through all remote voices infos.

3.107.3.9 RoundTripTime

```
int RoundTripTime [get]
```

Average time required voice packet to return to sender.

3.107.3.10 RoundTripTimeVariance

```
int RoundTripTimeVariance [get]
```

Average round trip time variation.

3.107.3.11 SuppressInfoDuplicateWarning

```
bool SuppressInfoDuplicateWarning [get], [set]
```

Do not log warning when duplicate info received.

3.108 VoiceComponent Class Reference

Inherits MonoBehaviour, and [ILoggableDependent](#).

Inherited by [PhotonVoiceView](#), [Recorder](#), [Speaker](#), [MicAmplifier](#), and [WebRtcAudioDsp](#).

Protected Member Functions

- virtual void **Awake** ()

Protected Attributes

- DebugLevel **logLevel** = DebugLevel.INFO

Properties

- [VoiceLogger](#) **Logger** [get, protected set]
- DebugLevel **LogLevel** [get, set]
- bool **IgnoreGlobalLogLevel** [get, set]

3.109 VoiceConnection Class Reference

Component that represents a client voice connection to [Photon](#) Servers.

Inherits [ConnectionHandler](#), and [ILoggable](#).

Inherited by [PhotonVoiceNetwork](#).

Public Member Functions

- bool [ConnectUsingSettings](#) (AppSettings overwriteSettings=null)
Connect to [Photon](#) server using [Settings](#)
- void [InitRecorder](#) ([Recorder](#) rec)
Initializes the [Recorder](#) component to be able to transmit audio.

Public Attributes

- AppSettings [Settings](#)
Settings to be used by this voice connection
- Func< int, byte, object, [Speaker](#) > [SpeakerFactory](#)
Special factory to link [Speaker](#) components with incoming remote audio streams
- float [MinimalTimeScaleToDispatchInFixedUpdate](#) = -1f
Configures the minimal Time.timeScale at which [Voice](#) client will dispatch incoming messages within LateUpdate.
- bool [AutoCreateSpeakerIfNotFound](#) = true
Auto instantiate a GameObject and attach a [Speaker](#) component to link to a remote audio stream if no candidate could be found

Protected Member Functions

- override void **Awake** ()
- virtual void **Update** ()
- virtual void **FixedUpdate** ()
- void [Dispatch](#) ()
Dispatches incoming network messages for [Voice](#) client. Called in FixedUpdate or LateUpdate.
- override void **OnDisable** ()
- virtual void **OnDestroy** ()
- virtual [Speaker](#) **SimpleSpeakerFactory** (int playerId, byte voiceId, object userData)
- virtual void **OnVoiceStateChanged** ([ClientState](#) fromState, [ClientState](#) toState)
- void **CalcStatistics** ()
- void **LinkSpeaker** ([Speaker](#) speaker, [RemoteVoiceLink](#) remoteVoice)

Protected Attributes

- List< [RemoteVoiceLink](#) > **cachedRemoteVoices** = new List<[RemoteVoiceLink](#)>()

Properties

- [VoiceLogger](#) [Logger](#) [get, protected set]
Logger used by this component
- DebugLevel [LogLevel](#) [get, set]
Log level for this component
- new [LoadBalancingTransport](#) **Client** [get]
- [VoiceClient](#) [VoiceClient](#) [get]
Returns underlying [Photon Voice](#) client.
- ClientState [ClientState](#) [get]
Returns [Photon Voice](#) client state.
- float [FramesReceivedPerSecond](#) [get]
Number of frames received per second.
- float [FramesLostPerSecond](#) [get]
Number of frames lost per second.
- float [FramesLostPercent](#) [get]
Percentage of lost frames.
- GameObject [SpeakerPrefab](#) [get, set]
Prefab that contains [Speaker](#) component to be instantiated when receiving a new remote audio source info
- [Recorder](#) [PrimaryRecorder](#) [get, set]
Main [Recorder](#) to be used for transmission by default
- DebugLevel **GlobalRecordersLogLevel** [get, set]
- DebugLevel **GlobalSpeakersLogLevel** [get, set]
- int **GlobalPlaybackDelay** [get, set]
- string [BestRegionSummaryInPreferences](#) [get, set]
Used to store and access the "Best Region Summary" in the Player Preferences.

Events

- Action< [Speaker](#) > [SpeakerLinked](#)
Fires when a speaker has been linked to a remote audio stream
- Action< [RemoteVoiceLink](#) > [RemoteVoiceAdded](#)
Fires when a remote voice stream is added

3.109.1 Detailed Description

Component that represents a client voice connection to [Photon](#) Servers.

3.109.2 Member Function Documentation

3.109.2.1 ConnectUsingSettings()

```
bool ConnectUsingSettings (
    AppSettings overwriteSettings = null )
```

Connect to [Photon](#) server using [Settings](#)

Parameters

<code>overwriteSettings</code>	Overwrites Settings before connecting
--------------------------------	---

Returns

If true voice connection command was sent from client

3.109.2.2 Dispatch()

```
void Dispatch ( ) [protected]
```

Dispatches incoming network messages for [Voice](#) client. Called in FixedUpdate or LateUpdate.

It may make sense to dispatch incoming messages, even if the timeScale is near 0. That can be configured with [MinimalTimeScaleToDispatchInFixedUpdate](#).

Without dispatching messages, [Voice](#) client won't change state and does not handle updates.

3.109.2.3 InitRecorder()

```
void InitRecorder (
    Recorder rec )
```

Initializes the [Recorder](#) component to be able to transmit audio.

Parameters

<code>rec</code>	The Recorder to be initialized.
------------------	---

3.109.3 Member Data Documentation**3.109.3.1 AutoCreateSpeakerIfNotFound**

```
bool AutoCreateSpeakerIfNotFound = true
```

Auto instantiate a GameObject and attach a [Speaker](#) component to link to a remote audio stream if no candidate could be found

3.109.3.2 MinimalTimeScaleToDispatchInFixedUpdate

```
float MinimalTimeScaleToDispatchInFixedUpdate = -1f
```

Configures the minimal Time.timeScale at which [Voice](#) client will dispatch incoming messages within LateUpdate.

It may make sense to dispatch incoming messages, even if the timeScale is near 0. In some cases, stopping the game time makes sense, so this option defaults to -1f, which is "off". Without dispatching messages, [Voice](#) client won't change state and does not handle updates.

3.109.3.3 Settings

```
AppSettings Settings
```

Settings to be used by this voice connection

3.109.3.4 SpeakerFactory

```
Func<int, byte, object, Speaker> SpeakerFactory
```

Special factory to link [Speaker](#) components with incoming remote audio streams

3.109.4 Property Documentation

3.109.4.1 BestRegionSummaryInPreferences

```
string BestRegionSummaryInPreferences [get], [set]
```

Used to store and access the "Best Region Summary" in the Player Preferences.

3.109.4.2 ClientState

```
ClientState ClientState [get]
```

Returns [Photon Voice](#) client state.

3.109.4.3 FramesLostPercent

```
float FramesLostPercent [get]
```

Percentage of lost frames.

3.109.4.4 FramesLostPerSecond

```
float FramesLostPerSecond [get]
```

Number of frames lost per second.

3.109.4.5 FramesReceivedPerSecond

```
float FramesReceivedPerSecond [get]
```

Number of frames received per second.

3.109.4.6 Logger

```
VoiceLogger Logger [get], [protected set]
```

[Logger](#) used by this component

3.109.4.7 LogLevel

```
DebugLevel LogLevel [get], [set]
```

Log level for this component

3.109.4.8 PrimaryRecorder

```
Recorder PrimaryRecorder [get], [set]
```

Main [Recorder](#) to be used for transmission by default

3.109.4.9 SpeakerPrefab

GameObject SpeakerPrefab [get], [set]

Prefab that contains [Speaker](#) component to be instantiated when receiving a new remote audio source info

3.109.4.10 VoiceClient

VoiceClient VoiceClient [get]

Returns underlying [Photon Voice](#) client.

3.109.5 Event Documentation

3.109.5.1 RemoteVoiceAdded

Action<[RemoteVoiceLink](#)> RemoteVoiceAdded

Fires when a remote voice stream is added

3.109.5.2 SpeakerLinked

Action<[Speaker](#)> SpeakerLinked

Fires when a speaker has been linked to a remote audio stream

3.110 AudioUtil.VoiceDetector< T > Class Template Reference

Simple voice activity detector triggered by signal level.

Inherits [IProcessor< T >](#), and [AudioUtil.IVoiceDetector](#).

Public Member Functions

- abstract T[] [Process](#) (T[] buf)
Process a frame of audio data.
- void **Dispose** ()

Protected Attributes

- float **norm**
- float **threshold**
- int **activityDelay**
- int **autoSilenceCounter** = 0
- int **valuesCountPerSec**
- int **activityDelayValuesCount**

Properties

- bool **On** [get, set]
If true, voice detection enabled.
- float **Threshold** [get, set]
Voice detected as soon as signal level exceeds threshold.
- bool **Detected** [get, protected set]
If true, voice detected.
- DateTime **DetectedTime** [get]
Last time when switched to detected state.
- int **ActivityDelayMs** [get, set]
Keep detected state during this time after signal level dropped below threshold.

Events

- Action **OnDetected**
Called when switched to detected state.

3.110.1 Detailed Description

Simple voice activity detector triggered by signal level.

3.110.2 Member Function Documentation

3.110.2.1 Process()

```
abstract T [] Process (
    T[] buf ) [pure virtual]
```

Process a frame of audio data.

Parameters

<i>buf</i>	Buffer containing input audio data
------------	------------------------------------

Returns

Buffer containing output audio data or null if frame has been discarded (VAD)

Implements [IProcessor< T >](#).

3.110.3 Property Documentation

3.110.3.1 ActivityDelayMs

```
int ActivityDelayMs [get], [set]
```

Keep detected state during this time after signal level dropped below threshold.

3.110.3.2 Detected

```
bool Detected [get], [protected set]
```

If true, voice detected.

3.110.3.3 DetectedTime

```
DateTime DetectedTime [get]
```

Last time when switched to detected state.

3.110.3.4 On

```
bool On [get], [set]
```

If true, voice detection enabled.

3.110.3.5 Threshold

```
float Threshold [get], [set]
```

[Voice](#) detected as soon as signal level exceeds threshold.

3.110.4 Event Documentation

3.110.4.1 OnDetected

Action OnDetected

Called when switched to detected state.

3.111 AudioUtil.VoiceDetectorCalibration< T > Class Template Reference

Calibration Utility for [Voice](#) Detector

Inherits [IProcessor< T >](#).

Public Member Functions

- [VoiceDetectorCalibration](#) ([IVoiceDetector](#) voiceDetector, [ILevelMeter](#) levelMeter, int samplingRate, int channels)
Create new [VoiceDetectorCalibration](#) instance.
- void [Calibrate](#) (int durationMs, Action< float > onCalibrated=null)
Start calibration.
- T[] [Process](#) (T[] buf)
Process a frame of audio data.
- void [Dispose](#) ()

Protected Attributes

- int [calibrateCount](#)

Properties

- bool [IsCalibrating](#) [get]

3.111.1 Detailed Description

Calibration Utility for [Voice](#) Detector

. Using this audio processor, you can calibrate the [IVoiceDetector.Threshold](#).

3.111.2 Constructor & Destructor Documentation

3.111.2.1 VoiceDetectorCalibration()

```
VoiceDetectorCalibration (
    IVoiceDetector voiceDetector,
    ILevelMeter levelMeter,
    int samplingRate,
    int channels )
```

Create new [VoiceDetectorCalibration](#) instance.

Parameters

<i>voiceDetector</i>	Voice Detector to calibrate.
<i>levelMeter</i>	Level Meter to look at for calibration.
<i>samplingRate</i>	Sampling rate of the audio signal (in Hz).
<i>numChannels</i>	Number of channels in the audio signal.

3.111.3 Member Function Documentation

3.111.3.1 Calibrate()

```
void Calibrate (
    int durationMs,
    Action< float > onCalibrated = null )
```

Start calibration.

Parameters

<i>durationMs</i>	Duration of the calibration procedure (in milliseconds).
-------------------	--

This activates the Calibration process. It will reset the given [LevelMeter](#)'s AccumAvgPeakAmp (accumulated average peak amplitude), and when the duration has passed, use it for the [VoiceDetector](#)'s detection threshold.

3.111.3.2 Process()

```
T [ ] Process (
    T [ ] buf )
```

Process a frame of audio data.

Parameters

<i>buf</i>	Buffer containing input audio data
------------	------------------------------------

Returns

Buffer containing output audio data or null if frame has been discarded (VAD)

Implements [IProcessor< T >](#).

3.112 AudioUtil.VoiceDetectorDummy Class Reference

Dummy [VoiceDetector](#) that doesn't actually do anything.

Inherits [AudioUtil.IVoiceDetector](#).

Properties

- bool **On** [get, set]
- float **Threshold** [get, set]
- bool **Detected** [get]
- int **ActivityDelayMs** [get, set]
- DateTime **DetectedTime** [get]
- Action **OnDetected**

Additional Inherited Members

3.112.1 Detailed Description

Dummy [VoiceDetector](#) that doesn't actually do anything.

3.113 AudioUtil.VoiceDetectorFloat Class Reference

[VoiceDetector](#) specialization for float audio.

Inherits [AudioUtil.VoiceDetector< float >](#).

Public Member Functions

- [VoiceDetectorFloat](#) (int samplingRate, int numChannels)
Create a new [VoiceDetectorFloat](#) instance.
- override float[] **Process** (float[] buffer)

Additional Inherited Members

3.113.1 Detailed Description

[VoiceDetector](#) specialization for float audio.

3.113.2 Constructor & Destructor Documentation

3.113.2.1 VoiceDetectorFloat()

```
VoiceDetectorFloat (  
    int samplingRate,  
    int numChannels )
```

Create a new [VoiceDetectorFloat](#) instance.

Parameters

<i>samplingRate</i>	Sampling rate of the audio signal (in Hz).
<i>numChannels</i>	Number of channels in the audio signal.

3.114 AudioUtil.VoiceDetectorShort Class Reference

[VoiceDetector](#) specialization for float audio.

Inherits [AudioUtil.VoiceDetector< short >](#).

Public Member Functions

- [VoiceDetectorShort](#) (int samplingRate, int numChannels)
Create a new [VoiceDetectorFloat](#) instance
- override short[] **Process** (short[] buffer)

Additional Inherited Members

3.114.1 Detailed Description

[VoiceDetector](#) specialization for float audio.

3.114.2 Constructor & Destructor Documentation

3.114.2.1 VoiceDetectorShort()

```
VoiceDetectorShort (  
    int samplingRate,  
    int numChannels )
```

Create a new [VoiceDetectorFloat](#) instance

Parameters

<i>samplingRate</i>	Sampling rate of the audio signal (in Hz).
<i>numChannels</i>	Number of channels in the audio signal.

3.115 VoiceEvent Class Reference

Static Public Attributes

- const byte [Code](#) = 202
Single event used for voice communications.
- const byte **FrameCode** = 203

3.115.1 Member Data Documentation

3.115.1.1 Code

```
const byte Code = 202 [static]
```

Single event used for voice communications.

Change if it conflicts with other event codes used in the same [Photon](#) room.

3.116 VoicelInfo Struct Reference

Describes stream properties.

Public Member Functions

- override string **ToString** ()

Static Public Member Functions

- static [VoicelInfo CreateAudioOpus](#) (POpusCodec.Enums.SamplingRate samplingRate, int channels, Opus↔Codec.FrameDuration frameDurationUs, int bitrate, object userdata=null)
Create stream info for an Opus audio stream.
- static [VoicelInfo CreateAudio](#) ([Codec](#) codec, int samplingRate, int channels, int frameDurationUs, object userdata=null)
Create stream info for an Opus audio stream.

Properties

- [Codec](#) [Codec](#) [get, set]
- int [SamplingRate](#) [get, set]
Audio sampling rate (frequency, in Hz).
- int [Channels](#) [get, set]
Number of channels.
- int [FrameDurationUs](#) [get, set]
Uncompressed frame (audio packet) size in microseconds.
- int [Bitrate](#) [get, set]
Target bitrate (in bits/second).
- int [Width](#) [get, set]
Video width (optional).
- int [Height](#) [get, set]
Video height (optional)
- object [UserData](#) [get, set]
Optional user data. Should be serializable by [Photon](#).
- int [FrameDurationSamples](#) [get]
Uncompressed frame (data packet) size in samples.
- int [FrameSize](#) [get]
Uncompressed frame (data packet) array size.

3.116.1 Detailed Description

Describes stream properties.

3.116.2 Member Function Documentation

3.116.2.1 CreateAudio()

```
static VoiceInfo CreateAudio (  
    Codec codec,  
    int samplingRate,  
    int channels,  
    int frameDurationUs,  
    object userdata = null ) [static]
```

Create stream info for an Opus audio stream.

Parameters

<i>samplingRate</i>	Audio sampling rate.
<i>channels</i>	Number of channels.
<i>frameDurationUs</i>	Uncompressed frame (audio packet) size in microseconds.
<i>bitrate</i>	Stream bitrate (in bits/second).
<i>userdata</i>	Optional user data. Should be serializable by Photon .

Returns

[VoiceInfo](#) instance.

3.116.2.2 CreateAudioOpus()

```
static VoiceInfo CreateAudioOpus (
    POpusCodec.Enums.SamplingRate samplingRate,
    int channels,
    OpusCodec.FrameDuration frameDurationUs,
    int bitrate,
    object userdata = null ) [static]
```

Create stream info for an Opus audio stream.

Parameters

<i>samplingRate</i>	Audio sampling rate.
<i>channels</i>	Number of channels.
<i>frameDurationUs</i>	Uncompressed frame (audio packet) size in microseconds.
<i>bitrate</i>	Stream bitrate (in bits/second).
<i>userdata</i>	Optional user data. Should be serializable by Photon .

Returns

[VoiceInfo](#) instance.

3.116.3 Property Documentation**3.116.3.1 Bitrate**

```
int Bitrate [get], [set]
```

Target bitrate (in bits/second).

3.116.3.2 Channels

```
int Channels [get], [set]
```

Number of channels.

3.116.3.3 FrameDurationSamples

```
int FrameDurationSamples [get]
```

Uncompressed frame (data packet) size in samples.

3.116.3.4 FrameDurationUs

```
int FrameDurationUs [get], [set]
```

Uncompressed frame (audio packet) size in microseconds.

3.116.3.5 FrameSize

```
int FrameSize [get]
```

Uncompressed frame (data packet) array size.

3.116.3.6 Height

```
int Height [get], [set]
```

Video height (optional)

3.116.3.7 SamplingRate

```
int SamplingRate [get], [set]
```

Audio sampling rate (frequency, in Hz).

3.116.3.8 UserData

```
object UserData [get], [set]
```

Optional user data. Should be serializable by [Photon](#).

3.116.3.9 Width

`int Width [get], [set]`

Video width (optional).

3.117 AudioUtil.VoiceLevelDetectCalibrate< T > Class Template Reference

Utility Audio Processor [Voice](#) Detection Calibration.

Inherits [IProcessor< T >](#).

Public Member Functions

- [VoiceLevelDetectCalibrate](#) (int `samplingRate`, int `channels`)
Create new [VoiceLevelDetectCalibrate](#) instance
- void [Calibrate](#) (int `durationMs`, Action< float > `onCalibrated`=null)
Start calibration
- T[] [Process](#) (T[] `buf`)
Process a frame of audio data.
- void **Dispose** ()

Properties

- [ILevelMeter](#) [LevelMeter](#) [get]
The [LevelMeter](#) in use.
- [IVoiceDetector](#) [VoiceDetector](#) [get]
The [VoiceDetector](#) in use
- bool **IsCalibrating** [get]

3.117.1 Detailed Description

Utility Audio Processor [Voice](#) Detection Calibration.

Encapsulates level meter, voice detector and voice detector calibrator in single instance.

3.117.2 Constructor & Destructor Documentation

3.117.2.1 VoiceLevelDetectCalibrate()

```
VoiceLevelDetectCalibrate (
    int samplingRate,
    int channels )
```

Create new [VoiceLevelDetectCalibrate](#) instance

Parameters

<i>samplingRate</i>	Sampling rate of the audio signal (in Hz).
<i>numChannels</i>	Number of channels in the audio signal.

3.117.3 Member Function Documentation

3.117.3.1 Calibrate()

```
void Calibrate (
    int durationMs,
    Action< float > onCalibrated = null )
```

Start calibration

Parameters

<i>durationMs</i>	Duration of the calibration procedure (in milliseconds).
<i>onCalibrated</i>	Called when calibration is complete. Parameter is new threshold value.

This activates the Calibration process. It will reset the given [LevelMeter](#)'s AccumAvgPeakAmp (accumulated average peak amplitude), and when the duration has passed, use it for the [VoiceDetector](#)'s detection threshold.

3.117.3.2 Process()

```
T [ ] Process (
    T [ ] buf )
```

Process a frame of audio data.

Parameters

<i>buf</i>	Buffer containing input audio data
------------	------------------------------------

Returns

Buffer containing output audio data or null if frame has been discarded (VAD)

Implements [IProcessor< T >](#).

3.117.4 Property Documentation

3.117.4.1 LevelMeter

`ILevelMeter LevelMeter` [get]

The [LevelMeter](#) in use.

3.117.4.2 VoiceDetector

`IVoiceDetector VoiceDetector` [get]

The [VoiceDetector](#) in use

3.118 VoiceLogger Class Reference

Inherits [ILogger](#).

Public Member Functions

- **VoiceLogger** (Object context, string tag, DebugLevel level=DebugLevel.ERROR)
- **VoiceLogger** (string tag, DebugLevel level=DebugLevel.ERROR)
- void **LogError** (string fmt, params object[] args)
- void **LogWarning** (string fmt, params object[] args)
- void **LogInfo** (string fmt, params object[] args)
- void **LogDebug** (string fmt, params object[] args)

Properties

- string **Tag** [get, set]
- DebugLevel **LogLevel** [get, set]
- bool **IsErrorEnabled** [get]
- bool **IsWarningEnabled** [get]
- bool **IsInfoEnabled** [get]
- bool **IsDebugEnabled** [get]

3.119 WebRtcAudioDsp Class Reference

Inherits [VoiceComponent](#).

Public Member Functions

- bool **SetOrSwitchAudioListener** (AudioListener audioListener)
Set the *AudioListener* to be used with this [WebRtcAudioDsp](#)
- bool **SetOrSwitchAudioOutCapture** (AudioOutCapture audioOutCapture)
Set the *AudioOutCapture* to be used with this [WebRtcAudioDsp](#)

Public Attributes

- bool **AECMobileComfortNoise**

Protected Member Functions

- override void **Awake** ()

Properties

- bool **AEC** [get, set]
- bool **AECMobile** [get, set]
- int **ReverseStreamDelayMs** [get, set]
- bool **NoiseSuppression** [get, set]
- bool **HighPass** [get, set]
- bool **Bypass** [get, set]
- bool **AGC** [get, set]
- bool **VAD** [get, set]

Additional Inherited Members

3.119.1 Member Function Documentation

3.119.1.1 SetOrSwitchAudioListener()

```
bool SetOrSwitchAudioListener (
    AudioListener audioListener )
```

Set the AudioListener to be used with this [WebRtcAudioDsp](#)

Parameters

<i>audioListener</i>	The audioListener to be used
----------------------	------------------------------

Returns

Success or failure

3.119.1.2 SetOrSwitchAudioOutCapture()

```
bool SetOrSwitchAudioOutCapture (
    AudioOutCapture audioOutCapture )
```

Set the [AudioOutCapture](#) to be used with this [WebRtcAudioDsp](#)

Parameters

<i>audioOutCapture</i>	The audioOutCapture to be used
------------------------	--------------------------------

Returns

Success or failure

3.120 WebRTCAudioLib Class Reference

Inherited by [WebRTCAudioProcessor](#).

Public Types

- enum **Error**
- enum **Param**

Public Member Functions

- static IntPtr **webrtc_audio_processor_create** (int samplingRate, int channels, int frameSize, int reverseSamplingRate, int reverseChannels)
- static int **webrtc_audio_processor_init** (IntPtr proc)
- static int **webrtc_audio_processor_set_param** (IntPtr proc, int param, int v)
- static int **webrtc_audio_processor_process** (IntPtr proc, short[] buffer, int offset, out bool voiceDetected)
- static int **webrtc_audio_processor_process_reverse** (IntPtr proc, short[] buffer, int bufferSize)
- static void **webrtc_audio_processor_destroy** (IntPtr proc)

3.121 WebRTCAudioProcessor Class Reference

Inherits [WebRTCAudioLib](#), and [IProcessor< short >](#).

Public Member Functions

- **WebRTCAudioProcessor** ([ILogger](#) logger, int frameSize, int samplingRate, int channels, int reverseSamplingRate, int reverseChannels)
- short[] **Process** (short[] buf)
- void **OnAudioOutFrameFloat** (float[] data)
- void **Dispose** ()

Static Public Attributes

- static readonly int[] **SupportedSamplingRates** = { 8000, 16000, 32000, 48000 }

Properties

- int **AECStreamDelayMs** [set]
- bool?? **AEC** [set]
- bool? **AECHighPass** [set]
- bool?? **AECMobile** [set]
- bool? **HighPass** [set]
- bool? **NoiseSuppression** [set]
- bool? **AGC** [set]
- bool? **VAD** [set]
- bool **Bypass** [set]

Additional Inherited Members

Index

- AccumAvgPeakAmp
 - AudioUtil.ILevelMeter, [43](#)
- AcquireOrCreate
 - ObjectPool< TType, TInfo >, [74](#), [75](#)
- ActivityDelayMs
 - AudioUtil.IVoiceDetector, [50](#)
 - AudioUtil.VoiceDetector< T >, [125](#)
- Actor
 - Speaker, [102](#)
- AddPostProcessor
 - LocalVoiceFramed< T >, [68](#)
- AddPreProcessor
 - LocalVoiceFramed< T >, [68](#)
- AllowBluetooth
 - Photon.Voice.IOS, [8](#)
- Ambient
 - Photon.Voice.IOS, [6](#)
- Audio
 - POpusCodec.Enums, [12](#)
- AudioClip
 - Recorder, [91](#)
- AudioClipWrapper, [13](#)
- AudioDesc, [13](#)
- AudioGroup
 - Recorder, [91](#)
- AudioInChangeNotifier, [14](#)
- AudioInEnumerator, [14](#)
- AudioOpus
 - Photon.Voice, [6](#)
- AudioOutCapture, [15](#)
- AudioProcessing
 - Photon.Voice.IOS, [6](#)
- AudioSampleType
 - Photon.Voice, [5](#)
- AudioSessionCategory
 - Photon.Voice.IOS, [6](#)
- AudioSessionCategoryOption
 - Photon.Voice.IOS, [7](#)
- AudioSessionMode
 - Photon.Voice.IOS, [8](#)
- AudioSessionParameters, [15](#)
- AudioSessionParametersPresets, [15](#)
 - Game, [15](#)
 - VoIP, [15](#)
- AudioSyncBuffer< T >, [16](#)
- AudioUtil, [16](#)
 - Convert, [18](#)
 - ForceToStereo< T >, [18](#)
 - Resample< T >, [19](#)
 - ResampleAndConvert, [19](#), [20](#)
- AudioUtil.ILevelMeter, [43](#)
 - AccumAvgPeakAmp, [43](#)
 - CurrentAvgAmp, [44](#)
 - CurrentPeakAmp, [44](#)
 - ResetAccumAvgPeakAmp, [43](#)
- AudioUtil.IVoiceDetector, [50](#)
 - ActivityDelayMs, [50](#)
 - Detected, [51](#)
 - DetectedTime, [51](#)
 - On, [51](#)
 - OnDetected, [51](#)
 - Threshold, [51](#)
- AudioUtil.LevelMeter< T >, [52](#)
 - Process, [53](#)
 - ResetAccumAvgPeakAmp, [53](#)
- AudioUtil.LevelMeterDummy, [53](#)
 - ResetAccumAvgPeakAmp, [54](#)
- AudioUtil.LevelMeterFloat, [54](#)
 - LevelMeterFloat, [54](#)
- AudioUtil.LevelMeterShort, [55](#)
 - LevelMeterShort, [55](#)
- AudioUtil.Resampler< T >, [100](#)
 - Process, [101](#)
 - Resampler, [100](#)
- AudioUtil.ToneAudioPusher< T >, [104](#)
 - SetCallback, [105](#)
 - ToneAudioPusher, [104](#)
- AudioUtil.ToneAudioReader< T >, [105](#)
 - Channels, [107](#)
 - Error, [107](#)
 - Read, [106](#)
 - SamplingRate, [107](#)
 - ToneAudioReader, [106](#)
- AudioUtil.VoiceDetector< T >, [123](#)
 - ActivityDelayMs, [125](#)
 - Detected, [125](#)
 - DetectedTime, [125](#)
 - On, [125](#)
 - OnDetected, [126](#)
 - Process, [124](#)
 - Threshold, [125](#)
- AudioUtil.VoiceDetectorCalibration< T >, [126](#)
 - Calibrate, [127](#)
 - Process, [127](#)
 - VoiceDetectorCalibration, [126](#)
- AudioUtil.VoiceDetectorDummy, [127](#)
- AudioUtil.VoiceDetectorFloat, [128](#)
 - VoiceDetectorFloat, [128](#)

- AudioUtil.VoiceDetectorShort, [129](#)
 - VoiceDetectorShort, [129](#)
- AudioUtil.VoiceLevelDetectCalibrate< T >, [134](#)
 - Calibrate, [135](#)
 - LevelMeter, [135](#)
 - Process, [135](#)
 - VoiceDetector, [136](#)
 - VoiceLevelDetectCalibrate, [134](#)
- Auto
 - POpusCodec.Enums, [12](#)
- AutoConnectAndJoin
 - PhotonVoiceNetwork, [81](#)
- AutoCreateRecorderIfNotFound
 - PhotonVoiceView, [83](#)
- AutoCreateSpeakerIfNotFound
 - VoiceConnection, [120](#)
- AutoLeaveAndDisconnect
 - PhotonVoiceNetwork, [81](#)
- AutoStart
 - Recorder, [91](#)
- Bandwidth
 - POpusCodec.Enums, [10](#)
- BestRegionSummaryInPreferences
 - VoiceConnection, [121](#)
- Bitrate
 - Recorder, [91](#)
 - VoiceInfo, [132](#)
- BufferReaderPushAdapter
 - BufferReaderPushAdapter< T >, [21](#)
- BufferReaderPushAdapter< T >, [20](#)
 - BufferReaderPushAdapter, [21](#)
 - Service, [21](#)
- BufferReaderPushAdapterAsyncPool
 - BufferReaderPushAdapterAsyncPool< T >, [22](#)
- BufferReaderPushAdapterAsyncPool< T >, [21](#)
 - BufferReaderPushAdapterAsyncPool, [22](#)
 - Service, [22](#)
- BufferReaderPushAdapterAsyncPoolCopy
 - BufferReaderPushAdapterAsyncPoolCopy< T >, [23](#)
- BufferReaderPushAdapterAsyncPoolCopy< T >, [23](#)
 - BufferReaderPushAdapterAsyncPoolCopy, [23](#)
 - Service, [24](#)
- BufferReaderPushAdapterAsyncPoolFloatToShort, [24](#)
 - BufferReaderPushAdapterAsyncPoolFloatToShort, [25](#)
 - Service, [25](#)
- BufferReaderPushAdapterAsyncPoolShortToFloat, [25](#)
 - BufferReaderPushAdapterAsyncPoolShortToFloat, [26](#)
 - Service, [26](#)
- BufferReaderPushAdapterBase
 - BufferReaderPushAdapterBase< T >, [27](#)
- BufferReaderPushAdapterBase< T >, [27](#)
 - BufferReaderPushAdapterBase, [27](#)
 - Dispose, [27](#)
 - Service, [28](#)
- Calibrate
 - AudioUtil.VoiceDetectorCalibration< T >, [127](#)
 - AudioUtil.VoiceLevelDetectCalibrate< T >, [135](#)
- ChannelId
 - RemoteVoiceInfo, [97](#)
- Channels
 - AudioUtil.ToneAudioReader< T >, [107](#)
 - IAudioDesc, [36](#)
 - POpusCodec.Enums, [11](#)
 - VoiceInfo, [132](#)
- ClearProcessors
 - LocalVoiceFramed< T >, [68](#)
- ClientState
 - VoiceConnection, [121](#)
- Code
 - VoiceEvent, [130](#)
- Codec
 - Photon.Voice, [5](#)
- ConnectAndJoin, [28](#)
- ConnectAndJoinRoom
 - PhotonVoiceNetwork, [80](#)
- ConnectUsingSettings
 - VoiceConnection, [119](#)
- Convert
 - AudioUtil, [18](#)
- Count
 - Framer< T >, [35](#)
- Create
 - LocalVoiceAudio< T >, [63](#)
- CreateAudio
 - VoiceInfo, [131](#)
- CreateAudioOpus
 - VoiceInfo, [132](#)
- CreateLocalVoice
 - VoiceClient, [112](#)
- CreateLocalVoiceAudio< T >
 - VoiceClient, [113](#)
- CreateLocalVoiceAudioFromSource
 - VoiceClient, [113](#)
- CreateLocalVoiceFramed< T >
 - VoiceClient, [114](#)
- CurrentAvgAmp
 - AudioUtil.ILevelMeter, [44](#)
- CurrentPeakAmp
 - AudioUtil.ILevelMeter, [44](#)
- DebugEchoMode
 - LocalVoice, [60](#)
 - Recorder, [91](#)
- DebugLostPercent
 - VoiceClient, [115](#)
- Decoder
 - RemoteVoiceOptions, [99](#)
- Default
 - Photon.Voice.IOS, [8](#)
- DefaultToSpeaker
 - Photon.Voice.IOS, [8](#)
- Delay
 - POpusCodec.Enums, [11](#)

- Delay10ms
 - POpusCodec.Enums, 11
- Delay20ms
 - POpusCodec.Enums, 11
- Delay2dot5ms
 - POpusCodec.Enums, 11
- Delay40ms
 - POpusCodec.Enums, 11
- Delay5ms
 - POpusCodec.Enums, 11
- Delay60ms
 - POpusCodec.Enums, 11
- DequeueOutput
 - IEncoder, 41
- Detected
 - AudioUtil.IVoiceDetector, 51
 - AudioUtil.VoiceDetector< T >, 125
- DetectedTime
 - AudioUtil.IVoiceDetector, 51
 - AudioUtil.VoiceDetector< T >, 125
- Disconnect
 - PhotonVoiceNetwork, 80
- Dispatch
 - VoiceConnection, 120
- Dispose
 - BufferedReaderPushAdapterBase< T >, 27
 - LoadBalancingTransport, 57
 - LocalVoiceFramed< T >, 68
 - ObjectPool< TType, TInfo >, 75
- DuckOthers
 - Photon.Voice.IOS, 7
- Dummy
 - LocalVoiceAudioDummy, 65
- EncoderDelay
 - OpusEncoder, 78
- Encrypt
 - LocalVoice, 61
 - Recorder, 92
- EndOfStream
 - IEncoder, 41
- Error
 - AudioUtil.ToneAudioReader< T >, 107
 - IAudioDesc, 36
 - IDecoder, 40
 - IEncoder, 41
- FactoryPrimitiveArrayPool< T >, 32
- FactoryReusableArray< T >, 33
- ForceToStereo< T >
 - AudioUtil, 18
- Frame
 - Framer< T >, 35
- FrameDuration
 - Recorder, 92
- FrameDurationSamples
 - VoiceInfo, 132
- FrameDurationUs
 - VoiceInfo, 133
- FrameOut< T >, 34
- Framer
 - Framer< T >, 34
- Framer< T >, 34
 - Count, 35
 - Frame, 35
 - Framer, 34
- FrameSize
 - LocalVoiceFramedBase, 70
 - VoiceInfo, 133
- FramesLost
 - VoiceClient, 115
- FramesLostPercent
 - VoiceConnection, 121
- FramesLostPerSecond
 - VoiceConnection, 122
- FramesReceived
 - VoiceClient, 116
- FramesReceivedPerSecond
 - VoiceConnection, 122
- FramesSent
 - LocalVoice, 61
 - VoiceClient, 116
- FramesSentBytes
 - LocalVoice, 61
 - VoiceClient, 116
- Fullband
 - POpusCodec.Enums, 11
- Game
 - AudioSessionParametersPresets, 15
- GlobalInterestGroup
 - LoadBalancingTransport, 58
- Height
 - VoiceInfo, 133
- IAudioDesc, 35
 - Channels, 36
 - Error, 36
 - SamplingRate, 36
- IAudioOut< T >, 36
- IAudioPusher< T >, 37
 - SetCallback, 37
- IAudioReader< T >, 38
- IDataReader< T >, 38
 - Read, 38
- IDecoder, 39
 - Error, 40
 - Input, 39
 - Open, 39
- IDecoderQueuedOutputImageNative, 40
- IEncoder, 40
 - DequeueOutput, 41
 - EndOfStream, 41
 - Error, 41
 - Info, 41
 - Output, 42
- IEncoderDirect< B >, 42

- Input, [42](#)
- ILocalVoiceAudio, [44](#)
 - LevelMeter, [45](#)
 - VoiceDetector, [45](#)
 - VoiceDetectorCalibrate, [45](#)
 - VoiceDetectorCalibrating, [45](#)
- ILoggable, [46](#)
- ILoggableDependent, [46](#)
- ILogger, [46](#)
- ImageBufferInfo, [46](#)
- ImageBufferNative, [47](#)
- ImageBufferNativeAlloc, [47](#)
- ImageBufferNativeGCHandleSinglePlane, [47](#)
- ImageBufferNativePool< T >, [47](#)
- ImageInputBuf, [48](#)
- ImageOutputBuf, [48](#)
- Info
 - IEncoder, [41](#)
 - LocalVoice, [61](#)
 - ObjectPool< TType, TInfo >, [76](#)
 - RemoteVoiceInfo, [97](#)
- Init
 - ObjectPool< TType, TInfo >, [75](#)
 - PhotonVoiceView, [83](#)
 - Recorder, [89](#), [90](#)
- InitRecorder
 - VoiceConnection, [120](#)
- Input
 - IDecoder, [39](#)
 - IEncoderDirect< B >, [42](#)
 - OpusCodec.Decoder< T >, [30](#)
 - RawCodec.Decoder< T >, [29](#)
- InputFactory
 - Recorder, [92](#)
- Instance
 - PhotonVoiceNetwork, [81](#)
- InterestGroup
 - LocalVoice, [61](#)
 - Recorder, [92](#)
- IOSAudioForceToSpeaker, [48](#)
- IProcessor< T >, [48](#)
 - Process, [49](#)
- IsCurrentlyTransmitting
 - LocalVoice, [61](#)
 - Recorder, [92](#)
- IServiceable, [49](#)
 - Service, [50](#)
- IsInitialized
 - Recorder, [92](#)
- IsLinked
 - Speaker, [103](#)
- IsPhotonViewReady
 - PhotonVoiceView, [84](#)
- IsPlaying
 - Speaker, [103](#)
- IsRecorder
 - PhotonVoiceView, [84](#)
- IsRecording
 - PhotonVoiceView, [84](#)
 - Recorder, [93](#)
- IsSetup
 - PhotonVoiceView, [84](#)
- IsSpeaker
 - PhotonVoiceView, [85](#)
- IsSpeakerLinked
 - PhotonVoiceView, [85](#)
- IsSpeaking
 - PhotonVoiceView, [85](#)
- IVoiceTransport, [52](#)
- Lag
 - Speaker, [103](#)
- LevelMeter
 - AudioUtil.VoiceLevelDetectCalibrate< T >, [135](#)
 - ILocalVoiceAudio, [45](#)
 - Recorder, [93](#)
- LevelMeterFloat
 - AudioUtil.LevelMeterFloat, [54](#)
- LevelMeterShort
 - AudioUtil.LevelMeterShort, [55](#)
- LoadBalancingFrontend, [56](#)
- LoadBalancingTransport, [56](#)
 - Dispose, [57](#)
 - GlobalInterestGroup, [58](#)
 - LoadBalancingTransport, [57](#)
 - Service, [58](#)
 - VoiceClient, [58](#)
- LoadBalancingTransport2, [58](#)
- LocalUserServiceable
 - LocalVoice, [62](#)
- LocalVoice, [59](#)
 - DebugEchoMode, [60](#)
 - Encrypt, [61](#)
 - FramesSent, [61](#)
 - FramesSentBytes, [61](#)
 - Info, [61](#)
 - InterestGroup, [61](#)
 - IsCurrentlyTransmitting, [61](#)
 - LocalUserServiceable, [62](#)
 - Reliable, [62](#)
 - RemoveSelf, [60](#)
 - TransmitEnabled, [62](#)
- LocalVoiceAudio< T >, [62](#)
 - Create, [63](#)
 - VoiceDetectorCalibrate, [64](#)
 - VoiceDetectorCalibrating, [64](#)
- LocalVoiceAudioDummy, [64](#)
 - Dummy, [65](#)
 - VoiceDetectorCalibrate, [65](#)
- LocalVoiceAudioFloat, [66](#)
- LocalVoiceAudioShort, [66](#)
- LocalVoiceFramed< T >, [66](#)
 - AddPostProcessor, [68](#)
 - AddPreProcessor, [68](#)
 - ClearProcessors, [68](#)
 - Dispose, [68](#)
 - PushData, [68](#)

- PushDataAsync, 69
- PushDataAsyncReady, 69
- LocalVoiceFramedBase, 69
 - FrameSize, 70
- LocalVoices
 - VoiceClient, 116
- LocalVoicesInChannel
 - VoiceClient, 114
- Logger, 70
 - VoiceConnection, 122
- LogLevel
 - VoiceConnection, 122
- LoopAudioClip
 - Recorder, 93
- Measurement
 - Photon.Voice.IOS, 8
- Mediumband
 - POpusCodec.Enums, 11
- MicAmplifier, 70
- MicAmplifierFloat, 70
- MicAmplifierShort, 71
- MicrophoneType
 - Recorder, 93
- MicWrapper, 71
- MicWrapperPusher, 71
- MinimalTimeScaleToDispatchInFixedUpdate
 - VoiceConnection, 120
- MixWithOthers
 - Photon.Voice.IOS, 7
- Mono
 - POpusCodec.Enums, 11
- MoviePlayback
 - Photon.Voice.IOS, 8
- MultiRoute
 - Photon.Voice.IOS, 7
- Music
 - POpusCodec.Enums, 12
- Narrowband
 - POpusCodec.Enums, 11
- NativeAndroidMicrophoneSettings, 72
- ObjectFactory< TType, TInfo >, 72
- ObjectPool
 - ObjectPool< TType, TInfo >, 74
- ObjectPool< TType, TInfo >, 73
 - AcquireOrCreate, 74, 75
 - Dispose, 75
 - Info, 76
 - Init, 75
 - ObjectPool, 74
 - Release, 75, 76
- On
 - AudioUtil.IVoiceDetector, 51
 - AudioUtil.VoiceDetector< T >, 125
- OnDetected
 - AudioUtil.IVoiceDetector, 51
 - AudioUtil.VoiceDetector< T >, 126
- OnRemoteVoiceInfoAction
 - VoiceClient, 116
- OnRemoteVoiceRemoveAction
 - RemoteVoiceOptions, 99
 - Speaker, 103
- Open
 - IDecoder, 39
 - OpusCodec.Decoder< T >, 30
 - RawCodec.Decoder< T >, 29
- OpusApplicationType
 - POpusCodec.Enums, 11
- OpusCodec, 76
- OpusCodec.Decoder< T >, 30
 - Input, 30
 - Open, 30
- OpusCodec.DecoderFactory, 31
- OpusCodec.Encoder< T >, 31
- OpusCodec.EncoderFloat, 32
- OpusCodec.EncoderShort, 32
- OpusCodec.Factory, 32
- OpusCodec.Util, 111
- OpusDecoder< T >, 77
- OpusEncoder, 77
 - EncoderDelay, 78
- OpusException, 78
- OpusLib, 78
- Output
 - IEncoder, 42
- Photon, 3
- Photon.Voice, 3
 - AudioOpus, 6
 - AudioSampleType, 5
 - Codec, 5
- Photon.Voice.IOS, 6
 - AllowBluetooth, 8
 - Ambient, 6
 - AudioProcessing, 6
 - AudioSessionCategory, 6
 - AudioSessionCategoryOption, 7
 - AudioSessionMode, 8
 - Default, 8
 - DefaultToSpeaker, 8
 - DuckOthers, 7
 - Measurement, 8
 - MixWithOthers, 7
 - MoviePlayback, 8
 - MultiRoute, 7
 - PlayAndRecord, 6
 - Playback, 6
 - Record, 6
 - SoloAmbient, 6
 - VideoChat, 9
 - VideoRecording, 8
 - VoiceChat, 8
- Photon.Voice.PUN, 9
- Photon.Voice.Unity, 9
- Photon.Voice.Unity.UtilityScripts, 10
- PhotonMicrophoneDeviceId

- Recorder, 93
- PhotonMicrophoneEnumerator
 - Recorder, 93
- PhotonVoiceCreatedParams, 79
- PhotonVoiceLagSimulationGui, 79
- PhotonVoiceNetwork, 79
 - AutoConnectAndJoin, 81
 - AutoLeaveAndDisconnect, 81
 - ConnectAndJoinRoom, 80
 - Disconnect, 80
 - Instance, 81
 - VoiceRoomNameSuffix, 81
 - WorkInOfflineMode, 81
- PhotonVoiceStatsGui, 82
- PhotonVoiceView, 82
 - AutoCreateRecorderIfNotFound, 83
 - Init, 83
 - IsPhotonViewReady, 84
 - IsRecorder, 84
 - IsRecording, 84
 - IsSetup, 84
 - IsSpeaker, 85
 - IsSpeakerLinked, 85
 - IsSpeaking, 85
 - RecorderInUse, 85
 - SetupDebugSpeaker, 84
 - SpeakerInUse, 85
 - UsePrimaryRecorder, 84
- PlayAndRecord
 - Photon.Voice.IOS, 6
- Playback
 - Photon.Voice.IOS, 6
- PlaybackOnlyWhenEnabled
 - Speaker, 103
- PlaybackStarted
 - Speaker, 103
- PlayerId
 - RemoteVoiceInfo, 98
- POpusCodec, 10
- POpusCodec.Enums, 10
 - Audio, 12
 - Auto, 12
 - Bandwidth, 10
 - Channels, 11
 - Delay, 11
 - Delay10ms, 11
 - Delay20ms, 11
 - Delay2dot5ms, 11
 - Delay40ms, 11
 - Delay5ms, 11
 - Delay60ms, 11
 - Fullband, 11
 - Mediumband, 11
 - Mono, 11
 - Music, 12
 - Narrowband, 11
 - OpusApplicationType, 11
 - RestrictedLowDelay, 12
 - SignalHint, 12
 - Stereo, 11
 - SuperWideband, 11
 - Voice, 12
 - Voip, 12
 - Wideband, 11
- PrimaryRecorder
 - VoiceConnection, 122
- PrimitiveArrayPool< T >, 86
- Process
 - AudioUtil.LevelMeter< T >, 53
 - AudioUtil.Resampler< T >, 101
 - AudioUtil.VoiceDetector< T >, 124
 - AudioUtil.VoiceDetectorCalibration< T >, 127
 - AudioUtil.VoiceLevelDetectCalibrate< T >, 135
 - IProcessor< T >, 49
- PushData
 - LocalVoiceFramed< T >, 68
- PushDataAsync
 - LocalVoiceFramed< T >, 69
- PushDataAsyncReady
 - LocalVoiceFramed< T >, 69
- RawCodec, 86
- RawCodec.Decoder< T >, 29
 - Input, 29
 - Open, 29
- RawCodec.Encoder< T >, 31
- ReactOnSystemChanges
 - Recorder, 94
- Read
 - AudioUtil.ToneAudioReader< T >, 106
 - IDataReader< T >, 38
- Record
 - Photon.Voice.IOS, 6
- Recorder, 86
 - AudioClip, 91
 - AudioGroup, 91
 - AutoStart, 91
 - Bitrate, 91
 - DebugEchoMode, 91
 - Encrypt, 92
 - FrameDuration, 92
 - Init, 89, 90
 - InputFactory, 92
 - InterestGroup, 92
 - IsCurrentlyTransmitting, 92
 - IsInitialized, 92
 - IsRecording, 93
 - LevelMeter, 93
 - LoopAudioClip, 93
 - MicrophoneType, 93
 - PhotonMicrophoneDeviceId, 93
 - PhotonMicrophoneEnumerator, 93
 - ReactOnSystemChanges, 94
 - RecordOnlyWhenEnabled, 94
 - ReliableMode, 94
 - RequiresRestart, 94
 - RestartRecording, 90

- SamplingRate, [94](#)
- SkipDeviceChangeChecks, [94](#)
- SourceType, [95](#)
- StartRecording, [90](#)
- StopRecording, [90](#)
- StopRecordingWhenPaused, [95](#)
- TransmitEnabled, [95](#)
- TrySamplingRateMatch, [95](#)
- TypeConvert, [95](#)
- UnityMicrophoneDevice, [95](#)
- UseOnAudioFilterRead, [96](#)
- UserData, [96](#)
- VoiceDetection, [96](#)
- VoiceDetectionDelayMs, [96](#)
- VoiceDetectionThreshold, [96](#)
- VoiceDetector, [96](#)
- VoiceDetectorCalibrate, [90](#)
- VoiceDetectorCalibrating, [97](#)
- Recorder.PhotonVoiceCreatedParams, [79](#)
- RecorderInUse
 - PhotonVoiceView, [85](#)
- RecordOnlyWhenEnabled
 - Recorder, [94](#)
- Release
 - ObjectPool< TType, TInfo >, [75](#), [76](#)
- Reliable
 - LocalVoice, [62](#)
- ReliableMode
 - Recorder, [94](#)
- RemoteVoiceAdded
 - VoiceConnection, [123](#)
- RemoteVoiceInfo, [97](#)
 - ChannelId, [97](#)
 - Info, [97](#)
 - PlayerId, [98](#)
 - VoiceId, [98](#)
- RemoteVoiceInfoDelegate
 - VoiceClient, [115](#)
- RemoteVoiceInfos
 - VoiceClient, [116](#)
- RemoteVoiceLink, [98](#)
- RemoteVoiceOptions, [98](#)
 - Decoder, [99](#)
 - OnRemoteVoiceRemoveAction, [99](#)
 - SetOutput, [99](#)
- RemoveLocalVoice
 - VoiceClient, [115](#)
- RemoveSelf
 - LocalVoice, [60](#)
- RequiresRestart
 - Recorder, [94](#)
- Resample< T >
 - AudioUtil, [19](#)
- ResampleAndConvert
 - AudioUtil, [19](#), [20](#)
- Resampler
 - AudioUtil.Resampler< T >, [100](#)
- ResetAccumAvgPeakAmp
 - AudioUtil.ILevelMeter, [43](#)
 - AudioUtil.LevelMeter< T >, [53](#)
 - AudioUtil.LevelMeterDummy, [54](#)
- RestartPlayback
 - Speaker, [102](#)
- RestartRecording
 - Recorder, [90](#)
- RestrictedLowDelay
 - POpusCodec.Enums, [12](#)
- RoundTripTime
 - VoiceClient, [117](#)
- RoundTripTimeVariance
 - VoiceClient, [117](#)
- SamplingRate
 - AudioUtil.ToneAudioReader< T >, [107](#)
 - IAudioDesc, [36](#)
 - Recorder, [94](#)
 - VoiceInfo, [133](#)
- Service
 - BufferReaderPushAdapter< T >, [21](#)
 - BufferReaderPushAdapterAsyncPool< T >, [22](#)
 - BufferReaderPushAdapterAsyncPoolCopy< T >, [24](#)
 - BufferReaderPushAdapterAsyncPoolFloatToShort, [25](#)
 - BufferReaderPushAdapterAsyncPoolShortToFloat, [26](#)
 - BufferReaderPushAdapterBase< T >, [28](#)
 - IServiceable, [50](#)
 - LoadBalancingTransport, [58](#)
 - VoiceClient, [115](#)
- SetCallback
 - AudioUtil.ToneAudioPusher< T >, [105](#)
 - IAudioPusher< T >, [37](#)
- SetOrSwitchAudioListener
 - WebRtcAudioDsp, [137](#)
- SetOrSwitchAudioOutCapture
 - WebRtcAudioDsp, [137](#)
- SetOutput
 - RemoteVoiceOptions, [99](#)
- Settings
 - VoiceConnection, [121](#)
- SetupDebugSpeaker
 - PhotonVoiceView, [84](#)
- SignalHint
 - POpusCodec.Enums, [12](#)
- SkipDeviceChangeChecks
 - Recorder, [94](#)
- SoloAmbient
 - Photon.Voice.IOS, [6](#)
- SourceType
 - Recorder, [95](#)
- Speaker, [101](#)
 - Actor, [102](#)
 - IsLinked, [103](#)
 - IsPlaying, [103](#)
 - Lag, [103](#)
 - OnRemoteVoiceRemoveAction, [103](#)

- PlaybackOnlyWhenEnabled, [103](#)
- PlaybackStarted, [103](#)
- RestartPlayback, [102](#)
- StartPlayback, [102](#)
- StopPlayback, [102](#)
- SpeakerFactory
 - VoiceConnection, [121](#)
- SpeakerInUse
 - PhotonVoiceView, [85](#)
- SpeakerLinked
 - VoiceConnection, [123](#)
- SpeakerPrefab
 - VoiceConnection, [122](#)
- StartPlayback
 - Speaker, [102](#)
- StartRecording
 - Recorder, [90](#)
- Stereo
 - POpusCodec.Enums, [11](#)
- StopPlayback
 - Speaker, [102](#)
- StopRecording
 - Recorder, [90](#)
- StopRecordingWhenPaused
 - Recorder, [95](#)
- SuperWideband
 - POpusCodec.Enums, [11](#)
- SuppressInfoDuplicateWarning
 - VoiceClient, [117](#)
- TestTone, [104](#)
- Threshold
 - AudioUtil.IVoiceDetector, [51](#)
 - AudioUtil.VoiceDetector< T >, [125](#)
- ToneAudioPusher
 - AudioUtil.ToneAudioPusher< T >, [104](#)
- ToneAudioReader, [107](#)
 - AudioUtil.ToneAudioReader< T >, [106](#)
- TransmitEnabled
 - LocalVoice, [62](#)
 - Recorder, [95](#)
- TrySamplingRateMatch
 - Recorder, [95](#)
- TypeConvert
 - Recorder, [95](#)
- UnityAndroidAudioInAEC, [108](#)
- UnityAudioOut, [108](#)
- UnityMicrophone, [108](#)
- UnityMicrophoneDevice
 - Recorder, [95](#)
- UnsupportedCodecException, [109](#)
 - UnsupportedCodecException, [109](#)
- UnsupportedSampleTypeException, [110](#)
 - UnsupportedSampleTypeException, [110](#)
- UseOnAudioFilterRead
 - Recorder, [96](#)
- UsePrimaryRecorder
 - PhotonVoiceView, [84](#)
- UserData
 - Recorder, [96](#)
 - VoiceInfo, [133](#)
- VideoChat
 - Photon.Voice.IOS, [9](#)
- VideoRecording
 - Photon.Voice.IOS, [8](#)
- Voice
 - POpusCodec.Enums, [12](#)
- VoiceChat
 - Photon.Voice.IOS, [8](#)
- VoiceClient, [111](#)
 - CreateLocalVoice, [112](#)
 - CreateLocalVoiceAudio< T >, [113](#)
 - CreateLocalVoiceAudioFromSource, [113](#)
 - CreateLocalVoiceFramed< T >, [114](#)
 - DebugLostPercent, [115](#)
 - FramesLost, [115](#)
 - FramesReceived, [116](#)
 - FramesSent, [116](#)
 - FramesSentBytes, [116](#)
 - LoadBalancingTransport, [58](#)
 - LocalVoices, [116](#)
 - LocalVoicesInChannel, [114](#)
 - OnRemoteVoiceInfoAction, [116](#)
 - RemoteVoiceInfoDelegate, [115](#)
 - RemoteVoiceInfos, [116](#)
 - RemoveLocalVoice, [115](#)
 - RoundTripTime, [117](#)
 - RoundTripTimeVariance, [117](#)
 - Service, [115](#)
 - SuppressInfoDuplicateWarning, [117](#)
 - VoiceConnection, [123](#)
- VoiceComponent, [117](#)
- VoiceConnection, [118](#)
 - AutoCreateSpeakerIfNotFound, [120](#)
 - BestRegionSummaryInPreferences, [121](#)
 - ClientState, [121](#)
 - ConnectUsingSettings, [119](#)
 - Dispatch, [120](#)
 - FramesLostPercent, [121](#)
 - FramesLostPerSecond, [122](#)
 - FramesReceivedPerSecond, [122](#)
 - InitRecorder, [120](#)
 - Logger, [122](#)
 - LogLevel, [122](#)
 - MinimalTimeScaleToDispatchInFixedUpdate, [120](#)
 - PrimaryRecorder, [122](#)
 - RemoteVoiceAdded, [123](#)
 - Settings, [121](#)
 - SpeakerFactory, [121](#)
 - SpeakerLinked, [123](#)
 - SpeakerPrefab, [122](#)
 - VoiceClient, [123](#)
- VoiceDetection
 - Recorder, [96](#)
- VoiceDetectionDelayMs
 - Recorder, [96](#)

- VoiceDetectionThreshold
 - Recorder, [96](#)
- VoiceDetector
 - AudioUtil.VoiceLevelDetectCalibrate< T >, [136](#)
 - ILocalVoiceAudio, [45](#)
 - Recorder, [96](#)
- VoiceDetectorCalibrate
 - ILocalVoiceAudio, [45](#)
 - LocalVoiceAudio< T >, [64](#)
 - LocalVoiceAudioDummy, [65](#)
 - Recorder, [90](#)
- VoiceDetectorCalibrating
 - ILocalVoiceAudio, [45](#)
 - LocalVoiceAudio< T >, [64](#)
 - Recorder, [97](#)
- VoiceDetectorCalibration
 - AudioUtil.VoiceDetectorCalibration< T >, [126](#)
- VoiceDetectorFloat
 - AudioUtil.VoiceDetectorFloat, [128](#)
- VoiceDetectorShort
 - AudioUtil.VoiceDetectorShort, [129](#)
- VoiceEvent, [130](#)
 - Code, [130](#)
- Voiceld
 - RemoteVoiceInfo, [98](#)
- VoiceInfo, [130](#)
 - Bitrate, [132](#)
 - Channels, [132](#)
 - CreateAudio, [131](#)
 - CreateAudioOpus, [132](#)
 - FrameDurationSamples, [132](#)
 - FrameDurationUs, [133](#)
 - FrameSize, [133](#)
 - Height, [133](#)
 - SamplingRate, [133](#)
 - UserData, [133](#)
 - Width, [133](#)
- VoiceLevelDetectCalibrate
 - AudioUtil.VoiceLevelDetectCalibrate< T >, [134](#)
- VoiceLogger, [136](#)
- VoiceRoomNameSuffix
 - PhotonVoiceNetwork, [81](#)
- VoIP
 - AudioSessionParametersPresets, [15](#)
- Voip
 - POpusCodec.Enums, [12](#)
- WebRtcAudioDsp, [136](#)
 - SetOrSwitchAudioListener, [137](#)
 - SetOrSwitchAudioOutCapture, [137](#)
- WebRTCAudioLib, [138](#)
- WebRTCAudioProcessor, [138](#)
- Wideband
 - POpusCodec.Enums, [11](#)
- Width
 - VoiceInfo, [133](#)
- WorkInOfflineMode
 - PhotonVoiceNetwork, [81](#)