

User Manual

MM Installation

Install with one click by executing `tools/install_environment.sh` (Mac users execute `tools/install_environment_m2.sh`)

MM运行方式

In the console, input

```
mm your_config
```

or

```
python motionmodel/start.py your_config
```

to run MM files. The config file is stored in the MM root directory by default.

Config File

The config file is mainly divided into five sections: **Main,Mask,Root,Algorithms,Paramater**

Main

Users need to specify the runtime environment here, `cpu` means execution with the CPU, `mps` means using the VRAM in the Mac chip for inference, and numbers represent using GPU numbers for inference.

```
gpu = cpu  
gpu = mps  
gpu = 0,1,2
```

Next, you need to specify `frame_step` to set the output interval. When `frame_step=1`, it only outputs MM at an interval of 1 (`mv0, mv1`). For example, with `frame_step=1,2,3`, it outputs (`mv0, mv1, mv2, mv3, mv4, mv5`).


```
frame_step = 1,2,3
```

Root

In this section, users need to specify the input file path and output file path.

```
root = pattern/1k
output = result/1k
```

Then MM inference is performed for all scenes in this path, as shown in the image below:



To run MM on a single scene, you can use

```
enable_single_input_mode_2D = 1
root_2D = path_to_your_scene
```


Depth and Disparity

Enable depth mode (generate disparity in 3D mode) by setting `cal_depth= 1`

```
cal_depth = 1
```

3D

Enable 3D mode by setting `3D_mode = 1`. You can use `enable_single_input_mode` to specify `left_root` and `right_root` directories separately, otherwise, the following structure is used by default.



###Note: When using the default structure, you need to specify the names of the left and right folders.

```
left_dir_name = left
right_dir_name = right
```

Algorithms

Users can change the core MM algorithm by changing the algorithm name. Please refer to the mmalgo in the config file for supported algorithms.

```
algorithm = kousei-v1
```

To specify other versions of the algorithm, you can add the version date, such as:

```
algorithm = kousei-v1-221013
```

Paramater

Users can control the image smoothing value by setting the `resize_rate`.

```
resize_rate_x = 1
resize_rate_y = 1
```

This value controls between 0.5-1. The smaller the value, the less memory consumed and the smoother the mv. For large images, if the mv quality is poor, try reducing it to improve smoothness.

For images with `film_border` or extended edges, add:

```
film_border = 0,0,0,0
```

to exclude the border effect. The four numbers represent the length of the top and bottom borders and the width of the left and right borders, respectively.

For mask mode, if the input mask is non-binary, modify threshold to control the edge blur.

```
threshold =0
```

The threshold value is 0-1. For foreground masks, 0 represents the outer ring, and 1 represents the inner ring. For background masks, it's the opposite.

MM update

```
./tools/update_mm.sh
```